General Stuff

- Density $\rho = \frac{\Delta m}{\Delta V}$
 - Uniform Density $\rho = \frac{m}{V}$
- Pressure $p = \frac{\Delta F}{\Delta A}$
 - Uniform Force on Flat Area $\rho = \frac{F}{4}$
 - Conversions $1atm = 1.01 \times 10^5 Pa = 760torr = 14.7 lb/in^2$
- Trig Relations are in Trigonometric Formulas, Section A.1.1.

2 Fluids

We must satisfy several parameters to make life easier, and to use most of these formulae.

- 1. Incompressible Density of the fluid is constant
- 2. Non-turbulent Flow Think of fluids swirling around an object
- 3. Isostatic Pressure Pressure inside the fluid is the same in all directions
- Pressure at Some Depth $p_2 = p_1 + \rho g (y_1 y_2)$
 - Pressure at Depth $h \to p = p_0 + \rho g h$
- Pascal's Principle 2 Parts
 - 1. $\vec{F_o} = \vec{F_i} \frac{A_o}{A_i}$
 - $2. \ d_o = d_i \frac{A_i}{A}$
 - When 2 pressures should be equal, their forces are inversely proportional
 - Set each pressure equal to each other, then solve for the missing variable.
- Archimedes' Principle $\vec{F}_{Up} = \vec{F}_{Down}$
 - Usually breaks down to $\vec{F}_{Bouyant} = \vec{F}_{q,Object}$
 - $-\vec{F}_{Bouyant} = m_{Object}g$
 - $-\vec{F}_{Bouyant} = \rho_{Object} V_{Object} g$
- Continuity of Fluids
 - $-A_1v_1 = A_2v_2$
- Bernoulli's Equation $p_1 + \frac{1}{2}\rho v_1^2 + \rho g y_1 = p_2 + \frac{1}{2}\rho v_2^2 + \rho g y_2$

 - Fluids at Rest $p_2=p_1+\rho g\left(y_1-y_2\right)$ Fluids not Changing Height $p_1+\frac{1}{2}\rho v_1^2=p_2+\frac{1}{2}\rho v_2^2$

3 Waves

Usually of form $y = y_m \sin(kx \pm \omega t)$ There are two types of waves:

- 1. Transverse Waves Waves where displacement from equilibrium is orthogonal to direction of propagation
 - String Waves
 - Electromagnetic Waves
- 2. Longitudinal Waves Waves where displacement from equilibrium is parallel to direction of propagation
 - Pressure Waves
 - Sound Waves (Which are a type of pressure wave)
- y_m Amplitude, m
- k Angular Wave Number, rad/m
 - $-k = \frac{2\pi}{1}$
 - $-\lambda$ is wavelength, m
- ω Angular Frequency, rad/s
 - $-\omega = 2\pi f$
 - f is frequency, Hz
 - Sign of this goes the opposite the direction the wave is going
 - 1. Wave going in positive direction (+), then the sign should be negative (-)
 - 2. Wave going in negative direction (-), then the sign should be positive (+)

- $v = \lambda f$, Wave Velocity, m/s
 - $-v = \frac{\omega}{2\pi} * \frac{2\pi}{k} = \frac{\omega}{k}$
 - This can be proven with the angular portion of any wave (inside the parentheses of trig function)

$$kx - \omega t = \text{Constant}$$

$$\frac{d}{dt} [kx - \omega t] = \frac{d}{dt} [\text{Constant}]$$

$$k\frac{dx}{dt} - \omega \frac{dt}{dt} = 0$$

$$kv - \omega = 0$$

$$kv = \omega$$

$$v = \frac{\omega}{k}$$

Since $\omega = 2\pi f$, then $k = \frac{\lambda}{2\pi}$

Wave Interference

Waves are nice, and they just sum when they interfere. Let:

$$y_1(x,t) = y\sin(kx - \omega t) \tag{3.1}$$

$$y_2(x,t) = y\sin(kx + \omega t + \varphi) \tag{3.2}$$

$$Y(x,t) = y\left[\sin\left(kx - \omega t\right) + \sin\left(kx + \omega t + \varphi\right)\right] \tag{3.3}$$

You can usually use Equation A.1 to simplify Equation 3.3.

Constructive/Destructive Interference

$$\phi = 2\pi \frac{PathLengthDiff}{\lambda} = 2\pi \frac{\Delta PLD}{\lambda}$$

$$n = \frac{\phi}{2\pi} = 4 \frac{PathLengthDiff}{\lambda}$$

- PathLengthDiff Is the Difference in path lengths that the waves must travel
- phi Angular Location of points of Complete Constructive/Destructive Interference
- \bullet n Number of locations where there is Complete Constructive/Destructive Interference

Standing Waves

This is actually the superposition of 2 waves, traveling in opposite directions, on a medium that is fixed at both ends, i.e. a taut string held by a wall.

Location of Nodes and Antinodes

- Nodes $x = n^{\frac{\lambda}{2}}$ for n = 0, 1, 2, ...
 - Always at closed ends of tubes
- Antinodes $x = (n + \frac{1}{2}) \frac{\lambda}{2}$ for n = 0, 1, 2, ...
 - Always at open ends of tubes

Resonant Frequencies/Harmonics

These can also be called harmonics. There is a resonant frequency for every number of nodes/antinodes on the standing wave.

$$f = \frac{v}{\lambda} = n \frac{v}{2L}$$

- L is the length of the medium (The String).
- λ is the wavelength of the wave formed.

This can be extended to find the base resonant frequency, if you know how many node levels are between the two resonant frequencies given, i.e. they say that the **NEXT** frequency, means n + 1.

$$f_{n+m} - f_n = (n+m)\frac{v}{2L} - n\frac{v}{2L} = m\frac{v}{2L}$$

Reflecting Sound

- D = (n+1) d = vt
 - -n is the number of reflections that occurred
 - -n+1 is used when we want the distance the wave covers

Sound in Different Mediums

Frequency is a property of a wave, and CANNOT BE ALTERED. This means that:

$$v = \lambda f$$
 $v_{Sound,Material1} = \lambda_{Material1} f_{Unique,Material1}$
 $v_{Sound,Material2} = \lambda_{Material2} f_{Unique,Material2}$
 $f_{Unique,Material1} = f_{Unique,Material2}$
 $\frac{v_{Sound,Material1}}{\lambda_{Material1}} = \frac{v_{Sound,Material2}}{\lambda_{Material2}}$

Doppler Effect

$$f' = f \frac{v \pm v_D}{v \pm v_S}$$

- Moving TOWARDS each other: Frequency Increase
- ullet Moving AWAY from each other: Frequency Decrease
- f Initial Frequency, Hz
- v Sound Speed, m/s
- v_D Detector Speed, m/s
- v_S Source Speed, m/s
- For Numerator:
 - If detector is moving towards the source, +
 - If detector is moving away from the source, -
- For Denominator:
 - If source is moving away from detector, +
 - If source is moving towards the detector, -

4 Thermodynamics

Defn 1 (Thermodynamics). *Thermodynamics* is the study of energy transfer between two macroscopic bodies driven by temperature differences.

Laws of Thermodynamics

Defn 2 (0th Law of Thermodynamics). If 2 bodies, A and B are in thermal equilibrium with a third body "T", then they are in thermal equilibrium with each other.

Defn 3 (1st Law of Thermodynamics).

$$dE_{Internal} = dQ - dT$$
, dQ and dT are inexact (path-dependent) differentials. (4.1)

Special Cases for the 1st Law of Thermodynamics:

- 1. Adiabatic Processes $dE_{Int} = -dW$
 - No heat exchange
 - Insulating
 - Something happens too quickly for system to keep up
- 2. Isothermal Processes $dT = 0 \rightarrow dE_{Int} = 0 \rightarrow dQ = dW$
- 3. Isobaric Processes dW = pdV, p(pressure) is constant
- 4. Cyclical Processes $dE_{Int} = 0 \rightarrow dQ = dW$
 - You end a cycle with the same internal energy when the cycle started

Defn 4 (2nd Law of Thermodynamics). If a cyclical process occurs in a CLOSED system, the entropy of the system increases for irreversible processes and remains constant for reversible processes. IT NEVER DECREASES!!

$$\Delta S \ge 0 \tag{4.2}$$

$$\Delta S = \int_{a}^{b} \frac{dQ\left(T\right)}{T} \tag{4.3}$$

 ΔS is a state-function, meaning it is path-independent.

Heat and Work

- $dW = \vec{F} ds$
- $\vec{F} = p(V, T) dV$
- $W = \int p(V, T) dV$ $W = \int p(V, T) dV$ $W = \frac{dQ}{dt}$ $W = \frac{\Delta Q}{\Delta t}$

Thermal Expansion

Occurs because the "springs" between each of the atoms in a lattice have energy applied by Heat (Temperature Change).

- $\frac{\Delta L}{L_0} = \alpha \Delta T$ (One-Dimensional Expansion)
- $\frac{dL}{L_0} = \alpha dT$ (One-Dimensional Expansion)
 - $-\alpha$ is a material-specific constant

Specific Heat/Heat Capacity

- $C = \frac{dQ}{dT} \leftarrow \text{Specific Heat}$
- $c = \frac{dQ}{mdT} \leftarrow \text{Mass Specific Heat}$

Heat of Phase Transitions

This is a constant unique to the material and the phase transition it is going through.

- Q = Lm
- - $-l_{Fusion}^{m_i}$ = Heat required to turn things from **SOLID TO LIQUID**
 - $-l_{Vapor}$ = Heat required to turn things from **LIQUID TO GAS**

Conduction Heat Transfer

- $P_{Conduction} = \frac{(T_H T_C)}{L} Ak$ L = Length

 - -A = Cross-Sectional Area
 - -k = Material's Thermal Conductivity

For multiple materials between 2 thermal reservoirs:

- $P_1 = P_2 = \ldots = P_n$
- Heat will only flow as fast as the slowest thermal conductor

5 Entropy

There is a heavy relationship between this and the 2nd Law of Thermodynamics.

Defn 5 (Entropy). Entropy is a measure of the number of available states.

$$S = k_B \ln \left(\Omega \right) \tag{5.1}$$

Entropy is NOT disorder.

6 Light

Defn 6 (Photon). A photon is a wave propagating through an electric field.

The various θ used in Equations (6.1), (6.2) are measured from the surface normal.

Chromatic Dispersion is the breaking up of polychromatic light by spectra. Think of Pink Floyd's Dark Side of the Moon album cover. This happens because shorter wavelength, higher frequency light has a slightly higher index of refraction.

Polychromatic_Light_Indices_Refraction.png

Figure 1: Indices of Refraction for Polychromatic Light

6.1 Reflection

$$\theta_{reflected} = \theta_{incident}$$
 (6.1)

6.2 Refraction

Defn 7 (Snell's Law).

$$n_{refract}\sin\left(\theta_{refract}\right) = n_{incident}\sin\left(\theta_{incident}\right)$$
 (6.2)

Defn 8 (Index of Refraction).

$$n_i = \frac{c}{v_i} \tag{6.3}$$

6.3 Total Internal Reflection

Total Internal Reflection occurs when the refracted light's angle is $\frac{\pi}{2}$.

$$n_{refract} \sin \left(\theta_{refract}\right) = n_{incident} \sin \left(\theta_{incident}\right), \text{ where } \theta_{refract} = \frac{\pi}{2}$$
 (6.4)

7 Quantum Mechanics

A Reference Material

A.1 Trigonometry

A.1.1 Trigonometric Formulas

$$\sin(\alpha) + \sin(\beta) = 2\sin\left(\frac{\alpha+\beta}{2}\right)\cos\left(\frac{\alpha-\beta}{2}\right)$$
 (A.1)