Computer Science 161 Nicholas Weaver

x86 Assembly

Adapted from CS 161 Spring 2022 - Lecture 3

Next: x86 Assembly and Call Stack

Computer Science 161 Nicholas Weave

Part CS 61C review

- How do computers represent numbers as bits and bytes?
- How do computers interpret and run the programs we write?
- O How do computers organize segments of memory?

Part new content

- How does x86 assembly work?
- How do you call a function in x86?

Computer Science 161 Nicholas Weaver

Number Representation

Units of Measurement

Computer Science 161
Nicholas Weaver

- In computers, all data is represented as bits
 - Bit: a binary digit, 0 or 1
- Names for groups of bits
 - 4 bits = 1 nibble
 - 8 bits = 1 byte
- How many bits/nibbles/bytes in 0ь 1000 1000 1000 1000?
 - 16 bits, or 4 nibbles, or 2 bytes

Hexadecimal

Computer Science 161 Nicholas Weaver

4 bits can be represented as
1 hexadecimal digit (base 16)

- How would you write0b11000110 in hex?
 - \circ 0xC6
 - Note: For clarity, we add 0₺ in front of bits and 0x in front of hex

Binary	Hexadecimal
0000	0
0001	1
0010	2
0011	3
0100	4
0101	5
0110	6
0111	7


Binary	Hexadecimal
1000	8
1001	9
1010	A
1011	В
1100	С
1101	D
1110	E
1111	F

Computer Science 161 Nicholas Weaver

Running C Programs

CALL (Compiler, Assembler, Linker, Loader)

Computer Science 161 Nicholas Weaver




CALL (Compiler, Assembler, Linker, Loader)

Computer Science 161 Nicholas Weave

- Compiler: Converts C code into assembly code (RISC-V, x86)
- Assembler: Converts assembly code into machine code (raw bits)
 - Think 61C's RISC-V "green sheet"
- Linker: Deals with dependencies and libraries
 - You can ignore this part for 161
- Loader: Sets up memory space and jumps into the machine code
 - Sometimes, there is an additional linking step right before loading, called dynamic loading
 - Result: The executable doesn't need to contain all the dependencies
 - This also provides additional mitigations, as we'll see later
- After these steps, execution begins, and C runtime library calls main!

CPU, Memory, and Registers

Computer Science 161 Nicholas Weaver



Computer Science 161 Nicholas Weaver

Memory Layout

C Memory Layout

Computer Science 161 Nicholas Weave

- At runtime, the loader tells your OS to give your program a big blob of memory
- On a 32-bit system, the memory has 32-bit addresses
 - On a 64-bit system, memory has 64-bit addresses
 - We use 32-bit systems in this class
- Each address refers to one byte, which means you have 232 bytes of memory

address 0x0000000


address Oxfffffff

C Memory Layout

Computer Science 161 Nicholas Weaver

Often drawn vertically for ease of viewing

But memory is still just a long array of bytes





C Memory Layout

address 0x00000000

Computer Science 161 Nicholas Weaver Often drawn vertically for ease of viewing address 0xFFFFFFF address 0xFFFFFFF But memory is still just a long array of bytes Higher addresses Higher addresses Each process has its own address space (virtual memory) Isolation: Two processes can read and write the I ower addresses Lower addresses same address but access different pieces of address 0x00000000 address 0x00000000 physical memory Least privilege: Virtual memory also enables the OS to control what memory a process can "see"

address 0x7FFFFFFF

x86 Memory Layout

Computer Science 161 Nicholas Weaver

Code

The program code itself (also called "text")

Data


Static variables, allocated when the program is started

Heap

- Dynamically allocated memory using malloc and free
- As more and more memory is allocated, it grows upwards

Stack:


- Local variables and stack frames
- As you make deeper and deeper function calls, it grows downwards



Registers

Computer Science 161 Nicholas Weaver

- Recall registers from CS 61C
 - Examples of RISC-V registers: a0, t0, ra, sp
- Registers are located on the CPU
 - This is different from the memory layout
 - Memory: addresses are 32-bit numbers
 - Registers: addresses are names (ebp, esp, eip)



Computer Science 161 Nicholas Weaver

x86 Architecture

Why x86?

Computer Science 161 Nicholas Weave

- It's the most commonly used instruction set architecture in consumer computers!
 - You are probably using an x86 computer right now... unless you're on a phone, tablet, or M1
 Mac
- You only need enough to be able to read it and know what is going on
 - We will make comparisons to RISC-V, but it's okay if you haven't taken 61C and don't know RISC-V; you don't need to understand the comparisons to understand x86
- However, if you have a choice, choose ARM
 - Significantly higher performance for the same cost
 - 64b ARM has some unique security features we will discuss later

What is x86?

Computer Science 161 Nicholas Weave

- Complex instruction set computer (CISC) architecture
 - The opposite of reduced instruction set computer (RISC) architecture
 - There are a lot of instructions... The full ISA manual is over 5,000 pages long!
 - We will not be teaching the full instruction set (obviously), just enough of the calling convention to be able to do Project 1
- Launched in 1978 with the Intel 8086 processor and eventually took over much of computing
 - Over 40 years ago! The ISA is very bloated because of this...
- 64-bit variant x86-64 launched in 1999 (but we won't study it)




x86 Fact Sheet

Computer Science 161 Nicholas Weaver

Little-endian

- The least-significant byte of multi-byte numbers is placed at the first/lowest memory address
- Same as RISC-V

storing the word 0x44332211 in memory:



#include <stdint.h>
uint8_t (1 byte)
uint32_t (4 bytes)

```
int main(void) {
    uint32_t num = 0xdeadbeef;

    // This prints "deadbeef".
    printf("%x", num);

    // This prints "ef be ad de".
    uint8_t *bytes = (uint8_t *) #
    for (size_t i = 0; i < 4; i++) {
        printf("%x ", bytes[i]);
    }
}</pre>
```

```
0xef 0xbe 0xad 0xde
```

x86 Registers

Computer Science 161 Nicholas Weaver

Storage units as part of the CPU architecture (not part of memory)

- Only 8 main general-purpose registers:
 - EAX, EBX, ECX, EDX, ESI, EDI: General-purpose
 - ESP: Stack pointer (similar to sp in RISC-V)
 - EBP: Base pointer (similar to fp in RISC-V)
 - We will discuss ESP and EBP in more detail later
- Instruction pointer register: EIP
 - Similar to PC in RISC-V

The main x86 registers...

Computer Science 161 Nicholas Weave

- General purpose: EAX-EDX (E stands for Extended)
 - What you use for computing and other stuff, sorta...
- Indexes & Pointers
 - EBP: "Frame pointer": points to the top/start of the current call frame on the stack ESP: "Stack pointer": points to the current stack
 - (Remember, stack grows down!)
 - PUSH and POP
 - Decrement the stack pointer and store something there
 - Load something and increment the stack pointer
 - Most operations are done with data on the stack…

https://www.cs.rutgers.edu/~pxk/419/notes/frames.html

The main x86 registers...


General purpose: EAX-EDX

What you use for computing and other stuff

Indexes & Pointers


Computer Science 161

- EBP: "Frame pointer": points to the top/sta
 ESP: "Stack pointer": points to the current
- (Remember, stack grows down!)
 - PUSH and POP
 - Decrement the stack pointer and store something the
 - Load something and increment the stack pointer
 - Most operations are done with data on the stac



Linux (32-bit) process memory layout

Computer Science 161



30

x86 Syntax


Computer Science 161
Nicholas Weave

- Register references are preceded with a percent sign %
 - Example: %eax, %esp, %edi
- Immediates are preceded with a dollar sign \$
 - Example: \$1, \$161, \$0x4
- Memory references use parentheses and can have immediate offsets
 - Example: 8 (%esp) dereferences memory 8 bytes above the address contained in ESP

x86 Assembly

Computer Science 161 Nicholas Weave


Instructions are composed of an opcode and zero or more operands.



- Pseudocode: EBX = EBX + 0x8
- The destination comes last
 - Contrast with RISC-V assembly, where the destination (RD) is first
- The add instruction only has two operands; and the destination is an input
 - Contrast with RISC-V, where the two source operands are separate (RS1 and RS2)
- This instruction uses a register and an immediate

x86 Assembly

Computer Science 161 Nicholas Weave



- Pseudocode: EAX = EAX ^ *(ESI + 4)
- This is a memory reference, where the value at 4 bytes above the address in ESI is dereferenced, XOR'd with EAX, and stored back into EAX
 - Most instructions can be register-register, register-immediate, register-memory, or memory-immediate (but not memory-memory)
 - How can you achieve a memory-memory operation?

Computer Science 161

Stack Layout

Stack Frames

Computer Science 161 Nicholas Weave


- When your code calls a function, space is made on the stack for local variables
 - This space is known as the stack frame for the function
 - The stack frame goes away once the function returns
- The stack starts at higher addresses. Every time your code calls a function, the stack makes extra space by growing down
 - Note: Data on the stack, such as a string, is still stored from lowest address to highest address. "Growing down" only happens when extra memory needs to be allocated.

Stack Frames

Computer Science 161 Nicholas Weaver

 To keep track of the current stack frame, we store two pointers in registers


- The EBP (base pointer) register points to the top of the current stack frame
 - Equivalent to RISC-V fp
- The ESP (stack pointer) register points to the bottom of the current stack frame
 - Equivalent to RISC-V sp (but x86 moves the stack pointer up and down a lot more than RISC-V does)




Pushing and Popping

Computer Science 161 Nicholas Weaver

- The push instruction adds an element to the stack
 - Decrement ESP to allocate more memory on the stack
 - Save the new value on the lowest value of the stack







Pushing and Popping

Computer Science 161 Nicholas Weaver

- The pop instruction removes an element from the stack
 - Load the value from the lowest value on the stack and store it in a register
 - Increment ESP to deallocate the memory on the stack





Why push and pop?



Computer Science 161 Nicholas Weaver

- This allows x86 to use "stack-machine"-style logic
 - Operations always operate on the top items on the stack and push the result back onto the stack
 - Example: a + b * c + d
 - PUSH a // a
 - PUSH b // a, b
 - PUSH c // a, b, c
 - MUL // a, (b*c)
 - ADD // (a+(b*c))
 - PUSH // (a+(b*c)), d
 - ADD // (a+(b*c))+d
 - Result is the last remaining item on the stack!
- First convert the expression to postfix notation, than apply stack operations. https://www.geeksforgeeks.org/arith metic-expression-evalution/
- Used to think this allowed for smaller code and simpler code generation
 - Reality? Not so much. RISC logic is equally efficient in code size in practice, especially with the compressed instructions for RISC-V.
 - But this misconception is why the Java VM is a stack machine too...
- (Not really a) Takeaway: Take 164 if you want to learn more about this


x86 Stack Layout

Computer Science 161 Nicholas Weave

- Local variables are always allocated on the stack
 - Contrast with RISC-V, which has plenty of registers that can be used for variables
- Individual variables within a stack frame are stored with the first variable at the highest address
- Members of a struct are stored with the first member at the *lowest* address.
- Global variables (not on the stack) are stored with the first variable at the lowest address

Stack Layout

Computer Science 161 struct foo { long long f1; // 8 bytes int f2; // 4 bytes // 4 bytes int f3; void func(void) { int a; // 4 bytes struct foo b; int c; // 4 bytes



this stack diagram? Options:

b.f1 b.f2 b.f3

34

Nicholas Weaver