

Get LCAI — swap Ethereum for native LCAI

Live app: orcavault.win/get-lcai/

A public, **non-custodial** page: you connect a wallet that holds **ETH on Ethereum**, pick an amount, get a live Uniswap **V3** quote, then swap **ETH** → **LCAI ERC-20** and bridge to **native LCAI on Lightchain (domain 9200)** via the **official** Hyperlane warp. Native LCAI is delivered to **your own Lightchain wallet** (same address). No backend, no relay unlock, no API keys.

This is **not** OrcaVault “Pay with Ethereum” (that sends native LCAI to the **app relay** to unlock uploads). This page is **buy-and-hold** for you.

This is **not** the self-hosted Base USDC warp. See [Hyperlane USDC warp](#).

What you do in the app

1. Open <https://orcavault.win/get-lcai/>
2. Connect MetaMask / Trust (must be able to use **Ethereum mainnet**).
3. Enter ETH (or tap a preset). The quote is live from Uniswap V3.
4. Approve swap, approve LCAI spend if asked, approve the bridge.
5. Wait: native LCAI is **not instant**. The official Lightchain Hyperlane relayer delivers after the Ethereum txs confirm. Switch the wallet to **Lightchain AI (9200)** to see the balance.

You sign every step. The page never holds funds.

Seeing your balance

Native LCAI lands on **Lightchain**, not Ethereum, so it won't appear in your wallet's default (Ethereum) view. To see it:

1. Add the Lightchain network to your wallet (Add Custom Network): - **Network name:** Lightchain AI - **RPC URL:** <https://rpc.mainnet.lightchain.ai> - **Chain ID:** 9200 - **Currency symbol:** LCAI - **Block explorer:** <https://lightscan.app>
2. Switch the wallet to **Lightchain AI**. LCAI is the native coin, so it shows as your main balance — in some wallets you may also need to toggle LCAI on under **Manage crypto**.
3. Delivery isn't instant: the official Hyperlane relayer mints native LCAI a few minutes after your bridge tx confirms.

Source of truth: some wallet indexers (e.g. Trust Wallet) lag or don't fully cover smaller networks, so the balance may read 0 even after it arrives. Search your address at lightscan.app — if it shows there, the LCAI is in your wallet regardless of what the wallet UI displays.

Also on getcai: ETH · Base → synthetic ETH (2026-09-27)

The "**ETH · Base**" option is a different rail from the ETH → LCAI swap above. It does **not** swap into LCAI — it moves your **native ETH on Base** across to **synthetic ETH on Lightchain**, delivered to the **same address**. Synthetic ETH is a payment token the Orca apps accept alongside LCAI/USDC; it carries real ETH value bridged from Base. There are **no pools and no fees** — you pay only the bridged amount plus interchain gas.

What you do:

1. In getcai, pick "**ETH · Base**" as what you Have. Connect a wallet holding **ETH on Base** (chain 8453). If two wallet extensions are installed, disable the one you're not using — a second extension can hijack the connect request.
2. Enter an amount and send. One transaction locks your ETH on Base.
3. Switch your wallet to **Lightchain AI (9200)**. Synthetic ETH mints to your address a few minutes after the Base tx confirms (once the relayer delivers). Confirm at lightscan.app if your wallet UI lags.

This is a self-hosted warp — delivery depends on the operator's validator + relayer being online, so mints are not instant. It is separate from Circle, from the official LCAI warp, and from the USDC warp — **rails never mix**. Builders who want to reproduce this route: see the [Hyperlane ETH warp guide](#).

Role	Address
Base native collateral (HypNative)	0x330a28CD6e7b71a040eeA0cEe6fa81540D1D32e9
Lightchain synthetic ETH (HypERC20)	0x620d3e60461651042812BDbCbB3733dE13967BD3
Base domain	8453
Lightchain domain	9200

Why V3

LCAI's Ethereum liquidity is a Uniswap **V3** LCAI/WETH pool (**0.3%**). There is **no V2 pool**. V2 quotes revert.

Public contracts (Ethereum unless noted)

Same official stack as the Pay-with-Ethereum rail; only the **recipient** differs (you vs an app relay).

Role	Address
LCAI ERC-20	0x9cA8530CA349c966Fe9ef903Df17a75B8A778927
WETH9	0xC02aaA39b223FE8D0A0e5C4F27eAD9083C756Cc2
Uniswap V3 SwapRouter	0xE592427A0AEce92De3Edee1F18E0157C05861564
Uniswap V3 Quoter	0xb27308f9F90D607463bb33eA1BeBb41C27CE5AB6

Role	Address
LCAI/WETH V3 pool (0.3%)	0xd047a370611437a1b8e6c2a95ea36f69fdda3be
Warp (Ethereum collateral)	0x01f80bb8e78e79881E8Ec7832fB6C2c59f64e353
Warp (Lightchain native mint)	0xEc7096A3116EE769457C939617375Ec1785AA6f1
Lightchain domain	9200

Safety

- Official warp only. Do not send LCAI ERC-20 to a random router.
- Keep enough ETH for swap + Uniswap fee + `quoteGasPayment` on the bridge.
- Not a CEX, not instant, not Circle. Slippage applies.
- Source: `get-lcai/` in the OrcaVault repo (relative `./eth-pay.js`, no DNS change).

Related: [Pay with Ethereum \(app unlock\)](#) · [bridge.lightchain.ai](#)