PRD: Transaction Routing Management

BANK A	Product Requirement Document

Product Name	Transaction Routing Console
Epic Link	EPIC-001: Routing enhancement
Project No	PROJECT-001
Document Status	IN PROGRESS
Product Manager	
Lead Product Manager	
Tech lead	
Engineering Manager	

Document Approval

Created by

Name	Title	Project Role	Signature
	Intern Product Manager	Intern Product Manager	

Reviewed by

Name	Title	Project Role	Signature
	Tech Lead	Tech Lead	

	Lead Product Manager	Product Manager	

Approved by

Name	Title	Project Role	Signature
	Principal Product Manager 3.1	Principal Product Manager 3.1	
	Engineering Manager	Engineering Manager	

Background

In Routing Console settings (bank code) right now only display one switching per one bank, business team want to be able to see and change the switching per bank per transaction

The current Routing Console supports only single-switching per bank code, forcing all transaction types (MPM, CPM, Transfer, etc.) to use the same provider. This lack of granularity limits operational control, increases the impact of switching-specific outages, and hinders the integration of CBT phase 2 & 3 (Cross Border & Tap), which requires specialized routing based on transaction protocols

Objective

- Enable independent switching configuration for each transaction type per bank
- Implement an automated logic that redirects traffic to a default route if a specific feature route is disabled
- Prepare the system to handle Cross Border and CBT-specific transactions efficiently

Relevant Documents

RFE Link	REFERENCE REMOVED

Requirements

1. QRIS MPM as Issuer (Domestic & Cross Border)

Scenario	Acceptance Criteria	Jira Link
QRIS MPM Domestic Payment as Issuer	**GIVEN** Mobile App sending Payment Request to SYS **WHEN** SYS check the Bank Code **THEN** the system must fulfill the following : • Check status of `DEFAULT_SWITCHING` for that Bank : ◦ **IF INACTIVE**, then immediately reject the transaction. When **routing is not found**, **send response code** `92` (**Invalid Routing**). ◦ **IF ACTIVE**, then proceed to specific route validation ▪ Check the Switching of QRIS MPM : • **IF ACTIVE**, then send the transaction to the designated switching and use messaging according to its technical specifications. • **IF ACTIVE but the Switching is** `null`, then use and send the transaction to `DEFAULT_SWITCHING` of that Bank (following the default switching's technical specifications). • **IF INACTIVE**, then use and send the transaction to `DEFAULT_SWITCHING` of that Bank (following the default switching's technical specifications).	
QRIS MPM Cross Border Inquiry	**GIVEN** Mobile App sending Inquiry Cross Border Request to SYS **WHEN** SYS identifies the Country Code **THEN** the system must fulfill the following : • Check status of `DEFAULT_SWITCHING` for the Country : ◦ **IF INACTIVE**, then immediately reject the transaction. When **routing is not found**, **send response code** `92` (**Invalid Routing**).	

	◦ **IF ACTIVE**, then proceed to the next validation ▪ Check the Switching of QRIS MPM Cross Border : • **IF ACTIVE**, then s**e**nd the transaction to the designated switching and use messaging according to its technical specifications. • **IF ACTIVE but the Switching is** `null`, then use and send the transaction to `DEFAULT_SWITCHING` of that Bank (following the default switching's technical specifications). • **IF INACTIVE**, then use and send the transaction to `DEFAULT_SWITCHING` of that Country (following the default switching's technical specifications).	
MPM Cross Border Payment	**GIVEN** Mobile App sending Payment Cross Border Request to SYS **WHEN** SYS receives the payment request **THEN** the system must fulfill the following : • Check status of `DEFAULT_SWITCHING` for that Bank : ◦ **IF INACTIVE**, then immediately reject the transaction. When **routing is not found**, **send response code** `92` (**Invalid Routing**). ◦ **IF ACTIVE**, then proceed to specific route validation ▪ Check the Switching of QRIS MPM Cross Border : • **IF ACTIVE**, then send the transaction to the designated switching and use messaging according to its technical specifications. • **IF ACTIVE but the Switching is** `null`, then use and send the transaction to `DEFAULT_SWITCHING` of that Bank (following the default switching's technical specifications).	

	• **IF INACTIVE**, then use and send the transaction to `DEFAULT_SWITCHING` of that Bank (following the default switching's technical specifications).	

2. QRIS CPM as Acquirer

Scenario	Acceptance Criteria	Jira Link
CPM Routing	**GIVEN** SYS receives a CPM Payment Request as Acquirer from Merchant App or EDC **WHEN** SYS identifies the Issuer's Bank Code **THEN** the system must fulfill the following : • Check the `DEFAULT_SWITCHING` status for that Bank : ◦ **IF INACTIVE**, then immediately reject the transaction and send response code to the Switching ◦ **IF ACTIVE**, then : ▪ Check the Switching of CPM : • **IF INACTIVE**, then reject the transaction and send response code to the Switching • **IF ACTIVE but the Switching is** `null`, then use and send the transaction to `DEFAULT_SWITCHING` of that Bank (following the default switching's technical specifications). • **IF ACTIVE**, then send the transaction to the designated switching and use messaging according to its technical specifications.	

3. QRIS TUNTAS (Transfer, Setor, Tarik) as Issuer

Scenario	Acceptance Criteria	Jira Link
Tuntas Transfer	**GIVEN** Mobile App user initiates QRIS Transfer to Other bank **WHEN** SYS idenifies the Destination Bank Code	

	THEN the system must fulfill the following : • Check status of `DEFAULT_SWITCHING` : ◦ **IF INACTIVE**, then immediately reject the transaction. When **routing is not found**, **send response code** `92` (**Invalid Routing**). ◦ **IF ACTIVE**, then proceed next validation ▪ Check status of Tuntas Transfer for the Bank switching : • **IF INACTIVE**, then use the `DEFAULT_SWITCHING` of the Bank (following the default switching's technical specifications). • **IF ACTIVE but the Switching is** `null`, then use and send the transaction to `DEFAULT_SWITCHING` of that Bank (following the default switching's technical specifications). • **IF ACTIVE**, then s**e**nd the transaction to the designated switching and use messaging according to its technical specifications.	
Tuntas Setor	**GIVEN** Other Bank Customer initiates QRIS Setor to Bank A Merchant Merchant App / EDC) **WHEN** SYS identifies the Issuer Bank Code **THEN** the system must fulfill the following : • Check status of `DEFAULT_SWITCHING` : ◦ **IF INACTIVE**, then immediately reject the transaction. When **routing is not found**, **send response code** `92` (**Invalid Routing**). ◦ **IF ACTIVE**, then proceed next validation ▪ Check status of Tuntas Setor of the Bank switching : • **IF INACTIVE**, then use the `DEFAULT_SWITCHING` of the Bank (following the default switching's technical specifications).	

	• **IF ACTIVE but the Switching is** `null`, then use and send the transaction to `DEFAULT_SWITCHING` of that Bank (following the default switching's technical specifications). • **IF ACTIVE**, then s**e**nd the transaction to the designated switching and use messaging according to its technical specifications.	
Tuntas Tarik	**GIVEN** Mobile App user initiates QRIS Tarik Tunai to Other Bank Merchant **WHEN** SYS identifies the Acquirer Bank Code **THEN** the system must fulfill the following : • Check status of `DEFAULT_SWITCHING` : ◦ **IF INACTIVE**, then immediately reject the transaction. When **routing is not found**, **send response code** `92` (**Invalid Routing**). ◦ **IF ACTIVE**, then proceed next validation ▪ Check status of Tuntas Tarik of the Bank switching : • **IF INACTIVE**, then use the `DEFAULT_SWITCHING` of the Bank (following the default switching's technical specifications). • **IF ACTIVE but the Switching is** `null`, then use and send the transaction to `DEFAULT_SWITCHING` of that Bank (following the default switching's technical specifications). • **IF ACTIVE**, then s**e**nd the transaction to the designated switching and use messaging according to its technical specifications.	

Yang bisa kita pilih switchingnya:

Jenis Transaksi	As Issuer / Acquirer	Switching Name

MPM Domestic	Issuer	SWITCH_A, SWITCH_B
MPM Cross Border	Issuer	SWITCH_A
CPM	Acquirer	SWITCH_A
TUNTAS Transfer	Issuer	SWITCH_A
TUNTAS Setor	Issuer	SWITCH_A
TUNTAS Tarik	Issuer	SWITCH_A

MPM Domestic CB SWITCH_A

Rollout Plan

SIT	
Performance Test / Load Test (*If needed)	
UAT	
SAT	
LIVE	