

Tutorials Questions Learning Paths For Businesses Product Docs

CONTENTS

Prerequisites

Step 1 — Installing Samba

Step 2 — Setting Samba's Global Options

Step 3 — Creating Users

Step 4 — Configuring the Samba Shares

Str - Logging Into the Samba Server



// TUTORIAL //

How To Set Up a Samba Share For A Small Organization on Ubuntu 16.04

Published on May 11, 2018

System Tools Ubuntu 16.04



Elliot Cooper and Kathleen Juell



The author selected the Tech Education Fund to receive a donation as part of the Write for DOnations program.

Introduction

Samba is an open-source implementation of the SMB/CIFS networking protocol used in Windows environments for shared services such as file and printer access and Active Directory. Samba can also be used to create cross-platform file shares in a configuration called a *standalone server*.

In this guide, you will install and configure a standalone Samba server to provide networked file stores or *shares* for a hypothetical small organization called **Exam**. This organization has several requirements for their file shares: 1. Every employee needs a personal, private file share; 2. All employees should have read and

write access to a common file share; 3. An administrative user should have read and write access to all personal shares and ownership of the common share.

Your Samba server will meet all of these requirements. You will also learn how to access the shares from Windows, Linux, and macOS.

Prerequisites

Before you begin this guide you'll need the following:

- An Ubuntu 16.04 server with a non-root sudo user. Please refer to the Ubuntu 16.04 initial server setup guide for more information. Samba has modest RAM and CPU requirements and will function well on a 1GB server. You are more likely to run out of storage space, so this should be your primary consideration when choosing your server size.
- Incoming TCP connections allowed on port 445. If you are using the UFW firewall,
 please refer to How To Set Up a Firewall with UFW on an Ubuntu and Debian Cloud
 Server for guidance. If you are using a different or external firewall, please refer to
 the relevant documentation.

Step 1 - Installing Samba

Let's start by installing Samba using Ubuntu's package management system.

Before installing new packages, let's update the local package index to include the most up-to-date versions from the Ubuntu repositories:

```
$ sudo apt-get update
```

Next, install Samba:

\$ sudo apt-get install samba

This command will install and start both the Samba server smbd and the Samba NetBIOS served. nmbd is not required for this tutorial, so in the interests of security you can stop an sable it with systemctl:

Сору

```
$ sudo systemctl stop nmbd.service
$ sudo systemctl disable nmbd.service
```

The sudo systemctl disable nmbd.service command will produce the following output when run:

```
Output

nmbd.service is not a native service, redirecting to systemd-sysv-install

Executing /lib/systemd/systemd-sysv-install disable nmbd

insserv: warning: current start runlevel(s) (empty) of script `nmbd' overrides LSB de

insserv: warning: current stop runlevel(s) (0 1 2 3 4 5 6) of script `nmbd' overrides
```

This output communicates that because nmbd does not have native systemd management configuration, it is being disabled by the older SysV init system.

To avoid security issues that can arise from running an unconfigured, network-enabled service, let's stop the Samba server until configuration details are in place:

```
$ sudo systemctl stop smbd.service
```

Samba is now installed and ready to be configured.

Step 2 – Setting Samba's Global Options

Let's define how the Samba server will behave by modifying its configuration file, located at /etc/samba/smb.conf. This file has two parts: a [global] section and a [shares] section. The [global] section configures the behavior of the Samba server, and the [shares] sections configure the file shares. Let's begin by setting directives in the [global] section.

Rather than editing /etc/samba/smb.conf directly, rename it to smb.conf.original and create a new file with the name smb.conf:

Copy

\$ sudo mv /etc/samba/smb.conf /etc/samba/smb.conf.orig

Before editing /etc/samba/smb.conf, let's check the available interfaces in order to tell Samba which it should recognize. Type the following:

Сору

```
$ ip link
```

Output

- 1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN mode DEFAULT groulink/loopback 00:00:00:00:00:00 brd 00:00:00:00:00
- 2: eth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state UP mode DE link/ether 02:21:2c:03:ef:e2 brd ff:ff:ff:ff:ff

This output indicates that 10 is the loopback interface and eth0 is the external network interface, though your external interface may differ. Take note of both: you'll include them with the interfaces directive in the [global] section of the smb.conf file.

Let's begin editing this file with nano or your favorite editor:

Copy

```
$ sudo nano /etc/samba/smb.conf
```

The [global] section of this file will define the server's name, role, and other details, including network interfaces:

/etc/samba/smb.conf

```
[global]
    server string = samba_server
    server role = standalone server
    interfaces = lo your_network_interface
    bind interfaces only = yes
    disable netbios = yes
    smb ports = 445
    log file = /var/log/samba/smb.log
    max log size = 10000
```

These directives specify the following:

- server string This is the identifying information that will be supplied to users during connections. You can use samba_server or another name that will identify your server. Throughout this tutorial, you will see the string samba.example.com to denote the Samba share for the organization **Example.com**.
- server role This defines what type of Samba server will be created. In this case it is a standalone server, i.e. a file share. Other server types include domain member servers and domain controllers.
- interfaces These are the network interfaces that Samba will bind to. 10 is the loopback interface (127.0.0.1) and is required. You will also need to include the external network interface you outputted earlier. This is usually eth0.
- bind interfaces only This ensures that Samba only binds to the interfaces listed on the interfaces line. As a security measure, this causes Samba to ignore packets that do not correspond to the specified interfaces.
- disable netbios This disables all NetBIOS functions that are not needed in a standalone server. Doing this simplifies the server name resolution process and the transport of SMB traffic.
- smb ports This sets the port that Samba will listen on. Port 445 is the standard port for Samba.
- log file This sets the name and location of Samba's log file.
- max log size This sets a size limit on the log file. The number listed is in bytes and equals 10MB. Some things to keep in mind when setting this size limit: When it is reached, Samba will generate a new log file and move the old contents to a duplicate with an .old extension. If the limit is exceeded again, the existing .old file will be destroyed. This prevents disk/partition space from being overwhelmed with the contents of a single log file. You should therefore define a file size that makes sense for your system resources.

If you want more detailed logging while you are setting up the server, append the following line to the [global] section:

/etc/samba/smb.conf

log level = 3 passdb:5 auth:5

This sets the log level to 3 (info), increasing the granularity of log information from the default setting of 1. The higher setting of 5 for the passdb and auth debug classes provides more information related to user authentication.

Save and close the file when you have finished creating this section.

Whenever you edit smb.conf, you should run the Samba utility testparm to check that ther so syntax errors:

```
$ testparm
```

Running the testparm command on the smb.conf file produces the following output:

```
Output
Load smb config files from /etc/samba/smb.conf
Loaded services file OK.
Server role: ROLE_STANDALONE

Press enter to see a dump of your service definitions
```

Pressing ENTER produces the following output:

```
Output

# Global parameters
[global]

server string = samba_server
interfaces = lo your_network_interface
bind interfaces only = Yes
server role = standalone server
log file = /var/log/samba/smb.log
max log size = 10000
smb ports = 445
disable netbios = Yes
idmap config * : backend = tdb
```

If testparm reports Loaded services file OK., then there are no syntax errors that would stop the Samba server from starting.

Configuring the [global] section is all that's required to start the Samba server. However, its functionality will be limited without share configurations. A share is comprised of two parts, a user and a directory, both of which must be created and configured to allow logins and testing. The next section will explain how to create users that can access the shares.

Step 3 - Creating Users

In this step, we will create users that can access the shares. They will need access as Samba and system users in order to authenticate with the Samba server when they log in artificial and write to the file system.

In the hypothetical company **Example.com** there are four employees who need to be added to the Samba server and created as users on the Linux system: **david**, **mike**, **jane**, and **lucy**. In addition to these four, there will be an **admin** user who will be able to access and administer the personal shares. This user will also own the common shares that everyone can access.

The first step to adding system users is creating home directories for each of them. Rather than using the standard home directories at /home/user, the Samba directories and data will be located at /samba/. Keeping Samba data in a single location and separated from other user data will make future management tasks such as backups easier.

Note: The users created in this guide are not intended to have SSH logins. If your users already have accounts on the server, you should create a dedicated Samba user for them in order to follow this guide.

The next section will explain the process to add the first user, **david**, but you will need to repeat this process for **mike**, **jane**, and **lucy**.

The first step is to create the directory where the Samba data will be stored, at the root of the file system. This directory will be called /samba/, and its group ownership will be set to sambashare, a group that was created when you installed Samba.

Execute the following commands to create the /samba/ directory and set the group ownership to sambashare:

```
Сору
```

```
$ sudo mkdir /samba/
$ sudo chown :sambashare /samba/
```

Next, create david's home directory under the /samba/ directory:

```
Copy
```

```
$ sudo mkdir /samba/david
```

Now, add david as a system user with the following command:



```
$ sudo adduser --home /samba/david --no-create-home --shell /usr/sbin/nologin --ingr
```

The options do the following:

- --home This sets the location of the user's home directory.
- --no-create-home This stops the adduser command from creating david's home directory. If the system were to create this directory, it would be populated with configuration files such as .bash_history that are not necessary for the current setup.
- --shell This sets which shell **david** will be allocated when he logs in by SSH. An SSH login is not needed for access to a Samba share; setting this to /usr/sbin/nologin will disable SSH logins.
- --in-group sambashare This adds the user to the sambashare group, giving them read and write access to their own shares and to the common share.

You will be prompted for a password when you run this command. Choose a unique, non-dictionary based password of 10 characters or more.

Now that the system user **david** exists, you can set the ownership and permissions on his Samba home directory:

Сору

```
$ sudo chown david:sambashare /samba/david/
$ sudo chmod 2770 /samba/david/
```

Setting the permissions of the directory to 2770 means that new files or directories created under /samba/david/ will inherit the group ownership of the parent directory rather than the primary group of the user that created the file or directory. This means, for example, that if the **admin** user were to create a new directory in **david**'s share, **david** would be able to read and write to it.

Next, add **david** to the Samba server. Samba keeps its own database of users and passwords, which it uses to authenticate logins. In order to log in, all users must be added to the Samba server and enabled. Execute the following smbpasswd commands to accomplish both of these tasks:

```
$ sudo smbpasswd -e david
```

The options used here do the following:

- -a This adds the user to the Samba server without enabling them.
- -e This enables a previously-added user.

The password that you enter here will be used to access the Samba share, and can differ from the system password.

The user **david** now exists as a system user without the ability to SSH into the server. He has a home directory at /samba/david, and is registered and enabled as a Samba user.

Repeat this process for every Samba user (mike, jane, and lucy).

To create the **admin** user, run through the following commands, changing the home directory to /samba/everyone/:

Сору

```
$ sudo mkdir /samba/ everyone
$ sudo adduser --home /samba/ everyone --no-create-home --shell /usr/sbin/nologin -
$ sudo chown admin:sambashare /samba/ everyone /
$ sudo chmod 2770 /samba/ everyone /
$ sudo smbpasswd -a admin
$ sudo smbpasswd -e admin
```

In addition to creating the **admin** user, let's create a group called **admins** to make the management of the server easier. With read and write permissions to each share, this group can simplify the work of adding and deleting users. For example, if individual users function as **admin** users and then leave the organization, they need to be individually removed from each share. New administrators also need to be manually added to every share. Creating an **admins** group and giving this group read-write access to the shares means adding and removing users requires only a single command.

Execute the following commands to create a new group called **admins** and add the user **admin** to this group:

```
$ sermod -G admins admin
```

Additional users can be added to the **admins** group by running the second command, sudo usermod -G admins admin, and substituting another user in place of admin.

The system configurations are now complete, with the organization **Example.com**'s users set as system and Samba users. Let's move on to configuring the Samba server so these users can access their share directories.

Step 4 - Configuring the Samba Shares

Each share will have its own section in the main Samba configuration file, /etc/samba/smb.conf, following the global parameters. These sections will define how each share will work.

Use the nano text editor again to open and edit this file:

Сору

```
$ sudo nano /etc/samba/smb.conf
```

The following configuration block will define each user's personal share:

/etc/samba/smb.conf

```
in the control of the control o
```

These options include:

- share_name This is the name of the share that you will use when logging in.
- path This is the absolute path to the share in the filesystem.
- browsable This sets whether or not other users are able to see the share. Enabling this option only allows other users of the Samba server to see the existence of the share. It does not confer any read or write permissions.
- read only This sets whether the valid users are able to write to the share.
- create mode This forces the permissions for any file written to the share.
- directory mode This forces the permissions for any directory created in the share.

• valid users - This is a list of the users who have access to the share. This setting can take usernames or system groups such as **admins**. Groups must be listed with an @ in front e.g. @admins.

Add the following share configuration block for **david**, defining his home directory, the permissions for this directory's group ownership, and the users that should have access to his share:

/etc/samba/smb.conf

```
[david]
    path = /samba/david
    browseable = no
    read only = no
    force create mode = 0660
    force directory mode = 2770
    valid users = david @admins
```

Note that the directory permissions set the group ownership to that of the parent directory.

Create a share block for **mike**, **jane**, and **lucy**. Change only the share [name], path, and valid users to reflect each of the user's names.

The [everyone] share will differ from the others in both [name], path, valid users, and browsable options, and will look like this:

/etc/samba/smb.conf

```
...
[everyone]
    path = /samba/everyone
    browseable = yes
    read only = no
    force create mode = 0660
    force directory mode = 2770
    valid users = @sambashare @admins
```

Giving the sambashare group read-write access to the share enables all of the users access to the share, since they were added to this group when they were created.

The mplete smb.conf file will look like this:

/etc/samba/smb.conf

```
[global]
        server string = samba_server
        server role = standalone server
        interfaces = lo your_network_interface
        bind interfaces only = yes
        disable netbios = yes
        smb ports = 445
        log file = /var/log/samba/smb.log
        max log size = 10000
[david]
        path = /samba/david
        browseable = no
        read only = no
        force create mode = 0660
        force directory mode = 2770
        valid users = david @admins
[mike]
        path = /samba/mike
        browseable = no
        read only = no
        force create mode = 0660
        force directory mode = 2770
        valid users = mike @admins
[jane]
        path = /samba/jane
        browseable = no
        read only = no
        force create mode = 0660
        force directory mode = 2770
        valid users = jane @admins
[lucy]
        path = /samba/lucy
        browseable = no
        read only = no
        force create mode = 0660
        force directory mode = 2770
        valid users = lucy @admins
[everyone]
        path = /samba/everyone
        browseable = yes
        read only = no
        force create mode = 0660
        force directory mode = 2770
        valid users = @sambashare @admins
```

Save and close the file when you have finished editing.

Test the configuration again:

Сору

```
$ testparm
```

This will produce output that looks like the following:

```
Output

Load smb config files from /etc/samba/smb.conf
rlimit_max: increasing rlimit_max (1024) to minimum Windows limit (16384)

Processing section "[david]"

Processing section "[jane]"

Processing section "[mike]"

Processing section "[lucy]"

Processing section "[everyone]"

Loaded services file OK.

Server role: ROLE_STANDALONE

Press enter to see a dump of your service definitions
```

With the configuration check complete, let's start the Samba server with systemct1:

Сору

```
$ sudo systemctl start smbd.service
```

The Samba server is now running and ready to accept logins. The next step is to log into the Samba server to test that it is working as expected. The following section will cover logging into the Samba server from Windows, Linux, and macOS.

Step 5 – Logging Into the Samba Server

In this section, we will cover how to access the Samba shares we created from Linux, Windows, and macOS.

Linux - The Command Line

You can use a tool called smbclient to access Samba from the command line. This pack not included by default on most Linux distributions, so you will need to install it with your local package manager.

On Debian and Ubuntu servers install smbclient with the following command:

Copy

```
$ sudo apt-get update
$ sudo apt-get install smbclient
```

On Fedora systems, use the following:

Сору

```
$ sudo dnf update
$ sudo samba-client
```

And on CentOS:

Сору

```
$ sudo yum update
$ sudo yum install samba-client
```

Note: On some Linux distributions smbclient will fail with the following error message:

```
Output

smbclient: Can't load /etc/samba/smb.conf - run testparm to debug it
```

If you see this error message, check to be sure that you have created the file at /etc/samba/smb.conf.

smbclient uses the following format to access Samba shares:

Сору

```
$ smbclient // your_samba_hostname_or_server_ip / share -U username
```

You content either your server's IP or the hostname you defined in /etc/samba/smb.conf to access the share. This example uses the hostname samba.example.com to access

david's share on the Samba server you created in the previous steps:

Сору

```
$ smbclient // samba.example.com / david -U david
```

If david wants access to the common share (everyone), change the command to:

Сору

```
$ smbclient // samba.example.com / everyone -U david
```

After running the smbclient command, you will be prompted for the Samba password and logged into a command line interface reminiscent of the FTP text interface:

```
smb: \>
```

This interface is most useful for testing usernames and passwords and read-write access. For example, you can create a directory and list its contents as follows:

Сору

```
smb: \> mkdir test
smb: \> ls
```

You should see the following output:

Remove the directory by typing:




Managing data in a share is often easier with a GUI tool. The next section will look at the built-in GUI tools for KDE.

Linux – KDE with Dolphin

Dolphin is the default file manager in KDE and has built-in functionality to access Samba shares.

After opening Dolphin, take the following steps:


- 1. Select **Network** from the **Places** list.
- 2. Click on Add Network Folder.



- 3. Select the Microsoft Windows network drive option.
- 4. Click Next
- 5. Enter the details for the Samba share:
 - Name This is a memorable name that will be displayed as a bookmark in Dolphin for the share.
 - **Server** This is the hostname or IP address of the Samba server. In this example it will be samba.example.com .
 - Folder This is the name of the share that was set in smb.conf.
- 6. Click Save & Connect.
- 7. Enter the username and password for the user you are going to access the Samba share with.
- 8. Click OK.

Dolphin will now connect and open the Samba share which will look like this:





You can now use the Samba share as if it were a local directory to copy, delete, and rename files and directories. The share will also appear as a permanent bookmark in the **Network** places.

MacOS - The Command Line

MacOS comes pre-installed with command line tools you can use to access a Samba share. Open the terminal with Launchpad by clicking on the **Terminal** icon.

This will open a command line terminal in your home directory. To mount the Samba share, you can create a new directory that will act as the mount point for the share. A mount point is the location where two file systems are joined: in this case, your local file system and the remote Samba file system.

Create a new directory called samba:

```
$ mkdir samba
```

Next, mount the Samba share under the new samba directory. This command has the form:

Copy

\$ ount_smbfs // username @ your_samba_hostname_or_server_ip / share ./ mount_p

Substituting the details from **Example.com** with user **david** looks like this:

Copy

```
$ sudo mount_smbfs // david @ samba.example.com / david ./ samba
```

The samba directory will now show the contents of the **david** share on the **Example.com** Samba server. Files and directories can be manipulated with the normal tools such as 1s, rm, and mkdir; however, the samba directory will be owned by root after the share has been mounted. You will therefore need to use sudo to access the samba directory and its contents.

To unmount the Samba share, run the umount command from the same directory where you ran the mkdir command:

Copy

```
$ umount samba
```

The next section will look at accessing a Samba share using the desktop GUI application in macOS.


MacOS - Desktop

MacOS is also able to access Samba shares using the Finder application.

Take the following steps:


- 1. Open **Finder** and click **Go** in the menubar.
- 2. Click on **Connect to Server** from the list of options.
- 3. Use a smb:// format URL that includes your username, your hostname or server IP, and the name of your share:
 - smb:// username @ your_samba_hostname_or_server_ip / share . In the example shown
 here, you will see the username david and the hostname samba.example.com .
- 4. Bookmark the Samba share by clicking on the button with a + symbol.
- 5. Click Connect





- 6. Select Registered User
- 7. Enter the username and password for the Samba share user.
- 8. Decide if you would like macOS to store the password.
- 9. Click Connect.

After you have successfully connected to the Samba share it will appear in Finder as shown here:



The next section will explore how to access Samba shares from Windows 10.

Win ws 10 - The Command Line

Mounting a Samba share from the Windows command line only requires a single command:

Сору

```
C:\> net use drive_letter \\ your_samba_hostname_or_server_ip \ share
```

Substitute the variables from user **david**'s share and set the drive letter to x::

Сору

```
C:\> net use X: \\ samba.example.com \ david
```

When this command is entered you will be prompted for **david**'s username and password. After entering these, you will receive an acknowledgment that the share was successfully mounted:

```
Output

Enter the user name for 'samba.example.com': david

Enter the password for samba.example.com:

The command completed successfully.
```

You will now be able to browse the Samba share in File Explorer and manipulate the files and directories as if they were local to your computer.


The next section will look at using Windows GUI tools to access a Samba share.

Windows 10 - Desktop

Windows 10 also has the native ability to connect to a Samba share. The following steps will connect you to your Samba share and keep it as a bookmark using Windows File Explorer. Begin these steps by opening File Explorer:

- 1. Right click on **This PC**.
- 2. Click on Add a network location and then Next on the page that follows.





- 3. Click on Choose a custom network location.
- 4. Click Next

ter the Windows style address of the Samba server and the share name. ws uses the following form of a Samba URL:


\\ your_samba_hostname_or_server_ip \ share \. In the example image the server

name is samba.example.com and the share name is david:

\\ samba.example.com \ david .

- 6. Click Next.
- 7. Enter the username and password for the user.
- 8. Decide whether or not you want Windows to remember the password.
- 9. Click OK.

File Explorer will now connect to the Samba share. Once the connection has successfully completed, a new location will be created under **This PC** in File Explorer:



You will now be able to use this folder to manage files and folders in the Samba share as if it were a local folder.

Conclusion

In this article, you have created cross-platform online file shares using the Samba server. You have also accessed these shares from Windows, Linux, and macOS.

Samba shares have become so common that many applications are able to access the data stored in them. These applications can extend the functionality and usefulness of your Samba shares. For example, the mobile version of the media player VLC can connect to and stream music and video from your Samba share. To access it, select **open MRL** and use the standard Samba URL:

smb:// username @ your_samba_hostname_or_server_ip / share . You can also use a Samba share as the destination for your backups with the cross-platform backup utility BackupPC.

In addition to acting as a simple file share, Samba can work with Windows Active Directory as either a domain controller or a member of a domain. The Samba Wiki User Documentation contains more information on how to do this.



Thanks for learning with the DigitalOcean Community. Check out our offerings for compute, storage, networking, and managed databases.

Learn more about our products →

About the authors



Elliot Cooper Author
Mr

I have been a Linux Systems Administrator and technical content creator for more than 20 years. I am passionate about using and promoting OSS.



Kathleen Juell Editor

Still looking for an answer?

Search for more help

Was this helpful?

Yes

No

X f in Y

Comments





This textbox defaults to using Markdown to format your answer.

You can type !ref in this text area to quickly search our full set of tutorials, documentation & marketplace offerings and insert the link!

Sign In or Sign Up to Comment



Sean Pierce • November 3, 2019

The ip link command spits out a verbose output, which the user is prompted to note for later use. However, it is unclear *what exactly* is to be used from this output. There is not a clear example of what we should be inputting in the smb.conf file for the Global - interfaces line. Please clarify! Thank you for your time!

Reply

michaelclemow • October 19, 2021

Mac OS clients may require browseable = yes to be able to see the smb share in finder. This was the one thing I had to change to see my share using Mac OS 10.14.6 (Mojave).

Reply

Mengz You • June 28, 2018

Good tutorial, but if I want a share directory access by anonymous (not need login), how to configure it?

Reply



This work is licensed under a Creative Commons Attribution-NonCommercial- ShareAlike 4.0 International License.



Try DigitalOcean for free

Click below to sign up and get \$200 of credit to try our products over 60 days!

Sign up

Popular Topics

Ubuntu

Linux Basics

JavaScript

Python

MySQL

Docker

Kubernetes


All tutorials →

Talk to an expert →

- Congratulations on unlocking the whale ambience easter egg! Click the whale button in the bottom left of your screen to toggle some ambient whale noises while you read.
- Thank you to the <u>Glacier Bay National Park & Preserve</u> and <u>Merrick079</u> for the sounds behind this easter egg.
- Interested in whales, protecting them, and their connection to helping prevent climate change? We recommend checking out the Whale and Dolphin Conservation.

Reset easter egg to be discovered again / Permanently dismiss and hide easter egg






Get our biweekly newsletter

Sign up for Infrastructure as a Newsletter.

Sign up →






Hollie's Hub for Good

Working on improving health and education, reducing inequality, and spurring economic growth? We'd like to help.

Learn more →



Become a contributor

Get paid to write technical tutorials and select a tech-focused charity to receive a matching donation.

Learn more →

Featured Tutorials

Kubernetes Course Learn Python 3 Machine Learning in Python

Getting started with Go Intro to Kubernetes

DigitalOcean Products

App Platform Virtual Machines Managed Databases Managed Kubernetes

Block Storage Object Storage Marketplace VPC Load Balancers

Welcome to the developer cloud

DigitalOcean makes it simple to launch in the cloud and scale up as you grow — whether you're running one virtual machine or ten thousand.

Learn more

