Virtual Memory, Demand Paging


ECE469, March 22

Yiying Zhang

replacement policy not in midterm demanding in midterm

Reading

- Dinosaur: Chapter 8, 9
- Comet: Ch 21 22



Rough Format of midterm



14 True or False (28 pts)


5 multiple choices (10 pts)

3 short-answer questions (12 pts)

- 3 big problems (16+24+10 pts)
 - Each big problem split into few smaller problems
 - Write (debug) some code

[lec13] The big picture – connecting the dots










Simple multiprogramming



[lec15] Sharing main memory




- Simple multiprogramming 4 drawbacks
 - Lack of protection
 - Cannot relocate dynamically

Single segment per process

Dynamic Memory Relocation

Entire address space needs to fit in mem


[lec15] 3. Dynamic memory relocation



- Instead of changing the address of a program before it's loaded, change the address dynamically during every reference
 - Under dynamic relocation, each programgenerated address (called a logical address or virtual address) is translated in hardware to a physical or real address at runtime


[lec15] Translation overview





- Actual translation is in hardware (MMU)
- Controlled in software
- CPU view
 - what program sees, virtual memory
- Memory view
 - physical memory


[lec15] Sharing main memory



- Simple multiprogramming 4 drawbacks
 - Lack of protection
 - Cannot relocate dynamically
 - → Base-and-bound
 - Single segment per process
 - → Paging, segmentation, etc.
 - Entire address space needs to fit in mem

Dynamic Memory Relocation

[lec15] Sharing main memory



- Simple multiprogramming 4 drawbacks
 - Lack of protection
 - Cannot relocate dynamically
 - → dynamic memory relocation: base&bound
 - Single segment per process
 - → dynamic memory relocation: segmentation, paging
 - Entire address space needs to fit in mem
 - More need for swapping
 - Need to swap whole, very expensive!

The last drawback




- So far we've separated the <u>process's view of</u> <u>memory from the OS's view</u> using a mapping mechanism
 - Each sees a different organization
 - Allows OS to shuffle processes around
 - Simplifies memory sharing
 - What is the essence of the mechanism that enables this?
- But, a user process had to be completely loaded into memory before it could run
- → Wasteful since a process only needs a small amount of its total memory at any time (reference locality!)

Instances of extra level of indirection



- Dynamic memory relocation
 - Base and bound
 - Segmentation
 - 1-level paging
 - 2-level paging
 - Segmentation plus paging

[lec1] What is an OS?




Extended (abstract) machine (answer 2)

- Much more ideal environment than the hardware
 - Ease to use
 - Fair (well-behaved)
 - Portable (back-compatible)
 - Reliable
 - Safe?
- Illusion of infinite, private resources
 - Single processor → many separate processors
 - Single memory → many separate, larger memories



?

Virtual Memory



- Definition: Virtual memory permits a process to run with only some of its virtual address space loaded into physical memory
- Key idea: Virtual address space translated to either
 - Physical memory (small, fast) or
 - Disk (backing store), large but slow
- Deep thinking what made above possible?
- Objective:
 - To produce the illusion of memory as big as necessary

Virtual Memory



- "To produce the illusion of memory as big as necessary"
 - Without suffering a huge slowdown of execution
 - What makes this possible?
 - Principle of locality
 - Knuth's estimate of 90% of the time in 10% of the code
 - There is also significant locality in data references

Virtual Memory Implementation




- Virtual memory is typically implemented via demand paging
- demand paging:
 - Load memory pages (from storage) "on demand"
 - paging with swapping, e.g., physical pages are swapped in and out of memory

Demand Paging (paging with swapping)



 If not all of a program is loaded when running, what happens when referencing a byte not loaded yet?

- How to detect this?
 - In software?




Demand Paging (paging with swapping)




 If not all of a program is loaded when running, what happens when referencing a byte not loaded yet?

- Hardware/software cooperate to make things work
 - Extend PTEs with an extra bit "present"
 - Any page not in main memory right now has the "present" bit cleared in its PTE
 - If "present" isn't set, a reference to the page results in a trap by the paging hardware, called page fault
 - What needs to happen when page fault occurs?

x86 Page Table Entry





What is happening before and after malloc()?




- Before malloc()?
- After malloc()?
- Upon first access?


- How to capture the first write to a virtual page?
 - e.g. want to trap into page fault handler
 - Use valid bit
 - In handler, check if vpage is malloced.
 - If not, segmentation fault
 - Else allocate physical page

Page Fault Handling in Demand Paging





Page fault handling (cont)




- On a page fault
 - Find an unused phy. page or a used phy. page (how?)
 - If the phy. page is used
 - If it has been modified (how to know?), write it to disk
 - Invalidate its current PTE and TLB entry (how?)
 - Load the new page from disk
 - Update the faulting PTE and its TLB entry
 - Restart the faulting instruction
- Supporting data structure
 - For speed: A list of unused physical pages (more later)
 - Data structure to map a phy. page to its pid and virtual address
 - Sounds faimiliar?

Deep thinking: Virtual Address vs. Virtual Memory




- Virtual address
 - Supported with dynamic memory relocation
 - Segmentation
 - Paging
- Virtual memory
 - Dynamic memory relocation + swapping
 - Demand paging
 - Demand segmentation

Tasks of the VM subsystem



- Once the hardware has provided basic capabilities for VM, OS must make two kinds of decisions
 - Page selection: when to bring pages into memory
 - Page replacement: which page(s) should be thrown out, and when

Page selection (when)



- Prepaging
 - Allocate physical page and (if from swap) bring a page into memory before it is referenced
 - Hard to do without a "prophet", may unnecessarily bring pages
- Request paging
 - Let user say which pages are needed when
 - Users don't always know best
 - And aren't always impartial
- Demand paging
 - Start up process with no pages loaded
 - Load a page when a page fault occurs, i.e., wait till it MUST be in memory
 - Almost all paging systems are demand paging

break





Names Every Systems Student Should Know

Why Are We Doing This?

- Really, you should know these people!
- They did some great work!
- Their work (still) have influence now



How Are We Going to Do This?



- One to two per lecture
- Turing award winners related to systems
- Scientists who have made contributions comparable to a turing award
- People who are still active (and alive)
 - Mainly systems people, some other
 - Academia and industry
- Disclaimer: The list is definitely incomplete. I may miss some, doesn't mean they are not important!

Alan Turing






Edsger Dijkstra

- Algorithms/systems
- Father of algorithms
- the "THE" OS



Page replacement algorithms? (which)





The BIG picture: Running at Memory Capacity



- Expect to run with all phy. pages in use
- Every "page-in" requires an eviction
- Goal of page replacement
 - Maximize hit rate → kick out the page that's least useful
- Challenge: how do we determine utility?
 - Kick out pages that aren't likely to be used again

Page replacement is a difficult policy problem

What makes finding the least useful page hard?




- Don't know future!
- Past behavior is a good indication of future behavior! (e.g. LRU)
 - temporal locality → kick out pages that have been used recently
- Perfect (past) reference stream hard to get
 - Every memory access would need bookkeeping
 - Is this feasible (in software? In hardware?)
- Minimize overhead
 - If no memory pressure, ideally no bookkeeping
 - In other words, make the common case fast (page hit)
- → Going after imperfect information, available cheaply
 - What is minimum hardware support that need to added?

Definitions (or, jargons asked during interviews)



- Pressure the demand for some resource (often used when demand exceeds supply)
 ex: the system experienced memory pressure
- Eviction throwing something out
 ex: cache lines and memory pages got evicted
- Pollution bringing in useless pages/lines
 ex: this strategy causes high cache pollution





- Thrashing extremely high rate of paging, usually induced by other decisions
- Locality re-use it makes the world go rounds!
- Temporal Locality re-use in time
- Spatial Locality re-use of close by locations

Performance metric for page replacement policies



- Give a sequence of memory accesses, minimize the # of page faults
 - Similar to cache miss rate
 - What about hit latency and miss latency?


Optimal or MIN


- Algorithm (also called Belady's Algorithm)
 - Replace the page that won't be used for the longest time
- Pros
 - Minimal page faults (can you prove it?)
 - Used as an off-line algorithm for perf. analysis
- Cons
 - No on-line implementation
- What was the CPU scheduling algorithm of similar nature?

What can we do without extra hardware support?



First-In-First-Out (FIFO)






- Algorithm
 - Throw out the oldest page
- Pros
 - Low-overhead implementation
- Cons
 - No frequency/no recency -> may replace the heavily used pages

Predicting future based on past



- "Principle of locality"
 - Recency:
 - Page recently used are likely to be used again in the near future
 - Frequency:
 - Pages frequently used (recently) are likely to be used frequently again in the near future
- Is this temporal or spatial locality?
- Why not spatial locality?

How to record locality in the past?




Software solution?


Exploiting locality needs some hardware support




- Reference bit
 - A hardware bit that is set whenever the <u>page</u> is referenced (read or written)


x86 Page Table Entry











Algorithm

- Check the reference-bit of the oldest page (first in)
- If it is 0, then replace it
- If it is 1, clear the referent-bit, put it to the end of the list, and continue searching

Pros


- Fast
- Frequency → do not replace a heavily used page

Cons

The worst case may take a long time


Clock: a simple FIFO with 2nd chance






- FIFO clock algorithm
 - Hand points to the oldest page
 - On a page fault, follow the hand to inspect pages
- Second chance
 - If the reference bit is 1, set it to 0 and advance the hand
 - If the reference bit is 0, use it for replacement
- What is the difference between Clock and the previous one?
 - Mechanism vs. policy?


Clock: a simple FIFO with 2nd chance





- What happens if all reference bits are 1?
- What does it suggest if observing clock hand is sweeping very fast?
- What does it suggest if clock hand is sweeping very slow?

We've focused on miss rate. What about miss latency?



- Key observation: it is cheaper to pick a "clean" page over a "dirty" page
 - Clean page does not need to be swapped to disk

- Challenge:
 - How to get this info?


Refinement by adding extra hardware support




- Reference bit
 - A hardware bit that is set whenever the page is referenced (read or written)

- Modified bit (dirty bit)
 - A hardware bit that is set whenever the page is written into

x86 Page Table Entry





Enhanced FIFO with 2nd-Chance Algorithm (used in Macintosh VM)



- Same as the basic FIFO with 2nd chance, except that it considers both (reference bit, modified bit)
 - (0,0): neither recently used nor modified (good)
 - (0,1): not recently used but dirty (not as good)
 - (1,0): recently used but clean (not good)
 - (1,1): recently used and dirty (bad)
 - When giving second chance, only clear reference bit
- Pros
 - Avoid write back
- Cons
 - More complicated, worse case scans multiple rounds

Enhanced FIFO with 2nd-Chance Algorithm – implementation

- On page fault, follow hand to inspect pages:
 - Round 1:
 - If bits are (0,0), take it
 - if bits are (0,1), record 1st instance
 - Clear ref bit for (1,0) and (1,1), if (0,1) not found yet
 - At end of round 1, if (0,1) was found, take it
 - If round 1 does not succeed, try 1 more round