

Paging Example 1

 Process' pages are allocated to frames in the physical memory.






Paging example 2

- Example Calculating internal fragmentation
 - Page size = 2,048 bytes
 - Process size = 72,766 bytes
 - 35 pages + 1,086 bytes
 - Internal fragmentation of 2,048 1,086 = 962 bytes
- Worst case fragmentation = 1 frame − 1 byte
- On average fragmentation = 1 / 2 frame size
 - So small frame sizes desirable?
 - But each page table entry takes memory to track
- Page sizes growing over time
 - Solaris supports two page sizes 8 KB and 4 MB
- Process view and physical memory are now very different.
- By implementation, a process can only access its own memory space.

Paging example 3- allocation of free frames



Before allocation

After allocation

Implementation of Page Table

- Page Tables are:
 - Kept in main memory (kernel's memory)
 - Written by the OS kernel (software)
 - Read by the Memory Management Unit (hardware)
- Two registers are used inside the MMU hardware to identify the page table:
 - Page-table base register (PTBR) points to the page table
 - Page-table length register (PTLR) indicates size of the page table
- Issues in this scheme:
 - Every data/instruction access requires two memory accesses; one for the page table and one for the data / instruction
 - The dual-memory-access problem can be solved by the use of a special fastlookup hardware cache called associative memory or translation look-aside buffers (TLBs)

Associative Memory

Associative memory – parallel search

Page #	Frame #


- Address translation (p, d)
 - If p is in associative register, get frame # out
 - Otherwise get frame # from page table in memory

```
0000
          Other module
          [space for qVar]
1008
1036
          Entry
                     proc a
          mov R1, #7
1220
1224
          st R1, [1008]
1228
          push R1
1232
          call 2334
          End of proc a
1399
          Start of Other module
2334
          Entry
                     put record
2670
          (optional symbol table)
2999
          (last location in module)
```

Absolute module e.g. PE (.exe), ELF, COFF, etc.

Paging Hardware With TLB

- Note the difference in structure between the TLB and the page table stored in main memory.
 - In the page table stored in main memory, each entry only has the frame number. The page number is used as an offset into a page table entry.
 - In the TLB, each entry has a page number and a frame number. Why?



Implementation of Page Table – TLB's

- Many TLBs store address-space identifiers (ASIDs) in each TLB entry – uniquely identifies each process to provide addressspace protection for that process
 - Otherwise need to flush at every context switch
- TLBs are typically small (64 to 1,024 entries)
- On a TLB page miss, value is loaded into the TLB from the page table (in memory) for faster access next time
 - If TLB is full → replacement policies must be considered.
 - Some entries can be wired down for permanent fast access
 - The new value is loaded by the MMU hardware without OS intervention.
- Thus, TLBs are:
 - Located inside the MMU (Hardware)
 - Read and written by the MMU (Hardware)

Effective Access Time for a page in main memory

- Let δ be the associative memory (TLB) lookup time and ϵ be the main memory access time.
- Define the percentage of time a page number is found in the associative memory as the hit ratio, $\boldsymbol{\alpha}$
- Effective Access Time (EAT)

For $\epsilon \gg \delta$,

EAT =
$$(\delta + \epsilon)\alpha + (\delta + 2\epsilon)(1 - \alpha)$$


EAT $\approx \epsilon\alpha + 2\epsilon(1 - \alpha)$

- Consider α = 80% and ϵ = 100ns for memory access
 - EAT = $0.80 \times 100 + 0.20 \times 200 = 120$ ns
- Consider more realistic hit ratio -> α = 99%, ϵ =100ns for memory access
 - EAT = $0.99 \times 100 + 0.01 \times 200 = 101 \text{ns}$

Memory Protection


- Memory protection implemented by associating protection bit with each frame to indicate if read-only or read-write access is allowed
 - Can also add more bits to indicate page execute-only, and so on
- Valid-invalid bit attached to each entry in the page table:
 - "valid" indicates that the associated page is in the process' logical address space, and is thus a legal page
 - "invalid" indicates that the page is not in the process' logical address space
 - Or use page-table length register (PTLR)
- Any violations result in an exception, thus invoking the kernel's handler

Valid (v) or Invalid (i) Bit In A Page Table



Shared pages

- System libraries
 may be shared via
 mapping into virtual
 address space
- Shared memory
 may be
 implemented by
 mapping pages
 (read, write and/or
 execute) into virtual
 address space



Shared Pages – cont.


Shared code and data

- One copy of read-only reentrant code (text) can be shared among processes (i.e., text editors, compilers, window systems)
- Shared data is useful for inter-process communication if sharing of readwrite pages is allowed
- Applicable to whole programs (e.g. text editors) as well as shared libraries.
- Such shard pages are similar to multiple threads sharing the same process space

Private (not shared) code and data

- Each process keeps a separate copy of its code and data
- The pages for the private code and data can appear anywhere in the virtual address space

Shared Pages - example



Segmentation

 Segmentation is a memory-management scheme that supports virtual memory

 A program is a collection of segments. A segment is a logical unit which may be data or code (text), such as://li>


• function (e.g. the main() function), or group of functions.

An Object

A bunch of global variables


- common block
- Stack
- arrays


C compilers produce multiple default sections/segments
 (.txt, .data, .bss, .stack, .const, etc.), but the
 programmer may define more sections and map
 different parts of the program to those sections.



Memory View of Segmentation

- Segmentation builds on the concept of relocation:
 - A program's virtual address space is divided into multiple segments (of variable length).
 - Segments may be relocated (as opposed to entire programs) and placed anywhere in memory.
 - A memory management unit (MMU) is needed to map a virtual address to a physical address.





physical memory space

Segmentation Architecture


Virtual address consists of a two-tuple:

```
<segment-number, offset>,
```

- Segment table maps two-dimensional virtual addresses into physical addresses; each table entry has:
 - base contains the starting physical address where a segment resides in memory
 - limit specifies the length of the segment
- Segment-table base register (STBR) points to the segment table's location in main memory
- Segment-table length register (STLR) indicates number of segments used by a program;

```
segment number s is legal if s < STLR
```

Segmentation Hardware



Segmentation Architecture (Cont.)


- Protection bits associated with segments. Each entry in segment table associate:
 - Valid bit = $0 \Rightarrow$ illegal segment
 - read/write/execute privileges
- With the use of a segment table, a program does not need to be loaded as a contiguous space, i.e. segments may be far apart from each others on the physical memory and the hardware will be able to produce the correct address to access each segment.
- Segment allocation is a variable partition allocation problem, which may result in external fragmentation.
- Code sharing (e.g. shared libraries) may occur at the segment level.

Structure of the Page Table

- Memory structures for paging can get huge using straight-forward methods
 - Consider a 32-bit logical address space as on modern computers
 - Page size of 4 KB (2¹²)
 - Page table would have 1 million entries (2³² / 2¹²)
 - If each entry is 4 bytes -> 4 MB of physical address space / memory for page table alone
 - That amount of memory used to cost a lot
 - Don't want to allocate that contiguously in main memory
- Hierarchical Paging
- Hashed Page Tables
- Inverted Page Tables

9.1 Virtual memory


- What we already know from paging:
 - Virtual address space logical view of how process is stored in memory
 - Usually start at address 0,
 - **Contiguous** addresses until end of space
 - Meanwhile, physical memory is organized in page frames. MMU must map logical (aka virtual) addresses to physical addresses;
 - Physical address space allocated to a process may not necessarily start at 0
 - May <u>not necessarily be contiguous</u>.
- Virtual memory may also allow a process to have a virtual address space that is much larger than the available physical memory. This may be implemented via:
 - Demand segmentation
 - Demand paging (more common, next topic)



Virtual memory That is Larger Than
Physical Memory


Virtual-address Space

- Usually the virtual address space for the stack section is designed to start at program's max virtual address and grow "downwards" while the heap grows "upwards" – (virtual addresses)
 - Maximizes address space use
 - Unused address space between the two is a hole.
 - Additional physical memory is needed if the heap or stack grow to a given new page
- Note that in 32-bit Linux, the lower 1 GB of every process is reserved for the kernel (code, data, heap and stack).
 - Shared amongst processes
 - Protected from user mode access.




Shared libraries using virtual memory

- This enables sparse address spaces with holes left for growth, i.e. allows future loading of dynamically linked libraries, shared memory, etc.
 - System libraries are shared via mapping into virtual address space
 - Shared memory is implemented by mapping pages (read-write) into the virtual address space



9.2 Demand Paging

- Memory segmentation is a refinement of variable partition strategies:
 - Instead of allocating entire programs using variable partitions → allocate segments instead
- Memory paging is a refinement of fixed memory partition strategies;
 - Instead of allocating entire programs using fixed partitions → allocate pages instead
- The concept of **memory swapping** dictated that we load an entire process into memory as demonstrated by diagram on the right (do you recall the **swap scheduler**?).
- How do we combine swapping strategies with paging to achieve a virtual memory space that is much larger than the available physical memory?
 - Swap individual pages instead of whole programs, when needed → demand paging




Memory swapping

Demand Paging

- Demand paging brings a page into memory only when it is needed, and thus only a portion of a program may be initially loaded by the OS:
 - Less I/O needed, no unnecessary I/O
 - Faster response for initial loading of programs
 - Less memory needed for running a process.
 - Higher degree of multiprogramming
- Page is needed ⇒ reference to it
 - not-in-memory ⇒ bring to memory (from backing store)
 - invalid reference (i.e. outside the process' addr. Space) \Rightarrow abort
- The pager is the kernel component that is in charge of loading/storing a page from/to the backing store.

Valid-Invalid Bit – another usage

- With each page table entry a valid—invalid bit is associated
 (v ⇒ in-memory memory resident, i ⇒ not-in-memory)
- Initially valid—invalid bit is set to i on all entries
- Example of a page table snapshot:



During MMU address translation, if valid—invalid bit in page table entry is i
 ⇒ page fault

Example of a page table when some pages are not in main memory


G

Н

logical

memory

- In demand paging, this is not the same usage of the valid bit as in the previous lecture, where it was used to determine whether a page is legal or not.
- The usage here is to determine whether a page is loaded into main memory or not.
- Demand paging is what gives virtual memory its essence.




Page Fault

• If there is a reference to a page, and it happens to be the first reference then it will cause an exception and invoke the operating system:

On a page fault:

- a) Operating system locates the page on the page table to decide:
 - Invalid reference ⇒ abort
 - Just not in memory, then continue to step b
- b) Find free frame
- c) Load page into frame via scheduled disk operation
- d) Modify the page table to indicate page now in memory
 - Set the frame number
 - Set validation bit = v
- e) Restart the instruction that caused the page fault

NOTE: Contrary to what "fault" might suggest, page faults do not represent errors, unless the page is not in the process' address space, and only in such case that it may be a true fault, a segmentation fault, which is an error.




Aspects of Demand Paging

- Extreme case start process with no pages in memory
 - OS sets instruction pointer to first instruction of process (what's that called?), non-memory-resident → page fault
 - Same occurs for every other process' pages on first access
 - Pure demand paging
- Actually, a given instruction could access multiple pages

 multiple page faults
 - Consider fetch and decode of instruction which adds 2 numbers from memory and stores result back to memory
 - Would this instruction exist in a RISC or in a CISC processor architecture?
- Pain decreased because of locality of reference
- Hardware support needed for demand paging
 - Page table with valid / invalid bit (H/W traps the OS if page invalid)
 - Secondary memory (swap device with swap space, e.g. hard drive)
 - Instruction restart

Instruction Restart issues

- Consider a machine instruction that could access several different locations (e.g. a "move multiple" type instruction)
 - block move (auto increment/decrement location)



- Restart the whole operation?
 - What if source and destination overlap?

Performance of Demand Paging

Stages in Demand Paging (worse case)

- 1. Trap to the operating system
- 2. Save the user registers and process state (for context switching)
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal and determine the location of the page on the disk
- 5. Allocate a free frame
- 6. Issue a read from the disk to a free frame:
 - 1. Wait in a queue for this device until the read request is serviced
 - 2. Wait for the device seek and/or latency time
 - 3. Begin the transfer of the page to a free frame
- 7. While waiting, allocate the CPU to some other user (i.e. do context switching)
- 8. Receive an interrupt from the disk I/O subsystem (I/O completed)
- 9. Save the registers and process state for the other user
- 10. Determine that the interrupt was from the disk
- 11. Correct the page table and other tables to show page is now in memory
- 12. Wait for the CPU to be allocated to this process again (or invoke the scheduler to run the next process)
- 13. Restore the user registers, process state, and new page table, and then resume the interrupted instruction

Performance of Demand Paging (Cont.)

- Three major activities
 - Service the interrupt careful coding means just several hundred instructions needed
 - Read the page lots of time
 - Restart the process again just a small amount of time
- Page Fault Rate $0 \le p \le 1$
 - if p = 0 no page faults
 - if p = 1, every reference is a fault
- Effective Access Time (EAT)
 - Assume a process is in steady state, i.e. all frames allocated to the process are already filled with process' pages and thus loading a new page requires the removal of one of its already loaded pages from memory in order to free up a frame.

```
EAT = (1 - p) x memory access
+ p (page fault overhead
+ swap page out
+ swap page in )
```

Demand Paging Example

• Memory access time = 200 nanoseconds. Average page-fault service time (overhead + swap in + swap out) = 8 milliseconds

EAT =
$$(1 - p) \times 200 + p$$
 (8 milliseconds)
= $(1 - p) \times 200 + p \times 8,000,000$
= $200 + p \times 7,999,800$

• If one access out of 1,000 causes a page fault, then

EAT = 8.2 microseconds.

This is a slowdown by a factor of 41!!

- If we need to limit the performance degradation to < 10 percent
 - 220 > 200 + 7,999,800 x p 20 > 7,999,800 x p
 - p < .0000025 (i.e. 2.5 in a million)
 - < one page fault in every 400,000 memory accesses


Demand Paging Optimizations

- Use swap space: Swap space I/O is faster than file system I/O, even if on the same secondary storage device.
 - Because swap allocated in larger chunks, less management needed than file system → faster access
 - Hence, copy entire process image to swap space at process load time
 - Then page in and out of swap space
 - Used in older BSD Unix
- For unmodified or read-only pages, page-in from program binary on disk, but discard (when time to do so) rather than paging-out when freeing frame
 - Used in Solaris and current BSD versions
- But the following pages still need to be written to swap space:
 - Pages associated with a file that are modified in memory but not yet written back to the file system
 - Anonymous R/W memory pages (not associated with a file), e.g. stack and heap pages.

Give an example of a read-only page


9.3 Copy-on-Write

- Copy-on-Write (COW) allows both parent and child processes to initially share the same pages in memory (except for stack pages).
 - If either process modifies a shared page, only then is the page copied



Copy-on-Write - cont.

 COW allows more efficient process creation as only modified pages are copied



COW – After process 1 modifies page C

Copy-on-Write - cont.

- In general, free frames are allocated from a pool of zero-fill-on-demand pages
 - Pool should always have free frames for fast demand page execution.
 - Don't want to have to free a frame as well as other processing on page fault
 - Why zero-out a page before allocating it?
- vfork() variation on fork() system call has parent suspend till the child calls execve() or aborts. Note that the execve() takes some parameters, including the path of the file containing the new program to be loaded.
 - Designed to have child immediately call either execve() or exit()
 - If child does anything else, it may corrupt the parent's address space.
 - Very efficient It differs from fork() in that it shares the same exact address space as the parent including the stack:
 - It does not copy the page table (uses the parent's page table, i.e. PTBR points to parent's page table)
 - Does not set copy-on-write bits for all writable pages in both processes.
 - Does not flush the TLB
 - Still copies file descriptors from parent process.
- In today's systems, the standard fork() is very efficient, thanks to the COW hardware → no need to use vfork()

Frame allocation and page replacement algorithms

- Frame-allocation algorithms determine how many frames are allocated to each process (dynamically or statically)
- Fetch policies decide on which page to fetch next. In Demand paging, the
 next page to fetch is the one that caused a page fault. The other alternative is
 to use prefetch, which is not common due to difficulty in predicting the next
 page.
- Page placement algorithms determine where to place a fetched page in the available frames (if more than one frame is available).
- Page-replacement algorithm determine which page to evict in order to free up a frame (if no free frames are available for a process) to load the new demanded page.
 - Want lowest page-fault rate on both first access and re-access
 - Evaluate algorithm by running it on a particular string of memory references (reference string, aka page trace) and computing the number of page faults on that string
 - A reference string contains accessed (referenced) page numbers, not offset addresses within a page.
 - Repeated access to the same page does not cause a page fault
 - Results depend on number of frames available

Frame allocation and page replacement algorithms – cont.

Page trace (aka reference string)

• In a 16-bit system, if we trace a particular process, we might record the following address sequence:

```
0x0100, 0x0432, 0x0101, 0x0612, 0x0102, 0x0103, 0x0104, 0x0101, 0x0611, 0x0102, 0x0103, 0x0104, 0x0101, 0x0610, 0x0102, 0x0103, 0x0104, 0x0101, 0x0609, 0x0102, 0x0105
```


• If the page size is 256, then the page trace is: 1, 4, 1, 6, 1, 6, 1, 6, 1

9.4 Page replacement


- What happens if there are no free frames? Options are:
 - Terminate process not a good idea
 - Page replacement find some page in memory (that is least used for example, determined by some algorithm) and page it out.
 - Performance want an algorithm which will result in minimum number of page faults
- Even if there are free frames in the system, it may be desired to prevent over-allocation of memory to one process and limit its allocated number of frames.
- A modify (dirty) bit may be used (for each page entry in the page table) to reduce overhead of page transfers – only modified pages are written to disk (if chosen to be evicted from main memory)
 - So now the page table has a valid bit, a cow bit and we just added a modify bit!


Need For Page Replacement

for user 2



for user 2





No page fault (page is in a memory frame)


page fault (page not in memory frame)
TLB not shown


9.4.1 Basic Page Replacement

Handling a page fault exception:


- 1. Find the location of the desired page on disk
- 2. Find a free frame:
 - If there is a free frame, use it
 - If there is no free frame, use a page replacement algorithm to select a victim frame
 - Write victim frame to disk if dirty (after changing its page table entry to invalid)
- 3. Bring the desired page into the (newly) free frame; update the page and frame tables
- 4. Continue the process by restarting the instruction that caused the trap

Note: now potentially 2 page transfers for page fault – increasing EAT






Graph of page faults versus the number of allocated frames



9.4.2 First-In-First-Out (FIFO) Algorithm

• In the proceeding examples, the reference string used is 7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1

• 3 frames allocated (3 pages can be in memory at a time per process)



15 page faults

- **Issue:** If a page is in constant use, but was loaded early in program execution, it is then picked for replacement, despite it being in constant usage → page faults (repeatedly)
- How to track ages of pages?
 - Just use a FIFO/queue

The Belady's anomaly

 Results may vary by reference string: consider 1,2,3,4,1,2,5,1,2,3,4,5

 Adding more frames can cause more page faults (instead of improving things)!



