

基于OpenWrt的网络路由器流量监测—OpenWrt网络配置与文件传输

type	Post
⊙ status	Published
m date	@2025/05/13
_≔ tags	工具 开发
⊙ category	网络开发

前面简单配置了OpenWrt的网络环境,但是在更新包时发现无法下载,报错"check your network settings and connectivity",尝试 ping 8.8.8.8 无法成功;为了实现文件传输,必须更新包,也就要求重新配置 网络端口。

```
8.8/packages/x86_64/base/Packages.gz, wget returned 4.

* opkg_download: Check your network settings and connectivity.

* opkg_download: Failed to download https://downloads.openwrt.org/releases/24.1

8.8/targets/x866/64/kmods/6.5.73-1-a21259e4f338851d27a6443a3a7f7f1f/Packages.gz, wget returned 4.

* opkg_download: Check your network settings and connectivity.

* opkg_download: Failed to download https://downloads.openwrt.org/releases/24.1

8.8/packages/x86_64/luci/Packages.gz, wget returned 4.

* opkg_download: Check your network settings and connectivity.

* opkg_download: Failed to download https://downloads.openwrt.org/releases/24.1

8.8/packages/x86_64/packages/Packages.gz, wget returned 4.

* opkg_download: Check your network settings and connectivity.

* opkg_download: Failed to download https://downloads.openwrt.org/releases/24.1

8.8/packages/x86_64/routing/Packages.gz, wget returned 4.

* opkg_download: Check your network settings and connectivity.

* opkg_download: Failed to download https://downloads.openwrt.org/releases/24.1

8.8/packages/x86_64/telephony/Packages.gz, wget returned 4.

* opkg_download: Check your network settings and connectivity.

* opkg_download: Check your network settings and connectivity.

root@OpenWrt:*# _
```

网络分析与配置

当前配置分析

```
config interface 'lan'
option device 'br-lan' # 桥接接口(通常包含多个物理接口)
option proto 'static' # 静态IP配置
option ipaddr '192.168.142.101' # LAN IP地址
option netmask '255.255.255.0' # 子网掩码
```

- 问题: 没有定义 WAN 接口,导致无法连接到上级网络(如光猫、主路由或互联网)。
- **现象**:路由表中只有 192.168.142.0/24 的本地路由,没有默认网关(0.0.0.0/0),因此无法访问外部地址(如 8.8.8.8)。

可能的解决方法

单接口切换为 WAN,通过其他方式管理 LAN 。

即:将 etho 完全作为 WAN 接口,通过 Wi-Fi 或虚拟接口 管理 LAN。

步骤 1: 修改网络配置

编辑 /etc/config/network:

```
# 移除 br-lan 对 eth0 的桥接
config device
  option name 'br-lan'
  option type 'bridge'
  # 删除 list ports 'eth0' (若有)
#配置 WAN 接口
config interface 'wan'
  option device 'eth0'
  option proto 'dhcp'
                      # 或静态 IP
#配置 LAN 接口(通过 Wi-Fi 或其他虚拟接口)
config interface 'lan'
  option device 'wlan0'
                        #假设使用无线作为 LAN
  option proto 'static'
  option ipaddr '192.168.142.101'
  option netmask '255.255.255.0'
```

最后实现效果如上图所示。

步骤 2: 启用 Wi-Fi (未实现)

- 1. 编辑 /etc/config/wireless ,启用无线接口。
- 2. 重启无线服务:

wifi up



实际上发现配置文件当中并没有相关参数,输入 iwinfo 指令后提示 not found ,说明硬件应该是不支持或者没有加载无线驱动,这部分有点麻烦,就暂时先跳过了。

步骤 3: 重启网络服务

输入指令:

/etc/init.d/network restart

重启之后,再次 ping 8.8.8.8 ,发现成功返回信息,说明可以成功连接上外网:

```
root@OpenWrt:~# ping 8.8.8.8

PING 8.8.8.8 (8.8.8.8): 56 data bytes
64 bytes from 8.8.8.8: seq=0 ttl=128 time=100.026 ms
64 bytes from 8.8.8.8: seq=1 ttl=128 time=74.927 ms
64 bytes from 8.8.8.8: seq=2 ttl=128 time=73.089 ms
64 bytes from 8.8.8.8: seq=3 ttl=128 time=73.367 ms
64 bytes from 8.8.8.8: seq=4 ttl=128 time=72.493 ms
64 bytes from 8.8.8.8: seq=4 ttl=128 time=72.493 ms
64 bytes from 8.8.8.8: seq=5 ttl=128 time=73.282 ms
64 bytes from 8.8.8.8: seq=6 ttl=128 time=73.726 ms
64 bytes from 8.8.8.8: seq=7 ttl=128 time=73.420 ms
64 bytes from 8.8.8.8: seq=8 ttl=128 time=73.258 ms
64 bytes from 8.8.8.8: seq=9 ttl=128 time=72.580 ms
64 bytes from 8.8.8.8: seq=9 ttl=128 time=73.022 ms
72[4]+ Stopped ping 8.8.8.8
```

步骤 4: 镜像换源

默认的源,其配置文件为: https://downloads.openwrt.org/ ,经常容易出现断联,可以考虑换为中科大的镜像源。

• 先打开配置文件 vim /etc/opkg/distfeeds.conf ,在里面将 <u>downloads.openwrt.org</u> 替换为 <u>mirrors.ustc.edu.cn</u> 。

```
src/gz openwrt_core https://mirrors.ustc.edu.cn/openwrt/releases/24.10.0/targets src/gz openwrt_base https://mirrors.ustc.edu.cn/openwrt/releases/24.10.0/package src/gz openwrt_kmods https://downloads.openwrt.org/releases/24.10.0/targets/x86/src/gz openwrt_luci https://downloads.openwrt.org/releases/24.10.0/packages/x86_src/gz openwrt_packages https://downloads.openwrt.org/releases/24.10.0/packages/src/gz openwrt_routing https://downloads.openwrt.org/releases/24.10.0/packages/xsrc/gz openwrt_telephony https://downloads.openwrt.org/releases/24.10.0/packages
```

• 再在/etc/opkg.conf文件将检查数字签名的选项删除。

```
dest root /
dest ram /tmp
lists_dir ext /var/opkg-lists
option overlay_root /overlay
option check_signature
~
```

下载samba包传输文件

更新软件源

输入 opkg update 命令,我们可以看到成功下载更新包(但是原来的 192.168.142.101被配置为WAN导致无法通过浏览器访问登录OpenWrt的界面,暂时不用管)

```
root@OpenWrt:~# opkg update
Downloading https://mirrors.ustc.edu.cn/openwrt/releases/24.10.0/targets/x86/64/
packages/Packages.gz
Updated list of available packages in /var/opkg-lists/openwrt_core
Downloading https://mirrors.ustc.edu.cn/openwrt/releases/24.10.0/packages/x86_64
/base/Packages.gz
Updated list of available packages in /var/opkg-lists/openwrt_base
Downloading https://downloads.openwrt.org/releases/24.10.0/targets/x86/64/kmods/
6.6.73-1-a21259e4f3308051d27a6443a3a7f7f1f/Packages.gz
Updated list of available packages in /var/opkg-lists/openwrt_kmods
Downloading https://downloads.openwrt.org/releases/24.10.0/packages/x86_64/luci/
Packages.gz
Updated list of available packages in /var/opkg-lists/openwrt_luci
Downloading https://downloads.openwrt.org/releases/24.10.0/packages/x86_64/packages/Packages.gz
Updated list of available packages in /var/opkg-lists/openwrt_packages
Downloading https://downloads.openwrt.org/releases/24.10.0/packages/x86_64/routing/Packages.gz
Updated list of available packages in /var/opkg-lists/openwrt_routing
Downloading https://downloads.openwrt.org/releases/24.10.0/packages/x86_64/telep
hony/Packages.gz
Updated list of available packages in /var/opkg-lists/openwrt_telephony
root@OpenWrt:~#
```

下载samba包

输入 opkg install luci-app-samba4 ,安装samba服务;输入 opkg install luci-i18n-samba4-zh-cn ,对 samba服务汉化。

samba配置

浏览器输入openwrt虚拟机的ip地址(我的是192.168.142.101),进入图形化配置界面,选择services下的网络共享,进行samba配置。

• 勾选启用扩展调整、强制同步I/0。在编辑模块处,将invalid users=root注 释掉;



• 添加共享目录。名称自选,目录路径自选,以名称shared_file、路径/mnt/p0 为例。勾选可浏览、允许匿名用户,创建权限掩码设置为0777,目录权限掩码设置为0777:

共享目录

请添加要共享的目录。每个目录指到已挂载设备上的文件夹。 强制 创建 目录 VFS 对 Apple 读 权限 权限 Timemachine 大 监 箬 宾 所 掩码 掩码 machine 共 小 (GB) 名 享 用 者 Shar **✓** 0777 0777 Delete Add

- 回到openwrt虚拟机中,创建对应目录: mkdir/mnt/p0。
- 修改目录权限: chmod -R 777 /mnt/p0 。

使用及测试共享文件

• 再在该路径下创建一个test.txt,虚拟机 vi /mnt/p0/test.txt



这里shared_file文件名只是虚拟的名称,比如我们尝试以下测试,发现并没有"shared file"实体存在:

```
root@OpenWrt:~# cd /mnt/p0/shared_file
-ash: cd: can't cd to /mnt/p0/shared_file: No such file or directory
root@OpenWrt:~# cd /mnt/p0
root@OpenWrt:/mnt/p0#
```

• 往里面写入"test write"字段:

打开后发现主机端确实同步了我们对共享文件的更新:





参考文章

• 一些引用

引用文章



有关Notion安装或者使用上的问题,欢迎您在底部评论区留言,一起交流

~