

*Operating
Systems:
Internals
and
Design
Principles*

Chapter 1

Computer System

Overview

Seventh Edition
By William Stallings

Operating Systems: Internals and Design Principles


“No artifact designed by man is so convenient for this kind of functional description as a digital computer. Almost the only ones of its properties that are detectable in its behavior are the organizational properties. Almost no interesting statement that one can make about on operating computer bears any particular relation to the specific nature of the hardware. A computer is an organization of elementary functional components in which, to a high approximation, only the function performed by those components is relevant to the behavior of the whole system.”




THE SCIENCES OF THE ARTIFICIAL ,
Herbert Simon

Operating System

- Exploits the hardware resources of one or more processors
- Provides a set of services to system users
- Manages secondary memory and I/O devices



Basic Elements




Processor

Controls the
operation of the
computer


Performs the
data processing
functions

Referred to as
the *Central
Processing Unit*
(CPU)



Main Memory

- Volatile
- Contents of the memory is lost when the computer is shut down
- Referred to as real memory or primary memory



I/O Modules


Moves data between the computer and external environments such as:

storage (e.g. hard drive)

communications equipment


terminals


System Bus



- Provides for communication among processors, main memory, and I/O modules

Top-Level View





Microprocessor

- Invention that brought about desktop and handheld computing
- Processor on a single chip
- Fastest general purpose processor
- Multiprocessors
- Each chip (socket) contains multiple processors (cores)

Graphical Processing Units (GPU's)

- Provide efficient computation on arrays of data using Single-Instruction Multiple Data (SIMD) techniques
- Used for general numerical processing
- Physics simulations for games
- Computations on large spreadsheets



G

P

U

Digital Signal Processors (DSPs)

- Deal with streaming signals such as audio or video
- Used to be embedded in devices like modems
- Encoding/decoding speech and video (codecs)
- Support for encryption and security




D

S

P

System on a Chip (SoC)

- To satisfy the requirements of handheld devices, the microprocessor is giving way to the SoC
- Components such as DSPs, GPUs, codecs and main memory, in addition to the CPUs and caches, are on the same chip



Instruction Execution

- A program consists of a set of instructions stored in memory

Two steps:

- processor reads (fetches) instructions from memory
- processor executes each instruction

Basic Instruction Cycle





Figure 1.2 Basic Instruction Cycle

Instruction Fetch and Execute

- The processor fetches the instruction from memory
- Program counter (PC) holds address of the instruction to be fetched next
 - PC is incremented after each fetch



Instruction Register (IR)

Fetched instruction is loaded into Instruction Register (IR)



- Processor interprets the instruction and performs required action:
 - Processor-memory
 - Processor-I/O
 - Data processing
 - Control

Characteristics of a Hypothetical Machine



(a) Instruction format



(b) Integer format

Program counter (PC) = Address of instruction
Instruction register (IR) = Instruction being executed
Accumulator (AC) = Temporary storage

(c) Internal CPU registers

0001 = Load AC from memory
0010 = Store AC to memory
0101 = Add to AC from memory

(d) Partial list of opcodes

Figure 1.3 Characteristics of a Hypothetical Machine

Example of Program Execution




Figure 1.4 Example of Program Execution
(contents of memory and registers in hexadecimal)

Interrupts

- Interrupt the normal sequencing of the processor
- Provided to improve processor utilization
 - most I/O devices are slower than the processor
 - processor must pause to wait for device
 - wasteful use of the processor




Common Classes of Interrupts




Table 1.1 Classes of Interrupts

Program	Generated by some condition that occurs as a result of an instruction execution, such as arithmetic overflow, division by zero, attempt to execute an illegal machine instruction, and reference outside a user's allowed memory space.
Timer	Generated by a timer within the processor. This allows the operating system to perform certain functions on a regular basis.
I/O	Generated by an I/O controller, to signal normal completion of an operation or to signal a variety of error conditions.
Hardware failure	Generated by a failure, such as power failure or memory parity error.

Flow of Control Without Interrupts



Interrupts: Short I/O Wait



(b) Interrupts; short I/O wait

Transfer of Control via Interrupts




Figure 1.6 Transfer of Control via Interrupts



Instruction Cycle With Interrupts




Figure 1.7 Instruction Cycle with Interrupts

Program Timing: Short I/O Wait




Figure 1.8 Program Timing: Short I/O Wait

Program Timing: Long I/O wait





Figure 1.9 Program Timing: Long I/O Wait

Simple Interrupt Processing






Figure 1.10 Simple Interrupt Processing

Changes for an Interrupt



Multiple Interrupts


An interrupt occurs while another interrupt is being processed

- e.g. receiving data from a communications line and printing results at the same time

Two approaches:

- disable interrupts while an interrupt is being processed
- use a priority scheme

Transfer of Control With Multiple Interrupts:




(a) Sequential interrupt processing

Sequential

Transfer of Control With Multiple Interrupts:

Nested



(b) Nested interrupt processing

Example Time Sequence of Multiple Interrupts






Figure 1.13 Example Time Sequence of Multiple Interrupts

Memory Hierarchy

- Major constraints in memory
 - ↗ amount
 - ↗ speed
 - ↗ expense
- Memory must be able to keep up with the processor
- Cost of memory must be reasonable in relationship to the other components



Memory Relationships



The Memory Hierarchy

- Going down the hierarchy:
 - decreasing cost per bit
 - increasing capacity
 - increasing access time
 - decreasing frequency of access to the memory by the processor




Figure 1.14 The Memory Hierarchy

Performance of a Simple Two-Level Memory




Figure 1.15 Performance of a Simple Two-Level Memory

Principle of Locality

- Memory references by the processor tend to cluster
- Data is organized so that the percentage of accesses to each successively lower level is substantially less than that of the level above
- Can be applied across more than two levels of memory

Secondary Memory



**Also referred
to as auxiliary
memory**

- External
- Nonvolatile
- Used to store program and data files



Cache Memory





- Invisible to the OS
- Interacts with other memory management hardware
- Processor must access memory at least once per instruction cycle
- Processor execution is limited by memory cycle time
- Exploit the principle of locality with a small, fast memory

Cache Principles



- Contains a copy of a portion of main memory
- Processor first checks cache
- If not found, a block of memory is read into cache
- Because of locality of reference, it is likely that many of the future memory references will be to other bytes in the block

Cache and Main Memory



Cache/Main-Memory Structure




Figure 1.17 Cache/Main-Memory Structure



Cache Read Operation






Figure 1.18 Cache Read Operation

Cache Design



Cache and Block Size

Cache Size

Small caches have significant impact on performance

Block Size

The unit of data exchanged between cache and main memory

Mapping Function

- * Determines which cache location the block will occupy





Two constraints affect design:

When one block is read in, another may have to be replaced

The more flexible the mapping function, the more complex is the circuitry required to search the cache


Replacement Algorithm

- ◆ Least Recently Used (LRU) Algorithm
 - effective strategy is to replace a block that has been in the cache the longest with no references to it
 - hardware mechanisms are needed to identify the least recently used block
 - chooses which block to replace when a new block is to be loaded into the cache



Write Policy

Dictates when the memory write operation takes place



- can occur every time the block is updated
- can occur when the block is replaced
 - minimizes write operations
 - leaves main memory in an obsolete state

I/O Techniques

- * When the processor encounters an instruction relating to I/O, it executes that instruction by issuing a command to the appropriate I/O module

Three techniques are possible for I/O operations:

Programme
d I/O

Interrupt-
Driven I/O

Direct Memory
Access (DMA)


Programmed I/O

- The I/O module performs the requested action then sets the appropriate bits in the I/O status register
- The processor periodically checks the status of the I/O module until it determines the instruction is complete
- With programmed I/O the performance level of the entire system is severely degraded

Interrupt-Driven I/O

Processor issues an I/O command to a module and then goes on to do some other useful work

The processor executes the data transfer and then resumes its former processing



The I/O module will then interrupt the processor to request service when it is ready to exchange data with the processor

More efficient than Programmed I/O but still requires active intervention of the processor to transfer data between memory and an I/O module

Interrupt-Driven I/O Drawbacks



- Transfer rate is limited by the speed with which the processor can test and service a device
- The processor is tied up in managing an I/O transfer
 - a number of instructions must be executed for each I/O transfer

Direct Memory Access (DMA)

- * Performed by a separate module on the system bus or incorporated into an I/O module

When the processor wishes to read or write data it issues a command to the DMA module containing:

- whether a read or write is requested
- the address of the I/O device involved
- the starting location in memory to read/write
- the number of words to be read/written

Direct Memory Access

- Transfers the entire block of data directly to and from memory without going through the processor
 - processor is involved only at the beginning and end of the transfer
 - processor executes more slowly during a transfer when processor access to the bus is required
- More efficient than interrupt-driven or programmed I/O

Symmetric Multiprocessors (SMP)



■ A stand-alone computer system with the following characteristics:

- two or more similar processors of comparable capability
- processors share the same main memory and are interconnected by a bus or other internal connection scheme
- processors share access to I/O devices
- all processors can perform the same functions
- the system is controlled by an integrated operating system that provides interaction between processors and their programs at the job, task, file, and data element levels

SMP Advantages

Performance

- a system with multiple processors will yield greater performance if work can be done in parallel

Scaling

- vendors can offer a range of products with different price and performance characteristics

Availability

- the failure of a single processor does not halt the machine

Incremental Growth

- an additional processor can be added to enhance performance

SMP Organization






Figure 1.19 Symmetric Multiprocessor Organization



Multicore Computer

- Also known as a chip multiprocessor
- Combines two or more processors (cores) on a single piece of silicon (die)
 - each core consists of all of the components of an independent processor
- In addition, multicore chips also include L2 cache and in some cases L3 cache



Intel Core i7

Supports two forms of external communications to other chips:

DDR3 Memory Controller

- brings the memory controller for the DDR (double data rate) main memory onto the chip
- with the memory controller on the chip the Front Side Bus is eliminated

QuickPath Interconnect (QPI)

- enables high-speed communications among connected processor chips

Intel Core i7




Figure 1.20 Intel Corei7 Block Diagram

Summary

■ Basic Elements

- processor, main memory, I/O modules, system bus
- GPUs, SIMD, DSPs, SoC
- Instruction execution
 - processor-memory, processor-I/O, data processing, control
- Interrupt/Interrupt Processing
- Memory Hierarchy
- Cache/cache principles and designs
- Multiprocessor/multicore