## CMP 1203

Lecture 4

### **Excess-M representation of Signed numbers**

- Define a set of values, split it into ranges and use one range to represent positive numbers, another for negative numbers.
- Maps decimal numbers
- Bias (M) is selected such that the range is split equally
- If using **n** bits to represent numbers, choose bias of  $2^{n-1} 1$ . E.g. For 4 bits, bias is  $2^{4-1} 1 = 7$
- Then excess-M representation simply adds M to that integer.
- Examples:
- 1.  $0_{10} = 0 + 7 = 7_{10} = 0111_2$
- 2.  $-7=-7+7=0_{10}=0000_2$
- 3.  $1111_2 = 15_{10}$ , 15-7 = 8. So  $1111_2 = +8_{10}$

## Recap

Integer		Binary strings representing the signed integer			
Decimal	Binary	Signed Magnitude	1's complement	2's complement	Excess-127
2	0000010	0000010	0000010	0000010	10000001
-2	0000010	10000010	11111101	11111110	01111101
100	01100100	01100100	01100100	01100100	11100011
-100	01100100	11100100	10011011	10011100	00011011

### **Unsigned Vs. Signed Numbers**

- Unsigned numbers are used to represent values which are guaranteed to be positive e.g. a memory address
- As a computer engineer/programmer, you must be able to manage both declare variable as a specific type e.g. *int*, unsigned int in C programming

#### Question

- What happens if we try to store values larger than specified number of bits?
- Unsigned numbers simply wrap around and start over at zero: return to zero e.g. if using 4 bits and add 1 to 1111, we get 0000
- Signed numbers use half their space for +ve numbers and the other for –ve numbers. Adding 1 to the largest positive 2's complement number (+7) 0111 results in 1000 (-8). Wraps around with change in sign!
- Need to anticipate these scenarios in program

### **Booth's Algorithm**

- To speed up multiplication, need more techniques e.g. those which use the presence of consecutive 0's or 1's
- Inspect 2 bits of the multiplier at a time Q(i)Q(i-1), 0
   ≤ I ≤ n-1
- If 01, add multiplicand and shift
- If 10, subtract multiplicand and shift
- If 00 or 11, only shift

### Examples

**Example** Consider the multiplication of the two positive numbers M = 0111 (7) and Q = 0011 (3) and assuming that n = 4. The steps needed are tabulated below.

M	$\boldsymbol{A}$	Q	<b>Q</b> (-1)		
0111	0000	0011	0	Initial value	
0111	1001	0011	0	A = A - M	
0111	1100	1001	1	ASR	End cycle #1
0111	1110	0100	1	ASR	End cycle #2
0111	0101	0100	1	A = A + M	
0111	0010	1010	0	ASR	End cycle #3
0111	0001	0101	1	ASR	End cycle #4
	+	21 (correct r	esult)		

<sup>\*2&#</sup>x27;s complement

<sup>\*</sup>arithmetic right shift

<sup>\*1</sup>st bit of shifted A is same as previous bit

# Floating Point Representation (Scientific Notation)

A FP number can be expressed in the form

$$\pm m^*b^e$$

 m = mantissa /significand , e = exponent , b = base( radix) of the exponent




Figure 4.11 Representation of a floating-point number

### Example

• 
$$17 = 17.0 \times 10^{0} = 1.7 \times 10^{1} = 0.17 \times 10^{2}$$

• 
$$17_{10} = 10001_2 \times 2^0 = 1000.1_2 \times 2^1 = 100.01_2 \times 2^2 = 10.001_2 \times 2^3 = 0.10001_2 \times 2^5$$
 etc.

• If we use 1 sign bit, 5 exponent bits and 8 bits for the significand then 0.10001<sub>2</sub> × 2<sup>5</sup> is:

0 00101 10001000

sign exponent significand

### Example

- Use excess-M representation for exponent to account for negative exponents
- e.g. using excess-15:

```
17_{10} becomes : e = 15+5 = 20
```

0 10100 10001000

sign exponent significand

#### Normalization

- Various representations for a single number
- 0 10101 10001000 =  $0.10001 \times 2^6$
- 0 10110 01000100 = 0.010001  $\times$  2<sup>7</sup>
- 0 10111 00100010 =?
- 0 11000 00010001 =?

Are all equivalent.

Normalization: The MSB must always be 1

Question: Express 0.0625 in normalized floating point form using the simple model with excess-15 bias (assume 5 and 8 bits for exponent and significand respectively)

### Floating point arithmetic

- 1. Re-write both as raised to same power
- 2. Add
- 3. Maintain bigger exponent and truncate low-order bit

	17-15= 2nd power	
0	10001	11001000
0	01111	10011010
	15-15=0 power	
	11.001000	
+	0.10011010	
	11.10111010	*normalise andmaintain 2nd power
0	10001	11101110

HOMEWORK: HOW DO WE REPRESENT ZERO IN THIS FORMAT?

### Floating point Arithmetic

0	10010	$ 11001000  = 0.11001000 \times 2^3$
X 0	10000	$10011010 = 0.10011010 \times 2^{1}$

- 0.11001000 X 0.10011010 = 0.0111100001010000
- Multiplying by  $2^3 \times 2^1 = 2^4$  gives 111.10000101
- Renormalizing gives:
- 0 10010 11110000
- Errors:
- Arise because computers have limited storage so cannot represent entire range of infinite real numbers
- e.g. in these examples, we cant represent bigger than 128 because they are bigger than 8 bits wide hence round off or drop low order bit
- Compute relative error as ratio (error/true value) \*100

### IEEE- 754 Floating Point Standard

- Single precision standard uses excess-127 bias and an 8-bit exponent.
- Significand assumes an implied 1 to the left of the radix point and is 23 bits
- Implied one is called "hidden bit or hidden 1"
- e.g:  $5.5 = 101.1 = 0.1011 \times 2^3$  is represented as  $1.011 \times 2^2$
- Exception to normalization rule!

TABLE 4.2 Characteristics of the IEEE Single and Double Floating-Point Formats

Characteristic	Single-precision	Double-precision	
Length in bits	32	64	
Fraction part in bits	23	52	
Hidden bits	1	1	
Exponent length in bits	8	11	
Bias	127	1023	
Approximate range	$2^{128} \approx 3.8 \times 10^{38}$	$2^{1024} \approx 9.0 \times 10^{307}$	
Smallest normalized number	$2^{-126} \approx 10^{-38}$	$2^{-1022} \approx 10^{-308}$	


### Range, Precision and Accuracy

- Range: interval from the smallest to the largest value e.g. for 8 bit 2's complement, range is -128 to + 128
- Accuracy: how close a number is to its true value e.g. if cant represent 0.01 within our range but we can find a number that is close to it or reasonably accurate
- Precision: signifies how much information we have about a value and the amount of information used to represent the value e.g. 1.666 and 1.6660 have 3 and 4 decimal digits of precision respectively but none is more accurate than the other
- \*\* accuracy and precision are usually confused

### Assembly Language Programming

- Necessary in some cases irrespective of presence of compiler
- Can shorten and fasten machine code than that generated by a compiler → useful in embedded systems or portable apps where resources are limited; write some part of code in assembly language
- Directly maps machine code into a form humans can understand

### Simple Machine



- Word size is 16 –bits
- Memory size is 4096 words
- 5 16-bit registers

Figure 3.1 A simple machine

- Program counter (PC) stores address of next instruction to be executed
- Instruction Register contains operation code portion of the instruction being executed
- •Address Register contains the address portion of the instruction being executed
- Accumulator (AC) –serves as source and destination for data
- Data register used to hold data

### Instruction Set

TABLE 3.1 Instruction Set of the Simple Processor

Operation code	Operand	Meaning of instruction
0000		Stop execution
0001	adr	Load operand from memory (location adr) into AC
0010	adr	Store contents of AC in memory (location adr)
0011		Copy the contents AC to DR
0100		Copy the contents of DR to AC
0101		Add DR to AC
0110		Subtract DR from AC
0111		And bitwise DR to AC
1000		Complement contents of AC
1001	adr	Jump to instruction with address adr
1010	adr	Jump to instruction adr if AC = 0

#### Processor supports 3 instruction types:

- •data transfer load, store and move data between registers AC and DR
- •data processing add, subtract, and, not
- program control jump and conditional jump

### Example

 Machine code to add contents of memory location 12, initialized to 350 and memory location 14 initialized to 96 and store the result in location 16, initialized to 0.

TABLE 3.2 Simple Machine Language Program in Binary (Example 1)

Memory location (bytes)	Binary instruction	Description
0000 0000 0000	0001 0000 0000 1100	Load the contents of location 12 in AC
0000 0000 0010	0011 0000 0000 0000	Move contents of AC to DR
0000 0000 0100	0001 0000 0000 1110	Load the contents of location 14 into AC
0000 0000 0110	0101 0000 0000 0000	Add DR to AC
0000 0000 1000	0010 0000 0001 0000	Store contents of AC in location 16
0000 0000 1010	0000 0000 0000 0000	Stop
0000 0000 1100	0000 0001 0101 1110	Data value 350
0000 0000 1110	0000 0000 0110 0000	Data value is 96
0000 0001 0000	0000 0000 0000 0000	Data value is 0

Column 1: memory location in binary for each instruction and operand

Column 2: lists contents of memory locations

\*\*\* observe difficulty to understand and debug

### Example

- Same program in HEX
- Reduces number of digits

TABLE 3.3 Simple Machine Language Program in Hexadecimal (Example 1)

Memory location (bytes) Hex instruction		
000	100C	
002	3000	
004	100E	
006	5000	
008	2010	
00A	0000	
00C	015E	
00E	0060	
010	0000	

### Instruction Mnemonics and Syntax

- Assembly programs are written in short abbreviations called mnemonics
- A mnemonic is an abbreviation that represents an actual machine instruction




Figure 3.2 Assembly instruction format

- -Label provides symbolic name for a memory address
- -Opcode contains symbolic abbreviation of a given operation
- -Operand consists of additional information or data required by the opcode
- -Comments: space for documentation for debugging and maintenance

For this example, comments are began with \
 START LD X \copy contents of location X into AC

TABLE 3.4 Assembly Language for the Simple Processor

Mnemonic	Operand	Meaning of instruction	
STOP		Stop execution	
LD	x	Load operand from memory (location x) into AC	
ST	x	Store contents of AC in memory (location x)	
MOVAC		Copy the contents AC to DR	
MOV		Copy the contents of DR to AC	
ADD		Add DR to AC	
SUB		Subtract DR from AC	
AND		And bitwise DR to AC	
NOT		Complement contents of AC	
BRA	adr	Jump to instruction with address adr	
BZ	adr	Jump to instruction $adr$ if $AC = 0$	

- Pseudo instructions/ assembler directives: commands understood by assembler but don't correspond to actual machine instructions
- In these examples W will be used to reserve a word in memory e.g.
- X
   W
   350 \reserve a word initialized to 350

- Write an assembly program to perform perform: Z
  - ← X\*Y; X,Y and Z are memory locations

```
\ Load X in AC
         LD X
         ST N
                            \ Store AC (X original value) in N
LOOP
         LD N
                            \setminus AC \leftarrow N
                           \ Go to EXIT if AC = 0 (N reached 0)
         BZ EXIT
         LD ONE
                           \setminus AC \leftarrow 1
         MOVAC
                           \ DR ← AC
                           \setminus AC \leftarrow N
         LD N
                                                                 What do you
                            \ subtract 1 from N
         SUB
         ST N
                            \ store decrements N
                                                                 notice?
         LD Y
                           \land AC \leftarrow Y
         MOVAC
                           \ DR ← AC
         LD Z
                           \ AC ← Z (partial product)
                            \ Add Y to Z
         ADD
         STZ
                            \ store the new value of Z
         BRA LOOP
EXIT
         STOP
X
                     5
                            \ reserve a word initialized to 5
         W
                     15
                            \ reserve a word initialized to 15
\mathbf{v}
         W
                            \ reserve a word initialized to 0
                            \ reserve a word initialized to 1
ONE
                            \ reserve a word initialized to 0
N
```

- Write an assembly program to perform perform: Z ← X\*Y; X,Y and Z are memory locations
- No multiplication but added Y X times (simple CPU doesn't have multiplication operation)
- N used as a counter initialized to X and then decremented by one after each addition
- BZ instruction is used to test for when N reaches 0
- Memory location is used to store N but needs to be loaded into AC before BZ is executed
- Also use a memory location (ONE) to store the constant 1
- Memory location Z contains partial products and eventually final result

```
\ Load X in AC
         LD X
         ST N
                            \ Store AC (X original value) in N
LOOP
         LD N
                            \setminus AC \leftarrow N
                            \ Go to EXIT if AC = 0 (N reached 0)
         BZ EXIT
         LD ONE
                            \setminus AC \leftarrow 1
         MOVAC
                            \ DR ← AC
                            \setminus AC \leftarrow N
         LD N
                            \ subtract 1 from N
         SUB
         ST N
                            \ store decrements N
         LD Y
                            \land AC \leftarrow Y
         MOVAC:
                            \ DR ← AC
         LD Z
                            \ AC ← Z (partial product)
         ADD
                            \ Add Y to Z
         STZ
                            \ store the new value of Z
         BRA LOOP
EXIT
         STOP
X
                     5
                            \ reserve a word initialized to 5
         W
                     15
                            \ reserve a word initialized to 15
\mathbf{v}
         W
                            \ reserve a word initialized to 0
                            \ reserve a word initialized to 1
ONE
                            \ reserve a word initialized to 0
         W
N
```

### **Assembler Directives and Commands**

- Some practical issues need to be considered when writing assembly language
- 1. Assembler directives
- 2. Use of symbols: used to represent numbers
- 3. Use of synthetic operations: enables programmers to use instructions not supported by the architecture translated by the assembler to those supported
- 4. Assembler syntax: some conventions are defined to refer to hardware components e.g. prefixes attached to names or values
- 5. Interaction with the operating system: hardware in some machines cant be accessed by a program directly but controlled by OS. Utilize system calls to do functions that are part of the OS

# How do we go from assembly language to execution?

- 1. Assembler reads program and generates machine code
- 2. Passed to linker which checks for calls to procedures in the link library and combines them with the object program to form executable program
- 3.Loader loads the program into memory and branches CPU to the starting address
- 4.Program begins execution




Figure 3.3 Assembly and execution process

#### Handout

- Linda Null and Julia Lobur, The Essentials of Computer Organization and Architecture, 4<sup>th</sup> Ed, Chapter 2 and 4
- Mostafa Abd-El-Barr, Hesham El-Rewini, Essentials of Computer Organization and Architecture, Chapter 3 and 4

#### References/ Handout

- Work out as many possible examples as you can!
- Linda Null and Julia Lobur, The Essentials of Computer Organization and Architecture, 4<sup>th</sup> Ed, Chapter 2
- Mostafa Abd-El-Barr, Hesham El-Rewini, Essentials of Computer Organization and Architecture, Chapter 4