

Semaphores, Condition Variables, and Monitors

CS61, Lecture 21
Prof. Stephen Chong
November 18, 2010

Announcements

- Lab 5 released!
 - Threading lab: simulating a banking system
 - Due Dec 2
 - See webpage for info
 - Partner sign up by Tuesday Nov 23rd

Last time

- We looked at locks
 - Two operations: acquire and release
 - At most one thread can hold a lock at a time
 - Can use to enforce mutual exclusion and critical sections
 - Considered how to efficiently implement

Higher-level synchronization primitives

- We have looked at one synchronization primitive: locks
- Locks are useful for many things, but sometimes programs have different requirements.
- Examples?
 - Say we had a shared variable where we wanted any number of threads to read the variable, but only one thread to write it.
 - How would you do this with locks?

```
Reader() {
   acquire(lock);
   mycopy = shared_var;
   release(lock);
   return mycopy;
}
```

```
Writer() {
   acquire(lock);
   shared_var = NEW_VALUE;
   release(lock);
}
```

What's wrong with this code?

Today

- Semaphores
- Condition variables
- Monitors

• Reading: 12.5

Semaphores

- Higher-level synchronization construct
 - Designed by Edsger Dijkstra in the 1960's
- Semaphore is a **shared counter**
- Two operations on semaphores:
 - P() or wait() or down()
 - From Dutch proeberen, meaning "test"



- **Atomic action**: Wait for semaphore value to become > 0, then **decrement** it
- V() or signal() or up()
 - From Dutch verhogen, meaning "increment"
 - Atomic action: Increment semaphore value by 1.

Semaphore Example

Semaphores can be used to implement locks:

```
Semaphore my_semaphore = 1; // Initialize to nonzero
int withdraw(account, amount) {
   P(my_semaphore);
   balance = get_balance(account);
   balance -= amount;
   put_balance(account, balance);
   V(my_semaphore);
   return balance;
}
```

- A semaphore where the counter value is only 0 or 1 is called a binary semaphore.
 - Essentially the same as a lock.

Simple Semaphore Implementation

```
struct semaphore {
   int val;
   thread_list waiting; // List of threads waiting for semaphore
}
```

```
P(semaphore Sem):  // Wait until > 0 then decrement
  while (Sem.val <= 0) {
    add this thread to Sem.waiting;
    block(this thread);
  }
  Sem.val = Sem.val - 1;
  return;</pre>
```

```
V(semaphore Sem):  // Increment value and wake up next thread
    Sem.val = Sem.val + 1;
    if (Sem.waiting is nonempty) {
        remove a thread T from Sem.waiting;
        wakeup(T);
    }
```

P() and V() must be atomic actions!

Simple Semaphore Implementation

```
struct semaphore {
   int val;
   thread_list waiting; // List of threads waiting for semaphore
}
```

```
P(semaphore Sem):  // Wait until > 0 then decrement
  while (Sem.val <= 0) {
    add this thread to Sem.waiting;
    block(this thread);
}
Sem.val = Sem.val - 1;
return;
P could be called by</pre>
```

remove a thread T from Sem.waiting;

```
v(semaphore Sem):  // Increment value and wake up next thread
Sem.val = Sem.val + 1;
if (Sem.waiting is nonempty) {
another thread while
this thread is waiting
```

wakeup(T);

Semaphore Implementation


- How do we ensure that the semaphore implementation is atomic?
- One option: use a lock for P() and V()
 - Make sure that only one P() or V() can be executed by any process at a time
 - Need to be careful to release lock before sleeping, acquire lock on waking up
- Another option: hardware support

Why are semaphores useful?

- A binary semaphore (counter is always 0 or 1) is basically a lock.
 - Start with semaphore value = 1
 - acquire() = P()
 - release() = V()
- The real value of semaphores becomes apparent when the counter can be initialized to a value other than 0 or 1.

The Producer/Consumer Problem

• Also called the Bounded Buffer problem. Mmmm... donuts






- Producer pushes items into the buffer.
- Consumer pulls items from the buffer.
- Producer needs to wait when buffer is full.
- Consumer needs to wait when the buffer is empty.


The Producer/Consumer Problem

Also called the Bounded Buffer problem.




- Producer pushes items into the buffer.
- Consumer pulls items from the buffer.
- Producer needs to wait when buffer is full.
- Consumer needs to wait when the buffer is empty.

An implementation



• What's wrong with this code?


An implementation



• What's wrong with this code?

An implementation with semaphores

Mmmm... donuts



```
Semaphore full = 0;
Producer() {
    int item;
    while (TRUE) {
         item = bake();
         P(empty);
         P(mutex);
         insert_item(item)
         V(mutex);
         V(full);
```

```
Consumer() {
     int item;
    while (TRUE) {
          P(full);
          P(mutex);
          item = remove_item();
         V(mutex);
         V(empty);
          eat(item);
```

Why is it important that P(empty) is before P(mutex)?

Otherwise a thread could acquire mutex and wait for empty; prevent another thread acquiring mutex. DEADLOCK! (more on this next week)

- Let's go back to the problem at the beginning of lecture.
 - Single shared object
 - Want to allow any number of threads to read simultaneously
 - But, only one thread should be able to write to the object at a time
 - (And, not interfere with any readers...)


```
Semaphore wrt = 1;
int readcount = 0;

Writer() {
   P(wrt);
   do_write();
   V(wrt);
}
```

 Seems simple, but this code is broken. Let's see how...

```
Reader() {
  readcount++;
  if (readcount == 1) {
    P(wrt);
  do_read();
  readcount--;
  if (readcount == 0) {
    V(wrt);
```

- Let's go back to the problem at the beginning of lecture.
 - Single shared object
 - Want to allow any number of threads to read simultaneously
 - But, only one thread should be able to write to the object at a time



- Let's go back to the problem at the beginning of lecture.
 - Single shared object
 - Want to allow any number of threads to read simultaneously
 - But, only one thread should be able to write to the object at a time
 - (And, not interfere with any readers...)

```
Semaphore wrt = 1;
int readcount = 0;

Writer() {
  P(wrt);
  do_write();
  V(wrt);
}
```

 Seems simple, but this code is broken. Let's see how...

```
Reader() {
  readcount++;
  if (readcount == 1) {
                        What if we context
  do_read();
                           switch here?
  readcount--;
  if (readcount == 0) {
    V(wrt);
      A writer thread might get the wrt lock,
        and subsequent reader threads run
                 without the lock!
```

- Problem: readcount is accessed by multiple threads concurrently without synchronization!
- Solution: Make "increment, test, P" and "decrement, test, V" atomic, by using a mutex.

```
Semaphore mutex = 1;
Semaphore wrt = 1;
int readcount = 0;

Writer() {
   P(wrt);
   do_write();
   V(wrt);
}
```

```
Reader() {
  P(mutex);
  readcount++;
  if (readcount == 1) {
    P(wrt);
  V(mutex);
  do_read();
  P(mutex);
  readcount--;
  if (readcount == 0) {
    V(wrt);
  V(mutex);
```

Issues with Semaphores

- Much of the power of semaphores derives from calls to P() and V() that are unmatched
 - See previous example!
 - Unlike locks, where acquire() and release() are always paired.
- This means it is a lot easier to get into trouble with semaphores.
 - Semaphores are a lot of rope to tie yourself in knots with...

Today

- Semaphores
- Condition variables
- Monitors

• Reading: 12.5

Condition Variables

- A **condition variable** represents some condition that a thread can:
 - Wait on, until the condition occurs; or
 - Notify other waiting threads that the condition has occurred
 - Very useful primitive for signaling between threads.
- Condition variable indicates an event; cannot store or retrieve a value from a CV
- Three operations on condition variables:
 - wait() Block until another thread calls signal() or broadcast() on the CV
 - signal() Wake up one thread waiting on the CV
 - broadcast() Wake up all threads waiting on the CV
- In Pthreads, the CV type is a pthread_cond_t.
 - Use pthread_cond_init() to initialize
 - pthread_cond_wait(&theCV, &someLock);
 - pthread_cond_signal(&theCV);
 - pthread_cond_broadcast(&theCV);

```
/* Thread B */
pthread_mutex_lock(&myLock);

counter++;
if (counter == 10) {
   pthread_cond_signal(&myCV);
}

pthread_mutex_unlock(&myLock);
```

- In pthreads, all condition variable operations **must** be performed while a mutex is locked!!!
 - Why is the lock necessary?

```
/* Thread B */
pthread_mutex_lock(&myLock);

counter++;
if (counter == 10) {
   pthread_cond_signal(&myCV);
}

pthread_mutex_unlock(&myLock);
```

- If no lock on Thread A:
 - Might wait after another thread sets counter to 10
- If no lock on Thread B:
 - No guarantee that increment and test is atomic

```
/* Thread B */
pthread_mutex_lock(&myLock);

counter++;
if (counter == 10) {
    pthread_cond_signal(&myCV);
}

pthread_mutex_unlock(&myLock);
```

What happens to the lock when you call wait on the CV?

```
/* Thread B */
pthread_mutex_lock(&myLock);

counter++;
if (counter == 10) {
    pthread_cond_signal(&myCV);
}

pthread_mutex_unlock(&myLock);
```

```
/* Thread B */
pthread_mutex_lock(&myLock);

counter++;
if (counter == 10) {
    pthread_cond_signal(&myCV);
}

pthread_mutex_unlock(&myLock);
```

```
/* Thread B */
pthread_mutex_lock(&myLock);

counter++;
if (counter == 10) {
    pthread_cond_signal(&myCV);
}

pthread_mutex_unlock(&myLock);
```

- wait() released the lock while Thread A is sleeping
 - That is why pthreads requires that the myLock is passed in

```
/* Thread B */
pthread_mutex_lock(&myLock);

counter++;
if (counter == 10) {
    pthread_cond_signal(&myCV);
}

pthread_mutex_unlock(&myLock);
```

```
pthread_mutex_t myLock;
pthread_cond_t myCV;
int counter = 0;

/* Thread A */
pthread_mutex_lock(&myLock);

while (counter < 10) {
    pthread_cond_wit(&myCV);
}

counter++;
if (counter == 10) {
    pthread_cond_signal(&myCV);
}

pthread_mutex_unlock(&myLock);</pre>
```

- **signal()** wakes up Thread A, but Thread A cannot proceed. Why?
 - Thread A requires lock to continue. Lock is still held by Thread B

- **signal()** wakes up Thread A, but Thread A cannot proceed. Why?
 - Thread A requires lock to continue. Lock is still held by Thread B

 Once Thread B releases lock, Thread A can acquire it and continue running

```
/* Thread B */
pthread_mutex_lock(&myLock);

counter++;
if (counter == 10) {
    pthread_cond_signal(&myCV);
}

pthread_mutex_unlock(&myLock);
```

```
/* Thread B */
pthread_mutex_lock(&myLock);

counter++;
if (counter == 10) {
    pthread_cond_signal(&myCV);
}

pthread_mutex_unlock(&myLock);
```

- Key ideas
 - wait() on a CV releases the lock
 - signal() on a CV wakes up a thread waiting on the CV
 - The thread that wakes up has to re-acquire the lock before wait() returns

```
Mmmm... donuts
```

```
int theArray[ARRAY_SIZE], size;
   pthread_mutex_t theLock;
   pthread_cond_t theCV;
   /* Initialize */
Propre pthread_mutex_init(&theLock, NULL);
   pthread_condvar_init(&theCV, NULL);
   void put(int val) {
       pthread_mutex_lock(&theLock);
       while (size == ARRAY_SIZE) {
           pthread_cond_wait(&theCV,
                              &theLock);
       addItemToArray(val);
       size++;
       if (size == 1) {
           pthread_cond_signal(&theCV);
       pthread_mutex_unlock(&theLock);
```



What's wrong with this code?





```
int theArray[ARRAY_SIZE], size;
   pthread_mutex_t theLock;
   pthread_cond_t theCV;
   /* Initialize */
Propre pthread_mutex_init(&theLock, NULL);
   pthread_condvar_init(&theCV, NULL);
   void put(int val) {
       pthread_mutex_lock(&theLock);
       while (size == ARRAY_SIZE) {
           pthread_cond_wait(&theCV,
                              &theLock);
       addItemToArray(val);
       size++;
       if (size == 1) {
           pthread_cond_signal(&theCV);
       pthread_mutex_unlock(&theLock);
```

Assumes only a single thread calling put() or get() at a time!

If two threads call get(), then two threads call put(), only one will be woken up!!

onuts

```
int get() {
    int item;
    pthread_mutex_lock(&theLock);
    while (size == 0) {
        pthread_cond_wait(&theCV,
                          &theLock);
    item = getItemFromArray();
    size--;
    if (size == ARRAY_SIZE-1) {
        pthread_cond_signal(&theCV);
    pthread_mutex_unlock(&theLock);
    return item;
```

```
int theArray[ARRAY_SIZE], size;
  pthread_mutex_t theLock;
  pthread_cond_t theCV;
   /* Initialize */
Prdpthread_mutex_init(&theLock, NULL);
  pthread_condvar_init(&theCV, NULL);
   void put(int val) {
       pthread_mutex_lock(&theLock);
       while (size == ARRAY_SIZE) {
           pthread_cond_wait(&theCV,
                             &theLock);
       addItemToArray(val);
       size++;
       pthread_cond_signal(&theCV);
       pthread_mutex_unlock(&theLock);
```

One fix: always signal

Less efficient but OK.

onuts

```
int get() {
    int item;
    pthread_mutex_lock(&theLock);
    while (size == 0) {
        pthread_cond_wait(&theCV,
                          &theLock);
    item = getItemFromArray();
    size--;
    pthread_cond_signal(&theCV);
    pthread_mutex_unlock(&theLock);
    return item;
```

ARDLE

```
int theArray[ARRAY_SIZE], size;
  pthread_mutex_t theLock;
  pthread_cond_t theCV;
  /* Initialize */
pthread_condvar_init(&theCV, NULL);
  void put(int val) {
      pthread_mutex_lock(&theLock);
      while (size == ARRAY_SIZE) {
          pthread_cond_wait(&theCV,
                          &theLock);
      addItemToArray(val);
      size++;
      if (size == 1) {
       pthread_cond_broadcast(&theCV);
      pthread_mutex_unlock(&theLock);
```



Wakes up all threads when the condition changes. Note: Only one thread will grab the lock when it wakes up. The others wake up and immediately wait to acquire the lock again.



```
int get() {
    int item;
    pthread_mutex_lock(&theLock);
    while (size == 0) {
        pthread_cond_wait(&theCV,
                          &theLock);
    item = getItemFromArray();
    size--;
    if (size == ARRAY_SIZE-1) {
     pthread_cond_broadcast(&theCV);
    pthread_mutex_unlock(&theLock);
    return item;
```

Today

- Semaphores
- Condition variables
- Monitors

• Reading: 12.5

 A monitor uses this style of locks and condition variables to protect resources and coordinate threads


A monitor is an object containing variables, condition variables,


and methods

 At most one thread can be active in a monitor at a time


```
monitor M {
    int size, theArray[ARRAY_SIZE];
    ConditionVariable emptyFull;
    void put(int x) {
      if (size == ARRAY_SIZE) wait(emptyFull);
      theArray[size] = x;
      size++;
      if (size == 1) broadcast(emptyFull);
    int get() {
      if (size == 0) wait(emptyFull);
      size--;
      if (size == ARRAY_SIZE-1) broadcast(emptyFull);
      return theArray[size];
```


- 1) Blue thread enters monitor
- 2) Other threads queue up






- 1) Blue thread enters monitor
- 2) Other threads queue up
- 3) Blue thread waits on CV






- 1) Blue thread enters monitor
- 2) Other threads queue up
- 3) Blue thread waits on CV
- 4) Another thread can enter monitor






- 1) Blue thread enters monitor
- 2) Other threads queue up
- 3) Blue thread waits on CV
- 4) Another thread can enter monitor
- 5) Thread calls signal. What happens now?



Hoare vs. Mesa Monitor Semantics

- The monitor signal() operation can have two different meanings:
- Hoare monitors (1974)
 - signal(CV) means to run the waiting thread immediately
 - Effectively "hands the lock" to the thread just signaled.
 - Causes the signaling thread to block
- Mesa monitors (Xerox PARC, 1980)
 - signal(CV) puts waiting thread back onto the "ready queue" for the monitor
 - But, signaling thread keeps running.
 - Signaled thread doesn't get to run until it can acquire the lock.
 - This is what we almost always use so do Pthreads, Java, C#, etc.
- What's the practical difference?
 - In Hoare-style semantics, the "condition" that triggered the notify() will always be true when the awoken thread runs
 - For example, that the buffer is now no longer empty
 - In Mesa-style semantics, awoken thread has to recheck the condition
 - Since another thread might have beaten it to the punch

- 1) Blue thread enters monitor
- 2) Other threads queue up
- 3) Blue thread waits on CV
- 4) Another thread (pink) can enter monitor
- 5) Pink thread calls signal. What happens now?
- 6) Pink thread leaves monitor
- 7) Another thread can enter monitor (which depends on implementation)



Java thread synchronization

- Java uses a form of monitors
- Every object can be a lock and a condition variable
- A thread executing a method m of object o marked synchronized must acquire lock o before executing
- Given an object o, can call o.wait(), o.notify(),
 o.notifyAll()

Bounded buffer in Java

```
class BoundedBuffer {
    private int size;
    private int theArray[ARRAY_SIZE];
    private Object emptyFullSemaphore = new Object();
    public synchronized void put(int x) {
      while (size == ARRAY_SIZE) emptyFull.wait();
      theArray[size] = x;
      size++;
      if (size == 1) emptyFull.notifyAll();
    public synchronized int get() {
      while (size == 0) emptyFull.wait();
      size--:
      if (size == ARRAY_SIZE-1) emptyFull.notifyAll();
      return theArray[size];
```

Almost, not quite. Some subtleties in using wait and notify.

The Big Picture

- Getting synchronization right is hard!
 - Even your TFs and faculty have been known to get it wrong.
 - Testing isn't enough.
 - Need to assume worst case: all interleavings are possible
- We need to synchronize for correctness
 - Unsynchronized code can cause incorrect behavior
 - But too much synchronization means threads spend a lot of time waiting, not performing productive work.

The Big Picture

- How to choose between locks, semaphores, condition variables, monitors?
- Locks are very simple and suitable for many cases.
 - Issues: Maybe not the most efficient solution
 - For example, can't allow multiple readers but one writer inside a standard lock.
- Condition variables allow threads to sleep while holding a lock
 - Just be sure you understand whether they use Mesa or Hoare semantics!
- Semaphores provide pretty general functionality
 - But also make it really easy to botch things up.
- Monitors are a "pattern" for using locks and condition variables that is often very useful.

Next Lecture

- Famous problems in synchronization
- Race conditions, deadlock, and priority inversion