Nama: Listian Prihutomo


NIM: L200170175

Kelas: D

# Kegiatan Praktikum Modul VII

## **Kegiatan 1. Topologi 1 (Static Routing)**

1. Membuat topologi seperti gambar dibawah ini. Beri nama masing-masing router dengan Eagle(router 1), Puma(router 2) dan Tiger(router 3) serta beri nama masing-masing PC dengan Leo(PC 1), Aries(PC 2) dan Virgo(PC 3).



- 2. Konfigurasi masing-masing interface pada tiap Router dengan alamat IP berikut ini:
  - Eagle (ethernet 0) = 172.21.10.10/24

```
Router on term
Enter configuration commands, one per line. End with CNTL/Z.
Router (config) #int fa0/0
Router (config-if) #ip add 172.21.10.10 255.255.255.0
Router (config-if) #no shutdown

Router (config-if) #
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
```

- Eagle (serial 0) = 172.21.1.1/24 dan Eagle (serial 1) = 172.21.2.1/24Router(config-if)#int se2/0 Router(config-if)#clock rate 2000000 Router(config-if)#ip add 172.21.1.1 255.255.255.0 Router(config-if) #no shutdown %LINK-5-CHANGED: Interface Serial2/0, changed state to down Router(config-if)#int se3/0 Router(config-if)#clock rate 2000000 Router(config-if) #ip add 172.21.2.1 255.255.255.0 Router(config-if) #no shutdown %LINK-5-CHANGED: Interface Serial3/0, changed state to down Router(config-if)# %LINK-5-CHANGED: Interface Serial2/0, changed state to up %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up %LINK-5-CHANGED: Interface Serial3/0, changed state to up %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up - Puma (ethernet 0) = 172.21.20.20/24Router>en Router#conf term Enter configuration commands, one per line. End with CNTL/Z. Router(config)#int fa0/0 Router(config-if) #ip add 172.21.20.20 255.255.255.0 Router(config-if) #no shutdown Router(config-if)# %LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up - Puma (serial 0) = 172.21.1.2/24 dan Puma (serial 1) = 172.21.3.2/24Router(config-if) #int se2/0 Router(config-if)#ip add 172.21.1.2 255.255.255.0 Router(config-if) #no shutdown Router(config-if)# %LINK-5-CHANGED: Interface Serial2/0, changed state to up %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up Router(config-if) #int se3/0 Router(config-if)#clock rate 2000000 Router(config-if) #ip add 172.21.3.2 255.255.255.0 Router(config-if) #no shutdown %LINK-5-CHANGED: Interface Serial3/0, changed state to down Router(config-if)# %LINK-5-CHANGED: Interface Serial3/0, changed state to up %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0,

changed state to up

- Tiger (ethernet 0) = 172.21.30.30/24

```
Router configuration commands, one per line. End with CNTL/Z.

Router (config) #int fa0/0

Router (config-if) #ip add 172.21.30.30 255.255.255.0

Router (config-if) #no shutdown

Router (config-if) #


%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
```


- Tiger (serial 0) = 172.21.2.3/24 dan Tiger (serial 1) = 172.21.3.3/24

```
Router(config-if)#int se2/0
Router(config-if) #ip add 172.21.2.3 255.255.255.0
Router(config-if) #no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0,
changed state to up
Router(config-if)#int se3/0
Router(config-if)#ip add 172.21.3.3 255.255.255.0
Router(config-if) #no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0,
changed state to up
```


- 3. Konfigurasi masing-masing PC dengan alamat IP berikut ini:
  - Leo (PC 1) = 172.21.10.1/24 dan default gateway (ipconfig/dg) 172.21.10.10




- Aries (PC 2) = 172.21.20.2/24 dan default gateway (ipconfig/dg) 172.21.20.20




- Virgo (PC 3) = 172.21.30.3/24 dan default gateway (ipconfig/dg) 172.21.30.30




- 4. Langkah pengujian untuk memastikan kesesuaian konfigurasi.
  - Lakukan ping dari PC leo ke router eagle (172.21.1.1)



- Lakukan ping dari PC aries ke router puma (172.21.1.2)



- Lakukan ping dari PC virgo ke router tiger (172.21.3.3)



- Lakukan ping dari router eagle ke router puma (172.21.1.2)

```
Router*en
Router*ping 172.21.1.2

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.21.1.2, timeout is 2
seconds:
!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/3
ms
```

- Lakukan ping dari router eagle ke router tiger (172.21.2.3)

```
Router#ping 172.21.2.3

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 172.21.2.3, timeout is 2 seconds:
!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/4 ms
```

- Lakukan ping dari router puma ke router tiger (172.21.3.3)

```
Router*en
Router*ping 172.21.3.3

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.21.3.3, timeout is 2
seconds:
!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/4
ms
```

5. Simpan konfigurasi seluruh device yang telah dilakukan



- 6. Pada mode user atau mode privileged, lihat route pada masing-masing router
  - Eagle

```
Router>en
Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile,
B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter
area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external
type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E -
EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia -
IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
     172.21.0.0/24 is subnetted, 3 subnets
        172.21.1.0 is directly connected, Serial2/0
        172.21.2.0 is directly connected, Serial3/0
С
        172.21.10.0 is directly connected, FastEthernet0/0
```

- Puma

```
Router>en
Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile,
B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter
area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external
type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E -
EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia -
IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
     172.21.0.0/24 is subnetted, 3 subnets
        172.21.1.0 is directly connected, Serial2/0
C
        172.21.3.0 is directly connected, Serial3/0
        172.21.20.0 is directly connected, FastEthernet0/0
```

- Tiger

```
Router>en
Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile,
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter
area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external
type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E -
EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia -
IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
     172.21.0.0/24 is subnetted, 3 subnets
        172.21.2.0 is directly connected, Serial2/0
        172.21.3.0 is directly connected, Serial3/0
        172.21.30.0 is directly connected, FastEthernet0/0
```

7. Dari router eagle lakukan ping ke alamat interface e0 router puma (172.21.20.20)

```
Router#ping 172.21.20.20

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 172.21.20.20, timeout is 2 seconds:
....

Success rate is 0 percent (0/5)
```

#### 8. Dari PC leo lakukan trace ke PC aries

Packet Tracer PC Command Line 1.0 C:\>tracert 172.21.20.2 Tracing route to 172.21.20.2 over a maximum of 30 hops: 1 1 ms 0 ms 172.21.10.10 0 ms 172.21.10.10 2 ×. 0 ms 0 ms × × 3 0 ms Request timed out. 172.21.10.10 4 w 0 ms 0 ms 5 × 0 ×. Request timed out. ms 172.21.10.10 6 0 ms 0 ms 7 × 0 ms Request timed out. 172.21.10.10 8 0 ms 0 ms 9 3 ms Request timed out. 10 0 ms 0 ms 172.21.10.10 11 Request timed out. 0 ms 12 × 172.21.10.10 1 ms 0 ms 13 Request timed out. 0 ms \* 14 172.21.10.10 0 ms 1 ms 15 0 ms Request timed out. 16 0 ms × 0 ms 172.21.10.10 17 Request timed out. 0 ms 18 × 172.21.10.10 0 ms 1 ms 19 Request timed out. 0 ms 0 ms 0 ms 20 172.21.10.10 21 Request timed out. 0 ms 22 172.21.10.10 0 ms 0 ms 23 × Request timed out. 0 ms 24 × 172.21.10.10 0 ms 0 ms × 25 0 ms Request timed out. 172.21.10.10 26 w 0 ms 3 ms 27 0 ms Request timed out. 28 172.21.10.10 0 ms 0 ms 29 0 ms Request timed out. 172.21.10.10 30 0 ms 0 ms Trace complete.

9. Dari PC leo lakukan trace ke alamat interface s0 router eagle (172.21.1.1)

- 10. Pada mode user atau mode privileged, tambahkan route table pada masing-masing rote untuk setiap alamat jaringan yang tidak terhubung secara langsung dengan interface router
  - Eagle

```
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #ip route 172.21.20.20 255.255.255.0 172.21.1.2
%Inconsistent address and mask
Router(config) #ip route 172.21.20.0 255.255.255.0 172.21.1.2
Router(config) #ip route 172.21.30.0 255.255.255.0 172.21.2.3
Router(config) #ex
Router#
%SYS-5-CONFIG I: Configured from console by console
Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile,
B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter
area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external
type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E -
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia -
IS-IS inter area
        * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
     172.21.0.0/24 is subnetted, 5 subnets
С
        172.21.1.0 is directly connected, Serial2/0
С
        172.21.2.0 is directly connected, Serial3/0
C
        172.21.10.0 is directly connected, FastEthernet0/0
        172.21.20.0 [1/0] via 172.21.1.2
        172.21.30.0 [1/0] via 172.21.2.3
Puma
Router>en
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #ip route 172.21.10.0 255.255.255.0 172.21.1.1
Router(config) #ip route 172.21.30.0 255.255.255.0 172.21.3.3
Router(config)#ex
Router#
%SYS-5-CONFIG_I: Configured from console by console
Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile,
B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external
type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E -
EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia -
IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
```

Gateway of last resort is not set

```
172.21.0.0/24 is subnetted, 5 subnets
C
       172.21.1.0 is directly connected, Serial2/0
С
       172.21.3.0 is directly connected, Serial3/0
s
       172.21.10.0 [1/0] via 172.21.1.1
C
       172.21.20.0 is directly connected, FastEthernet0/0
       172.21.30.0 [1/0] via 172.21.3.3
```

Tiger


Router>en Router#conf term

```
Router(config) #ip route 172.21.20.0 255.255.255.0 172.21.3.2
       Router(config) #ex
       %SYS-5-CONFIG I: Configured from console by console
       Router#show ip route
       Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile,
            D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter
            N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external
       type 2
            E1 - OSPF external type 1, E2 - OSPF external type 2, E -
             i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia -
       IS-IS inter area
             * - candidate default, U - per-user static route, o - ODR
             P - periodic downloaded static route
       Gateway of last resort is not set
           172.21.0.0/24 is subnetted, 5 subnets
             172.21.2.0 is directly connected, Serial2/0
             172.21.3.0 is directly connected, Serial3/0
       С
             172.21.10.0 [1/0] via 172.21.2.1
             172.21.20.0 [1/0] via 172.21.3.2
       С
             172.21.30.0 is directly connected, FastEthernet0/0
11. Dari PC leo lakukan ping ke PC aries, dan lakukan pula trace dari PC leo ke aries
    C:\>ping 172.21.20.2
    Pinging 172.21.20.2 with 32 bytes of data:
    Reply from 172.21.20.2: bytes=32 time=4ms TTL=126
    Reply from 172.21.20.2: bytes=32 time=3ms TTL=126
    Reply from 172.21.20.2: bytes=32 time=1ms TTL=126
    Reply from 172.21.20.2: bytes=32 time=14ms TTL=126
    Ping statistics for 172.21.20.2:
         Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
         Minimum = 1ms, Maximum = 14ms, Average = 5ms
    C:\>tracert 172.21.20.2
    Tracing route to 172.21.20.2 over a maximum of 30 hops:
                        0 ms
                                     5 ms
                                                 172.21.10.10
           1 ms
      2
           5 ms
                        l ms
                                     0 ms
                                                 172.21.1.2
                        1 ms
                                     0 ms
                                                 172.21.20.2
           4 ms
    Trace complete.
```

Enter configuration commands, one per line. End with CNTL/Z. Router(config) #ip route 172.21.10.0 255.255.255.0 172.21.2.1

### **Kegiatan 2. RIP (Routing Information Protocol)**

1. Dari Packet Tracker, buka (load) topologi NetMap Kegiatan 1.



2. Pada mode configuration, konfigurasi roting RIP pada router eagle

```
Router>en
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#network 172.21.0.0
```

3. Lihat konfigurasi routing RIP yang telah dibuat dengan perintah "show running-config" pada mode user. Perhatikan konfigurasi pada bagian "router rip"

```
Router#show running-config
Building configuration...
                                            interface FastEthernet0/0
                                            ip address 172.21.10.10 255.255.255.0
Current configuration : 795 bytes
                                            duplex auto
                                            speed auto
version 12.2
                                           interface FastEthernet1/0
no service timestamps log datetime msec
                                                                                  Ī
                                            no ip address
no service timestamps debug datetime msec
                                            duplex auto
no service password-encryption
                                            speed auto
                                                                                  Ţ
hostname Router
                                            interface Serial2/0
                                                                                  Ţ
                                            ip address 172.21.1.1 255.255.255.0
                                            clock rate 2000000
                                            interface Serial3/0
                                                                                 line con 0
                                            ip address 172.21.2.1 255.255.255.0
                                            clock rate 2000000
                                                                                  Ţ
                                                                                 line aux 0
                                            interface FastEthernet4/0
                                            no ip address
ip cef
                                            shutdown
no ipv6 cef
                                                                                 line vty 0 4
                                            interface FastEthernet5/0
                                            no ip address
                                                                                   login
                                            shutdown
                                            router rip
                                            network 172.21.0.0
                                           ip classless
                                            ip flow-export version 9
                                                                                 end
```

4. Lihat proses update routing RIP pada router eagle dengan perintah "debug ip rip" pada mode user. Tunggu beberapa saat untuk melihat proses yang terjadi.

```
Router#debug ip rip
RIP protocol debugging is on
Router#
Router#RIP: sending v1 update to 255.255.255.255 via
FastEthernet0/0 (172.21.10.10)
RIP: build update entries
     network 172.21.1.0 metric 1
     network 172.21.2.0 metric 1
RIP: sending v1 update to 255.255.255.255 via Serial2/0
(172.21.1.1)
RIP: build update entries
     network 172.21.2.0 metric 1
     network 172.21.10.0 metric 1
RIP: sending v1 update to 255.255.255.255 via Serial3/0
(172.21.2.1)
RIP: build update entries
     network 172.21.1.0 metric 1
     network 172.21.10.0 metric 1
RIP: sending v1 update to 255.255.255.255 via FastEthernet0/0
(172.21.10.10)
RIP: build update entries
     network 172.21.1.0 metric 1
      network 172.21.2.0 metric 1
```

- 5. Lakukan konfigurasi routing RIP pada router puma dan tiger. Perhatikan proses update routing RIP pada router eagle ketika konfigurasi router puma dan tiger dilakukan.
  - Konfigurasi routing RIP Puma

```
Router>en
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #router rip
Router(config-router) #network 172.21.0.0
Router(config-router) #ex
Router(config) #ex
Router#show running-config
                                     interface FastEthernet0/0
Building configuration...
                                      ip address 172.21.20.20 255.255.255.0
                                      duplex auto
Current configuration : 775 bytes
                                      speed auto
                                     interface FastEthernet1/0
no service timestamps debug datetime msec duplex auto
                                                                        Ţ
no service password-encryption
                                       shutdown
hostname Router
                                      interface Serial2/0
                                       ip address 172.21.1.2 255.255.255.0
                                      interface Serial3/0
                                       ip address 172.21.3.2 255.255.255.0
                                       clock rate 2000000
                                      interface FastEthernet4/0
                                                                        line con 0
                                      no ip address
ip cef
                                                                        line aux 0
                                      interface FastEthernet5/0
no ipv6 cef
                                      no ip address
                                       shutdown
                                                                        line vty 0 4
                                                                         login
                                      router rip
                                       network 172.21.0.0
                                                                        Ţ
                                                                        Ţ
                                                                        Ţ
                                      ip flow-export version 9
                                                                        end
```

#### - Update router RIP Puma

```
Router#debug ip rip
RIP protocol debugging is on
Router#RIP: received vl update from 172.21.1.1 on Serial2/0
      172.21.2.0 in 1 hops
      172.21.10.0 in 1 hops
RIP: sending v1 update to 255.255.255.255 via FastEthernet0/0
 (172.21.20.20)
RIP: build update entries
      network 172.21.1.0 metric 1
      network 172.21.2.0 metric 2
      network 172.21.3.0 metric 1
      network 172.21.10.0 metric 2
RIP: sending v1 update to 255.255.255.255 via Serial2/0
 (172.21.1.2)
RIP: build update entries
      network 172.21.3.0 metric 1
      network 172.21.20.0 metric 1
RIP: sending v1 update to 255.255.255.255 via Serial3/0
(172.21.3.2)
RIP: build update entries
      network 172.21.1.0 metric 1
      network 172.21.2.0 metric 2
      network 172.21.10.0 metric 2
      network 172.21.20.0 metric 1
```

### - Konfigurasi routing RIP Tiger

```
Router en
Router configuration commands, one per line. End with CNTL/Z.
Router (config) #router rip
Router (config - router) #network 172.21.0.0
Router (config - router) #ex
Router (config) #ex
```

```
interface FastEthernet0/0
Router#show running-config
                                         ip address 172.21.30.30 255.255.255.0
Building configuration...
                                         duplex auto
                                         speed auto
Current configuration : 755 bytes
                                        interface FastEthernet1/0
version 12.2
                                        no ip address
no service timestamps log datetime msec
                                         duplex auto
no service timestamps debug datetime msec speed auto
no service password-encryption
                                         shutdown
hostname Router
                                        interface Serial2/0
                                         ip address 172.21.2.3 255.255.255.0
                                        interface Serial3/0
                                         ip address 172.21.3.3 255.255.255.0
                                        interface FastEthernet4/0
                                                                               line con 0
                                         no ip address
                                                                               Ţ
                                         shutdown
ip cef
                                                                               line aux 0
no ipv6 cef
                                        interface FastEthernet5/0
                                         no ip address
                                         shutdown
                                                                               line vty 0 4
                                        router rip
                                                                                login
                                         network 172.21.0.0
                                                                               Ţ
                                        ip classless
                                                                               Ţ
                                        ip flow-export version 9
                                                                               ı
                                                                               end
```

#### - Update router RIP Tiger

```
Router#debug ip rip
RIP protocol debugging is on
Router#RIP: received v1 update from 172.21.3.2 on Serial3/0
      172.21.1.0 in 1 hops
      172.21.10.0 in 2 hops
      172.21.20.0 in 1 hops
RIP: sending vl update to 255.255.255.255 via FastEthernet0/0
(172.21.30.30)
RIP: build update entries
     network 172.21.1.0 metric 2
     network 172.21.2.0 metric 1
     network 172.21.3.0 metric 1
     network 172.21.10.0 metric 2
     network 172.21.20.0 metric 2
RIP: sending v1 update to 255.255.255.255 via Serial2/0
(172.21.2.3)
RIP: build update entries
      network 172.21.3.0 metric 1
      network 172.21.20.0 metric 2
      network 172.21.30.0 metric 1
RIP: sending v1 update to 255.255.255.255 via Serial3/0
(172.21.3.3)
RIP: build update entries
     network 172.21.2.0 metric 1
     network 172.21.10.0 metric 2
      network 172.21.30.0 metric 1
Router#no debug ip RIP: received v1 update from 172.21.2.1 on
Serial2/0
      172.21.1.0 in 1 hops
      172.21.10.0 in 1 hops
      172.21.20.0 in 2 hops
```

- % Incomplete command.
- 6. Dari PC leo lakukan trace ke PC aries


```
Packet Tracer PC Command Line 1.0
C:\>tracert 172.21.20.2
Tracing route to 172.21.20.2 over a maximum of 30 hops:
     10 ms
                0 ms
                          0 ms
                                    172.21.10.10
      1 ms
                          1 ms
                                    172.21.1.2
  2
                0 ms
  3
                0 ms
                          0 ms
                                    172.21.20.2
Trace complete.
```

7. Buat hubungan antara router eagle dan puma terputus dan perhatikan proses update routing RIP yang terjadi.

```
Router term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) int se2/0
Router(config-if) shutdown

Router(config-if) 
%LINK-5-CHANGED: Interface Serial2/0, changed state to administratively down

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to down
```




8. Dari PC leo lakukan trace ke PC aries

```
C:\>tracert 172.21.20.2
Tracing route to 172.21.20.2 over a maximum of 30 hops:
                                     172.21.10.10
                0 ms
                           0 ms
  2
      1 ms
                1 ms
                           4 ms
                                     172.21.2.3
  3
      10 ms
                1 ms
                           6 ms
                                     172.21.3.2
                14 ms
                           13 ms
                                     172.21.20.2
Trace complete.
```

### Kegiatan 3. EIGRP (Interior Gateway Routing Protocol)

1. Dari Packet Tracker, buka (load) topologi NetMap Kegiatan 1



2. Pada mode configuration, konfigurasi routing RIP pada router eagle

```
Router>en
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router eigrp 100
Router(config-router)#network 172.21.0.0
```

3. Lihat konfigurasi routing EIGRP yang telah dibuat dengan perintah "show running-config" pada mode user. Perhatikan pada bagian "router RIP"

```
Router#show running-config
                                           interface FastEthernet1/0
Building configuration...
                                            no ip address
                                            duplex auto
Current configuration: 815 bytes
                                            speed auto
                                            shutdown
version 12.2
no service timestamps log datetime msec
                                           interface Serial2/0
no service timestamps debug datetime msec
                                            ip address 172.21.1.1 255.255.255.0
no service password-encryption
                                            clock rate 2000000
hostname Router
                                           interface Serial3/0
                                            ip address 172.21.2.1 255.255.255.0
                                            clock rate 2000000
                                           interface FastEthernet4/0
                                            no ip address
                                            shutdown
                                           interface FastEthernet5/0
ip cef
                                            no ip address
no ipv6 cef
                                            shutdown
                                                                                   line con 0
                                           router eigrp 100
                                            network 172.21.0.0
                                                                                   line aux 0
                                            auto-summary
                                                                                   1
                                                                                   line vty 0 4
                                           ip classless
                                                                                    login
                                           ip flow-export version 9
                                                                                   Ţ
                                                                                   ı
                                                                                   end
```

4. Lihat proses transaksi routing EIGRP pada router eagle dengan perintah "debug eigrp packets"

```
Router#debug eigrp packet
EIGRP Packets debugging is on
        (UPDATE, REQUEST, QUERY, REPLY, HELLO, ACK)
Router#
EIGRP: Sending HELLO on Serial3/0
    AS 100, Flags 0x0, Seq 1/0 idbQ 0/0 iidbQ un/rely 0/0
EIGRP: Sending HELLO on Serial2/0
    AS 100, Flags 0x0, Seq 1/0 idbQ 0/0 iidbQ un/rely 0/0
EIGRP: Sending HELLO on FastEthernet0/0
    AS 100, Flags 0x0, Seq 1/0 idbQ 0/0 iidbQ un/rely 0/0
```

- 5. Lakukan konfigurasi routing EIGRP pada router puma dan tiger
  - Konfigurasi routing EIGRP Puma

```
Router>en
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #router eigrp 100
Router(config-router) #network 172.21.0.0
Router(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 100: Neighbor 172.21.1.1 (Serial2/0)
is up: new adjacency
                                       interface FastEthernet0/0
                                        ip address 172.21.20.20 255.255.255.0
Router#show running-config
                                        duplex auto
Building configuration...
                                        speed auto
Current configuration : 795 bytes
                                      interface FastEthernet1/0
                                        no ip address
version 12.2
                                        duplex auto
no service timestamps log datetime msec
                                        speed auto
no service timestamps debug datetime msec
                                        shutdown
no service password-encryption
                                       interface Serial2/0
hostname Router
                                        ip address 172.21.1.2 255.255.255.0
                                       interface Serial3/0
                                        ip address 172.21.3.2 255.255.255.0
                                        clock rate 2000000
                                       interface FastEthernet4/0
                                        no ip address
                                        shutdown
ip cef
                                       interface FastEthernet5/0
no ipv6 cef
                                        no ip address
                                                                            line con 0
                                        shutdown
                                                                            line aux 0
                                       router eigrp 100
                                        network 172.21.0.0
                                                                            line vty 0 4
                                        auto-summary
                                                                            login
                                                                            I
                                       ip classless
                                        ip flow-export version 9
                                                                            end
```

```
- Update pada routing EIGRP Puma
    Router#debug eigrp packets
    EIGRP Packets debugging is on
         (UPDATE, REQUEST, QUERY, REPLY, HELLO, ACK )
    EIGRP: Sending HELLO on FastEthernet0/0
      AS 100, Flags 0x0, Seg 6/0 idbQ 0/0 iidbQ un/rely 0/0
    EIGRP: Sending HELLO on Serial3/0
      AS 100, Flags 0x0, Seq 6/0 idbQ 0/0 iidbQ un/rely 0/0
    EIGRP: Sending HELLO on Serial2/0
      AS 100, Flags 0x0, Seq 6/0 idbQ 0/0 iidbQ un/rely 0/0
    EIGRP: Received HELLO on Serial2/0 nbr 172.21.1.1
      AS 100, Flags 0x0, Seq 6/0 idbQ 0/0
- Konfigurasi routing EIGRP Tiger
    Router>en
    Router#conf term
    Enter configuration commands, one per line. End with CNTL/Z.
    Router(config) #router eirgp 100
    % Invalid input detected at '^' marker.
    Router(config) #router eigrp 100
    Router(config-router) #network172.21.0.0
    % Invalid input detected at '^' marker.
    Router(config-router) #network 172.21.0.0
    Router(config-router)#
    %DUAL-5-NBRCHANGE: IP-EIGRP 100: Neighbor 172.21.3.2 (Serial3/0)
    is up: new adjacency
    %DUAL-5-NBRCHANGE: IP-EIGRP 100: Neighbor 172.21.2.1 (Serial2/0)
    is up: new adjacency
    Router#show running-config
                                       interface FastEthernet0/0
    Building configuration...
                                         ip address 172.21.30.30 255.255.255.0
                                          duplex auto
    Current configuration : 775 bytes
                                          speed auto
                                        interface FastEthernet1/0
                                         no ip address
    no service timestamps log datetime msec
    no service timestamps debug datetime msec — duplex auto
                                          speed auto
    no service password-encryption
                                          shutdown
    hostname Router
                                         interface Serial2/0
                                          ip address 172.21.2.3 255.255.255.0
                                         interface Serial3/0
                                          ip address 172.21.3.3 255.255.255.0
                                         interface FastEthernet4/0
                                         no ip address
                                          shutdown
    ip cef
                                                                               line con 0
                                         interface FastEthernet5/0
    no ipv6 cef
                                         no ip address
                                          shutdown
                                                                               line aux 0
                                         router eigrp 100
                                                                              line vty 0 4
                                          network 172.21.0.0
                                          auto-summary
                                                                               login
                                         ip classless
                                                                               ı
                                         ip flow-export version 9
                                                                               I
```

end

- Update pada routing EIGRP Tiger

6. Dari PC leo lakukan trace ke PC aries

```
Packet Tracer PC Command Line 1.0
C:\>tracert 172.21.20.2

Tracing route to 172.21.20.2 over a maximum of 30 hops:

1 25 ms 0 ms 0 ms 172.21.10.10
2 1 ms 4 ms 0 ms 172.21.1.2
3 * 0 ms 3 ms 172.21.20.2

Trace complete.
```

7. Buat hubungan antara router eagle dan puma terputus dan perhatikan proses update routing RIP yang terjadi

```
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int se2/0
Router(config-if) #shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to
administratively down
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0,
changed state to down
%DUAL-5-NBRCHANGE: IP-EIGRP 100: Neighbor 172.21.1.1 (Serial2/0)
is down: interface down
Router#debug eigrp packets
EIGRP Packets debugging is on
    (UPDATE, REQUEST, QUERY, REPLY, HELLO, ACK )
Router#
EIGRP: Received HELLO on Serial3/0 nbr 172.21.3.3
  AS 100, Flags 0x0, Seg 16/0 idbQ 0/0
EIGRP: Sending HELLO on FastEthernet0/0
  AS 100, Flags 0x0, Seq 16/0 idbQ 0/0 iidbQ un/rely 0/0
EIGRP: Sending HELLO on Serial3/0
  AS 100, Flags 0x0, Seq 16/0 idbQ 0/0 iidbQ un/rely 0/0
```

8. Dari PC leo lakukan trace ke PC aries

```
C:\>tracert 172.21.20.2
Tracing route to 172.21.20.2 over a maximum of 30 hops:
     0 ms
               0 ms
                         0 ms
                                   172.21.10.10
     0 ms
               1 ms
                         1 ms
                                  172.21.2.3
     2 ms
               5 ms
                                   172.21.3.2
                         0 ms
                         11 ms
                                   172.21.20.2
Trace complete.
```