
LA AURA POS

User Manual

A complete guide to selling, managing your catalog, and running your store — for Cashiers, Managers, Reporters, and Administrators.

Version 1.0 · July 2026

Contents

1. Welcome to La Aura POS	4
Who this manual is for	4
2. Getting Started	5
Signing in	5
Signing out	5
3. Finding Your Way Around	6
The account menu	6
4. Ringing Up a Sale	7
4.1 Finding a product	7
4.2 Adding an item to the cart	7
4.3 Managing the cart	7
4.4 Discount, tax, and payment	7
4.5 Attaching a customer (optional)	7
4.6 Completing the sale	8
5. Managing Products & Categories	9
5.1 The products list	9
5.2 Adding or editing a product	9
5.3 Deleting a product	10
5.4 Categories	10
6. Managing Customers	11
7. Viewing Transactions	12
7.1 Filtering the list	12
7.2 Viewing a transaction	12
7.3 Voiding or refunding a sale	12
8. Dashboard & Reporting	13
8.1 Home dashboard	13
8.2 Reporting	13

8.3 Exporting a PDF report	13
9. Managing User Accounts	14
10. The Audit Log	15
11. Language & Appearance	16
11.1 Switching language	16
11.2 Switching theme	16
12. Quick Reference: Roles & Permissions	17
13. Troubleshooting & FAQ	18

INTRODUCTION

1. Welcome to La Aura POS

La Aura POS is your store's point-of-sale system. It covers everything from ringing up a sale at the counter to managing your product catalog, tracking transactions, and reviewing sales performance. This manual walks through every screen in the app so any team member — new or experienced — can find their way around confidently.

The app works equally well in **English** and **Arabic** (with full right-to-left layout), and supports both a **light** and a **dark** theme. See **Chapter 11 — Language & Appearance** for how to switch.

Who this manual is for

Everyone who uses La Aura POS has a **role**, and the role determines what they can see and do. This manual is organized so you can read only the chapters relevant to your role, or read cover to cover if you manage the whole store.

Role	Typical user	What they mainly do
Cashier	Front-of-house staff	Ring up sales, look up past transactions (view only), manage the customer list.
Manager	Shift or store manager	Everything a Cashier does, plus manage products/categories, view the dashboard and reports, and void or refund sales.
Reporter	Owner, accountant, analyst	Read-only access to the dashboard, reports, and transaction history — no selling or catalog editing.
Admin	Store owner / IT administrator	Full access: everything above, plus managing user accounts and the audit log.

TIP Not sure what your role is?

Ask your store administrator, or check the bottom of the navigation menu — your name and role are always shown there.

GETTING STARTED

2. Getting Started

Signing in

1. Open La Aura POS in your web browser.
2. Enter the **email address** and **password** given to you by your administrator.
3. Select **Sign in**.

Once signed in, you're taken straight to the screen that matches your role: Cashiers and Managers land on the **Sell** screen or the **Home** dashboard; Reporters land on the **Home** dashboard.

TIP **Forgot your password?**

La Aura POS does not have a self-service “forgot password” flow yet. Ask an Administrator to open your account under **Users** and set a new password for you.

Signing out

Open the navigation menu and select **Log out** at the bottom, under your name. Always sign out when you step away from a shared till.

NAVIGATION

3. Finding Your Way Around

The left-hand sidebar (on mobile, tap the menu icon in the top-left corner) lists every section you have access to. Sections you don't have permission for simply don't appear.

Menu item	Takes you to
Home	The store's sales dashboard — today's numbers at a glance.
Sell	The point-of-sale screen where you ring up purchases.
Reporting	Deeper sales analytics: best sellers, cashier performance, insights.
Transactions	A searchable history of every sale, with full detail.
Catalog	Manage products and categories.
Customers	The customer directory used at checkout.
Users	Create and manage staff accounts (Admin only).
Audit Log	A record of every sign-in, sale, and change made in the system (Admin only).

The account menu

At the bottom of the sidebar you'll find, in order: a language switch (EN / عربي), a light/dark theme switch, your name and role, and the **Log out** button.

CASHIER · MANAGER

4. Ringing Up a Sale

The **Sell** screen is where every transaction happens. It has three parts: the product grid on the left, the cart in the middle, and the payment panel below the cart.

4.1 Finding a product

- Use the **search box** to find a product by name, SKU, or barcode.
- Or tap a **category chip** (e.g. “Coffee Drinks”, “Snacks”) to filter the grid; tap **All** to clear the filter.
- Each tile shows the product photo (if one was uploaded), its SKU, price, and remaining stock. Products that are out of stock are dimmed and can't be tapped.

4.2 Adding an item to the cart

Tap a product tile. What happens next depends on the product:

- **Simple product** (no sizes or extras) — it's added straight to the cart at quantity 1.
- **Product with sizes and/or extras** — a picker opens first. Choose a **size** (e.g. Small / Medium / Large, each with its own price), tick any **extras** you want to add (e.g. an extra shot, oat milk — each adds its own price), then select **Add to cart**.

4.3 Managing the cart

- Use the – and + buttons next to a line to change its quantity.
- Select the small trash icon to remove a line entirely.
- The selected size and any extras are shown under the product name, and are priced into that line automatically.

4.4 Discount, tax, and payment

- Enter a flat **Discount** amount and/or **Tax** amount if this sale needs one.
- Choose the **payment method**: Cash, Card, Mobile Money, or Other.
- The Subtotal, Discount, Tax, and Total update live as you build the cart.

TIP Totals are always double-checked by the server

Whatever appears on screen is a preview. When you select **Complete Sale**, the server recalculates the total from the actual product prices — this protects the store from a stale price or a tampered total ever being charged.

4.5 Attaching a customer (optional)

By default, a sale is recorded for a **Walk-in customer**. To attach it to someone in your customer directory instead, select the customer chip above the cart, then search for and choose their name. See **Chapter 6 — Customers** to add a new customer first.

4.6 Completing the sale

1. Review the cart and totals.
2. Select **Complete Sale**.
3. A receipt appears with a unique reference number (e.g. SALE-20260710-4EE5260C), the items sold, and the total paid.
4. Select **New Sale** to clear the cart and start the next transaction.

MANAGER · ADMIN

5. Managing Products & Categories

Open **Catalog** from the sidebar. It has two tabs: **Products** and **Categories**.

5.1 The products list

- Search by name, SKU, or barcode using the search box.
- Select a column heading (Name, SKU, Price, Stock) to sort by it; select again to reverse the order.
- Each row shows a thumbnail, name, SKU, category, price, and a stock badge (in stock / low stock / out of stock).
- Tap anywhere on a row to open its full detail view.
- Tick the checkboxes on the left to select multiple products, then use the toolbar that appears to delete them all at once.

5.2 Adding or editing a product

Select **New Product**, or open a product and select **Edit**. The form is organized into three parts:

About product

- **Product photo** — optional; shown on the Sell screen and Products list.
- **Name** (required) and **Arabic name** (optional) — the Arabic name is shown automatically to anyone using the app in Arabic; if it's left blank, the English name is shown instead so nothing ever appears empty.
- **SKU** (required, must be unique) and **Barcode** (optional).
- **Price** and **Stock** — the price used when the product has no sizes, and the quantity currently on hand.
- **Category** — optional; used for filtering on the Sell screen and in this list.

Sizes (optional)

Add one row per size (e.g. Small, Medium, Large), each with its own name, optional Arabic name, and price. If a product has any sizes, the cashier must choose one when selling it — the base Price field above is then only used for products with no sizes.

Extras (optional)

Add one row per optional add-on (e.g. Extra shot, Oat milk), each with its own name, optional Arabic name, and price. Cashiers can tick any number of extras when selling this product.

TIP Arabic names are optional everywhere

You never have to fill in an Arabic name to save a product, size, or extra. Anything left blank simply falls back to showing the English name when the app is switched to Arabic.

5.3 Deleting a product

Select the trash icon on a row (or select multiple rows and use the bulk delete button), then confirm. Deleting a product does not remove it from past sales records — historical transactions and reports are unaffected.

5.4 Categories

Switch to the **Categories** tab to add, rename, or remove categories. Each category has a **Name** and an optional **Arabic name**, exactly like products. A category that still has products assigned to it can't be deleted — reassign or remove those products first.

CASHIER · MANAGER

6. Managing Customers

Open **Customers** from the sidebar to view the store's customer directory.

1. Select **New Customer** to add someone — enter their **Full name** and **Phone number**, then **Save**.
2. Use the search box to find an existing customer by name or phone.
3. Select the pencil icon to edit a customer's details, or the trash icon to remove them.

Customers you add here immediately become available to attach to a sale from the Sell screen (see **4.5 — Attaching a customer**).

CASHIER · MANAGER · REPORTER · ADMIN

7. Viewing Transactions

Open **Transactions** from the sidebar to see every sale ever recorded, newest first.

7.1 Filtering the list

- Search by reference number, seller, customer name, or item.
- Filter by **payment method** or **status** (Completed, Voided, Refunded).
- Narrow the results to a specific date range using the **From** / **to** date fields.

7.2 Viewing a transaction

Select any row (or the eye icon at the end of the row) to open its full detail: who sold it and when, the customer, every item with its size and extras, and the subtotal, discount, tax, and grand total.

7.3 Voiding or refunding a sale

IMPORTANT Cashiers have read-only access to Transactions

Cashiers can search, filter, and open any transaction to see full detail — exactly like a Manager can — but the **Void** and **Refund** actions are only available to Managers and Admins. If you're signed in as a Cashier, you simply won't see those buttons; there is nothing to configure.

For Managers and Admins: open a completed sale and select **Refund** or **Void**. You can optionally record a reason. Voiding or refunding a sale automatically returns the sold items back into stock and is recorded in the Audit Log.

MANAGER · REPORTER · ADMIN

8. Dashboard & Reporting

8.1 Home dashboard

The **Home** screen gives a quick snapshot of how the store is doing. Use the **Today / This week / This month** toggle at the top to change the time range shown across every card:

- **Sales summary** — total sold in the period, compared with the previous equivalent period, plus average sale value and average items per sale.
- **Sales trend** — a chart of sales over the period, plus total transactions and items sold.
- **Low stock** — products running low, with a shortcut to the Catalog to restock them.
- **Recent sales** — the last five sales across the whole store, regardless of the date range selected.

8.2 Reporting

The **Reporting** screen goes deeper, using the same Today / This week / This month toggle:

- **Sales trend** — the same period chart, with transactions, items sold, and average sale.
- **Slow movers** — the products selling the least in this period.
- **Best sellers by revenue** — a chart of your top five earners.
- **Cashier performance** — sales count and revenue per cashier.
- **Areas for improvement** — dead stock (nothing sold, still on the shelf), stockout risk (selling fast and running low), and how often discounts are used.

8.3 Exporting a PDF report

Select **Export PDF** at the top of the Reporting screen to download a printable copy of the current report — useful for sharing with an owner or accountant who doesn't have a login.

ADMIN ONLY

9. Managing User Accounts

Open **Users** from the sidebar to create and manage staff accounts.

1. Select **New User**.
2. Enter their **Full name**, **Email**, and a temporary **Password**.
3. Choose their **Role**: Admin, Manager, Cashier, or Reporter (see the table in **Chapter 1** for what each role can do).
4. Select **Save**.

To stop someone from signing in without deleting their history, open their row and select **Deactivate** — this can be reversed at any time. Select the pencil icon on a row to edit a name, email, role, or reset a password.

ADMIN ONLY

10. The Audit Log

The **Audit Log** is a complete, unchangeable record of activity in La Aura POS: every sign-in, every sale, every product or user that was created, edited, or removed — who did it, when, and from which IP address.

Use the filters at the top to narrow the log to a specific type of action or a specific user, and select any row to see full details of what changed. This is the first place to look if something in the store's data looks wrong and you need to know who touched it.

EVERY ROLE

11. Language & Appearance

11.1 Switching language

La Aura POS is fully bilingual. In the sidebar (or the menu on mobile), select **EN** for English or **عربي** for Arabic. Switching to Arabic mirrors the entire layout right-to-left and shows Arabic product, category, size, and extra names wherever an administrator has entered them — anything without an Arabic name simply shows in English.

11.2 Switching theme

Select **Light** or **Dark** in the sidebar to change the app's appearance. This is a personal preference saved to your device and doesn't affect other users.

SUMMARY

12. Quick Reference: Roles & Permissions

A consolidated view of what each role can access. A checkmark (✓) means full access; “View only” means the screen is visible but nothing can be changed from it.

Screen / action	Cashier	Manager	Reporter	Admin
Sell (ring up sales)	✓	✓	—	✓
Customers	✓	✓	—	✓
Transactions — view	✓	✓	✓	✓
Transactions — void / refund	—	✓	—	✓
Home dashboard	—	✓	✓	✓
Reporting	—	✓	✓	✓
Catalog (products & categories)	—	✓	—	✓
Users	—	—	—	✓
Audit Log	—	—	—	✓

HELP

13. Troubleshooting & FAQ

A menu item I need is missing.

Menu items are shown based on your role. Check Chapter 1 and Chapter 12 to see what your role includes, and ask an Administrator to change your role if needed.

I can't void or refund a sale.

Only Managers and Admins can void or refund. If you're a Cashier, this is expected — see 7.3. Ask a Manager or Admin to do it for you.

A product or category shows in English even though I set an Arabic name.

Double-check the Arabic name field was saved on that exact item — sizes and extras each have their own separate Arabic name field, in addition to the product's own.

The total on screen doesn't match what I expected.

The number shown while building a cart is a live preview. The final charge is always recalculated by the server from current prices when you select Complete Sale, so a stale screen or a slow connection can never cause an incorrect charge.

A product I deleted still shows up in old sales.

This is expected and intentional — deleting a product only removes it from the catalog going forward. Historical transactions always keep the exact name and price recorded at the time of sale.

I forgot my password.

Ask an Administrator to reset it for you from the Users screen (see Chapter 9).

Still stuck? Contact your store administrator, who can review the Audit Log to see exactly what happened and when.