

Setup for Unity URP Projects

In your Unity URP Project:

0. Place a plane in your scene and reset the transform values.
1. Install the XR Interaction Toolkit v.3.1.2 (Window -> Package Management -> Package Manager -> Unity Registry -> Search for XR Interaction Toolkit -> click Install). After this step, import the XR Interaction Toolkit Starter Assets in the same window under Samples (click on "fix all" if the Project Validation Tab opens), place the XR Origin (the one with controllers) in your scene, and reset its transform values. Also disable or remove the Main Camera in/from your scene.
2. Install Animation Rigging v.1.3.0 (Window -> Package Management -> Package Manager -> Unity Registry -> Search for Animation Rigging).
3. Make sure the Genesis9RigSetup (Singleplayer)/Genesis9NormcoreRigSetup (for multiplayer) scripts are in your project in Assets/Editor.
4. Make sure you have the Animations Folder (inside the Unity Assets Folder) with the following files:
 1. Left Hand Default Pose
 2. Left Hand Grab Pose
 3. Left Hand Mask
 4. Left Hand Pinch Pose
 5. Right Hand Default Pose
 6. Right Hand Grab Pose
 7. Right Hand Mask
 8. Right Hand Pinch Pose
 9. VR Rig Animator
5. Make sure you have Daz3d installed and an account.
6. Make sure you have the IKFootSolver, AnimateOnInput, and IKTargetFollowVRRig scripts in your project inside the Unity Assets Folder.
7. Make sure you installed the XR Plugin Management (in Project Settings) and did the setup according to your needs.
8. If an error in ReadmeEditor.cs line 11 occurs, change Editor to UnityEditor.Editor.

Installing Daz3D Unity Bridge:

0. Open your Unity project (in the background).
1. Go to daz3d.com.
2. Search for "Daz to Unity Bridge".
3. Click the entry "Daz to Unity Bridge".
4. Click "Add to cart".
5. Click "view cart & checkout".
6. Log in with your account and place an order.
7. Open the DAZ Install Manager and search for "DAZ to Unity Bridge."
8. Click on "Ready to Download".
9. Click on "Download" next to the entry "DAZ to Unity Bridge."
10. After the download is completed, open Daz Studio.
11. On the top left, click File -> Send To -> Daz to Unity.
12. If the Unity project already exists, check Advanced Settings (if unchecked in the Window).
13. In the Unity Plugin Installer, select the Unity Version and Rendering Pipeline corresponding to your existing Unity project (2020+ URP).
14. Click on Install Plugin and navigate to your Unity Project and click "Select Folder".
15. A Unity Bridge Plugin Installer window should pop up, indicating to switch to the Unity Project.
16. In the Unity Project, an Import Window will appear. Click on Import.
17. Multiple Errors (check console): Change in ClothCollisionAssignerEditor.cs in line 8 Editor to UnityEditor.Editor, ClothToolsEditor.cs in line 9 Editor to UnityEditor.Editor and DTUConverter.cs line 2945 to public class DTUConverter.
18. The Script Updating Consent Window will open: Click on "Yes, for these files and others that might be found later".
19. Two JSON errors will occur. Search in your project folder for Simple JSON (Assembly Definition Asset); in the Inspector, uncheck the "Auto Referenced" box, scroll down, and click Apply.
17. A Daz3D option is now available in the menu bar in Unity.

18. If you click on it and on "Open DazToUnity Bridge window", the Daz To Unity Bridge Window should appear.
19. The bridge is now installed.

DAZ3D Avatar to Unity

0. Open your Unity Project.
1. In DAZ3D, open your created Avatar.
2. Click on File (top left) -> Send To -> Daz To Unity.
3. In the DazToUnity Bridge Window, select the Assets Folder of your Unity Project (DAZ3D will know that this is a new Unity Project and automatically check the option "Overwrite Unity Files").
4. Make sure that the Asset Type is set to Skeletal Mesh.
5. Click on Accept.
6. After the export phase, a pop-up will appear, notifying you to switch to your Unity project.
7. Click on Ok.
8. In Unity, an import window will open. After the import, you may be asked to update the API scripts. Click on "Yes, for these files and others that might be found later".
9. The Daz to Unity Window will appear and import the avatar to your project.
10. The avatar should now be in the Unity Scene.
11. In the Project Tab, look for Daz3D and unfold it. Unfold the entry "TheNameOfYourAvatar" and scroll to the prefab "TheNameOfYourAvatar" and click on it.
12. The Inspector with the Avatar Prefab selected will show the "TheNameOfYourAvatar" Import Settings.
13. Click on Rig -> Animation Type -> Humanoid -> Apply.
14. Search for the Unity Avatar Type of your DAZ3D Avatar (named as "TheNameOfYourAvatar" Avatar).
15. Click on "Configure Avatar" in the Inspector View with your "TheNameOfYourAvatar" Avatar (Avatar) selected.
16. In the Mapping Tab under Optional Bone, click on Hand under Left Arm and set the Rotation Z to -36.828. Next, the Hand under Right Arm and set Rotation Z to 44.465. Scroll down and click on Apply.
17. With the Avatar in the Scene selected, add the VR Rig Animator to the Controller slot in the Inspector.
18. With the Avatar in the Scene selected, click on Tools in the Unity Bar and "Setup Genesis 9 VR Rig Full" (without Normcore) or "Setup Genesis 9 Rig for Normcore".
19. Your avatar is now rigged and ready to use in your VR scene.