



MARKER CORNER · STAMP, CLIP TAB, LEGIBILITY TAB, LOGO

The corner holds four things.

Every one of them wants the slide's top-right. This deck renders the collision, because the arithmetic that keeps them apart has been wrong four times and every version of it passed CI.



Three are engine chrome. The fourth is yours.

- The status stamp
 - `confidential` and its shape variants paint on the section's own `::before`, flush to the corner.
- The clip tab
 - The overflow marker, reserving a row below whichever stamp is present.
- The legibility tab
 - The type-floor alarm, one row below the clip tab. Authoring only.
- The deck logo
 - The author's mark, at the frame inset — inside the tabs' band.

The first three have engine-owned geometry. The fourth does not.



Quarterly program review for the regional distribution network and its downstream partners across four operating

Throughput

Median order-to-dock time fell from 41 hours to 26 hours.

Cost

Unit handling cost is down 12% year over year.

Quarterly program review for the regional distribution network and its downstream partners across four operating



Throughput

Median order-to-dock time fell from 41 hours to 26 hours.

Cost

Unit handling cost is down 12% year over year.



Clearing the mark downward would put chrome in the body.

Stacking the tab below the logo needs about eighty pixels of drop, which lands a marker a third of the way into the slide — where no component expects it.

Horizontal keeps every occupant inside the top band, so nothing has to rule on whether a transient marker outranks permanent branding.

`logo:` plus `confidential` is close to the modal delivered board deck, and this is the reader register: the one the whole marker feature exists to serve.



A repositioned logo gives the space back.

- `logo-x` and `logo-y` together
 - Move the mark and switch it to left-anchoring. The corner is free, so the tabs reclaim the full width.
- `logo-scale`
 - Multiplies the mark's box. The reserve is written from the same tokens, so the two cannot drift.

Every logo injector stamps `data-logo-corner`, and only when the mark is left where it lands by default.



FOUR OCCUPANTS · ONE RESERVE EACH

The corner is a stack, and the
geometry owns the arithmetic.

*A fifth occupant needs one edit, in the
block that already holds the arithmetic.*