# Chapter 13: I/O Systems

Sections: 13.1-13.3.1 & 13.5

### Chapter 13: I/O Systems

- Overview
- I/O Hardware
- Application I/O Interface
- Kernel I/O Subsystem
- Transforming I/O Requests to Hardware Operations
- STREAMS
- Performance

### **Objectives**

 Explore the structure of an operating system's I/O subsystem

 Discuss the principles of I/O hardware and its complexity

 Provide details of the performance aspects of I/O hardware and software


#### Overview

- I/O management is a major component of operating system design and operation
  - Important aspect of computer operation
  - I/O devices vary greatly
  - Various methods to control them
  - Performance management
  - New types of devices frequent
- Ports, busses, device controllers connect to various devices
- Device drivers encapsulate device details
  - Present uniform device-access interface to I/O subsystem

#### I/O Hardware

- Incredible variety of I/O devices
  - Storage
  - Transmission
  - Human-interface
- Common concepts signals from I/O devices interface with computer
  - Port connection point for device
  - Bus daisy chain or shared direct access
    - PCI bus common in PCs and servers, PCI Express (PCIe)
    - expansion bus connects relatively slow devices
  - Controller (host adapter) electronics that operate port, bus, device
    - Sometimes integrated
    - Sometimes separate circuit board (host adapter)
    - Contains processor, microcode, private memory, bus controller, etc
      - Some talk to per-device controller with bus controller, microcode, memory, etc

## A Typical PC Bus Structure



### I/O Hardware (Cont.)


- I/O instructions control devices
- Devices usually have registers where device driver places commands, addresses, and data to write, or read data from registers after command execution
  - Data-in register, data-out register, status register, control register
  - Typically 1-4 bytes, or FIFO buffer
- Devices have addresses, used by
  - Direct I/O instructions
  - Memory-mapped I/O
    - Device data and command registers mapped to processor address space
    - Especially for large address spaces (graphics)

#### Device I/O Port Locations on PCs (partial)

#### FYI

I/O address range (hexadecimal)	device
000-00F	DMA controller
020–021	interrupt controller
040–043	timer
200–20F	game controller
2F8–2FF	serial port (secondary)
320-32F	hard-disk controller
378–37F	parallel port
3D0-3DF	graphics controller
3F0-3F7	diskette-drive controller
3F8-3FF	serial port (primary)

#### A Kernel I/O Structure




## **Polling**

- For each byte of I/O
  - 1. Read busy bit from status register until 0
  - 2. Host sets read or write bit and if write copies data into dataout register
  - 3. Host sets command-ready bit
  - 4. Controller sets busy bit, executes transfer
  - Controller clears busy bit, error bit, command-ready bit when transfer done
- Step 1 is busy-wait cycle to wait for I/O from device
  - Reasonable if device is fast
  - But inefficient if device slow
  - CPU switches to other tasks?
    - But if miss a cycle data overwritten / lost

#### Interrupts


- Polling can happen in 3 instruction cycles
  - Read status, logical-and to extract status bit, branch if not zero
  - How to be more efficient if non-zero infrequently?
- CPU Interrupt-request line triggered by I/O device
  - Checked by processor after each instruction
- Interrupt handler receives interrupts
  - Maskable to ignore or delay some interrupts
- Interrupt vector to dispatch interrupt to correct handler
  - Context switch at start and end
  - Based on priority
  - Some nonmaskable
  - Interrupt chaining if more than one device at same interrupt number

### Interrupt-Driven I/O Cycle






#### Interrupt-driven I/O Operation



### Life Cycle of An I/O Request



#### Intel Pentium Processor Event-Vector Table

#### FYI

vector number	description
0	divide error
1	debug exception
2	null interrupt
3	breakpoint
4	INTO-detected overflow
5	bound range exception
6	invalid opcode
7	device not available
8	double fault
9	coprocessor segment overrun (reserved)
10	invalid task state segment
11	segment not present
12	stack fault
13	general protection
14	page fault
15	(Intel reserved, do not use)
16	floating-point error
17	alignment check
18	machine check
19–31	(Intel reserved, do not use)
32–255	maskable interrupts


### Interrupts (Cont.)

- Interrupt mechanism also used for exceptions
  - Terminate process, crash system due to hardware error
- Page fault executes when memory access error
- System call executes via trap to trigger kernel to execute request
- Multi-CPU systems can process interrupts concurrently
  - If operating system designed to handle it
- Used for time-sensitive processing, frequent, must be fast

### **Direct Memory Access**

- Used to avoid programmed I/O (one byte at a time) for large data movement
- Requires DMA controller
- Bypasses CPU to transfer data directly between I/O device and memory
- OS writes DMA command block into memory
  - Source and destination addresses
  - Read or write mode
  - Count of bytes
  - Writes location of command block to DMA controller
  - Bus mastering of DMA controller grabs bus from CPU
    - Cycle stealing from CPU but still much more efficient
  - When done, interrupts to signal completion
- Version that is aware of virtual addresses can be even more efficient - DVMA

#### Six Step Process to Perform DMA Transfer



### Application I/O Interface

- I/O system calls encapsulate device behaviors in generic classes
- Device-driver layer hides differences among I/O controllers from kernel
- New devices talking already-implemented protocols need no extra work
- Each OS has its own I/O subsystem structures and device driver frameworks
- Devices vary in many dimensions
  - Character-stream or block
  - Sequential or random-access
  - Synchronous or asynchronous (or both)
  - Sharable or dedicated
  - Speed of operation
  - read-write, read only, or write only


#### Characteristics of I/O Devices

- Subtleties of devices handled by device drivers
- Broadly I/O devices can be grouped by the OS into
  - Block I/O
  - Character I/O (Stream)
  - Memory-mapped file access
  - Network sockets
- For direct manipulation of I/O device specific characteristics, usually an escape / back door
  - Unix ioctl() call to send arbitrary bits to a device control register and data to device data register

#### **Block and Character Devices**

- Block devices include disk drives
  - Commands include read, write, seek
  - Raw I/O, direct I/O, or file-system access
  - Memory-mapped file access possible
    - File mapped to virtual memory and clusters brought via demand paging
  - DMA
- Character devices include keyboards, mice, serial ports
  - Commands include get(), put()
  - Libraries layered on top allow line editing

#### Device-status Table



### Kernel I/O Subsystem

- Caching faster device holding copy of data
  - Always just a copy
  - Key to performance
  - Sometimes combined with buffering
- Spooling hold output for a device
  - If device can serve only one request at a time
  - i.e., Printing
- Device reservation provides exclusive access to a device
  - System calls for allocation and de-allocation
  - Watch out for deadlock


#### **Error Handling**

- OS can recover from disk read, device unavailable, transient write failures
  - Retry a read or write, for example
  - Some systems more advanced Solaris FMA, AIX
    - Track error frequencies, stop using device with increasing frequency of retry-able errors
- Most return an error number or code when I/O request fails
- System error logs hold problem reports


#### I/O Protection

- User process may accidentally or purposefully attempt to disrupt normal operation via illegal I/O instructions
  - All I/O instructions defined to be privileged
  - I/O must be performed via system calls
    - Memory-mapped and I/O port memory locations must be protected too


### Use of a System Call to Perform I/O



#### **UNIX I/O Kernel Structure**



## **Intercomputer Communications**



### Improving Performance

- Reduce number of context switches
- Reduce data copying
- Reduce interrupts by using large transfers, smart controllers, polling
- Use DMA
- Use smarter hardware devices
- Balance CPU, memory, bus, and I/O performance for highest throughput
- Move user-mode processes / daemons to kernel threads

# End of Chapter 13