# L'extension adjustbox

# Martin Scharrer martin@scharrer-online.de

CTAN: http://www.ctan.org/pkg/adjustbox-fr

VC: https://bitbucket.org/martin\_scharrer/adjustbox

Version v1.0 - 2012/05/21

×

#### **Abstract**

This package allows to adjust general (LA) $T_EX$  material in several ways using a key=value interface. It got inspired by the interface of  $\include graphics$  from the graphicx package. This package also loads the trimclip package which code was once included in this package.

## 1 Introduction

The standard MTEX package graphicx (the extended version of graphics) provides the macro \includegraphics[\(\lambda\)] {\(\file\) name\)} which can be used to include graphic files. Several options can be used to scale, resize, rotate, trim and/or clip the graphic. The macros \scalebox, \resizebox and \rotatebox are also provided to apply the corresponding operation on (\(\mathbe{L}\)) \text{TEX} material, which is subsequently placed inside a \hbox. However no macros are provided to trim or clip (\(\mathex{L}\)) \text{TEX} material, most likely because this operations are not done by \(\text{TEX}\) but by the output format, i.e. using PostScript (PS) or PDF operations.

This package started by providing the missing macros \clipbox and \trimbox. Then a general \adjustbox macro which allows to combine many operations using a key=value syntax was added and further extended until it represented the main feature of this package. Newly added keys are also provided as dedicated macros and corresponding environments. The \clipbox and \trimbox macros were then moved together with the required output driver code to a dedicated package trimclip. This allows documents and other packages to use these basic features without loading the full adjustbox package.

## 1.1 Dependencies

The adjustbox package and its trimclip sub-package require the author's other packages adjcalc (bundled with adjustbox) and collectbox, as well as the packages xkeyval, graphicx and ifpdf. The varwidth package is automatically loaded if installed, otherwise the varwidth and stack keys are disables as well as \stackbox and the stackbox environment. The ifoddpage package is automatically loaded if installed, otherwise the outer and inner keys are disables as well as \outersidebox

and \innersidebox macros and corresponding environments. For features which use colors the xcolor package must also be loaded manually (the color package is fine, too). The experimental split and pagebreak features also require the storebox package to be loaded manually.

## 1.2 Verbatim Support

The macros provided by adjustbox and trimclip read the content as a horizontal T<sub>E</sub>X box and not as an macro argument in order to support verbatim content. This means that the braces around the content can also be written as **\bgroup** and **\egroup**:

```
\adjustbox{key=value,...}\bgroup \( \content \\ \egroup \)
```

Special care is taken to allow the *(content)* to be a single macro (except **\bgroup**) without any braces:

```
\adjustbox{key=value,...}\somemacro
```

This is to support the habit of some MEX users to drop the braces for single token arguments. All environments support verbatim content. Note that the plainTeX syntax for environments (\adjustbox...\endadjustbox) can not be used because it will trigger \adjustbox as a macro. However, the braces around the content can be replaced by \bgroup and \egroup.

# 2 Package Options

This package accepts the following options:

export Exports most keys of \adjustbox to \includegraphics so that they can be used with this macro as well.

Export Sets \includegraphics to be identical to \adjincludegraphics, which also allows the usage of all \adjustbox keys.

pgf This option is passed to trimclip and makes it to use the pgf package for all clip operations. This overrides all automatically detected drivers.

PGF This option will pass the pgf to trimclip and enable the pgfmath option of adjcalc, i.e. the pgf package is used for clip operations and the pgfmath package is used to parse length arguments.

minimal Only load a minimal set of code, i.e. trimclip and \adjustbox/adjustbox but no additional keys and macros.

The following options define the way length values are processed by the provided macros. They are passed to the \adjcalcset macro of the adjcalc package and load any required packages. These options can also be used as local keys on \adjustbox. See the adjcalc manual for more details on them.

etex Uses the  $\epsilon$ -TEX primitive \glueexpr to parse length values.

calc Uses the calc package to parse length values.

pgfmath Uses the pgfmath package of the pgf bundle to parse length values.

defaultunit=\(\langle unit \rangle \) This sets the default unit used for values which accept length without units, e.g. trim.

In addition, all driver options of the trimclip package are also accepted and passed to it. All unknown options are passed to the graphicx package, which might pass them down to the graphics package.

## 3 Main Macros

The following macros and environments represent the main functionality of this package. Special care is taken so that the macros and the environments can have the same name. For starred environments the star can be either part of the name or an optional argument.

## 3.1 Adjust Box Content

```
\adjustbox{\langle key=value,...\rangle}{\langle content\rangle}
```

The \adjustbox macro allows the modification of general (L)TEX content using a key=value syntax. This can be seen as an extension of the \includegraphics macro from images to any (L)TEX material. The macro supports the all \includegraphics keys and many more. However, they are provided as a mandatory not as an optional argument, because an \adjustbox without options would not make sense and can be replaced by a simple \mbox. As already stated the content is read as a box, not as a macro argument, therefore verbatim or other special content is supported and the braces can also be replaced by \bgroup and \egroup. There is no starred version of this macro.

```
\begin{adjustbox}{\key=value,...\}
  \content\
\end{adjustbox}
```

The environment version of \adjustbox. A difference to the macro is that it includes \noindent to suppress paragraph indention.

#### 3.2 Adjust Images

```
\adjustimage{\langle key=value, ... \rangle}{\langle image filename \rangle}
```

This macro can be used as an extension of \includegraphics. While \adjustbox is based on the same interface as \includegraphics it provides more keys and allows global keys set by \adjustboxset. Most keys can be exported to \includegraphics using the export option, but there is no support for global keys\(^1\). Therefore it can make sense to use \adjustbox\(\lambda\)(\key\)/value pairs\(\rangle\)\(\lambda\)(\includegraphics\(\lambda\)(\filename\)\(\rangle\), which is the definition of \adjustimage. However, it does not use \includegraphics directly, but an internal macro, to allow the redefinition of \includegraphics. This

macro does not require the export option and therefore helps to avoid option clashes if adjustbox is loaded at several places.

```
\adjincludegraphics [\langle key/value pairs \rangle ] {\langle image filename \rangle }
```

Like \adjustimage but in the same format as \includegraphics, i.e. with an optional argument. This macro allows to use all features of \adjustbox on images, however special care must be taken if the values include '[]'. In this case either the whole value or the while optional argument must be wrapped in '{}': \adjincludegraphics [key={[.]},...]{..} or \adjincludegraphics [{key=[.],...}]{..}.

It is possible to redefine \includegraphics to \adjincludegraphics and this is done by the Export option (not to be confused with the export option).

# 3.3 Setting keys globally

```
\adjustboxset{\global keys to be executed before local keys\} \adjustboxset*{\global keys to be executed after local keys\}
```

Using these two macros all keys can be set globally, i.e. for all future \adjustbox macros and adjustbox environments. Note that these settings are actually *local* to the current TEX group and only really global if used in the preamble or outside any group. The normal macro will place all given keys before the keys used in first argument of \adjustbox / adjustbox, while the starred version will place them afterwards.

If these macros are used several times there keys are accumulated. This happens in the given order for the normal version and in reversed order for the starred version, i.e. the keys of further \adjustboxset or \adjustboxset\* are always added so they face inwards. If used without any keys but an empty argument, all keys previously set with the same macro are removed (from the current TeX scope). This means \adjustboxset{} clears all keys set be previously usages of \adjustboxset{\langle keys} and \adjustboxset\*{} clears all set by \adjustboxset\*{\langle keys}}. Such resets are again local to the current TeX group.

#### **Examples:**

```
The macros:
```

```
\adjustboxset{keya=1}
\adjustboxset*{keyc=3}
\adjustbox{keyb=2}{content}

are effectively the same as:
   \adjustbox{keya=1,keyb=2,keyc=3}{content}

The macros:
   \adjustboxset{keya=1,keyb=2}
   \adjustboxset{keyc=3,keyd=4}
   \adjustboxset*{keyc=3,keyh=8}
```

\adjustboxset\*{keyi=9,keyj=10}
\adjustbox{keye=5,keyf=6}{content}

are effectively the same as:

```
\adjustbox{keya=1,keyb=2,keyc=3,keyd=4,keye=5,keyf=6,
keyi=9,keyj=10,keyg=7,keyh=8}{content}
```

## 3.4 Argument Values

All length values given in the arguments of all macros and keys provided by this package are parsed by and advanced version of \setlength (called \adjsetlength) which uses either \epsilon-TeX expressions (default), the calc package (default fall-back) or the \pgfmathparse of the pgf package. This allows for arithmetic expressions in these arguments. See the package options in section 2 to learn how to change the used length parser. Note that early versions of this package used \pgfmathparse by default. Older documents therefore might need now use the pgfmath option to compile correctly.

Note that the four values for \trimbox and \clipbox as well as for the trim and viewport option of \adjustbox are separated by spaces. If the expression of any of this values holds a space or ends with a macro (eats trailing spaces!) it must be wrapped into braces '{ }'.

```
\width \height \depth \totalheight
```

These LTEX lengths hold the current dimensions of the content and can be used as part all length arguments. When the size of the content is changed by a key these lengths will be adjusted to hold the new size for all further keys. The totalheight is the height plus depth. With the patch option these lengths can also be used for \includegraphics.

```
\Width \Height \Depth \Totalheight
```

These LaTeX lengths hold the original dimension of original unchanged content and are not modified. They are useful if the size of the content is modified by several keys, but further keys should still work relative to the original content.

## **Default unit**

If no unit is provided for of the bounding box coordinates (llx, lly, urx, ury) in the trim and clip features then PostScript points (big points, bp, 72bp = 1 inch) are used, as it is the default behaviour of the trim and viewport options of graphicx's \includegraphics. Note that graphicx converts all values, independent if a unit is provided or not, internally to bp, because graphics where traditionally stored in Encapsulated PostScript (EPS) files. The more modern PDF files also use bp instead of pt. Because the adjustbox package macros target (L) TeX material and users will mostly use pt values this internal conversion to bp got disabled for them to avoid unnecessary rounding errors. Since v0.5 the default unit can be changed using the defaultunit=\( unit \) key (which is also usable as global package option).

# 4 Adjustbox Keys

This packages provides the following **\adjustbox** keys with matching macros and environments.

## 4.1 Trimming and Clipping

The following keys allow content to be trimmed (i.e. the official size is made smaller, so the remaining material laps over the official boundaries) or clipped (overlapping material is not displayed). These keys come in different variants, where the lower-case keys represent the behavior of the corresponding \includegraphics keys. The corresponding macros (\trimbox, \clipbox, etc.) and environments (trimbox, clipbox, etc.) are included in the accompanying trimclip package and are explained in its manual.

```
trim=\langle llx \rangle \langle lly \rangle \langle urx \rangle \langle ury \rangle trim=\langle all sites \rangle trim=\langle left/right \rangle \langle top/bottom \rangle
```

This key represents the original **trim** key of **\includegraphics** but accepts its value in different forms. Unlike most other keys it always acts on the original content independent in which order it is used with other keys. The key trims the given amounts from the lower left (ll) and the upper right (ur) corner of the box. This means that the amount  $\langle llx\rangle$  is trimmed from the left side,  $\langle lly\rangle$  from the bottom and  $\langle urx\rangle$  and  $\langle ury\rangle$  from the right and top of the box, respectively. If only one value is given it will be used for all four sites. If only two values are given the first one will be used for the left and right side (llx, urx) and the second for the bottom and top side (lly, ury).

```
\begin{tabular}{ll} {\tt viewport=} \langle \textit{llx} \rangle & \langle \textit{lly} \rangle & \langle \textit{urx} \rangle & \langle \textit{ury} \rangle \\ \\ \hline \end{tabular}
```

This key represents the original viewport key of \includegraphics. It always trims the original content to the given view port independent from its position.

```
clip
clip=true|false
```

This boolean key represents the original clip key of \includegraphics. It is intended to be used to make trim or viewport clip the trimmed material. Note that the material will still be part of the output file but is simply not shown. It might be exported from the output file using special tools, so using it to censor classified information is a bad idea.

```
 \begin{split} & \text{Trim=} \langle llx \rangle \ \langle lly \rangle \ \langle urx \rangle \ \langle ury \rangle \\ & \text{Trim=} \langle all \ sites \rangle \\ & \text{Trim=} \langle left/right \rangle \ \langle top/bottom \rangle \\ & \text{Viewport=} \langle llx \rangle \ \langle lly \rangle \ \langle urx \rangle \ \langle ury \rangle \\ \end{aligned}
```

The normal **trim** and **viewport** keys are applied on the original content before any resizing or (most) other keys take effect. This is because for **\includegraphics** the trimming is done by the internal graphic driver, while the effects can be applied

later (but can also be driver dependent). If the trim and viewport keys are used multiple times only the last values will be used for the trimming, i.e. the content is only trimmed once. The upper case variants Trim and Viewport will wrap the content internally in a \trimbox or \trimbox\* macro which can be applied multiple times, e.g. before and after the content is rotated. These two keys awaits the same format as the original keys. However, the clip key has no effect on them.

The Clip key will clip the given amounts from the current content and can be used several times if required. The starred version will use the given coordinates as viewport. These keys work by wrapping the content internally in a \clipbox or \clipbox\* macro.

## 4.2 Margins and Vertical Spacing

```
margin=\langle all sites \rangle margin=\langle left/right \rangle \tau top/bottom \rangle margin=\langle llx \rangle \langle lly \rangle \langle urx \rangle \langle ury \rangle
```

This key can be used to add a margin (white space) around the content. It can be seen as the opposite of **Trim**. The original baseline of the content is preserved because  $\langle lly \rangle$  is added to the depth. It is also available under the alternative name **padding**, which can be used to more visually distinguish an inner margin from an outer margin e.g. if a frame is added.

#### **Example:**

```
Before \adjustbox{padding=1ex 2ex 3ex 4ex,frame,margin=1ex 2ex 3ex 4ex}{Text} After
```




```
margin*=\langle all sites\rangle
margin*=\langle left/right\rangle \langle top/bottom\rangle
margin*=\langle llx\rangle \langle lly\rangle \langle urx\rangle \langle ury\rangle
```

This starred version is almost identical to the normal margin key, but also raises the content by the  $\langle lly \rangle$  amount, so that the original depth is preserved instead of the original baseline. Note that while margin is basically the opposite of Trim, margin\* is not the opposite of Trim\*. Instead it also takes the same values as the unstarred key and not viewport values like Trim\*. An alternative name of margin\* is padding\*.

#### **Example:**

```
Before \adjustbox{padding*=1ex 2ex 3ex 4ex,frame,margin*=1ex 2ex 3ex 4ex}{Text} Aft
```



```
vspace=\langle above/below\rangle
vspace=\langle above\rangle \langle below\rangle
```

The **vspace** key adds a vertical space before and after the content. This is done by adding paragraph breaks and **\vspace** macros, which will yield better spacing between paragraphs then when using the **margin** key. However **vspace** forces vertical mode around the content. Adding further keys after **vspace** will force restricted horizontal mode again and the vertical space will be ignored. For this situation the **margin** key is better suited.

```
vspace*=\langle above/below \rangle vspace*=\langle above \rangle \langle below \rangle
```

Identical to **vspace** but uses **\vspace**\* instead. The difference is that the vertical space is not ignored at page breaks, but its full amount is always forced.

## 4.3 Minimum and Maximum Size

The following keys allow to set a minimum or maximum size. The content will be scaled down or up if required.

```
min width=\langle width\rangle
max width=\langle width\rangle
min height=\langle height\rangle
max height=\langle height\rangle
min totalheight=\langle total height\rangle
max totalheight=\langle total height\rangle
```

These keys allow to set the minimum and maximum width, height or totalheight of the content. The current size of the content is measured and the content is resized if the constraint is not already met, otherwise the content is unchanged. Multiple usages of these keys are checked one after each other, and therefore it is possible that a later one is undoing the size changes of an earlier one. A good example is max width=\textwidth which will limit large content to the text width but will not affect smaller content.

```
min size={\(\didth\)}-{\(\dight\)}-\\
max size={\(\width\)}-{\(\dight\)}-\\
min totalsize={\(\width\)}-{\(\total height\)}-\\
max totalsize={\(\width\)}-{\(\total height\)}-\\
```

These keys allow to specify the minimum or maximum width and (total)height of the content together, which is more efficient than using the width and (total)height keys described earlier.

```
\minsizebox{\langle width\rangle} \{\langle content\rangle}
\minsizebox*{\langle width\rangle} \{\langle total height\rangle} \{\langle content\rangle}
```

This macro is like \resizebox of the graphics/x package, but only resizes the content if its natural size is smaller than the given \( \lambda width \rangle \text{ or \( \lambda height \rangle} \). If only one value should be set the other one can be replaced by '!'. If required the content is scaled up so that the width and height is equal or larger than the given values, but does not change the aspect ratio. The star variant uses the total height instead of only the height. This macro is used internally for the min width, min height, min totalheight and min totalsize keys.

#### **Examples:**

```
Some Text which will be enlarged

\[
\text{Some Text} \text{ which will be enlarged}
\]
\[
\text{minsizebox{!}{4ex}{\fbox{Some Text}} \text{ which will be enlarged}}
\]
\[
\text{Some Text} \text{ which will be enlarged}
\]
\[
\text{minsizebox*{!}{4ex}{\fbox{Some Text}} \text{ which will be enlarged}}
\]
\[
\text{Some Text} \text{ which will be enlarged}
\]
\[
\text{minsizebox{3cm}{!}{Some Text} \text{ which will be enlarged}}
\]
\[
\text{minsizebox{1cm}{!}{Some Text} \text{ which will be enlarged}}
\]
\[
\text{minsizebox{1cm}{!}{some Text} \text{ which will be enlarged}}
\]
\[
\text{minsizebox{1cm}{!}{some Text} \text{ which will be enlarged}}
\]
\[
\text{minsizebox{1cm}{!}{some Text} \text{ which will be enlarged}}
\]
\[
\text{minsizebox{1cm}{!}{some Text} \text{ already large enough}}
\]
```

This macro is like **\resizebox** of the graphics/x package, but only resizes the content if its natural size is larger than the given  $\langle width \rangle$  or  $\langle height \rangle$ . If only one value should be set the other one can be replaced by '!'. If required the content is

 scaled down so that the width and height is equal or smaller than the given values, but does not change the aspect ratio. The star variant uses the total height instead of only the height. This macro is used internally for the max width, max height, max totalheight and max totalsize keys.

#### **Examples:**

```
\maxsizebox{1cm}{1ex}{Some Text} which will be reduced

\someText Which will be reduced

\maxsizebox{!}{1ex}{\fbox{Some Text}} which will be reduced

\maxsizebox*{!}{1ex}{\fbox{Some Text}} which will be reduced

\maxsizebox*{!}{1ex}{\fbox{Some Text}} which will be reduced

\maxsizebox{1cm}{!}{Some Text} which will be reduced

\maxsizebox{3cm}{1cm}{{Some Text}} which will be reduced

\maxsizebox{3cm}{1cm}{Some Text}, already small enough
```

```
warn width warn width=\langle max width\rangle
```

If this key is used the current width of the content is measured and compared with the given maximum width (default is \linewidth). If the content is wider than this value by more than the TeX length \hfuzz (by default 0.1pt) an *Overfull hbox* warning is produced. The warning will include the source code position and the information that it was an adjustbox not a normal paragraph:

```
Overfull \hox (X.Ypt too wide) in adjustbox at line N Overfull \hox (X.Ypt too wide) in adjustbox at lines N-M
```

Note that this key is not able to take any horizontal space before the adjustbox into account. This includes a paragraph indention which might be present with \adjustbox.

This key is useful to be used before the horizontal alignment keys which change the official width of the content and prevent the normal *Overfull* warnings to take affect.

## 4.4 Scaling

```
scale = \langle factor \rangle
scale = \{\langle h-factor \rangle\} \{\langle v-factor \rangle\}
```

The normal **scale** key of graphicx only allows for one scale factor which is used for both the horizontal and vertical scaling. With adjustbox it is also possible to provide the horizontal and vertical scale factors separately.

## **Examples:**

```
\adjustbox{scale=2}{Some text!} Some text! \adjustbox{scale={2}{1}}{Some text!}
```

reflect

This key reflects the content by using  $\reflectbox$  internally, which is identical to  $\scalebox\{-1\}[1]$ , i.e. this key is identical to  $\scale=\{-1\}\{1\}$ .

## **Examples:**

```
\scalebox{$\langle h$-factor$\rangle$[$\langle v$-factor$\rangle]$ $\langle content$\rangle$} $$ \reflectbox{$\langle content$\rangle$}
```

These macros is provided by the loaded graphicx package and only mentioned here for the sake of completeness. See the grfguide for more details.

#### 4.5 Frame

The following keys can be used to draw frames around the content.

```
fbox
fbox=\langle rule width\rangle
fbox=\langle rule width\rangle \langle sep\rangle
fbox=\langle rule width\rangle \langle sep\rangle \langle margin\rangle
```

Draws a framed box around the content like \fbox would do. Using the optional space separated values the rule width, the separation (inner padding) and the outer margin can be set. If not they default to the values \fbox uses by default: \fboxrule, \fboxsep and zero margin.

## **Examples:**

```
\adjustbox{fbox}{Like \cs{fbox}}

\adjustbox{fbox=1pt}{With 1pt rule width}

With 1pt rule width

\adjustbox{fbox=1pt 2pt}{With 1pt rule width and 2pt separation}

With 1pt rule width and 2pt separation
```

```
\adjustbox{fbox={\fboxrule} 1pt}{With normal rule width and 1pt separation}

\With normal rule width and 1pt separation

\adjustbox{fbox=1pt 1pt 1pt}{With 1pt for rule width, separation and outer margin}

\With 1pt for rule width, separation and outer margin
```

```
frame
frame=\langle rule width\rangle
frame=\langle rule width\rangle \langle sep\rangle
frame=\langle rule width\rangle \langle sep\rangle \langle margin\rangle
```

The **frame** key as the same effect as the **fbox** key but is modeled after MEX's **\frame** macro (not the version beamer defines). This means it adds a tight frame with zero separation around the content by default. Besides that it accepts the same space separated values. This key is useful to easily add a tight frame around images where the normal separation wouldn't fit.

## **Examples:**

```
\adjustbox{frame}{Tight box}
```

Tight box

```
cfbox=\langle color \rangle cfbox=\langle color \rangle \rangle rule width \rangle cfbox=\langle color \rangle \rangle rule width \rangle \langle sep \rangle \rangle margin \rangle
```

Identical to **fbox** but uses the given color for the frame. The xcolor package must be loaded manually in order for this key to work.

## **Example:**

```
\adjustbox{cfbox=blue 1pt}{Like a blue \cs{fbox} with \cs{fboxrule}=1pt}
```

Like a blue \fbox with \fboxrule=1pt

```
cframe=\langle color \rangle cframe=\langle color \rangle rule width \rangle cframe=\langle color \rangle rule width \rangle \langle sep \rangle margin \rangle
```

Identical to **frame** but uses the given color for the frame. The xcolor package must be loaded manually in order for this key to work.

#### **Example:**

```
\adjustbox{cfbox=blue!50!green}
{Like a blue and green \cs{frame}}
```

Like a blue and green \frame


## 4.6 Vertical Alignment

The following keys can be used to adjust the vertical alignment and size of the content.

```
valign=\langle letter\rangle
```

This key allows to vertically align the content to the top, middle and bottom. The uppercase letters T, M and B align to the content top (i.e. all depth, no height), the geometric, vertical center (equal height and depth) and to the bottom (all height, no depth), respectively. This allows the alignment of content of different size, but will not result in good alignment with text. The lowercase letters t, m and b are aligning the content again to the top, center and bottom but take the current text size in account. The t letter leaves a certain height given by the macro  $\adjboxvtop$  (by default set to the height of  $\strut$ , i.e.  $\trutbox$ , which is .7\baselineskip), while b sets a certain depth given (as negative length) by the macro  $\adjboxvbottom$  (by default equal to the (negated)  $\strut$  depth, i.e.  $\dtrutbox$ , which is .3\baselineskip). The m letter will center towards the vertical center of the text line which is determined by the macro  $\adjboxvcenter$  (by default 1ex).

The following table shows the different alignments for three different sized blocks:



```
 \begin{array}{l} \mathtt{raise=}\langle amount \rangle \\ \mathtt{raise=}\{\langle amount \rangle\} \{\langle height \rangle\} \\ \mathtt{raise=}\{\langle amount \rangle\} \{\langle height \rangle\} \{\langle depth \rangle\} \\ \end{array}
```

 $<sup>^2\</sup>mathrm{A}$  macro and not a length is used to allow for font size relative values like 1ex.

#### **Examples:**

```
Is \adjustbox{raise=1ex}{higher}
than the normal text

Is \adjustbox{raise={1ex}{\height}}{higher}
than the normal text but sill has
its original official height

Is \higher than the normal text but sill has its original official height

Is \adjustbox{raise={1ex}{1ex}{0pt}}{higher and}
\rotatebox{-90}{deeper}} but with limited official
height and no depth.

Is \higher and \text{but with limited official height and no depth.}

Set height=\langle height \rightarrow

Set height=\langle height \rightarrow

Is \higher and \text{but with limited official height and no depth.}

Set height=\langle height \rightarrow

Is \higher and \text{but with limited official height and no depth.}

Is \higher and \text{but with limited official height and no depth.}

Is \higher and \text{but with limited official height and no depth.}
```

This sets the official height of the content without actual changing it. This can be seen as a form of trimming. It uses the same internal code as \raisebox{0pt}[(\height)]{\langle content}\}.

#### **Example:**

```
\adjustbox{set height=.5\height}
    {\shortstack{some stacked\\content}}
some stacked
    content
```

```
set depth=\langle depth \rangle
```

This sets the official depth of the content without actual changing it. This can be seen as a form of trimming. It uses the same internal code as \raisebox{0pt}[\height][\depth]{\content}\}.

#### **Example:**

```
\adjustbox{set depth=0pt}
    {\shortstack{some stacked\\content
    with \raisebox{-1ex}{depth}}}
    some stacked
    content with
    depth
```

```
set vsize=\{\langle height\rangle\}\{\langle depth\rangle\}
```

This sets the official height of depth of the content without actual changing it. This key is simply the combination of **set height** and **set depth**.

#### **Example:**

## 4.7 Horizontal Alignment

The following keys can be used to adjust the horizontal alignment and size of the content.

```
center center=\langle width\rangle
```

This key places the content in a horizontal box which is by default \linewidth wide (i.e. as wide as a normal text paragraph) and centers it in it. The effect is very similar to \centerline. The original content is unchanged, but simply identical white space is added as a left and right margin. This is useful if the content is a figure or table and can be used as a replacement for \centering. One important difference is that the content will then have the given width which might influence (sub-)caption placement. If the content is wider than the available width it will stick out on both sides equally without causing an overfull hbox warning. Note that when \adjustbox paragraph is used at the beginning of a paragraph the normal paragraph indention is added, which will push the while box to the right and might cause an overfull line. In such cases a \noindent must be added beforehand. The adjustbox environment already uses this macro.

#### **Examples:**

```
\adjustbox{center}{Some content}

Some content
\adjustbox{center=5cm}{Some content}

Some content

right
right=\langle width\rangle
```

Like **center** this key places the content in a box with the given width (by default **\linewidth**) but right aligns it. If the content is wider than the available width it will stick out into the left side without causing an overfull hbox warning.

#### **Examples:**

```
\adjustbox{right}{Some content}

Some content
\adjustbox{right=5cm}{Some content}
```

```
\begin{array}{c} \texttt{left} \\ \texttt{left=} \langle \textit{width} \rangle \end{array}
```

Like **center** this key places the content in a box with the given width (by default **\linewidth**) but left aligns it. If the content is wider than the available width it will stick out into the right side without causing an overfull hbox warning.

#### **Examples:**

```
\adjustbox{left}{Some content}
Some content
\adjustbox{left=5cm}{Some content}
```

Some content

```
inner inner=\langle width \rangle
```

Like **center**, **left** and **right** this key places the content in a box with the given width (by default **\linewidth**) but aligns it towards the inner margin. If the content is wider than the available width it will stick into the outer margin without causing an overfull hbox warning. In twoside mode this key is equal to **left** for odd pages and equal to **right** for even pages. For oneside mode it is equal to **left**. Note that the page-is-odd test might not always lead to correct results for some material close to a page boundary, because TEX might not have decided on which page it will be placed. This can be improved by loading the changepage package with the **strict** option, which uses a reference to determine the correct page number (and requires the usual additional compiler run).

```
{\tt outer} = \langle width \rangle
```

Identical to **inner** but aligns the content towards the outer margin. For oneside mode it is equal to **right**. If the content is wider than the available width it will stick into the outer inner without causing an overfull hbox warning.

```
\label{linear_content} $$ \liminf_{\langle content \rangle} \{\langle content \rangle\}$
```

```
\begin{innersidebox}[\langle width\rangle]
\langle content\rangle
\end{innersidebox}
```

Macro and environment version of the **inner** key. The optional width argument defaults to **\linewidth**. Both include a **\noindent** to avoid paragraph indention. If an paragraph indention is wanted it can be created by placing a \mbox{} or the identical \null macro before it.

```
\operatorname{\ooutersidebox}[\langle width\rangle] \{\langle content\rangle\}
```

```
\begin{outersidebox}[⟨width⟩]
  ⟨content⟩
\end{outersidebox}
```

Macro and environment version of the **outer** key. The optional width argument defaults to **\linewidth**. Both include a **\noindent** to avoid paragraph indention. If an paragraph indention is wanted it can be created by placing a \mbox{} or the identical \null macro before it.

## Lapping

The following features can be used to make the content lap over its left or right boundary. This is basically the same as trimming, but provides a different, more dedicated interface.

```
 \begin{split} & \texttt{lap=}\langle lap\ amount \rangle \\ & \texttt{lap=}\{\langle length \rangle\} \{\langle lap\ amount \rangle\} \end{split}
```

This key will make the content lap over the surrounding elements to the right or left by the given amount.. A positive amount will make the content lap over to the right and a negative one to the left. The optional  $\langle length \rangle$  argument allows to set the final width. If not used the resulting width will be the original width minus the absolute lap amount. This key internally uses  $\adjustrel{lapbox} \{\langle lap\ amount \rangle\} \{ \ldots \}$  and  $\adjustrel{lapbox} \{\langle lap\ amount \rangle\} \{ \ldots \}$ , respectively.

## **Examples:**

```
\adjustbox{lap=.5\width}{Some content}

\adjustbox{lap=-.5\width}{Some content}

\adjustbox{lap=\width}{Some content}

\adjustbox{lap=-\width}{Some content}

\adjustbox{lap=-\width}{\width}}{Some content}

Some content

\adjustbox{lap={\width}{\width}}{Some content}

Some content

\adjustbox{lap={\width}{-\width}}{Some content}

Some content

\adjustbox{lap={\width}{-\width}}{Some content}
```

rlap llap

This makes the content to be officially 0pt wide and lap over to the right or left, respectively, like the MTEX macros \rlap and \llap do. These are shortcuts for lap=\width and lap=-\width, respectively. The values for these keys are ignored and should not be used.

#### **Examples:**

```
\adjustbox{rlap}{Some content}

\adjustbox{llap}{Some content}

Some content
```

 $\label{lapbox[(width)]{(lap amount)}{(content)}} $$ \arrangle (\arrange \arrange \$ 

This macro is a generalisation of the MTEX core macros \rlap{\content\} and \llap{\content\} which lap the text to the right or left without taking any official space. The \llapbox macro can be used to only partially lap the content to the right (positive amount) or left (negative amount). As with all macros of this package the original width can be references using \width. The resulting official width of the box is normally the original width minus the absolute lap amount. However, it can also be set explicitly using the option argument. It is also possible to use lap amount which absolute values are larger than the original width. In this case the resulting official width will be zero by default and the content will padded with the required white space. Note that the lap amount always states the distance between the right side of the official box and the right side of the actual content for positive amounts or the distance between the left side of the official box and the left side of the actual content for negative values.

## **Examples:**

#### General lapping:

```
\lapbox{1cm}{Some Text}
                                                                Some Text
                                                           Some Text
\lapbox{-1cm}{Some Text}
                                                                 Some Text
\lapbox[4cm]{1cm}{Some Text}
                                                                      Some Text
\lapbox[3cm]{2cm}{Some Text}
Like \rlap:
                                                                   Some Text
\lapbox[Opt]{\width}{Some Text}
Like \llap:
                                                           Some Text
\lapbox[Opt]{-\width}{Some Text}
A centering \clap macro can be achieved using:
                                                               Some Text
\lapbox[0pt]{-.5\width}{Some Text}
                                                               Some Text
\lapbox[Opt]{.5\width}{Some Text}
```

## 4.8 Background

```
bgcolor=\(color\)
bgcolor=\((model\)\) \{\((color\)\)
```

This key adds a colored background to the content. The xcolor package (or color or xxcolor) needs to be loaded as well in order for this to work. The value is passed to an internal \color macro.

#### **Examples:**

```
\adjustbox{bgcolor=blue}{Text with blue background.}

\adjustbox{bgcolor={rgb}{0 0 1}}{Text with blue background in the RGB color model.}

\adjustbox{margin=1ex,bgcolor=green}{green with a little more margin}

\adjustbox{margin=1ex,bgcolor=green,margin=1pt,bgcolor=yellow}{Emulation of colored}
```

bgcolor\*=⟨color macro⟩

Like **bgcolor** but awaits a full color macro as value. This allows to use other macros as **\color** like **\blendcolors**. See the xcolor manual for more details.

#### **Examples:**

```
\color{blue}Blue text
\adjustbox{bgcolor*=\blendcolors{!10!yellow}\color{.}}{with a yellow-bluish background}

Blue text with a yellow-bluish background
\color{green}Green text
\adjustbox{bgcolor*=\blendcolors{!10!yellow}\color{.}}{with a yellow-greenish background}
```

Green text with a yellow-greenish background

```
bgimage=\langle filename\\
bgimage=\langle \langle key=value pairs for image\rangle \langle \langle ilename\rangle
```

Adds a background image to the content. The image is stretched if required to fit exactly to the content. It is also possible to provide \adjustbox or \includegraphics keys to modify the image (before the resizing is done).

\bgimagebox [\langle key=value pairs\] {\langle image filename\}

Standalone version of the bgimage key. Also available as bgimagebox environment.

## 4.9 Density / Pixel size

The following keys allow to adjust the effective length of pdftex special px (pixel) unit. This can be required for images which do not have the correct DPI meta-data included.

```
dpi=(number (dots per inch))
```

The **dpi** key provides a simple interface to set the pixel size to the given DPI (dots per inch) value. For pdflatex the length unit px can be used to specify pixels. However, the equivalent dimension (length) of one pixel must be set using the **\pdfpxdimen** length register. To set a specific DPI value this length must be set using **\setlength\pdfpxdimen**{1in/\(dots\)\}, which is done by the **dpi=**\(\langle dots\)\ key. Note that the key won't affect the setting for the content but only for the further used keys. However, it is possible to use **\setkeys**{adjbox}{dpi=\(number\)} inside the content or anywhere else in the document to set **\pdfpxdimen** using this interface.

#### **Example:**

```
\adjustbox{dpi=72,trim=10px,frame}{%
   \setkeys{adjbox}{dpi=72}%
   \textcolor{green}{\rule{50px}{50px}}%
}
```



```
pxdim=\langle length\rangle
```

Alternatively to the **dpi** key the **\pdfpxdimen** length can be set directly to the given value. Afterwards 1px will stand for the given (*length*).

## **Example:**

```
\adjustbox{pxdim=2pt,trim=2px,frame}
{\textcolor{green}{\rule{20pt}}{20pt}}}
```

# **4.10** Minipage or other inner environments which change the processing of the content

The following keys set the way the content is processed before it is stored it in a box. These keys will overwrite each other and only the latest used key will take effect. Because they affect the inner content directly their order relative to other, normal keys is not meaningful. Also they are only defined for adjustbox but do not apply for \includegraphics. Because they are therefore only used inside a mandatory argument and never in an optional these keys allow for optional bracket arguments.

```
\label{eq:minipage=(width)} $$ \minipage=[\langle position\rangle][\langle height\rangle][\langle inner\ position\rangle]\{\langle width\rangle\}$$
```

This key wraps the inner content in a minipage with the given \( \lambda width \rangle \) before it is stored as horizontal box. Its order relative to other keys is not meaningful (except that future keys of this sub-section will overwrite it). This allows for line breaks and

footnotes in the adjustbox. All optional arguments of minipage are supported. I only the width is given it does not have to be enclosed in braces. The  $\langle position \rangle$  argument must be 't' for top baseline, 'b' for bottom baseline and 'c' for center alignment relative to other text, i.e. defines the resulting baseline. If a  $\langle height \rangle$  is defined the  $\langle inner\ position \rangle$  defaults to  $\langle position \rangle$  but can also be 's' to stretch the content over the whole height. This requires the content to include some vertical stretchable material. Note that all length arguments can include arithmetic expressions like for other keys.

## **Examples:**

```
\adjustbox{minipage=5cm,angle=-10}{%
   Some example code which will
   be automatically broken or can include \\
   line breaks\footnote{AND footnotes!!}\\
   or verbatim \verb+@%^&}_+!%
}
```

```
Some example code which will be automatically broken or can include line breaks or verbatim @%^&}_!

aAND footnotes!!
```

```
Before \begin{adjustbox}{minipage=[b][3cm][s]{5cm}}
    Some example code

\vfill
    with line breaks\footnote{AND footnotes!!}

\vfill
    or verbatim \verb+@%^&}_+!%
\end{adjustbox} After
```

```
Some example code

with line breaks<sup>a</sup>

or verbatim 0%^&}_!

Before aAND footnotes!! After
```

```
tabular=[\(\rho\)] \{\(\column\) \specification\\\\} \tabular*=[\(\rho\)] \{\(\column\) \specification\\\\\} \array=[\(\rho\)] \{\(\column\) \specification\\\\\\\}
```

Places the content in a tabular, tabular\* or array environment, respectively. These keys require different implementations for macro (\adjustbox) and environment mode (adjustbox environment) in order to insert the end code correctly. Note that the environment mode is more efficient and fully stable, while the macro mode requires the last row to end with an explicit \\ (which can be followed by \hline or any other macro which uses \noalign internally). In macro mode the \\ is internally redefined to check for the closing brace. While this was successful tested for normal usages it might still cause issues with unusual or complicated cases. Note that these environments are taken as part of the content and so the usage of arithmetic expressions for length arguments is not supported.

#### **Examples:**

⟨content⟩
\end{stackbox}

```
\adjustbox{tabular=111}{%
                                                                                     C
      A & B & C \\hline
                                                                            a
                                                                                h
      a & b & c \\hline
\begin{adjustbox}{tabular=111}
     A & B & C \\
                                                                                B
                                                                                     C
                                                                                b
      a & b & c
\end{adjustbox}
stack=\langle horizontal alignment\rangle
stack={\(horizontal alignment\)}{\(\lambda\)}
\stackbox[\langle horizontal\ alignment \rangle][\langle vertical\ alignment \rangle] \{\langle content \rangle\}
\begin{stackbox} [\langle horizontal alignment \rangle ] [\langle vertical alignment \rangle ]
```

The **stack** key and its corresponding macro and environment can be used to stack multiple lines similar to the **\shortstack** macro, but both the horizontal and vertical alignment can be selected by a single letter each. Also a proper baseline skip is inserted. This is implemented using the varwidth environment which is based on the minipage environment. Its maximal width arguments is fixed internally to **\linewidth**.

Possible horizontal alignments are: '1' (left), 'r' (right), 'c' (centered, default), 'j' (justified). Possible vertical alignments are the same as for minipage: 't' (top baseline), 'b' (bottom baseline, default), 'c' (vertical centered). Because these arguments are always single letters the '{} 'around them can be skipped, so that the value can simple be two concatenated letters.

#### **Example:**

```
.\adjustbox{stack}{A\\B\\CC}.

B
.\adjustbox{stack=r}{A\\B\\CC}.

A
B
CC.

A
.\adjustbox{stack=r}{A\\B\\CC}.

A
.\adjustbox{stack=ct}{A\\B\\CC}.
```

```
innerenv=\{environment name\}
innerenv=\{\left\( \) environment options\right\}
```

Wraps the inner content in the given (<code>environment</code>) before it is stored as horizontal box. It should be kept in mind that there is some internal code between the begin of the environment and the content. For this reason a tabular, array or similar environment will not work here, because that code will be taken as part of the first cell. Note that such a environment is taken as part of the content and so the usage of arithmetic expressions for length arguments is not supported.

#### **Example:**

```
innercode={\langle begin code \rangle} {\langle end code \rangle}
```

Places the given code before and after the inner content before it is stored as horizontal box. Note that such code is taken as part of the content and so the usage of arithmetic expressions for length arguments is not supported.

## **Example:**

```
\adjustbox{innercode={\color{green}}{!}}{Content} Content
```

## 4.11 Floats and non-float replacements

The following keys can be used to turn an adjusted box into a float or a non-floating replacement which also allows for a caption. These keys must be used last and no other normal keys must be used afterwards, otherwise an error will occur because the added floating environment is boxed again.

```
caption=(caption text)
caption=[(short caption)] { (long caption)}
```

Defines a caption which will be used by a following **figure**, **float** or **nofloat** key. The position of the caption defaults to top for a table (non-)float and bottom for every other type.

```
captionabove=\( caption text \)
captionabove=\[ (short caption) \] \{ \langle long caption \rangle \}
```

Like the **caption** key but forces the placement of the caption above the content. The vertical skip above and below a normal below caption are reversed in this case to get proper spacing. However, this is not done if the caption package is loaded. It is recommended to load this package with the tableposition=above option.

```
captionbelow=\(caption text\)
captionbelow=[\((short caption\))] \{\((long caption\)\)\}
```

Like the **caption** key but forces the placement of the caption below the content.

```
{\tt label=} \langle \mathit{label} \rangle
```

Defines a label which will be used by a following figure, float or nofloat key.

```
figure
figure=⟨placement⟩
```

Turns the adjusted box into a figure. A previously used **caption** and **label** will be added. This is a specialised version of **float**={figure}.

```
float=\{float type\}
float={\{float type\}}[\{position\}]
```

Turns the adjusted box into a float of the given type, i.e. figure, table or any other custom defined float. A previously used caption and label will be added.

```
nofloat=\langle float type\rangle
```

This will add a non-floating replacement of the given float type (figure, table, etc.). The will place the content always at the current position which can lead to bad pagebreaking. A caption will be in the same format as for real floats of the same type. A previously used caption and label will be added.

```
\begin{adjnofloat}{\( float type \) }
  \\ \content \\
\end{adjnofloat}
```

This environment is used internally by **nofloat** to create a non-floating replacement of the given float type (figure, table, etc.). It can also be used directly with other code or be redefined to change the behavior of **nofloat**. Any redefinition should include \def\@captype{#1} to set the caption type. The environment will be used in plain form, i.e. \adjnofloat ... \endadjnofloat, so if a group is required in a redefinition it should be added manually using \begingroup and \endgroup.

## 4.12 Adding own Code or Environments

```
env=\langle environment name \rangle env=\langle \langle environment name \rangle \rangle \langle environment options \rangle
```

Adds an <code>(environment)</code> around the content and the already existing code around it which was added by other keys beforehand. Potential <code>(environment options)</code> (or any other code) can follow the environment name if it was set inside braces. At this stage the content is already boxed and format macros won't have any effect on any included text. For this the <code>innerenv</code> key needs to be used instead.

```
addcode = {\langle code \ before \rangle} {\langle code \ afters \rangle}
```

Adds some (*code before*) and some (*code after*) the content and the already existing code around it which was added by other keys beforehand. At this stage the content is already boxed and format macros won't have any effect on any included text.

```
appcode=\langle code afterwards\rangle
```

Appends come (*code after*) the content and the already existing code around it which was added by other keys beforehand. More complex code should be enclosed in braces.

```
\verb|precode=| \langle code| before \rangle|
```

Prepends come (*code afterwards*) the content and the already existing code around it which was added by other keys beforehand. More complex code should be enclosed in braces.

```
execute=\langle code \rangle
```

Simply executes the code immediately. This is done in the key processing phase and is intended mostly for debugging purposes. Previous (normal) keys won't have an effect yet.

```
Execute=\langle code \rangle
```

Simply executes the code immediately. This is done in the key processing phase for inner environments (see subsection 4.10) and is intended mostly for debugging

purposes. Only previously used special keys for modifying the boxing of the content will have an effect yet. All other keys are not yet processed.

## 4.13 Change or discard content

```
phantom
phantom=h
phantom=v
```

This key replaces the content with an empty phantom box of the same dimension. If the 'h' or 'v' value is used the box will only have the same horizontal size or vertical sizes (height and depth) while using zero for the other dimension(s). For this the standard MTEX macros \phantom, \hphantom and \vphantom are used internally.

This macro produces an empty box with the given width, height and depth. It is equivalent to  $\displaystyle \frac{-\langle depth\rangle}{\langle width\rangle}{\langle height\rangle}+\langle depth\rangle}$  but more efficient and more user friendly.

#### **Example:**

Before \fbox{\phantombox{1cm}{2ex}{1ex}} After



gobble
discard

These two keys are aliases and will discard the content after it was fully processed. Any keys used after one of this keys will operate on an empty content. These keys can be used in combination of the **gstore** ... keys to only measure but not typeset some content.

content=\( new content \)

This key discards the current content completely after it was fully processed and all earlier keys were applied and sets the content to the given (*new content*). This can be used to implement some draft box or censoring features.

#### **Example:**

```
\adjustbox{frame, rotate = -30, gstore sizes = \somelengtha {}{}\somelengthb,
    content = {Censored!}, rotate = 30, totalheight = \somelengtha, width = \somelengthb, frame
    {The real content}
```



#### 4.14 Store box content

```
gstore=(\boxregister)
gstore*=(\boxregister)
```

These keys globally store the current content into the given box register. With the normal version the content is still preserved and can be further adjusted. With the starred version the content will be consumed and further keys will be applied to an empty content.

```
gstore width=\\lengthregister\\
gstore height=\\lengthregister\\
gstore depth=\\lengthregister\\
gstore totalheight=\\lengthregister\\
```

These key globally store the width, height, depth and totalheight into a length register, respectively. The content will not be altered by these keys. There are no starred versions like for **gstore**. If the content should only be measured but not typeset the **gobble/discard** key can be used afterwards.

```
\verb|gstore sizes=| \langle lengthregister| \langle lengthreg
```

Stores all four size values (width, height, depth and totalheight) of the content in the given length registers. This key should be used if more than one dimension should be stored, because it is much more efficient than using multiple of the above keys. If a dimension is not required it can be replaced by an empty argument, i.e. '{}'. Trailing dimensions can be skipped altogether if they are not required.

## 4.15 Experimental Keys

The following features are experimental and may not work correctly yet. At the moment the storebox package must be loaded manually for this keys.

```
\ \left( \left( split \ width \right) \right) \left( \left( split \ height \right) \right) \left( \left( content \right) \right)
```

This macro boxes the given content and splits it in multiple fragments of the given width and height. This is done row by row starting from the upper left corner. The last column and row can have a smaller size than requested. Every fragment is placed using \splitboxcmd{\fragment box\} which is empty by default but can be redefined to e.g. draw a frame around each fragment. After every row except the last the macro \splitboxnewline is inserted which defaults to \\, but can also be redefined freely. After the last row the macro \splitboxlastnewline is inserted which defaults to \splitboxnewline.

The \splitbox content is stored using \storebox from the storebox package and therefore the whole content should only be stored once in the output file if the format is supported by that package (currently only PDF).

```
\begin{splitbox}{\langle split width\rangle} {\langle split height\rangle}
\content\rangle
\end{splitbox}
```

Environment version of \splitbox.

```
split={\langle split width\rangle} {\langle split height\rangle}
```

The split key can be used with \adjustbox and uses \splitbox internally.

```
\pagebreakbox{\(content\)}
```

The \pagebreakbox macro will split the content into multiple parts so that if fits on the current page. If it is larger than the rest of the current page and the full next page it is broken again until the last part fits on a page. This doesn't take any baselines into account and text line in the content may be split in two. This might be compensated manually by redefining the \pagebreakboxoffset macro (default: '\ht\strutbox'), which adjust the vertical offset of the first part.

```
\begin{pagebreakbox}
\end{pagebreakbox}
```

Environment version of \pagebreakbox.

```
pagebreak
```

The key version of \pagebreakbox. There should no be any further keys used afterwards, because they will interfere with the page breaks.

# 5 Defining own Keys

The following macros can be used to define own keys or redefine existing ones.

Defines the new adjustbox key with the given default value if no value is provided. The value can be accessed inside the code as #1 Without a default value an error is raised if the value is missing. An error is raised if the key is already defined.

The normal form will add the code to the internal token register just before the previous content which is wrapped inside braces:  $\langle code \rangle \{\langle previous \, content \rangle \}$ . Subsequent keys will receive this as content. The code can therefore read the content as macro argument. If the dimension of the content need to be accessed it should be boxed first using  $\collectbox\{\langle code \rangle\}$ . Then the dimension are available using the usual macros and the content can be typeset using  $\BOXCONTENT$ . See the collectbox for additional information.

The starred form simply executes the given code in the internal group without changing the token register. In this case the content is not directly accessible and all subsequent keys are not yet processed. This form is useful to locally change settings for the current \adjustbox macro or adjustbox environment.

Like \newadjustboxkey but will redefine an existing key. An error is raised if the key is not already defined.

```
\provideadjustboxkey { $\langle key \rangle } [ $\langle default\ value \rangle ] { $\langle code \rangle } \\ provideadjustboxkey * { $\langle key \rangle } [ $\langle default\ value \rangle ] { $\langle code \rangle } \\
```

Like \newadjustboxkey but will define the key only if it is not already defined.

Like \newadjustboxkey but will always define the key independent if it is already defined or not.