# L'extension graphicx\*

D. P. Carlisle

S. P. Q. Rahtz

28/10/2014

Ce fichier est maintenu par l'équipe du « LATEX Project ». Les rapports d'anomalie peuvent être envoyés en anglais à http://latex-project.org/bugs.html (catégorie graphics)

### 1 Introduction

Cette extension propose une interface alternative aux fonctions de graphics de IATEX  $2_{\varepsilon}$  Les noms de commandes fournis sont les mêmes que ceux de l'extension standard et elles utilisent les mêmes fonctions internes. Cependant, la signification des arguments optionnels est différente. Notez que seuls les arguments optionnels ont changé : tout document qui utilise uniquement les commandes de graphics avec les arguments obligatoires et/ou les versions étoilées fonctionne de façon identique (avec une implémentation quasiment identique) avec les deux extensions.

## 2 Key=Value Interface

Quand la décision de mettre en place IATEX  $2_{\varepsilon}$  a été prise, certains « principes directeurs » ont été établis (et publié dans l'annonce initiale). L'un d'entre eux était que toutes les nouvelles fonctionnalités « se conformeront aux conventions de la version 2.09 ». Cela signifiait en particulier que les nouvelles commandes devraient obéir, pour leurs arguments, aux mêmes règles de syntaxe de base que les commandes existantes.

\*Standard IATEX optional arguments are positional. If a command were to take three optional arguments, then there would be no way of specifying only the third, one would have to give all three, even if the first two were repeats of the default values. Basically this means that 'standard' optional arguments are not suitable if there is more than one option. Various existing packages (for IATEX 2.09) have recognised this, and used 'named arguments' in various forms. Perhaps the two most noticeable are psfig and pstricks. With 'named arguments' (sometimes called 'attributes') each option is not tied to a particular position, but rather

<sup>\*</sup>Ce fichier a pour numéro de version v1.0g et a été mis à jour le 28/10/2014.

given a name (or key) and any options that must be set are set by explicitly associating this name with the desired value.

The members of the LaTeX3 project do appreciate the importance of this kind of syntax, but felt that rather than extending the syntax of LaTeX in an uncoordinated way, it would be better to keep with 'standard arguments' in LaTeX  $2_{\varepsilon}$ , which is intended as a 'consolidation of existing LaTeX variants'. The long term planning for an eventual LaTeX3 release will then be able to consider the whole LaTeX user interface, and a suitable syntax for named arguments. It is important that such an interface design is not hampered by having to retain compatibility with earlier attempts at a named argument syntax. For this reason this graphicx package, which uses the named argument mechanism from the keyval package should be considered 'non standard' although it is supported by the same mechanism, and same authors as the 'standard' graphics package.

### 3 The User Interface

\includegraphics  $*[\langle key\text{-}val\ list\rangle] \{\langle file\rangle\}$ \includegraphics  $*[\langle llx, lly\rangle] [\langle urx, ury\rangle] \{\langle file\rangle\}$ Include a graphics file.

The star form is just for compatibility with the standard interface, and essentially just adds clip to the keys specified. Similarly the second, two-optional argument form is for increased compatibility with the standard package. The two optional argument form is not needed in the keyval interface.

Various 'keys' or named arguments are supported.

**bb** Set the bounding box. The argument should be four dimensions, separated by spaces.

bbllx,bblly,bburx,bbury Set the bounding box. Mainly for compatibility with older packages. bbllx=a,bblly=b,bburx=c,bbury=d is equivalent to bb = a b c d.

natwidth,natheight Again an alternative to bb. natheight=h,natwidth=w
is equivalent to bb = 0 0 h w.

**viewport** Modify the bounding box specified in the file. The four values specify a bounding box *relative* to the llx,lly coordinate of the original box.

**trim** Modify the bounding box specified in the file. The four values specify the amounts to remove from the left, bottom, right and top of the original box.

hiresbb Boolean valued key. Defaults to true. Causes TEX to look for %%HiResBoundingBox comments rather than the standard %%BoundingBox. May be set to false to override a default setting of true specified by the hiresbb package option.

angle Rotation angle.
origin Rotation origin (see \rotatebox, below).

width Required width, a dimension (default units bp). The graphic will be scaled to make the width the specified dimension.

height Required height. a dimension (default units bp).

totalheight Required totalheight (i.e., height + depth). a dimension (default units bp). Most useful after a rotation (when the height might be zero).

**keepaspectratio** Boolean valued key (like clip). If it is set to true, modify the meaning of the width and height (and totalheight) keys such that if both are specified then rather than distort the figure is scaled such that neither dimension exceeds the stated dimensions.

scale Scale factor.

clip Either 'true' or 'false' (or no value, which is equivalent to 'true'). Clip the graphic to the bounding box (or viewport if one is specified).

draft a boolean valued key, like 'clip'. locally switches to draft mode, ie. do not include the graphic, but leave the correct space, and print the filename.

type Specify the file type. (Normally determined from the file extension.)

ext Specify the file extension. Only for use with type.

read Specify the 'read file' which is used for determining the size of the graphic. Only for use with type.

**command** Specify the file command. Only for use with type.

The arguments are interpreted left to right. clip, draft, bb,, and bbllx etc. have the same effect wherever they appear, but the scaling and rotation keys interact.

Any scaling that is specified before rotation, is handled by the internal graphics inclusion function. Rotation, or any later scaling is handled by implicitly calling \rotatebox or \scalebox. So [height=1in,angle=90] scales the graphic to 1in, then rotates it, so it is one inch wide. [angle=90,height=1in] first rotates, then scales the result so that it is 1 in high. A driver that can scale included graphics, but not arbitrary text will not be able to support the second form, as it will require a call to \scalebox, but the first form should work as there the scaling is handled by \Ginclude@graphics.

\rotatebox  $[\langle key\text{-}val\ list\rangle] \{\langle angle\rangle\} \{\langle text\rangle\}$ 

Rotate text.

The keys supported by \rotatebox are:

origin Specify the centre of rotation. origin= $\langle label \rangle$ , where the labels are up to two of lrctbB (B denotes the baseline, as for PSTricks).

**x,y** An alternative to origin.  $x=\langle dimen \rangle$ ,  $y=\langle dimen \rangle$  The x, y coordinate of the centre of rotation. As usual \height etc may be used.

units Specify the units used in the main argument. eg units=-360 would mean that the argument referred to degrees *clockwise* instead of the default anti-clockwise rotation.

As an example \rotatebox[origin=c]{180}{text} will rotate "text" around its centre, thus creating a final box of the same dimensions as the original box. This is to be contrasted to the default behaviour, which rotates around the reference point on the baseline, thus producing a box that is mainly below the baseline.

## 4 Implementation

```
1 (*package)
```

One new option is handled by keyval. It suppresses the error normally generated if an unknow keyval key is used. (This helps porting between drivers that use extended interfaces.)

```
2 \DeclareOption{unknownkeysallowed}
```

3 {\PassOptionsToPackage\CurrentOption{keyval}}

All other options are handled by the graphics package.

- 4 \DeclareOption\*{\PassOptionsToPackage\CurrentOption{graphics}}
- 5 \ProcessOptions

This package requires these two building blocks.

6 \RequirePackage{keyval,graphics}

## 4.1 Graphics Inclusion

First we declare the 'bounding box' keys. These all use  $\Gin@defaultbp$  so that the  $\langle value \rangle$  can be given as a length in the usual TEX units such as cm or as an integer, taken as bp.

```
\KV@Gin@bb
```

```
7 \define@key{Gin}{bb}
8 {\Gin@bboxtrue\Gread@parse@bb#1 \\}

\KV@Gin@bbllx
\KV@Gin@bbly 9 \define@key{Gin}{bbllx}
\KV@Gin@bburx 10 {\Gin@bboxtrue\Gin@defaultbp\Gin@llx{#1}}
\KV@Gin@bbury 11 \define@key{Gin}{bblly}
12 {\Gin@bboxtrue\Gin@defaultbp\Gin@lly{#1}}
13 \define@key{Gin}{bburx}
14 {\Gin@bboxtrue\Gin@defaultbp\Gin@urx{#1}}
15 \define@key{Gin}{bbury}
16 {\Gin@bboxtrue\Gin@defaultbp\Gin@ury{#1}}
```

\KV@Gin@hiresbb

If set to true (the default) T<sub>E</sub>X will look for bounding box comments of the form %%HiResBoundingBox (which typically have real values) instead of the standard %%BoundingBox (which should have integer values). It may be set to false to override a package option of hiresbb.

```
17 \define@key{Gin}{hiresbb}[true]{%
18  \edef\Gread@BBox{%
19  \Opercentchar\Opercentchar
20  \csname if#1\endcsname HiRes\fi
21  BoundingBox}}
```

\KV@Gin@natheight \KV@Gin@natheight

22 \let\KV@Gin@natwidth\KV@Gin@bburx 23 \let\KV@Gin@natheight\KV@Gin@bbury

### \KV@Gin@viewport \KV@Gin@trim

A 'viewport' is a user-specified area of the graphic to be included. It should not be confused with the 'Bounding Box' of a PS file. In fact, the origin for a viewport specification is the (llx,lly) lower left coordinate of the bounding box. If a viewport is specified, and clipping is turned on, clipping is based on the viewport, not on the boundingbox.

Both 'viewport' and 'trim' were suggested (and originally, but differently, implemented) by Arthur Ogawa.

```
24 \define@key{Gin}{viewport}
             {\let\Gin@viewport@code\Gin@viewport\Gread@parse@vp#1 \\}
26 \define@key{Gin}{trim}
             {\let\Gin@viewport@code\Gin@trim\Gread@parse@vp#1 \\}
```

#### \Gread@parse@vp

Grabs four bounding box values like \Gread@parse@bp but saves them in alternative macros that are used in the viewport and trim cases to modify the bounding box read from the file.

```
28 \def\Gread@parse@vp#1 #2 #3 #4 #5\\{%
    \Gin@defaultbp\Gin@vllx{#1}%
    \Gin@defaultbp\Gin@vlly{#2}%
    \Gin@defaultbp\Gin@vurx{#3}%
    \Gin@defaultbp\Gin@vury{#4}}%
```

#### \Gin@viewport

If a viewport is specified, reset the bounding box coordinates by adding the original origin, \Gin@llx, \Gin@lly to the new values specified as the viewport. The original Bounding box coordinates are saved in \Gin@ollx... some drivers might need this information (currently just tcidvi).

```
33 \def\Gin@viewport{%
    \let\Gin@ollx\Gin@llx
34
    \let\Gin@olly\Gin@lly
    \let\Gin@ourx\Gin@urx
36
    \let\Gin@oury\Gin@ury
    \dimen@\Gin@llx\p@\advance\dimen@ \Gin@vurx\p@
38
                        \edef\Gin@urx{\strip@pt\dimen@}%
40
    \dimen@\Gin@lly\p@\advance\dimen@ \Gin@vury\p@
                         \edef\Gin@ury{\strip@pt\dimen@}%
41
    \dimen@\Gin@llx\p@\advance\dimen@ \Gin@vllx\p@
42
                         \edef\Gin@llx{\strip@pt\dimen@}%
43
    \dimen@\Gin@lly\p@\advance\dimen@ \Gin@vlly\p@
44
                        \edef\Gin@lly{\strip@pt\dimen@}}
```

\Gin@trim If a trim is specified, reset the bounding box coordinates by trimming the four specified values off each side of the graphic.

```
46 \def\Gin@trim{%
    \let\Gin@ollx\Gin@llx
47
    \let\Gin@olly\Gin@lly
```

```
\let\Gin@ourx\Gin@urx
                             \let\Gin@oury\Gin@ury
                             \dimen@\Gin@llx\p@\advance\dimen@ \Gin@vllx\p@
                                                 \edef\Gin@llx{\strip@pt\dimen@}%
                             \dimen@\Gin@lly\p@\advance\dimen@ \Gin@vlly\p@
                         54
                                                 \edef\Gin@lly{\strip@pt\dimen@}%
                             \dimen@\Gin@urx\p@\advance\dimen@ -\Gin@vurx\p@
                                                 \edef\Gin@urx{\strip@pt\dimen@}%
                         56
                             \dimen@\Gin@ury\p@\advance\dimen@ -\Gin@vury\p@
                                                 \edef\Gin@ury{\strip@pt\dimen@}}
                         58
              \Gin@vllx Four macros to hold the modifiers for the bounding box for viewport and trim
              \Gin@vlly specifications.
              \Gin@vurx 59 \let\Gin@vllx\Gin@llx\let\Gin@vlly\Gin@llx
              \Gin@vury 60 \let\Gin@vurx\Gin@llx\let\Gin@vury\Gin@llx
          \KV@Gin@angle Specify a rotation. This is just handled by wrapping the \includegraphics com-
                         mand in a call to the internal version of \rotatebox. Normally this is the 'stan-
                         dard' version but if an origin key is used in \includegraphics then the keyval
                         version of origin is used, and the origin key is passed on.
                         61 \define@key{Gin}{angle}
                                      {\Gin@esetsize
                         62
                                       \@tempswatrue
                                       \@tempa}
        \KV@Gin@origin Pass the origin key value on to \rotatebox. \Gin@erotate is initialised to
                         \Grot@box@std later in the file, after the latter has been defined.
                         66 \define@key{Gin}{origin}[c]{%
                         67 \def\Gin@erotate{\Grot@box@kv[origin=#1]}}
                        Save the required height and width. The actual scaling is done later.
         \KV@Gin@width
         \KV@Gin@height
                        68 \define@key{Gin}{width}{\def\Gin@ewidth{#1}}
                         69 \define@key{Gin}{height}{\def\Gin@eheight{#1}}
                         The same as height key, but locally changes \Gin@eresize to \totalheight from
    \KV@Gin@totalheight
                         its default value of \height.
                         70 \define@key{Gin}{totalheight}{%
                             \def\Gin@eresize{\totalheight}\def\Gin@eheight{#1}}
                         Boolean valued key (like clip). If it is set to true, modify the meaning of the width
\KV@Gin@keepaspectratio
                         and height (and totalheight) keys such that if both are specified then rather
                         than distort the figure the figure is scaled such that neither dimension exceeds the
                         stated dimensions.
                         72 \define@key{Gin}{keepaspectratio}[true]{%
                         73 \lowercase{\Gin@boolkey{#1}}{iso}}
```

```
\KV@Gin@scale If the scaling is being handled externally, wrap \includegraphics in the inter-
               nal form of \scalebox, otherwise locally define \Gin@req@sizes to calculate the
               required sizes based on scale factor.
               74 \define@key{Gin}{scale}{%
                  \if@tempswa
                     76
               77
               78
                   \else
               79
                     \def\Gin@req@sizes{%
                       \def\Gin@scalex{#1}\let\Gin@scaley\Gin@exclamation
               80
                       \Gin@req@height\Gin@scalex\Gin@nat@height
               81
               82
                       \Gin@req@width\Gin@scalex\Gin@nat@width}%
                   \fi
               83
                   \@tempswatrue}
\KV@Gin@draft Locally set the draft switch to true. This is used by the code in graphics package
               to suppress the file inclusion.
               85 \define@key{Gin}{draft}[true]{%
               86 \lowercase{\Gin@boolkey{#1}}{draft}}
 \KV@Gin@clip Locally set the clip switch to true. This is used by the code in graphics package to
               suppress the printing of anything outside the bounding box specified.
               87 \define@key{Gin}{clip}[true]{%
               88 \lowercase{\Gin@boolkey{#1}}{clip}}
 \KV@Gin@type If you use 'type' you must use no extension in the main argument and you must
               use 'ext'. You can also use 'read' and 'command'.
               89 \define@key{Gin}{type}{%
                  \def\Ginclude@graphics##1{%
               91
                     \begingroup
                     \def\Gin@base{##1}%
                     \edef\@tempa{{#1}{\Gin@eread}{\Gin@ecom{##1\Gin@eext}}}%
                     \expandafter\Gin@setfile\@tempa
               94
                     \endgroup}}
               95
  \KV@Gin@ext
              Specify an extension, for use with the 'type' key.
               96 \define@key{Gin}{ext}{\def\Gin@eext{#1}}
               97 \let\Gin@eext\@empty
 \KV@Gin@read Specify a read file, for use with the 'type' key. You may want to globally set
               this to * using \setkeys. * means read the graphic file for size info, as in
               \DeclareGraphicsRule.
               98 \define@key{Gin}{read}{%
               99 \def\Gin@eread{#1}%
              100 \def\@tempa{*}\ifx\@tempa\Gin@eread\def\Gin@eread{\Gin@eext}\fi}
```

101 \let\Gin@eread\@empty

```
\KV@Gin@command Specify a command, for use with the 'type' key.
                102 \define@key{Gin}{command}{\def\Gin@ecom##1{#1}}
                103 \let\Gin@ecom\@firstofone
                Helper function for defining boolean valued functions. The order of arguments
   \Gin@boolkey
                 allows \lowercase to only act on the user-supplied argument.
                104 \def\Gin@boolkey#1#2{%
                     \csname Gin0#2\ifx\relax#1\relax true\else#1\fi\endcsname}
 \Gin@esetsize Arrange for the final size to be set, either by wrapping the include graphics call
                 in \scalebox, or by redefining \Gin@req@sizes appropriately.
                106 \def\Gin@eresize{\height}
                107 \def\Gin@esetsize{%
                      \let\@tempa\Gin@exclamation
                108
                     \if@tempswa
                 External. Wrap the \includegraphics command in a call to the internal form of
                 \scalebox to handle the rotation.
                        \edef\@tempa{\toks@{\noexpand
                                 \Gscale@@box\noexpand\Gin@eresize
                                  {\Gin@ewidth}{\Gin@eheight}{\the\toks@}}}%
                112
                        \@tempa
                     \else
                114
                 Internal. Handle scaling with the \includegraphics command directly rather
                 than calling \scalebox.
                        \ifx\Gin@ewidth\@tempa
                116
                          \ifx\Gin@eheight\@tempa
                 No resizing.
                117
                         \else
                 Just height specified.
                118
                             \let\Gin@@eheight\Gin@eheight
                119
                             \def\Gin@req@sizes{%
                               \Gscale@div\Gin@scaley\Gin@@eheight\Gin@nat@height
                               \let\Gin@scalex\Gin@exclamation
                               \setlength\Gin@req@height\Gin@@eheight
                               \Gin@req@width\Gin@scaley\Gin@nat@width}%
                         \fi
                        \else
                          \ifx\Gin@eheight\@tempa
                 Just width specified.
                             \let\Gin@@ewidth\Gin@ewidth
                             \def\Gin@req@sizes{%
                128
                               \Gscale@div\Gin@scalex\Gin@@ewidth\Gin@nat@width
                               \let\Gin@scaley\Gin@exclamation
                               \setlength\Gin@req@width\Gin@@ewidth
                               \Gin@req@height\Gin@scalex\Gin@nat@height}%
```

\else

Both height and width specified.

```
134 \let\Gin@Gewidth\Gin@ewidth
135 \let\Gin@Geheight\Gin@eheight
```

At this point can locally redefine \Gin@nosize. Instead of generating an error, just set the 'natural' size to be the 'requested size'. Previous versions of this package did not allow the use of height and width unless the natural size was known as otherwise LATEX can not calculate the scale factor. However many drivers (especially for bitmap formats) can work this out themselves, so as long as both height and width are given, so LATEX knows the size to leave, accept this. This assumes the code in the driver file will use the 'required height' information, not the scale factors, which will be set to 1!.

Donald Arseneau requested this feature. If both height and width are chosen, choose the smaller scale factor rather than distort the graphic. This mode is turned on with the keepaspectratio key.

```
\ifGin@iso
                                      \ifdim\Gin@scaley\p@>\Gin@scalex\p@
                    143
                                        \let\Gin@scaley\Gin@scalex
                    146
                                        \let\Gin@scalex\Gin@scaley
                                      \fi
                                    \fi
                                    \Gin@req@width\Gin@scalex\Gin@nat@width
                                    \Gin@req@height\Gin@scaley\Gin@nat@height}%
                               \fi
                             \fi
                         \fi
                    154
                          \let\Gin@ewidth\Gin@exclamation
                          \let\Gin@eheight\Gin@ewidth}
  \Gin@req@height The required final size.
   \verb|\Gin@req@width||_{156} \verb|\newdimen|\Gin@req@height||
                    157 \newdimen\Gin@req@width
\Gin@outer@scalex Scale factors to pass to \scalebox.
\verb|\Gin@outer@scaley||_{158} \verb|\letGin@outer@scalex|| relax|
                    159 \let\Gin@outer@scaley\relax
```

\Gin@angle Rotation angle.

160 \let\Gin@angle\relax

```
\Gin@ewidth Final size, initialised for no scaling.
 \verb|\Gin@eheight||_{161} \verb|\let\Gin@ewidth\Gin@exclamation||
              162 \let\Gin@eheight\Gin@ewidth
  \Gin@scalex Scale factors. Initialised for no scaling.
  \verb|\Gin@scaley||_{163} \\ | | def \\ | Gin@scalex\{1\}|
              164 \let\Gin@scaley\Gin@exclamation
       \Gin@i Use the same top level \includegraphics command as the standard interface.
               This will set the clipping switch, and then call \Gin@i.
              165 \def\Gin@i{\%}
              166 \def\Gin@reg@sizes{%
                     \Gin@req@height\Gin@nat@height
                     \Gin@reg@width\Gin@nat@width}%
              168
                  \@ifnextchar[\Gin@ii{\Gin@ii[]}}
              169
      \Gin@ii Look for a second optional argument. If one optional argument is present, call
               \setkeys to process it,
              170 \def\Gin@ii[#1]#2{%
                      171
                      \ifx\@tempa\@tempb
              172
                        \def\@tempa{\Gin@iii[#1][}%
                        \expandafter\@tempa
              174
                      \else
                       \begingroup
                         \@tempswafalse
                         \toks@{\Ginclude@graphics{#2}}%
              178
                         \setkeys{Gin}{#1}%
                         \Gin@esetsize
              180
                         \the\toks@
              181
              182
                       \endgroup
              183
                       fi
                    Rotation
               5
   \rotatebox Look for an optional argument.
              184 \def\rotatebox{%
                   \leavevmode
              186
                    \@ifnextchar[\Grot@box@kv\Grot@box@std}
\Grot@box@std If no KV argument, just repeat the standard definition.
              187 \long\def\Grot@box@std#1#2{%
                    \Grot@setangle{#1}%
              188
                   \stbox\z@\hbox{{#2}}%
              189
              190 \Grot@x\z@
              191 \Grot@y\z@
                  \Grot@box}
```

```
\Grot@box@kv
                193 \long\def\Grot@box@kv[#1]#2#3{%
                     \@begin@tempboxa\hbox{#3}%
                        \Grot@x\width \divide\Grot@x\tw@
                196
                        \Grot@y\height \advance\Grot@y-\depth \divide\Grot@y\tw@
                        \setkeys{Grot}{#1}%
                        \setbox\z@\box\@tempboxa
                198
                199
                        \Grot@setangle{#2}%
                        \Grot@box
                     \@end@tempboxa}
                201
                     There are two ways of specifying the centre of rotation.
\KV@Grot@origin origin=\langle label \rangle, where the labels are up to two of lrctbB (B denotes the baseline,
                 as for PSTricks).
                202 \define@key{Grot}{origin}[c]{%
                203 \0tfor\0tempa:=#1\do{%
                204
                        \if r\@tempa \Grot@x\width\else
                        \if t\@tempa \Grot@y\height\else
                206
                207
                        \if b\@tempa \Grot@y-\depth\else
                        \if B\@tempa \Grot@y\z@\fi\fi\fi\fi\fi\}}
     \KV@Grot@x x = \langle dimen \rangle, y = \langle dimen \rangle The x, y coordinate of the centre of rotation. As usual
     \KV@Grot@y \height etc may be used.
                209 \define@key{Grot}{x}{\setlength\Grot@x{#1}}
                210 \define@key{Grot}{y}{\setlength\Grot@y{#1}}
\KV@Grot@units 'units' specifies the number or units in one anti-clockwise circle. So the default is
                 360. -360 gives clockwise rotation, 6.283185 gives radians etc.
                211 \define@key{Grot}{units}{%
                212 \def\Grot@setangle##1{%
                213 \dimen@##1\p@
                214 \dimen@ii#1\p@
                215 \divide\dimen@ii360\relax
                    \divide\dimen@\dimen@ii
                     \edef\Grot@angle{\number\dimen@}}}
                217
   \Gin@erotate Initialise the rotation command to use in \includegraphics.
                218 \let\Gin@erotate\Grot@box@std
                219 (/package)
```