

ArtemiS Administrator Guide

Configure clients, products, printing, and access

IT staff and template administrators · v1.0

Introduction

This guide is for people who **configure** ArtemiS: paths, printers, clients/products, template layouts, and who may open **Settings**.

Operators who only run daily batches should use the *Production User Guide* instead.

****Access:**** Settings opens only for Windows PC/domain administrators, or for users and groups explicitly authorized in ****Manage access****. There is no separate ArtemiS password — your Windows login is used.

Opening Settings

1. Start ArtemiS.
2. Click **Settings** at the bottom of the left sidebar.

If access is denied, your Windows account is not authorized. A domain administrator must add you under **Access** → **Manage access**.



Settings overview *Figure 1 — Settings: clients and products on the left; configuration tabs on the right.*

Settings layout

Area	Purpose
Clients and products	Search, add, edit, duplicate, delete
General tab	Folders, database path, audit, import/export
Printing tab	Registered printers, print engine, search groups
Access tab	Who may open Settings
Language tab	Default language, themes, extra translations

General tab — files and paths

Central workorders folder

Root folder where CSV work orders are stored. Each **search group** is a **subfolder** inside this path.

Example:

C:\Artemis\Workorders\

PADRAO\ ← group "PADRAO"

EXPRESS\ ← group "EXPRESS"

Old\ ← created automatically under each group after processing

After editing the path, click **Save**.

Database path

Location of the SQLite database (`database.db`) with clients, products, layouts, printers, and access rules.

- **Single PC:** a local path is fine.
- **Multiple PCs:** point every station to the **same network path** (UNC), e.g.
`\\server\Artemis\database.db`, so layouts stay in sync.

****Shared database:**** Avoid editing clients or layouts from many PCs at the same time. SQLite on a network share can lock or corrupt if many users write simultaneously. Prefer one central administrator for layout changes.

Audit / logs

Optional central audit database for configuration and production events. Leave empty to store audit data next to the main database.

Click **Audit / logs** to review recent actions.

Import and export

- **Import** — load a product layout from a JSON file (from another site or backup).
- **Export** — save the selected product layout to JSON for backup or migration.

 General tab Figure 2 — General tab: paths, audit, import/export.

Printing tab

Registered printers

Printers shown on the Production screen are **registered** here, not every Windows printer automatically.

Click **Manage printers**:

 Manage printers *Figure 3 — Register Windows printer names and friendly display names.*

Field	Meaning
Windows name	Exact name as shown in Windows Printers
Display name	Label operators see in the combo box
Active on production screen	Uncheck to hide without deleting
Notes	Optional reminder (tray, room, etc.)

Use **Search Windows** to discover installed printers on the current PC, then **Add selected**.

Each production PC still prints to **its local** Windows printers. Register the same logical printer on every station where operators need it.

Print engine

Choose how jobs are sent to the printer (e.g. PDFtoPrinter or Ghostscript). Click **Save engine** after changing.

Ghostscript status is shown on this tab. In deployed builds, Ghostscript ships inside the application folder.

Search groups (subfolders)

Click **Manage search subfolders** to add or remove group names.

 Manage search groups *Figure 4 — Group names map to subfolders under the central workorders folder.*

Adding a group **creates the matching folder on disk** if it does not exist. Operators then pick that group on the Production screen.

Access tab

PC and domain administrators always have access to Settings.

To allow non-admin operators (e.g. prepress staff):

1. Open **Manage access**.
2. Search for a **domain user** or **domain group** (preferred).
3. Add the selected principal.



Manage access *Figure 5 — Authorized Windows users and groups.*

Principal type	Example	Notes
Domain user	COMPANY\maria.silva	Works on any domain-joined PC
Domain group	COMPANY\Artemis-Admins	Recommended for teams
Local user	PC-NAME\localuser	Only valid on that PC

Remove access by selecting a row and clicking **Remove selected**.

Language and appearance

On the **Language** tab:

- **Default language on startup** — saved for all users on that PC (operators can still switch language on Production).
- **Extra language folder** — optional `.json` translation files.
- **Color theme** — applies after restarting ArtemiS.

Clients and products

Every printable layout belongs to a **client** and **product** pair. The first line of each WO CSV identifies which layout to use.

Add a client

1. Click **Add client**.
2. Enter a short name (e.g. customer code).
3. Confirm.

Add a product

1. Select a client in the list.
2. Click **Add product**.
3. Enter product name, paper color, orientation, and paper size.
4. Save — the **template editor** opens for layout design.

Edit an existing product

Select client → select product → **Edit** to open the template editor.

Duplicate or delete

- **Duplicate** — copy a product under the same or another client (useful for small layout variants).
- **Delete client** — removes the client and all its products (requires confirmation).



Clients and products *Figure 6 — Client list, product list, and actions.*

Template editor (layout design)

The editor is where you place text, barcodes, logos, and lines on the AR form.

 Template editor *Figure 7 — Visual editor with toolbox, canvas, and properties panel.*

Canvas and orientation

Choose a sheet layout:

- Three ARs vertical
- Two ARs horizontal or vertical
- Full A4 sheet

Set **paper color** and size to match physical stock used in production.

Tools (left toolbar)

Tool	Use for
Select	Move and resize elements
Line / Rectangle	Rules and boxes
Text	Fixed labels
Counter	Sequential numbers
Segment	Multi-part fields
Barcode	Code 128, Code 39, etc.
Image	Client logo (stored in database)

Select an element to edit properties: position, font, rotation, CSV column binding, default value.

CSV column binding

Variable fields (name, address, AR number) link to **CSV columns** from the work order file (e.g. `coluna_2`). Use the properties panel to pick the column.

If a column name in the layout does not exist in the CSV, that field is ****silently omitted**** on the printed form. Always test with a real WO file before production.

Testing a layout

Use **Test PDF** (or equivalent preview action) to generate a sample PDF and check alignment on paper.

Keyboard shortcuts

Key	Action
Delete	Remove selected element
Arrow keys	Nudge position
Ctrl+Z	Undo (up to 10 steps)
Ctrl+C	Duplicate selected elements (segments are not duplicated)

Save the layout when alignment is correct. The product is then available the next time an operator scans a matching WO.

Typical setup workflow

1. Set **central workorders folder** and **database path** (General).
2. Register **printers** and **search groups** (Printing).
3. Grant **access** to layout editors if they are not domain admins (Access).
4. **Add client** and **add product**.
5. Design and test the layout in the **template editor**.
6. Run a test batch from Production with **Create PDF** before going live on paper.

Network deployment checklist

Item	Recommendation
Database	Single UNC path, regular backup
Workorder folders	Shared or consistent paths per site
Settings access	Domain groups, not individual PCs
Layout changes	One administrator at a time
Printers	Register per production PC
Ghostscript / dist	Deploy full dist/ folder from build

Troubleshooting (administrators)

Problem	What to check
Operator cannot open Settings	Access tab → add user/group; or use domain admin
Product not found on scan	Client/product names in CSV vs database
Wrong alignment	Template editor → Test PDF; check orientation and paper size
Printer not in list	Manage printers → register and mark active
Group missing on Production	Manage search subfolders → add group
Mixed paper error for operators	Same product/paper rules — expected behavior

Getting help

Keep exported JSON backups of critical products. Document your central folder layout and registered printer names for each production PC.

ArtemiS Administrator Guide — English

ArtemiS — ArtemiS Administrator Guide