Spring boot 配置参数一览

```
# CORE PROPERTIES
   # SPRING 相关配置 (ConfigFileApplicationListener)
   spring.config.name= # config file name (default to 'application')
   spring.config.location= # location of config file
   # profile相关配置
   spring.profiles= # comma list of active profiles
# 系统配置相关参数 (SpringApplication)
   spring.main.sources=
   spring.main.web-environment= # detect by default
   spring.main.show-banner=true
   spring.main...= # see class for all properties
18 # 日志配置相关参数
19 logging.path=/var/logs
20 logging.file=myapp.log
   logging.config=
# IDENTITY (ContextIdApplicationContextInitializer)
   spring.application.name=
   spring.application.index=
   # tomcat相关配置参数 (ServerProperties)
   server.port=8080
29 server.address= # bind to a specific NIC
   server.session-timeout= # session timeout in seconds
   server.context-path= # the context path, defaults to '/'
   server.servlet-path= # the servlet path, defaults to '/'
   server.tomcat.access-log-pattern= # log pattern of the access log
   server.tomcat.access-log-enabled=false # is access logging enabled
   server.tomcat.protocol-header=x-forwarded-proto # ssl forward headers
   server.tomcat.remote-ip-header=x-forwarded-for
   server.tomcat.basedir=/tmp # base dir (usually not needed, defaults to
   tmp)
  server.tomcat.background-processor-delay=30; # in seconds
39 server.tomcat.max-threads = 0 # number of threads in protocol handler
   server.tomcat.uri-encoding = UTF-8 # character encoding to use for URL
   decoding
```

```
# springmvc相关配置参数 (HttpMapperProperties)
43 http.mappers.json-pretty-print=false # pretty print JSON
44 http.mappers.json-sort-keys=false # sort keys
   spring.mvc.locale= # set fixed locale, e.g. en_UK
   spring.mvc.date-format= # set fixed date format, e.g. dd/MM/yyyy
   spring.mvc.message-codes-resolver-format= # PREFIX ERROR CODE /
   POSTFIX ERROR CODE
   spring.view.prefix= # MVC view prefix
   spring.view.suffix= # ... and suffix
   spring.resources.cache-period= # cache timeouts in headers sent to browser
   spring.resources.add-mappings=true # if default mappings should be added
   # thymeleaf相关配置参数 (ThymeleafAutoConfiguration)
   spring.thymeleaf.prefix=classpath:/templates/
   spring.thymeleaf.suffix=.html
   spring.thymeleaf.mode=HTML5
   spring.thymeleaf.encoding=UTF-8
   spring.thymeleaf.content-type=text/html # ;charset=<encoding> is added
   spring.thymeleaf.cache=true # set to false for hot refresh
   # freemark相关配置参数 (FreeMarkerAutoConfiguration)
   spring.freemarker.allowRequestOverride=false
   spring.freemarker.allowSessionOverride=false
   spring.freemarker.cache=true
   spring.freemarker.checkTemplateLocation=true
   spring.freemarker.contentType=text/html
   spring.freemarker.exposeRequestAttributes=false
   spring.freemarker.exposeSessionAttributes=false
   spring.freemarker.exposeSpringMacroHelpers=false
   spring.freemarker.prefix=
   spring.freemarker.requestContextAttribute=
   spring.freemarker.settings.*=
   spring.freemarker.suffix=.ftl
   spring.freemarker.templateEncoding=UTF-8
   spring.freemarker.templateLoaderPath=classpath:/templates/
   spring.freemarker.viewNames= # whitelist of view names that can be
   resolved
   # groovy模板相关配置参数 (GroovyTemplateAutoConfiguration)
   spring.groovy.template.allowRequestOverride=false
   spring.groovy.template.allowSessionOverride=false
   spring.groovy.template.cache=true
   spring.groovy.template.configuration.*= # See Groovy's
   TemplateConfiguration
   spring.groovy.template.contentType=text/html
84 spring.groovy.template.prefix=classpath:/templates/
   spring.groovy.template.suffix=.tpl
   spring.groovy.template.templateEncoding=UTF-8
   spring.groovy.template.viewNames= # whitelist of view names that can be
   resolved
```

```
# velocity模板相关配置参数 (VelocityAutoConfiguration)
   spring.velocity.allowRequestOverride=false
    spring.velocity.allowSessionOverride=false
    spring.velocity.cache=true
    spring.velocity.checkTemplateLocation=true
    spring.velocity.contentType=text/html
    spring.velocity.dateToolAttribute=
    spring.velocity.exposeRequestAttributes=false
    spring.velocity.exposeSessionAttributes=false
    spring.velocity.exposeSpringMacroHelpers=false
    spring.velocity.numberToolAttribute=
    spring.velocity.prefix=
    spring.velocity.properties.*=
    spring.velocity.requestContextAttribute=
    spring.velocity.resourceLoaderPath=classpath:/templates/
    spring.velocity.suffix=.vm
    spring.velocity.templateEncoding=UTF-8
    spring.velocity.viewNames= # whitelist of view names that can be resolved
    # INTERNATIONALIZATION (MessageSourceAutoConfiguration)
    spring.messages.basename=messages
    spring.messages.cacheSeconds=-1
    spring.messages.encoding=UTF-8
    # 安全相关配置参数 (SecurityProperties)
security.user.name=user # login username
security.user.password= # login password
    security.user.role=USER # role assigned to the user
security.require-ssl=false # advanced settings ...
119 security.enable-csrf=false
security.basic.enabled=true
121 security.basic.realm=Spring
122 security.basic.path= # /**
security.headers.xss=false
124 security.headers.cache=false
security.headers.frame=false
security.headers.contentType=false
    security.headers.hsts=all # none / domain / all
    security.sessions=stateless # always / never / if_required / stateless
129 security.ignored=false
    # 数据源相关配置参数(DataSourceAutoConfiguration & DataSourceProperties)
   spring.datasource.name= # name of the data source
    spring.datasource.initialize=true # populate using data.sql
    spring.datasource.schema= # a schema (DDL) script resource reference
    spring.datasource.data= # a data (DML) script resource reference
    spring.datasource.platform= # the platform to use in the schema resource
    (schema-${platform}.sql)
```

```
spring.datasource.continueOnError=false # continue even if can't be
    initialized
spring.datasource.separator=; # statement separator in SQL initialization
spring.datasource.driverClassName= # JDBC Settings...
    spring.datasource.url=
    spring.datasource.username=
spring.datasource.password=
    spring.datasource.max-active=100 # Advanced configuration...
    spring.datasource.max-idle=8
   spring.datasource.min-idle=8
    spring.datasource.initial-size=10
    spring.datasource.validation-query=
    spring.datasource.test-on-borrow=false
    spring.datasource.test-on-return=false
    spring.datasource.test-while-idle=
    spring.datasource.time-between-eviction-runs-millis=
    spring.datasource.min-evictable-idle-time-millis=
    spring.datasource.max-wait-millis=
    # mongdb相关配置参数 (MongoProperties)
spring.data.mongodb.host= # the db host
    spring.data.mongodb.port=27017 # the connection port (defaults to 27107)
    spring.data.mongodb.uri=mongodb://localhost/test # connection URL
    spring.data.mongo.repositories.enabled=true # if spring data repository
    support is enabled
    # springDataJPA相关配置参数(JpaBaseConfiguration,
    HibernateJpaAutoConfiguration)
spring.jpa.properties.*= # properties to set on the JPA connection
    spring.jpa.openInView=true
    spring.jpa.show-sql=true
spring.jpa.database-platform=
    spring.jpa.database=
    spring.jpa.generate-ddl=false # ignored by Hibernate, might be useful for
    other vendors
    spring.jpa.hibernate.naming-strategy= # naming classname
    spring.jpa.hibernate.ddl-auto= # defaults to create-drop for embedded dbs
    spring.data.jpa.repositories.enabled=true # if spring data repository
    support is enabled
    # solr相关配置参数(SolrProperties})
    spring.data.solr.host=http://127.0.0.1:8983/solr
    spring.data.solr.zkHost=
    spring.data.solr.repositories.enabled=true # if spring data repository
    support is enabled
# elasticsearch相关配置参数(ElasticsearchProperties})
spring.data.elasticsearch.cluster-name= # The cluster name (defaults to
    elasticsearch)
```

```
spring.data.elasticsearch.cluster-nodes= # The address(es) of the server
node (comma-separated; if not specified starts a client node)
spring.data.elasticsearch.local=true # if local mode should be used with
client nodes
spring.data.elasticsearch.repositories.enabled=true # if spring data
repository support is enabled
# flyway相关配置参数(FlywayProperties)
flyway.locations=classpath:db/migrations # locations of migrations scripts
flyway.schemas= # schemas to update
flyway.initVersion= 1 # version to start migration
flyway.prefix=V
flyway.suffix=.sql
flvwav.enabled=true
flyway.url= # JDBC url if you want Flyway to create its own DataSource
flyway.user= # JDBC username if you want Flyway to create its own
DataSource
flyway.password= # JDBC password if you want Flyway to create its own
DataSource
# liquibase相关配置参数(LiquibaseProperties)
liquibase.change-log-classpath:/db/changelog/db.changelog-master.yaml
liquibase.contexts= # runtime contexts to use
liquibase.default-schema= # default database schema to use
liquibase.drop-first=false
liquibase.enabled=true
# JMX
spring.jmx.enabled=true # Expose MBeans from Spring
# rabbitmg相关配置参数(RabbitProperties)
spring.rabbitmq.host= # connection host
spring.rabbitmq.port= # connection port
spring.rabbitmq.addresses= # connection addresses (e.g.
myhost:9999,otherhost:1111)
spring.rabbitmq.username= # login user
spring.rabbitmq.password= # login password
spring.rabbitmq.virtualhost=
spring.rabbitmq.dynamic=
# redis相关配置参数(RedisProperties)
spring.redis.host=localhost # server host
spring.redis.password= # server password
spring.redis.port=6379 # connection port
spring.redis.pool.max-idle=8 # pool settings ...
spring.redis.pool.min-idle=0
spring.redis.pool.max-active=8
spring.redis.pool.max-wait=-1
```

```
# activemg相关配置参数(ActiveMQProperties)
    spring.activemq.broker-url=tcp://localhost:61616 # connection URL
226 spring.activemq.user=
    spring.activemq.password=
    spring.activemq.in-memory=true # broker kind to create if no broker-url is
    specified
    spring.activemq.pooled=false
    # hornetg相关配置参数(HornetQProperties)
    spring.hornetq.mode= # connection mode (native, embedded)
    spring.hornetq.host=localhost # hornetQ host (native mode)
    spring.hornetq.port=5445 # hornetQ port (native mode)
    spring.hornetq.embedded.enabled=true # if the embedded server is enabled
    (needs hornetq-jms-server.jar)
    spring.hornetq.embedded.serverId= # auto-generated id of the embedded
    server (integer)
    spring.hornetq.embedded.persistent=false # message persistence
    spring.hornetq.embedded.data-directory= # location of data content (when
    persistence is enabled)
    spring.hornetq.embedded.queues= # comma separate queues to create on
    startup
    spring.hornetq.embedded.topics= # comma separate topics to create on
    spring.hornetq.embedded.cluster-password= # customer password (randomly
    generated by default)
# JMS (JmsProperties)
    spring.jms.pub-sub-domain= # false for queue (default), true for topic
    # springbatch相关配置参数(BatchDatabaseInitializer)
    spring.batch.job.names=job1,job2
    spring.batch.job.enabled=true
    spring.batch.initializer.enabled=true
    spring.batch.schema= # batch schema to load
    # aop相关配置参数
    spring.aop.auto=
    spring.aop.proxy-target-class=
    # FILE ENCODING (FileEncodingApplicationListener)
    spring.mandatory-file-encoding=false
    # SPRING SOCIAL (SocialWebAutoConfiguration)
    spring.social.auto-connection-views=true # Set to true for default
    connection views or false if you provide your own
    # SPRING SOCIAL FACEBOOK (FacebookAutoConfiguration)
    spring.social.facebook.app-id= # your application's Facebook App ID
    spring.social.facebook.app-secret= # your application's Facebook App
    Secret
```

```
# SPRING SOCIAL LINKEDIN (LinkedInAutoConfiguration)
spring.social.linkedin.app-id= # your application's LinkedIn App ID
spring.social.linkedin.app-secret= # your application's LinkedIn App
Secret
# SPRING SOCIAL TWITTER (TwitterAutoConfiguration)
spring.social.twitter.app-id= # your application's Twitter App ID
spring.social.twitter.app-secret= # your application's Twitter App Secret
# SPRING MOBILE SITE PREFERENCE (SitePreferenceAutoConfiguration)
spring.mobile.sitepreference.enabled=true # enabled by default
# SPRING MOBILE DEVICE VIEWS
(DeviceDelegatingViewResolverAutoConfiguration)
spring.mobile.devicedelegatingviewresolver.enabled=true # disabled by
spring.mobile.devicedelegatingviewresolver.normalPrefix=
spring.mobile.devicedelegatingviewresolver.normalSuffix=
spring.mobile.devicedelegatingviewresolver.mobilePrefix=mobile/
spring.mobile.devicedelegatingviewresolver.mobileSuffix=
spring.mobile.devicedelegatingviewresolver.tabletPrefix=tablet/
spring.mobile.devicedelegatingviewresolver.tabletSuffix=
# -----
# ACTUATOR PROPERTIES
# MANAGEMENT HTTP SERVER (ManagementServerProperties)
management.port= # defaults to 'server.port'
management.address= # bind to a specific NIC
management.contextPath= # default to '/'
# ENDPOINTS (AbstractEndpoint subclasses)
endpoints.autoconfig.id=autoconfig
endpoints.autoconfig.sensitive=true
endpoints.autoconfig.enabled=true
endpoints.beans.id=beans
endpoints.beans.sensitive=true
endpoints.beans.enabled=true
endpoints.configprops.id=configprops
endpoints.configprops.sensitive=true
endpoints.configprops.enabled=true
endpoints.configprops.keys-to-sanitize=password,secret
endpoints.dump.id=dump
endpoints.dump.sensitive=true
endpoints.dump.enabled=true
endpoints.env.id=env
endpoints.env.sensitive=true
endpoints.env.enabled=true
endpoints.health.id=health
endpoints.health.sensitive=false
```

```
endpoints.health.enabled=true
   endpoints.info.id=info
316 endpoints.info.sensitive=false
    endpoints.info.enabled=true
    endpoints.metrics.id=metrics
    endpoints.metrics.sensitive=true
    endpoints.metrics.enabled=true
    endpoints.shutdown.id=shutdown
    endpoints.shutdown.sensitive=true
    endpoints.shutdown.enabled=false
    endpoints.trace.id=trace
    endpoints.trace.sensitive=true
    endpoints.trace.enabled=true
    # MVC ONLY ENDPOINTS
    endpoints.jolokia.path=jolokia
    endpoints.jolokia.sensitive=true
    endpoints.jolokia.enabled=true # when using Jolokia
    endpoints.error.path=/error
    # JMX ENDPOINT (EndpointMBeanExportProperties)
    endpoints.jmx.enabled=true
    endpoints.jmx.domain= # the JMX domain, defaults to 'org.springboot'
    endpoints.jmx.unique-names=false
    endpoints.jmx.enabled=true
    endpoints.jmx.staticNames=
    # JOLOKIA (JolokiaProperties)
    jolokia.config.*= # See Jolokia manual
    # REMOTE SHELL
    shell.auth=simple # jaas, key, simple, spring
    shell.command-refresh-interval=-1
    shell.command-path-pattern= # classpath*:/commands/**,
    classpath*:/crash/commands/**
348 shell.config-path-patterns= # classpath*:/crash/*
    shell.disabled-plugins=false # don't expose plugins
    shell.ssh.enabled= # ssh settings ...
351 shell.ssh.keyPath=
    shell.ssh.port=
    shell.telnet.enabled= # telnet settings ...
    shell.telnet.port=
    shell.auth.jaas.domain= # authentication settings ...
    shell.auth.key.path=
    shell.auth.simple.user.name=
    shell.auth.simple.user.password=
    shell.auth.spring.roles=
361 # GIT INFO
spring.git.properties= # resource ref to generated git info properties
```