CS162 Operating Systems and Systems Programming Lecture 9

Synchronization 4: Semaphores, Monitors and Readers/Writers

February 14th, 2023

Prof. John Kubiatowicz

http://cs162.eecs.Berkeley.edu

Recall: Atomic Read-Modify-Write

```
test&set (&address) {
                                 /* most architectures */
      result = M[address];
                               // return result from "address" and
                                 // set value at "address" to 1
      M[address] = 1;
      return result;
swap (&address, register) { /* x86 */
      temp = M[address];  // swap register's value to
      M[address] = register;  // value at "address"
      register = temp;
 compare&swap (&address, reg1, reg2) { /* x86 (returns old value), 68000 */
      if (reg1 == M[address]) { // If memory still == reg1,
          M[address] = reg2; // then put reg2 => memory
          return success;
                                 // Otherwise do not change memory
      } else {
          return failure;
 load-linked&store-conditional(&address) { /* R4000, alpha */
      loop:
           11 r1, M[address];
                                  // Can do arbitrary computation
           movi r2, 1;
           sc r2, M[address];
           begz r2, loop;
```

Recall: Better Locks using test&set

- Can we build test&set locks without busy-waiting?
 - Mostly. Idea: only busy-wait to atomically check lock value

```
- int guard = 0; // Global Variable!
  int mylock = FREE; // Interface: acquire(&mylock);
                                    release(&mylock);
  acquire(int *thelock) {
                                          release(int *thelock) {
                                             // Short busy-wait time
     // Short busy-wait time
                                             while (test&set(guard));
     while (test&set(guard));
                                             if anyone on wait queue {
     if (*thelock == BUSY) {
                                                take thread off wait queue
        put thread on wait queue;
                                                Place on ready queue;
        go to sleep() & guard = 0;
                                             } else {
        // guard == 0 on wakup!
                                                *thelock = FREE;
     } else {
        *thelock = BUSY;
                                             guard = 0;
        guard = 0;
```

- Note: sleep has to be sure to reset the guard variable
 - Why can't we do it just before or just after the sleep?

2/14/2023

Recall: Linux futex: Fast Userspace Mutex

- ptr to a timespec structure that specifies a timeout for the op
- Interface to the kernel sleep() functionality!
 - Let thread put themselves to sleep conditionally!
- futex is not exposed in libc; it is used within the implementation of pthreads
 - Can be used to implement locks, semaphores, monitors, etc...


Recall: Lock Using Atomic Instructions and Futex

- Three (3) states:
 - UNLOCKED: No one has lock
 - LOCKED: One thread has lock
 - CONTESTED: Possibly more than one (with someone sleeping)
- Clean interface!
- Lock grabbed cleanly by either
 - compare_and_swap()
 - First swap()
- No overhead if uncontested!
- Could build semaphores in a similar way!

```
typedef enum { UNLOCKED, LOCKED, CONTESTED } Lock;
Lock mylock = UNLOCKED; // Interface: acquire(&mylock);
                                      release(&mylock);
acquire(Lock *thelock) {
  // If unlocked, grab lock!
  if (compare&swap(thelock,UNLOCKED,LOCKED))
     return;
  // Keep trying to grab lock, sleep in futex
  while (swap(mylock,CONTESTED) != UNLOCKED))
     // Sleep unless someone releases here!
     futex(thelock, FUTEX WAIT, CONTESTED);
}
release(Lock *thelock) {
  // If someone sleeping,
  if (swap(thelock,UNLOCKED) == CONTESTED)
     futex(thelock,FUTEX WAKE,1);
```

Producer-Consumer with a Bounded Buffer

- Problem Definition
 - Producer(s) put things into a shared buffer
 - Consumer(s) take them out
 - Need synchronization to coordinate producer/consumer



- Need to synchronize access to this buffer
- Producer needs to wait if buffer is full
- Consumer needs to wait if buffer is empty
- Example 1: GCC compiler
 - cpp | cc1 | cc2 | as | ld
- Example 2: Coke machine
 - Producer can put limited number of Cokes in machine
 - Consumer can't take Cokes out if machine is empty
- Others: Web servers, Routers,




Consume

Producer

Bounded Buffer Data Structure (sequential case)

```
typedef struct buf {
  int write_index;
  int read_index;
  <type> *entries[BUFSIZE];
} buf_t;
```



- Insert: write & bump write ptr (enqueue)
- Remove: read & bump read ptr (dequeue)
- How to tell if Full (on insert) Empty (on remove)?
- And what do you do if it is?
- What needs to be atomic?

Bounded Buffer – first cut

```
mutex buf_lock = <initially unlocked>
Producer(item) {
  acquire(&buf_lock);
 while (buffer full) {}; // Wait for a free slot
  enqueue(item);
  release(&buf lock);
                                Will we ever come out
                                of the wait loop?
Consumer() {
  acquire(&buf lock);
 while (buffer empty) {}; // Wait for arrival
  item = dequeue();
  release(&buf_lock);
  return item
```

Bounded Buffer – 2nd cut



```
mutex buf_lock = <initially unlocked>
```

```
Producer(item) {
    acquire(&buf_lock);
    while (buffer full) {release(&buf_lock); acquire(&buf_lock);}
    enqueue(item);
    release(&buf_lock);
}

Consumer() {
    acquire(&buf_lock);
    while (buffer empty) {release(&buf_lock); acquire(&buf_lock);}
    item = dequeue();
    release(&buf_lock);
    return item
}
```

Higher-level Primitives than Locks

- What is right abstraction for synchronizing threads that share memory?
 - Want as high a level primitive as possible
- Good primitives and practices important!
 - Since execution is not entirely sequential, really hard to find bugs, since they happen rarely
 - UNIX is pretty stable now, but up until about mid-80s
 (10 years after started), systems running UNIX would crash every week or so concurrency bugs
- Synchronization is a way of coordinating multiple concurrent activities that are using shared state
 - This lecture presents some ways to structuring sharing


Semaphores



- Semaphores are a kind of generalized lock
 - First defined by Dijkstra in late 60s
 - Main synchronization primitive used in original UNIX
- Definition: a Semaphore has a non-negative integer value and supports the following operations:
 - Set value when you initialize
 - Down() or P(): an atomic operation that waits for semaphore to become positive, then decrements it by 1
 - » Think of this as the wait() operation
 - Up() or V(): an atomic operation that increments the semaphore by 1, waking up a waiting P, if any
 - » This of this as the signal() operation
- Technically examining value after initialization is not allowed.

Semaphores Like Integers Except...

- Semaphores are like integers, except:
 - No negative values
 - Only operations allowed are P and V can't read or write value, except initially
 - Operations must be atomic
 - » Two P's together can't decrement value below zero
 - » Thread going to sleep in P won't miss wakeup from V even if both happen at same time
- POSIX adds ability to read value, but technically not part of proper interface!
- Semaphore from railway analogy
 - Here is a semaphore initialized to 2 for resource control:



Two Uses of Semaphores

Mutual Exclusion (initial value = 1)

- Also called "Binary Semaphore" or "mutex".
- Can be used for mutual exclusion, just like a lock:

```
semaP(&mysem);
  // Critical section goes here
semaV(&mysem);
```

Scheduling Constraints (initial value = 0)

- Allow thread 1 to wait for a signal from thread 2
 - thread 2 schedules thread 1 when a given event occurs
- Example: suppose you had to implement ThreadJoin which must wait for thread to terminate:

```
Initial value of semaphore = 0
ThreadJoin {
    semaP(&mysem);
}
ThreadFinish {
    semaV(&mysem);
}
```

Revisit Bounded Buffer: Correctness constraints for solution

- Correctness Constraints:
 - Consumer must wait for producer to fill buffers, if none full (scheduling constraint)
 - Producer must wait for consumer to empty buffers, if all full (scheduling constraint)
 - Only one thread can manipulate buffer queue at a time (mutual exclusion)
- Remember why we need mutual exclusion
 - Because computers are stupid
 - Imagine if in real life: the delivery person is filling the machine and somebody comes up and tries to stick their money into the machine
- General rule of thumb: Use a separate semaphore for each constraint
 - Semaphore fullBuffers; // consumer's constraint
 - Semaphore emptyBuffers;// producer's constraint
 - Semaphore mutex; // mutual exclusion

Bounded Buffer, 3rd cut (coke machine)

```
Semaphore fullSlots = 0; // Initially, no coke
            Semaphore emptySlots = bufSize;
                                          // Initially, num empty slots
            Semaphore mutex = 1;
                                         // No one using machine
            Producer(item) {
                semaP(&emptySlots);
                                         // Wait until space
                                             Wait until machine free
                semaP(&mutex);
                Enqueue(item);
                semaV(&mutex)
                semaV(&fullSiots);
                                          // Tell consumers there is
                                                                       Critical sections
                                          // more coke
                                                                       using mutex
                                      fullSlots signals coke
                                                                       protect integrity
            Consumer()
                                                                       of the queue
                semaP(&fullSlots);
                                          // Check if there's a coke
                semaP(&mutex);
                                          // Wait until machine free
emptySlots\
                item = Dequeue();
                semaV(&mutex);
signals space
                                          // tell producer need more
                semaV(&emptySlots);
                return item;
```

Discussion about Solution

Why asymmetry?

Decrease # of empty slots

Increase # of occupied slots

- Producer does: semaP(&emptyBuffer), semaV(&fullBuffer)
- Consumer does: semaP(&fullBuffer), semaV(&emptyBuffer)

Decrease # of occupied slots

Increase # of empty slots

- Is order of P's important?
- Is order of V's important?
- What if we have 2 producers or 2 consumers?

```
Producer(item) {
    semaP(&mutex);
    semaP(&emptySlots);
    Enqueue(item);
    semaV(&mutex);
    semaV(&fullSlots);
}
Consumer() {
    semaP(&fullSlots);
    semaP(&mutex);
    item = Dequeue();
    semaV(&mutex);
    semaV(&emptySlots);
    return item;
}
```

Administrivia

- Midterm This Thursday, 7-9pm (February 16)!
 - In person: 150 Wheeler unless you have alternative from us
 - You are responsible for all materials up to and including today's lecture!
 - » Including Semaphores and Monitors
- You get one (1) double-side page of handwritten notes
 - Hand drawn figures, hand written notes
 - No copying of figures directly from slides, no microfiche, etc.
 - Redraw them if you want them on your notes!
- If you are sick, let us know.
 - Do not come to the midterm!
- No class on Thursday
 - I will have extra office hours during class time
- Do not seek out information about projects or homework from previous terms!
 - This includes solutions, rubrics, any other information!
 - Something like this constitutes academic dishonesty


Semaphores are good but...Monitors are better!

- Semaphores are a huge step up; just think of trying to do the bounded buffer with only loads and stores or even with locks!
- Problem is that semaphores are dual purpose:
 - They are used for both mutex and scheduling constraints
 - Example: the fact that flipping of P's in bounded buffer gives deadlock is not immediately obvious. How do you prove correctness to someone?
- Cleaner idea: Use locks for mutual exclusion and condition variables for scheduling constraints
- Definition: Monitor: a lock and zero or more condition variables for managing concurrent access to shared data
 - Some languages like Java provide this natively
 - Most others use actual locks and condition variables
- A "Monitor" is a paradigm for concurrent programming!
 - Some languages support monitors explicitly

Condition Variables

- How do we change the consumer() routine to wait until something is on the queue?
 - Could do this by keeping a count of the number of things on the queue (with semaphores), but error prone
- Condition Variable: a queue of threads waiting for something inside a critical section
 - Key idea: allow sleeping inside critical section by atomically releasing lock at time we go to sleep
 - Contrast to semaphores: Can't wait inside critical section
- Operations:
 - Wait(&lock): Atomically release lock and go to sleep.
 Re-acquire lock later, before returning.
 - Signal(): Wake up one waiter, if any
 - Broadcast(): Wake up all waiters
- Rule: Must hold lock when doing condition variable ops!

Monitor with Condition Variables



- Lock: the lock provides mutual exclusion to shared data
 - Always acquire before accessing shared data structure
 - Always release after finishing with shared data
 - Lock initially free
- Condition Variable: a queue of threads waiting for something inside a critical section
 - Key idea: make it possible to go to sleep inside critical section by atomically releasing lock at time we go to sleep
 - Contrast to semaphores: Can't wait inside critical section

Infinite Synchronized Buffer (with condition variable)

Here is an (infinite) synchronized queue:

```
Producer(item) {
  Consumer() {
  acquire(&buf lock);
                       // Get Lock
  while (isEmpty(&queue)) {
    cond_wait(&buf_CV, &buf_lock); // If empty, sleep
  item = dequeue(&queue);  // Get next item
release(&buf_lock);  // Release Lock
  return(item);
```

Mesa vs. Hoare monitors

Need to be careful about precise definition of signal and wait.
 Consider a piece of our dequeue code:

```
while (isEmpty(&queue)) {
    cond_wait(&buf_CV,&buf_lock); // If nothing, sleep
}
    item = dequeue(&queue); // Get next item

- Why didn't we do this?
    if (isEmpty(&queue)) {
        cond_wait(&buf_CV,&buf_lock); // If nothing, sleep
    }
    item = dequeue(&queue); // Get next item
```

- Answer: depends on the type of scheduling
 - Mesa-style: Named after Xerox-Park Mesa Operating System
 Most OSes use Mesa Scheduling!
 - Hoare-style: Named after British logician Tony Hoare

Hoare monitors

- Signaler gives up lock, CPU to waiter; waiter runs immediately
- Then, Waiter gives up lock, processor back to signaler when it exits critical section or if it waits again

- On first glance, this seems like good semantics
 - Waiter gets to run immediately, condition is still correct!
- Most textbooks talk about Hoare scheduling
 - However, hard to do, not really necessary!
 - Forces a lot of context switching (inefficient!)

Mesa monitors

- Signaler keeps lock and processor
- Waiter placed on ready queue with no special priority

```
Put waiting thread on ready queue acquire(&buf_lock);

...

while (isEmpty(&queue)) {

cond_signal(&buf_CV);

...

cond_wait(&buf_CV, &buf_lock);

...

release(&buf_lock));

schedule thread

lock.Release();
```

- Practically, need to check condition again after wait
 - By the time the waiter gets scheduled, condition may be false again so, just check again with the "while" loop
- Most real operating systems do this!
 - More efficient, easier to implement
 - Signaler's cache state, etc still good


Bounded Buffer – 4rd cut (Monitors, pthread-like)

```
lock buf lock = <initially unlocked>
condition producer CV = <initially empty>
condition consumer CV = <initially empty>
Producer(item) {
  acquire(&buf lock);
  while (buffer full) { cond wait(&producer CV, &buf lock); }
  enqueue(item);
  cond_signal(&consumer CV)
                                    What does thread do
  release(&buf lock);
                                    when it is waiting?
                                     - Sleep, not busywait!
Consumer() {
  acquire(buf lock);
  while (buffer empty) { cond wait(&consumer CV, &buf lock); }
  item = dequeue();
  cond signal(&producer CV);
  release(buf lock);
  return item
```

Again: Why the while Loop?

- MESA semantics
- For most operating systems, when a thread is woken up by signal(), it is simply put on the ready queue
- It may or may not reacquire the lock immediately!
 - Another thread could be scheduled first and "sneak in" to empty the queue
 - Need a loop to re-check condition on wakeup
- Is this busy waiting?

Readers/Writers Problem



- Motivation: Consider a shared database
 - Two classes of users:
 - » Readers never modify database
 - » Writers read and modify database
 - Is using a single lock on the whole database sufficient?
 - » Like to have many readers at the same time
 - » Only one writer at a time

Basic Structure of *Mesa* Monitor Program

- Monitors represent the synchronization logic of the program
 - Wait if necessary
 - Signal when change something so any waiting threads can proceed
- Basic structure of mesa monitor-based program:

```
lock
while (need to wait) {
    condvar.wait();
}
unlock

do something so no need to wait

lock

condvar.signal();

Check and/or update
    state variables

Check and/or update
    state variables

unlock
```

Basic Readers/Writers Solution


- Correctness Constraints:
 - Readers can access database when no writers
 - Writers can access database when no readers or writers
 - Only one thread manipulates state variables at a time
- Basic structure of a solution:
 - Reader()

Wait until no writers Access data base Check out - wake up a waiting writer

- Writer()

Wait until no active readers or writers Access database Check out - wake up waiting readers or writer

- State variables (Protected by a lock called "lock"):
 - » int AR: Number of active readers; initially = 0
 - » int WR: Number of waiting readers; initially = 0
 - » int AW: Number of active writers; initially = 0
 - » int WW: Number of waiting writers; initially = 0
 - » Condition okToRead = NIL
 - » Condition okToWrite = NIL



Code for a Reader

```
Reader() {
 // First check self into system
 acquire(&lock);
 while ((AW + WW) > 0) { // Is it safe to read?
                          // No. Writers exist
   WR++;
    cond wait(&okToRead,&lock);// Sleep on cond var
   WR--;
                          // No longer waiting
  }
                          // Now we are active!
 AR++;
 release (&lock);
 // Perform actual read-only access
 AccessDatabase(ReadOnly);
 // Now, check out of system
 acquire(&lock);
 AR--;
                          // No longer active
 if (AR == 0 \&\& WW > 0) // No other active readers
    cond signal(&okToWrite);// Wake up one writer
 release(&lock);
```

Code for a Writer

```
Writer() {
  // First check self into system
  acquire(&lock);
 while ((AW + AR) > 0) { // Is it safe to write?
                          // No. Active users exist
    WW++;
    cond wait(&okToWrite,&lock); // Sleep on cond var
                         // No longer waiting
    ₩W--;
                          // Now we are active!
 AW++;
 release (&lock);
  // Perform actual read/write access
 AccessDatabase(ReadWrite);
  // Now, check out of system
  acquire(&lock);
                          // No longer active
 AW--;
                         // Give priority to writers
  if (WW > 0) {
    cond signal(&okToWrite);// Wake up one writer
  } else if (WR > 0) { // Otherwise, wake reader
    cond broadcast(&okToRead); // Wake all readers
  release(&lock);
```

- Use an example to simulate the solution
- Consider the following sequence of operators:
 - -R1, R2, W1, R3
- Initially: AR = 0, WR = 0, AW = 0, WW = 0

- R1 comes along (no waiting threads)
- AR = 0, WR = 0, AW = 0, WW = 0

R1 comes along (no waiting threads)

```
• AR = 0, WR = 0, AW = 0, WW = 0
```

```
Reader() {
   acquire(&lock);
   while ((AW + WW))
                            // Is it safe to read?
                             // No. Writers exist
      cond wait(&okToRead, &lock);// Sleep on cond var
                             // No longer waiting
   AR++;
                             // Now we are active!
   release(&lock);
   AccessDBase(ReadOnly);
   acquire(&lock);
   AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
   release(&lock);
```

R1 comes along (no waiting threads)

```
• AR = 1. WR = 0. AW = 0. WW = 0
Reader() {
   acquire(&lock);
   while ((AW + WW) > 0) { // Is it safe to read?
                             // No. Writers exist
      cond wait(&okToRead,&lock);// Sleep on cond var
                            // No longer waiting
   AR++;
                             // Now we are active!
   release(&lock);
   AccessDBase(ReadOnly);
   acquire(&lock);
   AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
    release(&lock);
```

R1 comes along (no waiting threads)

```
• AR = 1. WR = 0. AW = 0. WW = 0
Reader() {
    acquire(&lock);
    while ((AW + WW) > 0) { // Is it safe to read?
                              // No. Writers exist
      cond wait(&okToRead,&lock);// Sleep on cond var
                             // No longer waiting
      WR = -\overline{;}
    AR++;
                              // Now we are active!
    release(&lock);
    AccessDBase(ReadOnly);
    acquire(&lock);
    AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
    release(&lock);
```

R1 accessing dbase (no other threads)

```
• AR = 1. WR = 0. AW = 0. WW = 0
Reader() {
   acquire(&lock);
   while ((AW + WW) > 0) { // Is it safe to read?
                            // No. Writers exist
      cond wait(&okToRead, &lock);// Sleep on cond var
                         // No longer waiting
   AR++;
                             // Now we are active!
   release(&lock);
   AccessDBase (ReadOnly)
   acquire(&lock);
   AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
   release(&lock);
```

- R2 comes along (R1 accessing dbase)
- AR = 1, WR = 0, AW = 0, WW = 0

R2 comes along (R1 accessing dbase)

```
• AR = 1. WR = 0. AW = 0. WW = 0
Reader() {
   acquire(&lock);
   while ((AW + WW))
                     > 0) { // Is it safe to read?
                             // No. Writers exist
      cond wait(&okToRead, &lock);// Sleep on cond var
                             // No longer waiting
   AR++;
                             // Now we are active!
   release(&lock);
   AccessDBase(ReadOnly);
   acquire(&lock);
   AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
   release(&lock);
```

R2 comes along (R1 accessing dbase)

```
• AR = 2, WR = 0, AW = 0, WW = 0
Reader() {
   acquire(&lock);
   while ((AW + WW) > 0) { // Is it safe to read?
                             // No. Writers exist
      cond wait(&okToRead, &lock);// Sleep on cond var
                            // No longer waiting
   AR++;
                             // Now we are active!
   release(&lock);
   AccessDBase(ReadOnly);
   acquire(&lock);
   AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
    release(&lock);
```

R2 comes along (R1 accessing dbase)

```
• AR = 2. WR = 0. AW = 0. WW = 0
Reader() {
    acquire(&lock);
    while ((AW + WW) > 0) { // Is it safe to read?
                              // No. Writers exist
      cond wait(&okToRead, &lock);// Sleep on cond var
                             // No longer waiting
      WR - -\overline{;}
    AR++;
                              // Now we are active!
    release(&lock);
    AccessDBase(ReadOnly);
    acquire(&lock);
    AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
    release(&lock);
```

cond wait(&okToRead, &lock);// Sleep on cond var

// No longer waiting

// Now we are active!

R1 and R2 accessing dbase

AccessDBase (ReadOnly)

release(&lock);

AR++;

```
acquire(&lock);
AR--;
if (AR == 0 && WW > 0)
```

Assume readers take a while to access database Situation: Locks released, only AR is non-zero

- W1 comes along (R1 and R2 are still accessing dbase)
- AR = 2, WR = 0, AW = 0, WW = 0

W1 comes along (R1 and R2 are still accessing dbase)

```
• AR = 2, WR = 0, AW = 0, WW = 0
```

W1 comes along (R1 and R2 are still accessing dbase)

```
    AR = 2, WR = 0, AW = 0, WW = 1

Writer() {
  acquire(&lock);
  AW++;
  release (&lock);
  AccessDBase (ReadWrite) ;
  acquire(&lock);
    cond signal(&okToWrite);
  } else if (WR > 0)
    cond broadcast(&okToRead);
  release (&lock);
```

- R3 comes along (R1 and R2 accessing dbase, W1 waiting)
- AR = 2, WR = 0, AW = 0, WW = 1

```
Reader() {
   acquire(&lock);
    while ((AW + WW) > 0) { // Is it safe to read?
                              // No. Writers exist
      cond wait(&okToRead, &lock);// Sleep on cond var
                              // No longer waiting
      WR - -\overline{;}
    AR++;
                              // Now we are active!
    release(&lock);
    AccessDBase(ReadOnly);
    acquire(&lock);
    AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
    release(&lock);
```

R3 comes along (R1 and R2 accessing dbase, W1 waiting)

```
    AR = 2, WR = 0, AW = 0, WW = 1
```

```
Reader() {
   acquire(&lock);
   while ((AW + WW))
                            // Is it safe to read?
                             // No. Writers exist
      cond wait(&okToRead, &lock);// Sleep on cond var
                             // No longer waiting
   AR++;
                             // Now we are active!
   release(&lock);
   AccessDBase(ReadOnly);
   acquire(&lock);
   AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
    release(&lock);
```

R3 comes along (R1 and R2 accessing dbase, W1 waiting)

```
    AR = 2, WR = 1, AW = 0, WW = 1
```

```
Reader() {
    acquire(&lock);
    while ((AW + WW) > 0) { // Is it safe to read?
                           // No. Writers exist
      cond wait(&okToRead, &lock);// Sleep on cond var
                             // No longer waiting
      WR - -\overline{;}
    AR++;
                              // Now we are active!
    lock.release();
    AccessDBase(ReadOnly);
    acquire(&lock);
    AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
    release(&lock);
```

R3 comes along (R1, R2 accessing dbase, W1 waiting)

```
    AR = 2, WR = 1, AW = 0, WW = 1

Reader() {
    acquire(&lock);
    while ((AW + WW) > 0) { // Is it safe to read?
                             // No. Writers exist
      WR++;
      cond wait(&okToRead,&lock);// Sleep on cond var
      WR--;
                             // No longer waiting
    AR++;
                             // Now we are active!
    release(&lock);
    AccessDBase(ReadOnly);
    acquire(&lock);
    AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
    release(&lock);
```

R1 and R2 accessing dbase, W1 and R3 waiting

Status:

- R1 and R2 still reading
- W1 and R3 waiting on okToWrite and okToRead, respectively

```
    AR = 2, WR = 1, AW = 0, WW = 1

Reader() {
    acquire(&lock);
    while ((AW + WW) > 0) { // Is it safe to read?
                              // No. Writers exist
      cond wait(&okToRead, &lock);// Sleep on cond var
                           // No longer waiting
      WR - -\overline{;}
    AR++;
                              // Now we are active!
    release(&lock);
    AccessDBase(ReadOnly);
   acquire(&lock);
    AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
    release(&lock);
```

```
    AR = 1, WR = 1, AW = 0, WW = 1

Reader() {
    acquire(&lock);
    while ((AW + WW) > 0) { // Is it safe to read?
                              // No. Writers exist
      cond wait(&okToRead, &lock);// Sleep on cond var
                           // No longer waiting
      WR - -\overline{;}
    AR++;
                              // Now we are active!
    release(&lock);
    AccessDBase(ReadOnly);
    acquire(&lock);
   AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
    release(&lock);
```

```
    AR = 1, WR = 1, AW = 0, WW = 1

Reader() {
    acquire(&lock);
    while ((AW + WW) > 0) { // Is it safe to read?
                             // No. Writers exist
      cond wait(&okToRead, &lock);// Sleep on cond var
                          // No longer waiting
      WR - -\overline{;}
    AR++;
                              // Now we are active!
    release(&lock);
    AccessDBase(ReadOnly);
    acquire(&lock);
    AR--;
   if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
    release(&lock);
```

```
    AR = 1, WR = 1, AW = 0, WW = 1

Reader() {
    acquire(&lock);
    while ((AW + WW) > 0) { // Is it safe to read?
                              // No. Writers exist
      cond wait(&okToRead, &lock);// Sleep on cond var
                          // No longer waiting
      WR - -\overline{;}
    AR++;
                              // Now we are active!
    release(&lock);
    AccessDBase(ReadOnly);
    acquire(&lock);
    AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
    release(&lock);
```

 R1 finishes (W1 and R3 waiting) AR = 1, WR = 1, AW = 0, WW = 1 Reader() { acquire(&lock); while ((AW + WW) > 0) { // Is it safe to read? // No. Writers exist cond wait(&okToRead,&lock);// Sleep on cond var // No longer waiting WR--; AR++; // Now we are active! release(&lock); AccessDBase(ReadOnly); acquire(&lock); AR--; if (AR == 0 && WW > 0)cond signal(&okToWrite); release(&lock);

 R1 finishes (W1, R3 waiting) • AR = 0, WR = 1, AW = 0, WW = 1 Reader() { acquire(&lock); while ((AW + WW) > 0) { // Is it safe to read? // No. Writers exist cond wait(&okToRead,&lock);// Sleep on cond var // No longer waiting AR++; // Now we are active! release(&lock); AccessDBase(ReadOnly); acquire(&lock); AR--; if (AR == 0 && WW > 0)cond signal(&okToWrite); release(&lock);

 R1 finishes (W1, R3 waiting) • AR = 0, WR = 1, AW = 0, WW = 1 Reader() { acquire(&lock); while ((AW + WW) > 0) { // Is it safe to read? // No. Writers exist cond wait(&okToRead,&lock);// Sleep on cond var // No longer waiting AR++; // Now we are active! release(&lock); AccessDBase(ReadOnly); acquire(&lock); AR--; if (AR == 0 && WW > 0)cond signal(&okToWrite); release(&lock);

R1 signals a writer (W1 and R3 waiting)

```
    AR = 0, WR = 1, AW = 0, WW = 1

Reader() {
   acquire(&lock);
   while ((AW + WW) > 0) { // Is it safe to read?
                            // No. Writers exist
      cond wait(&okToRead,&lock);// Sleep on cond var
                         // No longer waiting
   AR++;
                             // Now we are active!
   release(&lock);
   AccessDBase(ReadOnly);
   acquire(&lock);
   AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
   release(&lock);
```

 W1 gets signal (R3 still waiting) AR = 0, WR = 1, AW = 0, WW = 1 Writer() { acquire(&lock); // Is it safe to write?
// No. Active users exist while ((AW + AR) > 0) { WW++; AW++;release (&lock); AccessDBase (ReadWrite) ; acquire(&lock); cond signal(&okToWrite); } else if (WR > 0) cond broadcast(&okToRead);

release (&lock);

W1 gets signal (R3 still waiting)

```
    AR = 0. WR = 1. AW = 0. WW = 0

Writer() {
    acquire(&lock);
                                   // Is it safe to write?
// No. Active users exist
    while ((AW + AR) > 0) {
       cond wait(&okToWrite, &lock);// Sleep on cond var
WW--; // No longer waiting
    AW++;
    release (&lock);
    AccessDBase (ReadWrite) ;
    acquire(&lock);
       cond signal(&okToWrite);
     } else if (WR > 0)
       cond broadcast(&okToRead);
    release (&lock);
```

 W1 gets signal (R3 still waiting) AR = 0. WR = 1. AW = 1. WW = 0 Writer() { acquire(&lock); // Is it safe to write?
// No.,Active users exist while ((AW + AR) > 0) { AW++;release(&lock); AccessDBase (ReadWrite) ; acquire(&lock); cond signal(&okToWrite); } else if (WR > 0) cond broadcast(&okToRead); release (&lock);

W1 accessing dbase (R3 still waiting)

```
• AR = 0. WR = 1. AW = 1. WW = 0
Writer() {
   acquire(&lock);
   AW++;
   release (&lock);
   AccessDBase (ReadWrite)
   acquire(&lock);
     cond signal(&okToWrite);
   } else if (WR > 0)
     cond broadcast(&okToRead);
   release (&lock);
```

 W1 finishes (R3 still waiting) • AR = 0. WR = 1. AW = 1. WW = 0 Writer() { acquire(&lock); AW++;release (&lock); AccessDBase (ReadWrite) ; acquire(&lock); cond signal(&okToWrite); } else if (WR > 0) cond broadcast(&okToRead); release (&lock);

 W1 finishes (R3 still waiting) • AR = 0. WR = 1. AW = 0. WW = 0 Writer() { acquire(&lock); AW++;release (&lock); AccessDBase (ReadWrite) ; acquire(&lock): cond signal(&okToWrite); } else if (WR > 0) cond broadcast(&okToRead);

release (&lock);

W1 finishes (R3 still waiting)

```
• AR = 0. WR = 1. AW = 0. WW = 0
Writer() {
   acquire(&lock);
   AW++;
   release (&lock);
   AccessDBase(ReadWrite);
   acquire(&lock);
     cond signal(&okToWrite);
   } else if (WR > 0)
     cond broadcast(&okToRead);
   release (&lock);
```

W1 signaling readers (R3 still waiting)

```
    AR = 0, WR = 1, AW = 0, WW = 0

Writer() {
   acquire(&lock);
   AW++;
   release (&lock);
   AccessDBase(ReadWrite);
   acquire(&lock);
     cond signal(&okToWrite);
   } else_if (WR > 0)
     cond broadcast(&okToRead);
   release (&lock);
```

R3 gets signal (no waiting threads)

```
• AR = 0, WR = 1, AW = 0, WW = 0
Reader() {
   acquire(&lock);
   while ((AW + WW) > 0) { // Is it safe to read?
                             // No. Writers exist
      WR++;
      cond wait(&okToRead,&lock);// Sleep on cond var
                            // No longer waiting
      WR--;
   AR++;
                             // Now we are active!
   release(&lock);
   AccessDBase(ReadOnly);
   acquire(&lock);
   AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
   release(&lock);
```

R3 gets signal (no waiting threads)

```
• AR = 0, WR = 0, AW = 0, WW = 0
```

```
Reader() {
   acquire(&lock);
   while ((AW + WW) > 0) { // Is it safe to read?
                             // No. Writers exist
      WR++;
      cond wait(&okToRead, &lock);// Sleep on cond var
      WR--;
                             // No longer waiting
   AR++;
                             // Now we are active!
   release(&lock);
   AccessDBase(ReadOnly);
   acquire(&lock);
   AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
    release(&lock);
```

R3 accessing dbase (no waiting threads)

```
• AR = 1. WR = 0. AW = 0. WW = 0
Reader() {
    acquire(&lock);
    while ((AW + WW) > 0) { // Is it safe to read?
                             // No. Writers exist
      cond wait(&okToRead,&lock);// Sleep on cond var
                         // No longer waiting
      WR - -\overline{;}
    AR++;
                             // Now we are active!
    release(&lock);
    AccessDBase (ReadOnly)
    acquire(&lock);
    AR--;
    if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
    release(&lock);
```

R3 finishes (no waiting threads)

```
• AR = 1. WR = 0. AW = 0. WW = 0
Reader() {
   acquire(&lock);
   while ((AW + WW) > 0) { // Is it safe to read?
                            // No. Writers exist
      cond wait(&okToRead,&lock);// Sleep on cond var
                         // No longer waiting
   AR++;
                            // Now we are active!
   release(&lock);
   AccessDBase(ReadOnly);
   acquire(&lock);
   AR--;
   if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
   release(&lock);
```

R3 finishes (no waiting threads)

```
• AR = 0, WR = 0, AW = 0, WW = 0
Reader() {
   acquire(&lock);
   while ((AW + WW) > 0) { // Is it safe to read?
                            // No. Writers exist
      cond wait(&okToRead,&lock);// Sleep on cond var
                         // No longer waiting
   AR++;
                            // Now we are active!
   release(&lock);
   AccessDbase(ReadOnly);
   acquire(&lock);
   AR--;
   if (AR == 0 \&\& WW > 0)
      cond signal(&okToWrite);
   release(&lock);
```

Questions

Can readers starve? Consider Reader() entry code:

What if we erase the condition check in Reader exit?

```
AR--; // No longer active

if (AR == 0 && WW > 0) // No other active readers

cond_signal(&okToWrite);// Wake up one writer
```

Further, what if we turn the signal() into broadcast()

```
AR--; // No longer active cond_broadcast(&okToWrite); // Wake up sleepers
```

- Finally, what if we use only one condition variable (call it "okContinue") instead of two separate ones?
 - Both readers and writers sleep on this variable
 - Must use broadcast() instead of signal()

Use of Single CV: okContinue

```
Reader() {
                                          Writer() {
                                               // check into system
    // check into system
                                               acquire(&lock);
    acquire(&lock);
    while ((AW + \dot{W}\dot{W}) > 0) {
                                               while ((AW + AR) > 0) {
                                                 WW++:
       WR++:
       cond wait(&okContinue,&lock);
                                                 cond wait(&okContinue,&lock);
       WR - - ;
                                                 WW--;
                                              AW++;
    AR++;
    release(&lock);
                                               release(&lock);
    // read-only access
                                               // read/write access
                                              AccessDbase(ReadWrite);
    AccessDbase(ReadOnly);
    // check out of system
                                               // check out of system
                                               acquire(&lock);
    acquire(&lock);
    AR--;
                                               AW--;
    if (AR == 0 \&\& WW > 0)
                                               if (WW > 0){
       cond signal(&okContinue);
                                                 cond signal(&okContinue);
    release(&lock);
                                               } else if (WR > 0) {
                                                 cond broadcast(&okContinue);
                                               release(&lock);
```

What if we turn okToWrite and okToRead into okContinue (i.e. use only one condition variable instead of two)?

Use of Single CV: okContinue

```
Reader() {
                                          Writer() {
                                               // check into system
    // check into system
                                               acquire(&lock);
    acquire(&lock);
    while ((AW + \dot{W}\dot{W}) > 0) {
                                               while ((AW + AR) > 0) {
                                                 WW++:
       WR++;
       cond wait(&okContinue,&lock);
                                                 cond wait(&okContinue,&lock);
       WR - - ;
                                                 WW--;
                                              AW++;
    AR++;
    release(&lock);
                                               release(&lock);
    // read-only access
                                               // read/write access
                                              AccessDbase(ReadWrite);
    AccessDbase(ReadOnly);
    // check out of system
                                               // check out of system
                                               acquire(&lock);
    acquire(&lock);
    AR--;
                                               AW--;
    if (AR == 0 \&\& WW > 0)
                                               if (WW > 0){
       cond signal(&okContinue);
                                                 cond signal(&okContinue);
    release(&lock);
                                               } else if (WR > 0)
                                                 cond broadcast(&okContinue);
```

Consider this scenario:

- R1 arrives
- W1, R2 arrive while R1 still reading → W1 and R2 wait for R1 to finish
- Assume R1's signal is delivered to R2 (not W1)

Use of Single CV: okContinue

```
Reader() {
                                          Writer() {
                                               // check into system
    // check into system
    acquire(&lock);
                                               acquire(&lock);
    while ((AW + WW) > 0) {
                                               while ((AW + AR) > 0) {
                                                 WW++:
       WR++:
        cond wait(&okContinue,&lock);
                                                 cond wait(&okContinue,&lock);
       WR--;
                                               WW--;
    AR++;
                                               AW++;
    release(&lock);
                                               release(&lock);
    // read-only access
                                               // read/write access
    AccessDbase(ReadOnly);
                                               AccessDbase(ReadWrite);
    // check out of system
                                               // check out of system
    acquire(&lock);
                                               acquire(&lock);
                                               AW--;
    AR--;
    if (AR == 0 \&\& WW > 0)
                                               if (WW > 0 | WR > 0){
       cond broadcast(&okContinue);
                                                 cond broadcast(&okContinue);
    release(&lock);
                                               release(&lock);
                      Need to change to
                                                                   Must broadcast()
                       broadcast()!
                                                                    to sort things out!
```

Can we construct Monitors from Semaphores?

- Locking aspect is easy: Just use a mutex
- Can we implement condition variables this way?

```
Wait(Semaphore *thesema) { semaP(thesema); }
Signal(Semaphore *thesema) { semaV(thesema); }
```

Does this work better?

```
Wait(Lock *thelock, Semaphore *thesema) {
    release(thelock);
    semaP(thesema);
    acquire(thelock);
}
Signal(Semaphore *thesema) {
    semaV(thesema);
}
```

Construction of Monitors from Semaphores (con't)

- Problem with previous try:
 - P and V are commutative result is the same no matter what order they occur
 - Condition variables are NOT commutative
- Does this fix the problem?

```
Wait(Lock *thelock, Semaphore *thesema) {
    release(thelock);
    semaP(thesema);
    acquire(thelock);
}
Signal(Semaphore *thesema) {
    if semaphore queue is not empty
        semaV(thesema);
}
```

- Not legal to look at contents of semaphore queue
- There is a race condition signaler can slip in after lock release and before waiter executes semaphore.P()
- It is actually possible to do this correctly
 - Complex solution for Hoare scheduling in book
 - Can you come up with simpler Mesa-scheduled solution?

Mesa Monitor Conclusion

- Monitors represent the synchronization logic of the program
 - Wait if necessary
 - Signal when change something so any waiting threads can proceed
- Typical structure of monitor-based program:

```
lock
while (need to wait) {
    condvar.wait();
}
unlock

do something so no need to wait

lock
condvar.signal();
Check and/or update
    state variables

Wait if necessary

Check and/or update
    state variables

unlock
```

C-Language Support for Synchronization

- C language: Pretty straightforward synchronization
 - Just make sure you know *all* the code paths out of a critical section

```
int Rtn() {
     acquire(&lock);
                                                           Proc A
                                                                      Stack growth
     if (exception) {
                                                           Proc B
        release(&lock);
                                                        Calls setimp
        return errReturnCode;
                                                           Proc C
                                                        acquire(&lock)
     release(&lock);
                                                           Proc D
     return OK;
                                                           Proc E
– Watch out for setjmp/longjmp!
                                                        Calls longjmp
```

- » Can cause a non-local jump out of procedure
- » In example, procedure E calls longjmp, poping stack back to procedure B
- » If Procedure C had lock.acquire, problem!

Concurrency and Synchronization in C

Harder with more locks

```
void Rtn() {
  lock1.acquire();
  if (error) {
  lock1.release();
     return;
  lock2.acquire();
  if (error) {
     lock2.release()
     lock1.release();
     return;
  lock2.release();
  lock1.release();
```

```
Is goto a solution???
void Rtn() {
  lock1.acquire();
  if (error) {
    goto release_lock1_and_return;
  lock2.acquire();
  if (error) {
    goto release both and return;
release both and return:
  lock2.release();
release lock1 and return:
  lock1.release();
```

C++ Language Support for Synchronization

- Languages with exceptions like C++
 - Languages that support exceptions are problematic (easy to make a non-local exit without releasing lock)
 - Consider:

```
void Rtn() {
   lock.acquire();
   ...
   DoFoo();
   ...
   lock.release();
}
void DoFoo() {
   ...
   if (exception) throw errException;
   ...
}
```

– Notice that an exception in DoFoo() will exit without releasing the lock!

C++ Language Support for Synchronization (con't)

Must catch all exceptions in critical sections

```
– Catch exceptions, release lock, and re-throw exception:
    void Rtn() {
       lock.acquire();
       try {
          DoFoo();
       } catch (...) {     // catch exception lock.release();     // release lock
          throw; // re-throw the exception
       lock.release();
    void DoFoo() {
       if (exception) throw errException;
```

Much better: C++ Lock Guards

```
#include <mutex>
int global_i = 0;
std::mutex global_mutex;

void safe_increment() {
   std::lock_guard<std::mutex> lock(global_mutex);
   ...
   global_i++;
   // Mutex released when 'lock' goes out of scope
}
```

Python with Keyword

 More versatile than we show here (can be used to close files, database connections, etc.)

```
lock = threading.Lock()
...
with lock: # Automatically calls acquire()
   some_var += 1
   ...
# release() called however we leave block
```

Java synchronized Keyword

- Every Java object has an associated lock:
 - Lock is acquired on entry and released on exit from a synchronized method
 - Lock is properly released if exception occurs inside a synchronized method
 - Mutex execution of synchronized methods (beware deadlock)

```
class Account {
   private int balance;

   // object constructor
   public Account (int initialBalance) {
      balance = initialBalance;
   }
   public synchronized int getBalance() {
      return balance;
   }
   public synchronized void deposit(int amount) {
      balance += amount;
   }
}
```

Java Support for Monitors

- Along with a lock, every object has a single condition variable associated with it
- To wait inside a synchronized method:

```
- void wait();
- void wait(long timeout);
```

To signal while in a synchronized method:

```
- void notify();
- void notifyAll();
```

Conclusion

- Semaphores: Like integers with restricted interface
 - Two operations:
 - » P(): Wait if zero; decrement when becomes non-zero
 - » V(): Increment and wake a sleeping task (if exists)
 - » Can initialize value to any non-negative value
 - Use separate semaphore for each constraint
- Monitors: A lock plus one or more condition variables
 - Always acquire lock before accessing shared data
 - Use condition variables to wait inside critical section.
 - » Three Operations: Wait(), Signal(), and Broadcast()
- Monitors represent the logic of the program
 - Wait if necessary
 - Signal when change something so any waiting threads can proceed
 - Monitors supported natively in a number of languages
- Readers/Writers Monitor example
 - Shows how monitors allow sophisticated controlled entry to protected code