CS334 Assignment1

SID: 12012919

Name: 廖铭骞

1) [20pts] make qemu 指令将指向makefile对应的label,该指令对应于:

```
qemu-system-riscv64 \
  -machine virt \
  -nographic \
  -bios default \
  -device loader,file=bin/ucore.bin,addr=0x80200000
```

请解释以上指令中每个参数的作用

-machine virt 指定用来仿真模拟的机器: RISC-V VirtIO board 仿真板

-nographic 禁用图像输出,指定是使用非图形化界面。且将串行IO重定向输入输出到控制台。

-bios default 加载指定的文件, 将OpenSBI 代码加载到 0x80000000 起始处

-device loader, file=bin/ucore.bin, addr=0x80200000 基于一种 Misc 设备加载器添加设备,使用 bin/ucore.bin 作为直接运行程序,且加载程序的程序入口地址位于0x80200000

2) [20pts] 请查阅资料,理解并解释/lab/tools/kernel.ld文件中每一行的作用(<u>https://sourceware.or</u> g/binutils/docs/ld/Scripts.html)

```
/* Simple linker script for the ucore kernel.
    See the GNU ld 'info' manual ("info ld") to learn the syntax. */
OUTPUT_ARCH(riscv) /*Specify a particular output machine architecture.
In this case, the machine architecture is riscv*/
ENTRY(kern_entry) /*set the entry point. In this case, the entry point is set as kern_entry*/
BASE_ADDRESS = 0x80200000; /* assigm the 0x80200000 to BASE_ADDRESS */
SECTIONS /*A keyword followed by a series of symbol assignments and output section descriptions enclosed in curly braces*/
{
        /* Load the kernel at this address: "." means the current address
*/
        . = BASE_ADDRESS; /* "." as the location counter, here assign
0x802000000 to it*/
```

```
/* combine all the .text.kern_entry, .text .stub, .text.*,
.gnu.linkonce.t.* input file into a .text section */
    .text : { /* programming code output sections, followed by the
input files which should be placed into the output section*/
        *(.text.kern_entry) /* The input section that should be placed
into the .text output section*/
        *(.text .stub .text.* .gnu.linkonce.t.*) /* The input section
that should be placed into the .text output section*/
   }
   PROVIDE(etext = .); /* Define the 'etext' symbol to this value */
/*combine all the .rodata .rodata.* .gnu.linkonce.r.* input files into
a .rodata output section*/
    .rodata : { /* read-only data output sections, followed by the
input files which should be placed into the output section*/
        *(.rodata .rodata.* .gnu.linkonce.r.*) /* The input section
that should be placed into the .text output section*/
   }
    \cdot = ALIGN(0x1000); /* Adjust the address for the data segment to
the next page */
   /* The read-write initialized data segment, the usage is similar
to .text */
   /* The input section that should be placed into the .data output
section*/
       *(.data)
        *(.data.*)
   }
   /* The sdata segment*/
    .sdata : {
    /* The input section that should be placed into the .sdata output
section*/
       *(.sdata)
       *(.sdata.*)
   }
   PROVIDE(edata = .);/* Define the 'edata' symbol to the location of
current value of location counter */
   /* The read-write zero initialized data segment, the usage is
similar to .text, followed by the input files which should be placed
into the output .bss section */
    .bss : {
```

```
/* The input sections that should be placed into the .bss output
section*/
          *(.bss)
          *(.bss.*)
          *(.sbss*)
}

PROVIDE(end = .);/* Define the 'end' symbol to the location of
current value of location counter */

/DISCARD/: {/* Any input sections which are assigned to an output
section named '/DISCARD/' are not included in the output file.*/
           *(.eh_frame .note.GNU-stack) /*All ".eh_frame" and ".note.GNU-
stack" input section willnot included in the output file*/
    }
}
```

3) [**10pts**] 请解释 /lab/kern/init/init.c 中 main函数中 memset(edata, 0, end - edata); 的参数及语句作用。(需要读到的代码有init.c, kernel.ld)

参数:

edata, 标志着 .bss output section 的起始位置

0,标志着将要给对应内存块填充的内容,初始化的值

end - edata, 通过阅读 kernel.ld 代码,发现 end 代表着 .bss output section 的结束位置,而 end - edata 恰好就是 .bss section 的大小

语句作用

该语句通过显式地规定需要填充字节块的大小,将对应的内存区域(.bss output section)全部填充为 0,进行区域的初始化操作。

4) [20pts] 请描述cputs()指令是如何通过sbi打印字符的。

cputs() 先是通过调用cputch(),输出字符串中的单字符直到遇到'\0', 最后输出'\n', cputch() 的作用是将单个字符写入标准输出流。之后 cputch() 通过调用 cons_putc(), 而 cons_putc() 又调用sbi_console_putchar(),通过传入需要在控制台中打印的字符来进一步传给sbi_call(), 在 sbi_call 当中传入 SBI_CONSOLE_PUTCHAR 作为 sbi_type 指示指令为打印字符,剩余参数还有要打印的字符,以及两个0 进行 sbi_call() 的调用。

在 sbi_call() 当中,通过使用内联汇编,将传入参数指定的寄存器当中的值存入相应的寄存器(sbi_type 的值存入 x17寄存器,传入的字符 arg0 的值存入 x10寄存器),之后使用ecall 进行系统调用,交给 OpenSBI 执行,将传入的字符在屏幕中打印显示出来,最后再将 x10 寄存器的值,也就是 arg0 作为返回值返回。

5) [30pts] 编程题 请理解使用ecall打印字符的原理,实现一个 shutdown() 关机函数。(所有修改到的代码请截图和运行结果截图一起放在报告中)

为了能在 init.c 当中使用 shutdown() 函数,先在 stdio.h 当中声明该方法,之后在 stdio.c 当中实现。经过查看 cputch() 方法,发现是通过调用 console.h 当中的 cons_putc()来实现,所以在 shutdown()函数当中,我们也通过进一步调用 console.h 当中的,将要实现的 cons_shutdown()来进一步实现,截图如下。

之后, 我们关注于 cons_shutdown() 函数的实现。

通过对 cons_putc() 实现的查看,发现它进一步调用了 sbi.h 当中的 sbi_console_putchar() 方法进行系统调用实现。

于是我们参考这样的实现方法,在 cons_shutdown() 当中调用 sbi_shutdown()方法

之后发现在 sbi.c 当中,并没有实现该方法,通过查看 sbi_console_putchar()方法,发现是通过调用 sbi_call()进行实现。

最终,我们通过阅读 sbi_call() 方法的参数作用,实现了 sbi_shutdown() 方法

最终运行截图如下: