Lecture 10 I/O

Prof. Yinqian Zhang


Summer 2022

I/O Management

- · So far, we have learned how to manage CPU and memory
- Challenges of I/O management
 - Diverse devices: each device is slightly different
 - How can we standardize the interfaces to these devices?
 - Unreliable device: media failures and transmission errors
 - · How can we make them reliable?
 - Unpredictable and slow devices
 - How can we manage them if we do not know what they will do or how they will perform?


A Classic View of Computer System

- A single CPU attached to the main memory of the system via memory bus or interconnect.
- Some devices (graphics and some other higher-performance I/O devices) are connected to the system via a general I/O bus (e.g., PCI)
- Finally, a peripheral bus, such as SCSI, SATA, or USB, connects slow devices to the system, including disks, mice, and keyboards



A Canonical View of Devices

- Interface
 - The hardware interface a device present to the rest of the system
 - Status registers: check the current status of the device
 - Command register: tell the device to perform a certain task
 - Data register: pass data to the device or get data from the device.
- Internal structures
 - Implementation of the abstract of the device




Basic I/O: Polling

- To write a byte of data to device
 - Step 1: OS waits until the device is ready to receive a command by repeatedly reading the status register;
 - Step 2: OS sends some data down to the data register;
 - Step 3: OS writes a command to the command register
 - Step 4: OS waits for the device to finish by again polling it in a loop, waiting to see if it is finished

```
While (STATUS == BUSY)
   ; // wait until device is not busy
Write data to DATA register
Write command to COMMAND register
    (starts the device and executes the command)
While (STATUS == BUSY)
   ; // wait until device is done with your request
```


Issues of Polling

- Polling: frequent checking the status of I/O devices
- Polling is inefficient and inconvenient
 - Polling wastes CPU time waiting for slow devices to complete its activity
 - If CPU switches to other tasks, data may be overwritten
 - e.g., keyboard data overflow the buffer




Efficient I/O: Interrupts

- Instead of polling the device repeatedly, the OS can issue a request, put the calling process to sleep, and context switch to another task.
- When the device is finally finished with the operation, it will raise a hardware interrupt, causing the CPU to jump into the OS at a predetermined interrupt handler



Polling or Interrupt?

- Polling works better for fast devices
 - Data fetched with first poll
- Interrupt works better for slow devices
 - Context switch is expensive
- Hybird approach if speed of the device is not known or unstable
 - Polls for a while
 - Then use interrupts



Hardware Support for Interrupts

- Interrupt-request line, a CPU wire, triggered by I/O device
 - Checked by processor after each instruction
 - Save CPU state and jumps to the interrupt handler

Interrupt-controller hardware

- Defer interrupt handling during critical processing
- Dispatch to proper interrupt handler
- Support multi-level interrupts, high- and low-priority interrupts

Software Support for Interrupts

- Interrupt handler receives interrupts
 - Maskable to ignore or delay some interrupts
 - Some are nonmaskable, e.g., unrecoverable memory errors.
- A table of interrupt vectors to specify interrupt-handling routine
 - Dispatch interrupt to correct handler
 - Interrupt chaining if more than one device at the same interrupt number
 - · Interrupt handlers on the corresponding chain are called one by one
 - The size of the interrupt table (i.e., number of interrupt vectors) and length of interrupt chains are results of system design trade-off.
 - Priority of interrupts: high-priority interrupts can preempt low-priority interrupts


Aside: Interrupts and Exceptions

- Interrupt mechanism also used for exceptions
 - Page fault is an exception that raises interrupts
 - Dividing by 0
 - Attempting to execute a privileged instruction from user mode
- Software interrupts, or traps
 - System call is made by executing a special instruction called software interrupts to trigger kernel to execute request
 - Lower priority interrupt
- Multi-CPU systems can process interrupts concurrently
 - If operating system designed to handle it

More Efficient Data Movement: DMA

- DMA is used to avoid programmed I/O for large data movement
 - Programmed I/O (PIO): when CPU is involved in data movement
 - PIO consumes CPU time
 - bypasses CPU to transfer data directly between I/O device and memory
- OS writes DMA command block into memory
 - Source and destination addresses
 - Read or write mode
 - Count of bytes
 - Writes location to DMA controller
 - Bus mastering of DMA controller grabs bus from CPU
 - Cycle stealing from CPU but still much more efficient
 - When done, interrupts to signal completion

More Efficient Data Movement: DMA



Methods Of Device Interaction

- Explicit I/O instructions
 - in/out instructions on x86: out 0x21,AL
 - I/O instructions are privileged instructions
- Memory-mapped I/O
 - Registers/memory appear in physical address space
 - I/O accomplished with load and store instructions
 - I/O protection with address translation

I/O address range (hexadecimal)	device
000-00F	DMA controller
020–021	interrupt controller
040–043	timer
200-20F	game controller
2F8–2FF	serial port (secondary)
320-32F	hard-disk controller
378–37F	parallel port
3D0-3DF	graphics controller
3F0-3F7	diskette-drive controller
3F8-3FF	serial port (primary)

Memory-Mapped Display Controller

Memory-Mapped I/O

 Hardware maps control registers and display memory into physical address space

· Addresses set by HW jumpers or at boot time

 Simply writing to display memory (also called the "frame buffer") changes image on screen

Addr: 0x8000F000 — 0x8000FFFF

· Writing graphics description to cmd queue

• Say enter a set of triangles describing some scene

Addr: 0x80010000 — 0x8001FFFF

 Writing to the command register may cause on-board graphics hardware to do something

· Say render the above scene

• Addr: 0x0007F004

0x80020000

0x80010000

0x8000F000

0x0007F004 0x0007F000

Graphics Command Queue


Display Memory

Command Status

> Physical Address Space

CS334 Operating Systems (H)


Kernel I/O Structure



Device Drivers

- Device Driver: Device-specific code in the kernel that interacts directly with the device hardware
 - Supports a standard, internal interface
 - Same kernel I/O system can interact easily with different device drivers
 - Special device-specific configuration supported with the ioctl() system call
- Device Drivers typically divided into two pieces:
 - Top half: accessed in call path from system calls
 - implements a set of standard, cross-device calls like open(), close(), read(), write(), ioctl(), strategy()
 - This is the kernel's interface to the device driver
 - Top half will start I/O to device, may put thread to sleep until finished
 - Bottom half: run as interrupt routine
 - · Gets input or transfers next block of output
 - May wake sleeping threads if I/O now complete

Life Cycle of An I/O Request



Application I/O Interface

- I/O system calls encapsulate device behaviors in generic classes
- Device-driver layer hides differences among I/O controllers from kernel
- New devices talking already-implemented protocols need no extra work
- Each OS has its own I/O subsystem structures and device driver frameworks
- Devices vary in many dimensions
 - Character-stream or block
 - · Sequential or random-access
 - Synchronous or asynchronous
 - Sharable or dedicated
 - Speed of operation
 - · read-write, read only, or write only

Characteristics of I/O Devices (Cont'd)

- Subtleties of devices handled by device drivers
- Broadly I/O devices can be grouped by the OS into
 - Block I/O
 - Character I/O (Stream)
 - Memory-mapped file access
 - Network sockets
- For direct manipulation of I/O device specific characteristics from user-space applications
 - Unix ioctl() call to send arbitrary bits to a device control register and data to device data register

Block and Character Devices

- Block devices include disk drives
 - Commands include read, write, seek
 - Raw I/O, allows direct file-system access
 - Applications (e.g., database) do not need buffering or locking by filesystems
 - · Memory-mapped file access possible
 - · File mapped to virtual memory via demand paging
 - DMA
- · Character devices include keyboards, mice, serial ports
 - Commands include get(), put() of one character
 - Libraries layered on top allow line editing


Nonblocking and Asynchronous I/O

- Blocking process suspended until I/O completed
 - · Processes moved from run queue to wait queue
- Nonblocking I/O call returns as much as available
 - Returns quickly with count of bytes read or written
- Asynchronous process runs while I/O executes
 - An alternative to nonblocking I/O
 - I/O request will be completed at some future time
 - I/O subsystem signals process when I/O completed
 - Software interrupt
 - Signal
 - · Callback routine

Summary

- Two techniques to make I/O more efficient
 - Interrupts
 - DMA
- Two approaches to control devices
 - Explicity I/O instructions
 - Memory-mapped I/O
- The notion of device drivers
 - OS encapsulates low-level details and makes it easier to build the rest of the OS in a device-neutral fashion.

Thank you!



CS334 Operating Systems (H)