Week 3:

Performance Evaluation

CSC 469 / CSC 2208

Fall 2018



University of Toronto, Department of Computer Science



Overview

- Common question: "How fast does program X run on machine Y?"
- Near-perfect timing measurements on a compute systems should be straightforward. Or is it?
- Many factors that can vary from one execution of a program to another
 - Switching between processes => scheduling processor resources depends on number of users sharing the system, network traffic, timing of disk operations
 - Access patterns to caches => not just current process, other concurrent processes too
 - Branch prediction logic => history can vary
- 2 basic mechanisms: interval counting, cycle counting
- Goal: methods to get reliable measurements of program performance




Performance Evaluation Topics

- Time scales
- Interval counting
- Cycle counting
- K-best measurement scheme
- Performance metrics
- Amdahl's Law



Computer Time Scales



- Two fundamental time scales:
 - Processor: ~1 nanosecond (10⁻⁹ secs)
 - External events: ~10 milliseconds (10⁻² secs)
 - Keyboard input, disk seek, screen refresh
- Implication
 - Can execute many instructions while waiting for external event
 - · Basis for multiprogramming




Measurement

- What does it mean to ask "How much time does program X require?"
 - CPU time
 - How many total seconds are used when executing X?
 - Measure used for most applications
 - Some dependence on other system activities
 - Actual ("Wall clock") time
 - How many seconds elapsed between start and completion of X?
 - Depends on system load, I/O times, etc.
- How does time get measured?
- How does sharing impact measurement and performance?




"Time" on a Computer System





Activity Periods: Light Load




- Most of the time spent executing one process
- Periodic interrupts every 10ms
 - Interval timer

- Other interrupts
 - Due to I/O activity
- Inactivity periods
 - System time spent processing interrupts



Activity Periods: Heavier Load



- Sharing processor with one other active process
- From perspective of this process, system appears to be "inactive" for ~50% of the time
 - Other process is executing




Interval Counting

- OS measures runtimes using interval timer
 - Maintain 2 counts per process
 - User time and system time
 - On each timer interrupt, increment counter for currentlyexecuting process
 - User time if running in user mode
 - System time if running in kernel mode
 - Reported by unix "time" command (or getrusage in C program)




Interval Counting Example

(a) Interval Timings




(b) Actual Times



Imprecise: Timing at the granularity of the timer interval!



Accuracy of Interval Counting



- Interval timer reports 70 ms
- Min Actual = 60 + e
- Max Actual = 80 e

- Worst case
 - Timer interval δ
 - Single measurement can be off by +/- δ
 - No bound on error for multiple measurements
- Average case
 - Over/under estimates tend to balance out
 - Provided total run time is large enough (~100 timer intervals, or 1 second)



Cycle Counters

- Most modern systems have built in registers that are incremented every clock cycle
 - Very fine grained
 - Maintained as part of process state
 - Possible to save & restore with context switches
 - In Linux, counts elapsed global time
 - Special assembly code instruction to access
 - On (recent model) Intel machines:
 - 64 bit counter.
 - RDTSC instruction sets **%edx** to high order 32-bits, **%eax** to low order 32-bits



Cycle Counter Period

- Wrap-around times for 2 GHz machine
 - Low order 32-bits wrap around every $2^{32} / (2 * 10^9) = 2.1$ seconds
 - High order 64-bits wrap around every 2^{64} / $(2 * 10^9) = 9223372037$ seconds
 - 293 years
- For 5 GHz machine
 - Low order 32-bits wrap every 0.86 seconds
 - High order 64-bits wrap every 116 years
- See tutorial notes for usage details



Measuring program execution

Wrap rdtsc instruction within an access_counter function call (use inline assembly – see tutorial)

```
static u_int64_t start = 0;
void access_counter(unsigned* hi, unsigned* low);
void start counter() {
    unsigned hi, lo;
    access_counter(&hi, &lo);
    start = ((u_int64_t)hi << 32) | 10;
}
u_int64_t get_counter() {
    unsigned ncyc_hi, ncyc_lo;
    access_counter(&ncyc_hi, &ncyc_lo);
    return (((u_int64_t)ncyc_hi << 32) | ncyc_lo) - start;</pre>
```

Measuring Cycles (Basic Idea):

- Get current value of cycle counter
- Compute something
- Get new value of cycle counter
- Get elapsed time (in cycles) by subtraction



Measurement Pitfalls

Overhead

- Calling get_counter() incurs small amount of overhead
- Want to measure long enough code sequence to compensate
- Unexpected Cache Effects
 - Warm vs cold caches, artificial hits or misses
 - e.g., these are actual measurements (taken with the Alpha cycle counter):



Dealing with Overhead & Cache Effects

Execute P() once to warm up cache (both data and instr)

- Do we expect code to access the same data repeatedly?
- Some functions don't execute in the cache
- Depends on both the algorithm and the data set



Dealing with Overhead & Cache Effects

- What if it's more likely that the code will access new data with each execution?
 - To force timing code to measure the performance of code under "cold caches", we could flush caches before the actual experiment
 - Example: Write code that does some operations on a large dummy array to evict existing cached blocks
 - Problem: clearing caches may also clear all instructions of P() from L2
 - Overestimates time for P()
 - Side note: on Linux, can clear page cache using:
 - sudo sh -c 'echo 1 >/proc/sys/vm/drop_caches'



Dealing with Overhead & Cache Effects

- Execute P() once to warm up cache
- Keep doubling the number of times we execute P() until some threshold is reached
 - Used CMIN = 50000

```
int count = 1;
double ctr meas = 0;
double cycles;
do {
  int reps = count;
 P();
                             /* Warm up cache */
 get counter();
 while (reps-- > 0)
   P();
  ctr meas = get counter();
  cycles = ctr meas / count;
  count += count;
} while (ctr_meas < CMIN); /* Make sure we have enough */</pre>
return cycles / (1e6 * MHZ);
```




Context Switching

- Context switches can also affect cache performance
 - e.g., (foo1, foo2) cycles on an unloaded timing server:
 - 71,002, 23,617
 - 67,968, 23,384
 - 68,840, 23,365
 - 68,571, 23,492
 - 69,911, 23,692
- Why do context switches matter?
 - Cycle counter only accumulates when running user process (in this example)
 - Some amount of overhead
 - Caches polluted by OS and other user's code & data
 - Cold misses occur when process is restarted
- Measurement Strategy
 - Try to measure uninterrupted code execution



Detecting Context Switches

- Clock Interrupts
 - Processor clock causes interrupt every Δt seconds
 - Typically $\Delta t = 1-10 \text{ ms}$
 - Same as interval timer resolution



Can detect by seeing if interval timer has advanced during measurement

```
start = get_etime();  /* timer_gettime() wrapper, measures thread time */

/* Perform Measurement */

if (get_etime() - start > 0)
   /* Discard measurement */
```



Detecting Context Switches (Cont.)

- External Interrupts
 - E.g., due to completion of disk operation
 - Occur at unpredictable times and generally take a long time to service
- Detecting
 - See if real time clock has advanced
 - Using coarse-grained timer

Similer to get_etime(), but uses CLOCK_REALTIME

- Reliability
 - Good, but not 100%
 - Can't get clean measurements on heavily loaded system



It's worse than that...

- Modern OS may support multiple clock sources
 - E.g. Linux:

```
wolf:~> cat
/sys/devices/system/clocksource/clocksource0/
available_clocksource
tsc hpet acpi_pm
```

```
wolf:~> cat
/sys/devices/system/clocksource/clocksource0/
current_clocksource
```

tsc


But tsc may not be a stable source of timing information



Improving Accuracy

K-Best Measurements

- Assume that bad measurements always overestimate time
 - True if main problem is due to context switches or interference effects
- Take multiple samples (e.g., N = 20) until lowest K are within some small tolerance of each other
 - Choose fastest measurement from the K-Best



- In some cases, errors can both under and overestimate time (e.g., when using interval timers)
 - Look for cluster of samples within some tolerance of each other





Portability: Time of Day Clock

- Return elapsed time since some reference time (e.g., Jan 1, 1970)
- Example: Unix gettimeofday() command
- Coarse grained vs fine grained (e.g., ~3μsec resolution on older Linux, 10 msec resolution on Windows NT, same as cycle counter on new Linux)
- Possibly lots of overhead making call to OS
- Different underlying implementations give different resolutions

```
#include <sys/time.h>
#include <unistd.h>

struct timeval tstart, tfinish;
double tsecs;
gettimeofday(&tstart, NULL);
P();
gettimeofday(&tfinish, NULL);
tsecs = (tfinish.tv_sec - tstart.tv_sec) +
    1e6 * (tfinish.tv_usec - tstart.tv_usec);
```



Measurement Summary

- Timing is highly case and system dependent
 - What is overall duration being measured?
 - > 1 second: interval counting is OK
 - << 1 second: must use cycle counters, otherwise accuracy low!
 - On what hardware / OS / OS version?
 - Accessing counters
 - How is gettimeofday() implemented
 - Timer interrupt overhead
 - Scheduling policy
- Devising a Measurement Method
 - Long durations: use Unix timing functions
 - Short durations
 - If possible, use gettimeofday; Otherwise must work with cycle counters
 - K-best scheme most successful



Measurement Summary

- It's difficult to get accurate times
 - Compensating for overhead
 - But can't always measure short procedures in loops
 - global state, mallocs, changes cache behavior
 - Getting accurate timings on heavily loaded systems is especially difficult!
 - Frequency scaling may also be an issue
- It's difficult to get repeatable times
 - Cache effects due to ordering and context switches
- Every system is different!
- Moral of the story:
 - Adopt a healthy skepticism about measurements!
 - Always subject measurements to sanity checks.



Hardware Performance Monitoring

- Modern CPUs contain counters for low-level architectural events e.g.
 - instructions executed, branches taken, cache accesses, etc.
- Example using perf tools:
 - perf stat --repeat \$N -e \$event1 -e \$event2 -e \$event3 -e \$event4 -- someprogram
 - Events: cycles, instructions, cache-references, branch-instructions, branch-misses, L1-dcache-loads, L1-dcache-load-misses, L1-icache-loads, LLC-stores, iTLB-loads, dTLB-load-misses, syscalls:sys_enter, syscalls:sys_exit, etc. (lots!)
 - perf stat --repeat 5 -e cycles -e instructions -e cache-references -e cache-misses
 -e syscalls:sys_enter -e syscalls:sys_exit -- sh -c "/usr/bin/postgres --single mydb
 -D \$PGDATA < query.sql > /dev/null"

```
10074181817
                                                0.000 \, \text{M/sec}
                                                                       0.098%)
              cycles
                                                                       0.003%)
12648819036
              instructions
                                                1.256 IPC
                                                0.000 M/sec
   73553771
             cache-references
                                                                       0.152%)
     476347
             cache-misses
                                                0.000 M/sec
                                                                       0.915%)
      55834
              syscalls:sys enter
                                                0.000 M/sec
                                                                       0.000%)
      55834
              syscalls:sys exit
                                                0.000 M/sec
                                                                       0.000%)
3.806739355
              seconds time elapsed
                                              0.160%)
```



Hardware Performance Monitoring

- Hard to use because
 - Limited number of counters

 can't count all interesting events at the same time
 - Non-standard (libraries like PAPI help)
 - Poor documentation
 - Extracting performance insight from low-level microarchitectural events is tough



From Measurement to Experiment

- 1. Metrics a measurable quantity that is the basis for comparison
 - Choosing a good metric requires deciding what factors are most important
 - Latency, bandwidth, throughput are common in computer systems
 - Give me some other ones...
 - Capacity, utilization, overhead, useful work, etc...
- 2. A system to measure
 - Model
 - Simulation
 - "Live"
- 3. A set of tests to perform on the target system
 - Benchmarks
- What else?



1. Choosing Metrics

- What performance metric should be used to compare the following?
 - Two disk drives

Two transaction processing systems

Two packet retransmission algorithms

Two clock scaling algorithms for reducing energy usage



Characteristics of a good performance metric

- Intuitive (For all stakeholders)
- Reliable
 - Trusted for useful comparison and prediction
 - Repeatable
- Easy to measure
 - No complicated metric that's difficult to measure correctly
- Consistent
 - Definition is the same across different configurations and different systems
 - In many cases not necessarily true (ex. MIPS and MFLOPS)
- Independent of outside influences
 - No intervention from vendors to influence the composition of the metric to their benefit



2. Choosing a system to measure

Models

- rigorous mathematical model, insight into effects of different parameters
- before a system is built

Simulation

- simulate the system operation (or small parts)
- Live System
 - implement the system in full and measure its performance directly
 - get the test infrastructure set up and test it "live"



Techniques – pros and cons

Models

- + cheap, fast to develop
- highly simplified, not always accurate, depends on accuracy of assumptions

Simulation

- + flexibility: easy to vary parameters, test assumptions
- cost/time depends on level of detail, less detailed simulations may leave out important factors

Live System

- + real results, can't overlook contribution of other components
- can be hard to interpret, effects of specific parameters may be hard to isolate
- expensive: buy test infrastructure, implement the system in full, etc.



General advice

- Simulation is generally the most widely-used
 - Not necessarily the best though
- Generally recommended to use combination of techniques, if possible
- Don't trust the results produced by just one method
 - Validate one method with another
 - e.g., modeling + simulation, simulation + live system



3. Choosing experiments

- Suppose that the performance of a system depends on the following three factors:
 - Garbage collection technique used (concurrent, stop and copy, none)
 - Type of workload (office desktop computing, database server, scientific computing)
 - Type of CPU (Pentium, POWER PC)

How many experiments are needed?

How do you quantify the performance impact of each factor?



Designing Workloads

- Can't always measure "real" workload
 - Want repeatability
 - · Want to test new ideas, can't deploy in real setting
- Macro benchmarks emulate typical workloads
- May be run by large community
 - SPEC
 - TPC
- Vigilance is still needed
 - E.g., scaling issues
 - E.g., file system benchmarking



And then there's analysis

- Why performance analysis is an "art" not a "science":
- Given the following measurements of throughput:

System:	Workload 1	Workload 2
А	20	10
В	10	20

• What is a fair comparison?



Some possibilities...

Absolute:

System	Workload1	Workload2	Average
Α	20	10	15
В	10	20	15

Performance of A relative to B:

System	Workload1	Workload2	Average
А	2x	0.5x	1.25x
В	1x	1x	1x

Performance of B relative to A:

System	Workload1	Workload2	Average
Α	1x	1x	1x
В	0.5x	2x	1.25x



General Advice

- Understand the goals
 - Solid understanding of the problem, Solid understanding of the system
 - Difficult => Goals may change once problem is better understood
- Be careful about bias
 - "system X is better than system Y"
 - Don't select metric for highlighting a particular system, conduct a proper comparison
 - Findings may be skewed by bias => inaccurate/incomplete conclusions
- Use a systematic approach
 - Arbitrary selection of system parameters, metrics, workloads => inaccurate/incomplete conclusions



More advice

- Understand the phenomena being measured
 - Is variance caused by experimental noise or is there intrinsic variance?
- Decide if you want the minimum, mean or median
- Avoid common pitfalls
 - Measure the whole operation (e.g. file read vs. mmap)
 - Measure the operation you intend to measure
- Combine micro and macro benchmarks



Amdahl's Law

 A friend is planning to visit you from Montreal, and you are driving to Algonquin Park for a week of camping. Your friend must choose between Via Rail (\$114, 9 hours, return) and WestJet (\$267 2.5 hours, return). The drive to Algonquin park will take 3.5 hours each way.

	Time MTL->TO->MTL	Total trip time	Speedup over VIA
VIA	9 hours	16 hours	1
WestJet	2.5 hours	9.5 hours	1.7

 Taking the plane (which is 3.6 times faster) speeds up the overall trip by only a factor of 1.7!



Speedup

Old program (unenhanced)

$$\mathsf{T}_1$$

 T_2

Old time: $T = T_1 + T_2$

New program (enhanced)

$$T_1' = T_1$$

 $T_2' \leq T_2$

New time: $T' = T_1' + T_2'$

Speedup: $S_{overall} = T / T'$

 T_1 = time that can NOT be enhanced.

 T_2 = time that can be enhanced.

T₂' = time after the enhancement.

When we speed up one part of a program, the overall system performance depends on both how significant the part is, and how much it was sped up.



Computing Speedup

Two key parameters:

$$\begin{aligned} &F_{enhanced} = T_2 \, / \, T \qquad \text{(fraction of original time that can be improved)} \\ &S_{enhanced} = T_2 \, / \, T_2 \, \text{(speedup of enhanced part)} \\ &T' = T_1 \, ' + T_2 \, ' = T_1 + T_2 \, ' = T(1 - F_{enhanced}) + T_2 \, ' \\ &= T(1 - F_{enhanced}) + (T_2 / S_{enhanced}) \qquad \text{[by def of S}_{enhanced}] \\ &= T(1 - F_{enhanced}) + T(F_{enhanced} / S_{enhanced}) \qquad \text{[by def of F}_{enhanced}] \\ &= T((1 - F_{enhanced}) + F_{enhanced} / S_{enhanced}) \end{aligned}$$

Amdahl's Law:

$$S_{\text{overall}} = T / T' = 1/((1 - F_{\text{enhanced}}) + F_{\text{enhanced}} / S_{\text{enhanced}})$$

- Key idea:
 - Amdahl's Law quantifies the general notion of diminishing returns.
 - It applies to any activity, not just computer programs.



Trip example revisited

- Suppose you have the option of taking a rocket from MTL to TO (15 minutes)
- Or a wormhole opens between MTL and TO (0 minutes)

	Time MTL→TO→MTL	Total trip time	Speedup over VIA
VIA	9 hours	16 hours	1
WestJet	2.5 hours	9.5 hours	1.7
Rocket	0.25 hours	7.25 hours	2.2
Wormhole	0 hours	7 hours	2.3



Lessons from Amdahl's Law

•
$$S_{overall} = 1 / ((1 - F_{enhanced}) + F_{enhanced} / S_{enhanced})$$

- Ex1: Calculate *Min* and *Max* speedup bounds:
 - $Min \leq S_{overall} \leq Max$
- Ex2: Calculate $\max S_{overall'}$ for the following values of $F_{enhanced'}$

- 0
- 0.5
- 0.75
- 0.875

- 0.9375
- 0.96875
- 0.984375
- 0.9921875

What do you notice?



Lessons from Amdahl's Law

Useful Corollary of Amdahl's law:

Remember:
$$S_{overall} = 1 /$$

• 1
$$\leq$$
 S_{overall} \leq 1 / (1 - F_{enhanced})

((1 – F _{enhanced})	+ F / S enhanced
-------------------------------	------------------

Fenhanced	Max S _{overall}	Fenhanced	Max S _{overall}
0.0	1	0.9375	16
0.5	2	0.96875	32
0.75	4	0.984375	64
0.875	8	0.9921875	128

- Moral: It is hard to speed up a program.
- Moral++: It is easy to make premature optimizations.
- What does this say about parallel systems?



Other Maxims

- Second Corollary of Amdahl's law:
 - When you identify and eliminate one bottleneck in a system,
 something else will become the bottleneck
 - Recall week1 (problems in complex systems)?