Making H5P Multi-Thread Safe: A Sketch Design

John Mainzer Lifeboat, LLC

5/30/24

Due to the absence of design documentation for the H5P package this document is an attempt to outline the reverse-engineered design and to offer the beginnings of a design for a multi-thread safe re-implementation of H5P. For completeness Appendix 3 contains a design document for HDF5 generic properties found on the internet but not included in the current HDF5 documentation maintained by The HDF Group.

IntroductionIntroduction	4
H5P at Present	4
H5P Data Structures	
Properties	
Property List Classes	
Property Lists	
Selected Operations on Property List Classes	10
Property List Class Creation	
Property List Class Copy	11
Adding and Deleting Properties from an Existing Property List Class	12
Deleting Property List Classes	15
Iteration over Properties in a Property List Class	
Selected Operations on Property Lists	16
Property List Creation, Deletion, and Copy	16
Property Insertion and Deletion	
Property Value Get and Set	20
Property List Encode and Decode	22
Getting a Property Lists Parent Property List Class	22
Comments on the Current Implementation of Property Lists	23
Multi-Thread Issues in H5P	24
Use of other HDF5 packages in H5P	24

Multi-thread thread issues in H5P proper	26
Proposed Solution	26
Data Structures	26
Public API Function Outlines	42
Private API Function Outlines	42
Next Steps	42
Appendix 1 – H5P public API calls	43
Appendix 2 – H5P internal API calls	150
Appendix 3 – Original Proposal For Generic Properties?	164
Generic Properties Overview and Justification	164
Generic Properties Implementation	
API Changes for Implementing Generic Properties	
New API Function Definitions	
Examples:	187
Appendix 4: Property and Property List Class Callbacks	189
Root Property List Class	190
Data Transfer Property List (DXPL) Class	191
Maximum Temp Buffer Size Property	
Type conversion buffer property	
Background buffer property	
Background buffer type property	
B-Tree node splitting ratios property	
Vien allocation function property	
Vien allocation information property	
Vien free function property	
Vlen free information property	
I/O transfer mode property (H5D_XFER_IO_XFER_MODE)	
I/O transfer mode property (H5D_XFER_MPIO_COLLECTIVE_OPT)	
I/O transfer mode property (H5D_XFER_MPIO_CHUNK_OPT_HARD)	
I/O transfer mode property(H5D_XFER_MPIO_CHUNK_OPT_NUM)	
I/O transfer mode property (H5D_XFER_MPIO_CHUNK_OPT_RATIO)	
Chunk Optimization mode property	
Actual I/O mode property	201
Local cause of broken collective I/O property	202
Global cause of broken collective I/O property	202
EDC property	202
Filter callback property	
Type conversion callback property	
Data transform property	
Dataset selection property	
File Access Property List (FAPL) Class (ROOT $ ightarrow$ FAPL)	206
File Mount Property List (FMPL) Class (ROOT → FMPL)	206

VOL Initialization Property List (VIPL) Class (ROOT ->VIPL)	. 207
Link Access Property List (LAPL) Class (ROOT $ ightarrow$ LAPL)	. 207
Object Creation Property List (OCRTPL) Class (ROOT $ ightarrow$ OCRTPL)	. 208
Object Copy Property List (OCPYPL) Class (ROOT $ ightarrow$ OCPYPL)	. 208
String Creation Property List (STRCRTPL) Class (ROOT $ ightarrow$ STRCRTPL)	. 209
Datatype Access Property List (TAPL) Class (ROOT $ ightarrow$ LAPL $ ightarrow$ TAPL)	. 209
Attribute Access Property List (AAPL) Class (ROOT $ ightarrow$ LAPL $ ightarrow$ AAPL)	. 210
Group Access Property List (GAPL) Class (ROOT $ ightarrow$ LAPL $ ightarrow$ GAPL)	. 210
Datatype Creation Property List (TCPL) Class (ROOT $ ightarrow$ OCPL $ ightarrow$ TCPL)	. 211
Dataset Creation Property List (DCRTPL) Class (ROOT $ ightarrow$ OCPL $ ightarrow$ DCRTPL)	. 212
Dataset Access Property List (DAPL) Class (ROOT $ ightarrow$ LAPL $ ightarrow$ DAPL)	. 212
Group Creation Property List (GCRTPL) Class (ROOT $ ightarrow$ OCRTPL $ ightarrow$ GCRTPL)	. 213
Attribute Creation Property List (ACRTPL) Class (ROOT $ ightarrow$ STRCRTPL $ ightarrow$ ACRTPL)	. 213
Link Creation Property List (LCRTPL) Class (ROOT $ ightarrow$ STRCRTPL $ ightarrow$ LCRTPL)	. 214
Map Create Property List (MCRTPL) Class (ROOT $ ightarrow$ OCRTPL $ ightarrow$ MCRTPL)	. 214
Map Access Property List (MAPL) Class (ROOT $ ightarrow$ LAPL $ ightarrow$ MAPL)	. 215
Reference Access Property List (RACCPL) Class (Root $ ightarrow$ FAPL $ ightarrow$ RACCPL)	. 216
File Creation Property List (FCRTPL) Class (ROOT $ ightarrow$ OCRTPL $ ightarrow$ GCRTPL $ ightarrow$ FCRTPL)	. 216

Introduction

H5P provides support for the property lists used throughout HDF5. It must depend on H5I since property lists are accessed via IDs – instances of hid_t to be precise. Similarly, it must depend on H5E for error reporting. While in principle, there seems no reason why H5P proper should have any other dependencies, it should be no surprise at this point that this is not the case.

More generally, since H5P includes support for getting and setting the various properties associated with the various standard property lists – FCPL (File Creation Property List), FAPL (File Access Property List), etc. – there must be at least minimal interaction with the packages configured with these properties. In principle, this should be limited to structure definitions, constants, and a bit of sanity checking – all items with little or no multi-thread safety significance. While this is certainly true in some cases, at present I don't know the extent to which it is true in general.

This version of the RFC is a large improvement over the previous version, but it is still a work in progress. While I have completed my review of the core property list code, and an initial review of the initialization process for HDF5 library defined property list classes, I have only glanced at the various HDF5 library specific property list class and property specific callbacks – which are a source of the interactions with packages configured via the property lists.

While this deficit must be addressed before we commit to any of the designs outlined in this RFC, I am now in position to discuss the structure of the property list facility in some detail – and have done so in the next section.

This discussion is longer and more detailed than I would like. However, a good understanding of the current implementation is necessary to motivate the solutions proposed.

H5P at Present

In the context of HDF5, a property list is conceptually a list of (<name>, <value>) pairs used to pass configuration data into HDF5 API calls.¹ Given this use case, it is convenient to define property list classes, which facilitate creation of default property lists for a given purpose (i.e., creating an HDF5 file) which have a specified set of (<name>, <value>) pairs. These property lists can then be edited as necessary for the purpose at hand.

Further, new properties can be added to both property list classes and property lists. At the application program level, the major use case for this feature is adding configuration data for externally developed Virtual File Drivers (VFD) and VOL connectors to the appropriate HDF5 defined property lists.

¹ In a few cases, it is also used to pass data back out to the application program.

H5P exists to provide property list services to the HDF5 library proper, and also to application programs. The basic services may be summarized as follows:

- Create, delete, copy, modify, and compare property list classes, and also iterate through properties in a property list class.
 - Here a property list class is best thought of as an archetype for newly created property lists of the desired structure. It specifies the properties that appear in a new property list derived from a target class along with their default values. While the actual implementation is different, conceptually new property list classes are created by duplicating an existing class, and then either adding new properties or overwriting the default values of inherited properties.
- Create, delete, copy, compare, encode, and decode property lists. Get and set the values of properties in a property list. Delete properties from a given property list. Insert new properties into a given property list. Iterate through the properties in a property list.

In terms of internal architecture, the property list code employs a design that echoes a number of ideas from object-oriented programming languages. This design decision creates a number of issues for both the existing single thread implementation and any revision or re-write to add multi-thread support.

H5P Data Structures

There are three main structures used in H5P:

- H5P genprop t used represent properties,
- H5P genclass t used to represent property list classes, and
- H5P genlist t used to represent property lists.

There is also H5P_libclass_t, which is used to construct tables that control the construction of the HDF5 library defined property list classes. As my review of H5P initialization is still in progress, a discussion of this structure will have to wait for the next revision of this RFC. For those who can't wait, there are preliminary notes in Appendix 2.

Properties

The fundamental elements in property lists and property list classes are properties, which are stored in instances of H5P_genprop_t – whose definition is reproduced below.

```
/* Define structure to hold property information */
typedef struct H5P_genprop_t {
    /* Values for this property */
    char * name; /* Name of property value */
    size_t size; /* Size of property value */
    void * value; /* Pointer to property value */
    H5P_prop_within_t type; /* Type of object the property is within */
    hbool_t shared_name; /* Whether the name is shared or not */

    /* Callback function pointers & info */
    H5P_prp_create_func_t create; /* Function to call when a property is created */
    H5P_prp_set_func_t set; /* Function to call when a property value is set */
    H5P_prp_get_func_t get; /* Function to call when a property value is retrieved */

    H5P_prp_encode_func_t encode; /* Function to call when a property is encoded */
    H5P_prp_decode_func_t decode; /* Function to call when a property is decoded */
    H5P_prp_copy_func_t copy; /* Function to call when a property is deleted */
    H5P_prp_compare_func_t cmp; /* Function to call when a property is copied */
    H5P_prp_close_func_t close; /* Function to call when a property is compared */
    H5P_prp_close_func_t close; /* Function to call when a property is compared */
    H5P_prp_close_func_t close; /* Function to call when a property is compared */
    H5P_prp_close_func_t close; /* Function to call when a property is compared */
    H5P_prp_close_func_t close; /* Function to call when a property is closed */
}
```

At the fundamental level, a property consists of a name, a value stored in a buffer, and an optional set of functions to be called on property

- create,
- set,
- get,
- encode,
- decode,
- delete (from a property list),
- copy,
- compare, and
- close (of the host property list).

Since there are no constraints on theses callbacks, they present an obvious risk from a multithread perspective. For properties defined by the HDF5 library, this should be manageable, since this code is under the control of the library. Externally defined properties are of greater concern.

The type field is used to note whether the property is contained in a property list class, or a property list proper.

Property List Classes

Property list classes can be thought of as templates for property lists – in essence they specify the properties contained in property lists based on a given property list class, along with their

default values². Property list classes are stored in instances of H5P_genclass_t – whose definition is reproduced below.

```
/* Define structure to hold class information */
struct H5P genclass t {
  struct H5P_genclass_t *parent; /* Pointer to parent class */
char * name; /* Name of property list class */
H5P_plist_type_t type; /* Type of property */
size_t nprops; /* Number of properties in class */
unsigned plists; /* Number of property lists that have been
                                               created since the last modification to
                                                 the class */
                             classes; /* Number of classes that have been derived since the last modification to the class
   unsigned
                                                since the last modification to the class */
                             ref_count; /* Number of outstanding ID's open on this
   unsigned
                                                 class object */
                              class object */
deleted; /* Whether this class has been deleted and is
   hbool t
                                                 waiting for dependent classes & proplists
                                                 to close */
                            revision; /* Revision number of a particular class
   unsigned
                                                 (global) */
                                           /* Skip list containing properties */
   H5SL t
                           * props;
   /* Callback function pointers & info */
   H5P cls create func t create func; /* Function to call when a property list
                                               is created */
                              create data; /* Pointer to user data to pass along to
   void *
                                                create callback */
   H5P cls copy func t copy func; /* Function to call when a property list
                                               is copied */
                              copy_data; /* Pointer to user data to pass along to
   void *
   copy callback */
H5P_cls_close_func_t close_func; /* Function to call when a property list
                                                is closed */
                              close data; /* Pointer to user data to pass along to
   void *
                                                close callback */
};
```

Conceptually, a property list class is a named list of properties with default values, decorated by functions to be called when a derived property list is created, copied, or closed, and finally, a pointer its parent property list class.

The pointer to the parent class is central here, as the set of properties contained in the property list class is defined to be set of all properties that appear in a given instance of H5P_genclass_t A, plus all properties that appear in the singly linked list of instances of H5P_genclass_t for which A is the first entry (see below for management of duplicate properties). This linked list must always terminate in the ROOT property list class, which is created by the HDF5 library at initialization, and contains no properties.

While no single instance of H5P_genclass_t can contain two or more properties of the same name, different instances of H5P_genclass_t may contain properties of the same name. When

² But note that properties may be either added to or removed from individual property lists.

searching for a property in a linked list of instances of H5P_genclass_t, the first such property encountered shadows any later properties of the same name.

The properties (really instances of H5P_genprop_t) that reside in a property list class are stored in a skip list – which is implemented in the H5SL package. Note that this package is not thread safe, and – to a first order approximation – has been the primary cause of HDF5 performance degradation seen since HDF5 version 1.6³.

nprops is used to track the number of unique properties in the target instance of H5P genclass t.

The classes field is used to maintain a count of the number of property list classes whose parent pointers point to this instance of H5P_genclass_t. Similarly, the plists field is used to maintain a count of the number of property lists that point to this instance of H5P_genclass_t with their pclass fields (see below).

The type field indicates which of the HDF5 defined property list classes this is, with an additional option for user defined property list classes. The definition of H5P_plist_type_t is reproduced below.

```
typedef enum H5P plist type t {
  H5P_TYPE_USER
  H5P TYPE ROOT
  H5P TYPE OBJECT CREATE
  H5P TYPE FILE CREATE
  H5P TYPE FILE ACCESS
  H5P TYPE DATASET CREATE = 5,
  H5P TYPE DATASET ACCESS = 6,
  H5P TYPE DATASET XFER
  H5P TYPE FILE MOUNT
  H5P_TYPE_GROUP_CREATE = 9,
H5P_TYPE_GROUP_ACCESS = 10,
  H5P TYPE DATATYPE CREATE = 11,
  H5P_TYPE_DATATYPE_ACCESS = 12,
  H5P
       _{\text{TYPE\_STRING\_CREATE}} = 13,
  H5P TYPE ATTRIBUTE CREATE = 14,
  H5P_TYPE_OBJECT_COPY = 15,
H5P_TYPE_LINK_CREATE = 16,
  H5P TYPE LINK ACCESS = 17,
  H5P TYPE ATTRIBUTE ACCESS = 18,
  H5P TYPE VOL INITIALIZE = 19,
  H5P_TYPE_MAP_CREATE = 20,
H5P_TYPE_MAP_ACCESS = 21,
  H5P TYPE REFERENCE ACCESS = 22,
  H5P TYPE MAX TYPE
} H5P plist type t;
```

The remaining fields – ref_count, deleted, and revision – appear to exist to support modifications to property list classes at run time.

³ I will argue later that skip lists should be removed from the property list implementation.

The revision field is set to a new, unique integer each time a property list class is created or modified. However, since multiple instances of H5P_genclass_t containing identical values are possible, its utility is questionable.

Once created, property list classes are normally stored in the index and (at least from a user perspective) are accessed via IDs. However, it is possible for a property list class (specifically an instance of H5P_genclass_t) to have multiple IDs, or no ID at all. The ref_count field is used to track the number of IDs in the index. The deleted field is set to TRUE when ref_count drops to zero. However, an instance of H5P_genclass_t is not deleted until the ref_count, classes, and plists fields all drop to zero. Further, it is possible for an instance of H5P_genclass_t which has lost all its references in the index to be re-inserted in the index — at which point ref_count in incremented and the deleted field is set back to FALSE. The mechanics of this will be discussed in greater detail when we discuss operations on property list classes and property lists below.

Property Lists

Conceptually, a property list is simply a list of (name, value) pairs. In H5P, property lists are stored in instances of H5P_genlist_t – whose definition is reproduced below.

```
/* Define structure to hold property list information */
struct H5P genplist t {
  H5P_genclass_t *pclass; /* Pointer to class info */
hid_t plist_id; /* Copy of the property list ID (for use in
                                  close callback) */
  size_t
                   nprops;
                               /* Number of properties in class */
                               // This comment appears to be in error. In the
                                // context of a property list, nprops seems to be
                               // the number of properties in the property list.
                                \ensuremath{//} While the number of properties in a property list
                               // and in its immediate parent property list class will
                               // usually match, this need not be the case.
  hbool t
                   class init; /* Whether the class initialization callback
                                   finished successfully */
                               /* Skip list containing names of deleted properties */
  H5SL t *
                   del;
                   props;
  H5SL t *
                               /* Skip list containing properties */
```

Here, the props skip list contains all the properties that may have a value that is different from the default values listed in the properties of the same name in the linked list of property list classes (strictly speaking of instances of H5P_genclass_t) whose head is pointed to by the pclass field⁴. I say "may" here, as properties are copied from the base property list class(es) to the newly created property list if they have "copy" or "create" callbacks associated with them. While these callbacks are run on the default value to generate the value for the property in the new property list, this need not modify the property value.

⁴ Or the parent property list class(es) for short.

As shall be seen, it is also possible for a property list to contain properties that do not appear in the parent property list class(es), or for a property to be reset to its default value without being removed from the props skip list.

The del skip list contains the names of properties that have been deleted from the property list. This is necessary, as in the absence of its name appearing in the del skip list, any property that doesn't appear in the props skip list is assumed to retain its default value – which is obtained by searching the parent property list class(es), starting with pclass—props.

The class_init boolean is used to record whether the create_func's (if any) of the parent property list class(es) completed without error when the property list was created. If they didn't, the corresponding close_func's are not run when the property list is closed.

Like property list classes, property lists are entered into the index. Unlike property list classes, the resulting IDs appear to be unique, and are stored in the plist_id field of the associated instance of H5P genlist t.

With this discussion of the underlying data structures in hand, we now proceed to discussions of selected operations on property list classes and property lists. For details on omitted operations, please see the appendices, or the source code.

Operations on properties are always incidental to these operations, and thus are covered in passing.

Selected Operations on Property List Classes

The details of the various public and private API calls that operate on property list classes are discussed in detail in the appendices. Some of these operations are what one would expect, and thus are not covered here.

This section boils these discussions down as much as possible, and focuses on operations that are either central, that highlight issues with the existing implementation, or that are likely to present challenges to a multi-thread safe implementation.

Property List Class Creation

New property lists are created via calls to

All HDF5 library property list classes are created by the H5P package during initialization, so there is no library private API call for this purpose. The package function call for creating a new property list class (but not installing it in the index) is

which is called by H5Pcreate_class() and other public API calls.

H5Pcreate_class does pretty much what one would expect – it calls H5P__create_class() to

- Allocate a new instance of H5P genclass t,
- Copy the supplied data into it,
- Create the props skip list,
- Set the nprops, plists, and classes fields to zero,
- Set deleted to FALSE,
- Set revision to a unique number, and
- Set ref count to zero.

Assuming that the par_class parameter is not NULL, it sets the parent field to point to the parent property list class, and increments parent \rightarrow classes.

After H5P__create_class() returns, H5Pcreate_class inserts the new property list class in the index, which increments its ref count field in passing.

Property List Class Copy

While one wouldn't expect much use for a property list copy facility internally, the current property list implementation uses it heavily when modifying existing property list classes.

Interestingly, while there is a public API call

```
hid t H5Pcopy(hid t plist id)
```

that can create a copy of a property list class, insert it in the index, and return the id of the copy, the user level documentation on this API call doesn't mention this capability.

This is may be a documentation bug, as there is the obvious use case of creating a customized version of a HDF5 defined property list class⁵. On the other hand, it may be an attempt to steer the user towards H5Pcreate_class() for this purpose, as that would at least allow the possibility of different property list class names. But if this is the case, why leave in the capability?

In contrast, the H5P package internal function

```
H5P_genclass_t * H5P__copy_pclass(H5P_genclass_t *pclass)
```

is used heavily in operations that modify existing property list classes, and is outlined here in preparation for these discussions.

H5P__copy_pclass() first calls H5P__create_class() to construct a duplicate of the instance of H5P_genclass_t that forms the source property list class. It then walks the props skip list of the source, duplicates each property, and inserts it into the props skip list in the duplicate. Note that the function does not insert the new instance of H5P_genclass_t in the index, or increment the classes field in the parent property list class.

Adding and Deleting Properties from an Existing Property List Class

As suggested earlier, the decision to employ a design that echoes ideas from object-oriented programming languages presents a number of issues that are not handled gracefully. Here is where the cracks begin to show.

An obvious question when modifying existing property list classes is what happens to existing property lists and property list classes that are derived from the property list class that is being modified? Several possible solutions present themselves:

- 1. Avoid the problem by making property list classes with derived property lists or property list classes read only.
- 2. Propagate changes through all derived property lists and property list classes.
- 3. Version the property list class so that the previously derived property lists and property list classes can still reference the version of the property list class from which they are derived.

⁵ For example, a version of the FAPL property list class that includes a property needed to configure a user supplied VFD.

I don't have design documentation for the implementation of the property list facility in HDF5 – indeed, it is quite possible that such documentation never existed⁶. Thus, I don't know what considerations went in to the choice between these options and any others I have missed.⁷ However, from examination of the code, option 3 appears to have been selected. I say appears, as this apparent decision is not implemented uniformly.

In the public API, new properties can be inserted into an existing property list class⁸ via two different calls:

Internally, all property list classes are created and populated during H5P package initialization, and hence there is not a library private function for this purpose. The call used here is

which simply inserts the new properties into the property list without versioning. This works, because at this point the target property list can't have any derived property lists or property list classes.

H5Pregister2() first looks up a pointer to the target property list class (call it A) and then calls H5P_register().

⁶ Until relatively recently, RFCs proposing modifications or extensions to the HDF5 library usually discussed only public API changes and motivation – with little or no attention to implementation details.

⁷ But note Appendix 3, in which I have reproduced what appears to be an early RFC for the current implementation of H5P.

⁸ Including HDF5 library defined property list classes.

H5P__register() starts by checking to see if A has any immediately derived property list classes or property lists. If it doesn't, H5P register() simply calls H5P register real() to:

- Create the specified property and insert it into A (specifically to insert it into the skip list pointed to by the props field),
- Increment the nprops field, and
- Set A's revision field to a new unique number.

In contrast, if A does have immediately derived property list classes or property lists, H5P register():

- Calls H5P__copy_pclass() (see above) to duplicate A call this copy A-Prime.
- Calls H5P__register_real() (see above) to create the new property and insert it into A-Prime.

After H5P__register() returns, H5Pregister2() checks to see if A-prime has been created. If it has, it calls H5I_subst() to replace A in the index with A-Prime and H5P_close_class() to decrement the ref_count field of A – which will be deleted when its ref_count, classes, and plists fields all drop to zero.

Observe that as a result of this process, we now have (at least) two versions of the property list class A – of which only the latest one is accessible via the index, with the previous version(s) being accessible only via the property list classes and property lists derived from that version. Note that this matches the user documentation, which states that modifications to property list classes only effect property lists created after the modification.

As shall be seen, this design decision has further implications when the user attempts to look up the parent class of a property list – see the section **Getting a Property Lists Parent Property List Class** below.

The public call for deleting a property from a property list class is

herr_t H5Punregister(hid_t pclass_id, const char *name)

⁹ A property list class A has immediately derived property list class(es) or property list(s) if there exists one or more property list classes (i.e., instances of H5P_genclass_t) whose parent fields point to A and/or one or more property lists (i.e., instances of H5P_genlist_t) whose pclass fields point to A. This is determined via inspection of A's classes and plists fields. If either of these fields contain a positive value, the property list class A has immediately derived property list class(es) and or property list(s).

All property deletions in the HDF5 library are done within the H5P package, and thus there is no internal API call for this purpose. The H5P package function that performs property deletions from property list classes is

```
herr_t H5P__unregister(H5P_genclass_t *pclass, const char *name)
```

In addition to being called by H5Punregister() it is also used in H5Pcopy_prop().

H5Punregister() simply looks up a pointer to the instance of H5P_genclass_t (call it A) that forms the root of the data structure that represents the target property list class, passes this pointer along with the name of the target property to H5P__unregister(), and returns.

H5P_unregister() makes no test for immediately derived property lists or property list classes. It unconditionally:

- Deletes the named property from A's list of properties (an error is flagged if the named property doesn't exist),
- Decrements the nprops field, and
- Sets A's revision field to a new unique number.

This has the effect of deleting the named property from all derived property lists that have not yet changed the value of the target property from its default – which will cause the H5Pget() and H5Pset() calls to fail when invoked on the deleted property.

As this directly contradicts the user documentation, and since the behavior of H5P__unregister() is appropriate in its other use in H5Pcopy_prop(), this is probably a bug – which should be fixed if the current property list implementation is retained.

Deleting Property List Classes

The public API for deleting a property list class is

```
herr_t H5Pclose_class(hid_t plist_id);
```

There is no corresponding internal API or H5P package function – which should be no surprise given that a property list class can't be deleted until its ref_count, classes, and plists fields all drop to zero.

H5Pclose_class() calls H5I_dec_app_ref() with the id associated with the target property list class – call it A. This has the effect of decrementing the reference count on the index entry (not to be confused with the reference counts on A). If this index reference count drops to zero, H5I

deletes the entry from the index, and calls H5P__close_class_cb() to allow H5P to do the appropriate cleanup.

H5P__close_class_cb() calls H5P__close_class() which calls H5P__access_class() which does the real work.

H5P__access_class() is a bit of a Swiss army function. Depending on its parameters, it will increment or decrement the ref_count, classes, or plists fields of the target property list class. When all of these fields drop to zero, it decrements the classes field of the parent property list class via a recursive call to itself, and then discards the target property list class.

Iteration over Properties in a Property List Class

The main point to be made here is that the H5Piterate() public API exists, and presents a variety of multi-thread safety issues. While we are far from making such decisions, it should probably be dealt with like the other iteration functions encountered in this effort.

Selected Operations on Property Lists

As with property list classes, the details of the various public and private API calls that operate on property lists are discussed in detail in the appendices.

As before, the objective is to cover central operations, to highlight issues with the existing implementation, and to point out challenges for a multi-thread safe implementation.

Note that some public API calls operate on both property list classes and property lists – and thus appear both in this section, and the previous discussion of selected operations on property list classes.

Property List Creation, Deletion, and Copy

The public API call to create a new property list is

```
hid_t H5Pcreate(hid_t cls_id)
```

Its internal API cognate is

```
hid_t H5P_create_id(H5P_genclass_t *pclass, hbool_t app_ref);
```

which is called almost immediately by H5Pcreate(), which looks up the pointer to the parent property list class (call it P), and then passes it to H5P create id().

H5P create id() first calls H5P create() which does most of the work. In particular it:

- Allocates and initializes a new instance of H5P_genlist_t, along with its associated skip lists. Call this new property list A
- Scans the properties in the parent property list class(es) starting with P, being careful to skip any properties with duplicate names after the first instance has been encountered.
 For each such property, it tests to see if it has a create callback, and if so, it duplicates the property (calling its create callback in passing) and inserts it into the skip list pointed to by A's props field.
- Calls H5P access class() to increment P's plists field.
- Returns a pointer to A

After H5P__create() returns, H5P_create_id() inserts A into the index, and then scans the list of parent property list class(es), starting with P and executes their create callbacks (the create_func field in H5P_genclass_t). If all these functions complete successfully, its sets A's class_init field to TRUE. Regardless of the success of the create callbacks, H5P__create returns the new ID associated with A, which is the returned to the user by H5Pcreate().

The public API call for discarding a property list is

```
herr t H5Pclose(hid t plist id);
```

Its private API cognate is

```
herr_t H5P_close(H5P_genplist_t *plist)
```

which is used extensively in error cleanup and also by H5I to discard property lists whose reference count has dropped to zero.

H5Pclose() calls H5I_dec_app_ref() with the id associated with the target property list – call it A. This has the effect of decrementing the reference count on the index entry. If this index reference count drops to zero, H5I deletes the entry from the index, and calls H5P__close_list_cb() to discard A.

H5P close list cb() is just a pass through function that calls H5P close()

H5P_close() does the actual work. It is a long and involved function – simplifying as much as possible, it

• Tests to see if A's class_init field is TRUE. If it is, it scans the list of parent property list class(es), starting with *pclass and executes each property list class's close callback (the close_func field in H5P_genclass_t) in order.

- Scans the entries in A's props skip list, and calls the close callback for each property that has one.
- Scans the entries in the parent property list class(es) props skip list, starting with the parent property list class pointed to by A's parent field. For each such entry, it tests to see if a property of that name appears in A's props or del skip lists, or earlier in the current scan. If not, it calls that property's close callback it if exists.
- Decrement A's immediate parent property list class's plists field via a call to H5P_access_class(). Recall that may result in the discard of one or more of the property lists class(es) of A.
- Discard the props and del skip lists maintained by A, along with their contents.
- Discard A's base instance of H5P genlist t.

The public API call to copy property lists is

```
hid t H5Pcopy(hid t plist id)
```

Recall that this API call also works on property list classes, although this fact is not mentioned in the user documentation. The private API cognate is

```
hid_t H5P_copy_plist(const H5P_genplist_t *old_plist, hbool_t app_ref)
```

The process for copying a property list is similar to that for creating a property list. The major differences are the use of property copy callbacks, and the need to copy properties from the base property list. See the appendices for details.

Property Insertion and Deletion

The whole idea of either inserting or deleting properties from an existing property list is a departure from the object-oriented notions that appear to have been the basis of the property list facility. However, it does allow user processes to insert new properties in a property list without modifying HDF5 library defined property list classes, or creating modified copies of same. As such, it has obvious uses for properties that are only needed once.

The public API for inserting properties into an existing property list is

```
herr_t H5Pinsert2(hid_t plist_id, const char *name, size_t size, void *value, H5P_prp_set_func_t prp_set, H5P_prp_get_func_t prp_get, H5P_prp_delete_func_t prp_del, H5P_prp_copy_func_t prp_copy, H5P_prp_compare_func_t prp_cmp, H5P_prp_close func t prp_close)
```

The private API cognate is

```
herr_t H5P_insert(H5P_genplist_t *plist, const char *name, size_t size, void *value, H5P_prp_set_func_t prp_set, H5P_prp_get_func_t prp_get, H5P_prp_encode_func_t prp_encode, H5P_prp_decode_func_t prp_decode, H5P_prp_delete_func_t prp_delete, H5P_prp_copy_func_t prp_copy, H5P_prp_compare_func_t prp_cmp, H5P_prp_close func t prp_close)
```

H5Pinsert2() looks up a pointer to the target property list (call it A) and then passes this pointer to H5P_insert() along with the necessary parameters.

H5P_insert() verifies that the skip list referenced by A's props field doesn't contain a property of the supplied name, and returns an error if does.

It then checks A's deleted list (referenced by the del field) to see if it contains the supplied name, and removes it from the deleted list it is found.

If the supplied name doesn't appear in the deleted list, H5P_insert() next searches for a property of the supplied name in A's parent property list class(es), and returns an error if this search is successful.

With this sanity checking complete, H5P_insert() creates the new property as specified by its parameters, inserts it in the skip list referenced by A's props field, increments A's nprops field, and returns

The public API for deleting properties from property lists is

```
herr_t H5Premove(hid_t plist_id, const char *name)
```

Its private API cognate is

```
herr_t H5P_remove(H5P_genplist_t *plist, const char *name)
```

H5Premove() looks up a pointer to the target property list (call it A) and then passes this pointer to H5P_remove() along with the name of the target property. H5P_remove() in turn calls H5P__do_prop() to do the actual work.

H5P__do_prop() is another swiss army function. It scans the target property list for the target name, and then applies one of the supplied functions depending on where the target property is found. In this case, it performs as follows:

Test to see if the target name already appears in A's deleted list, and fail if it does.

Search for the target property in A's props skip list. If it is found, run the properties deletion callback, insert the properties name in A's deleted list, remove the property from the skip list, free it, decrement A's nprops field, and return.

If the search of A's props skip list fails, search the properties of A's parent property list class(es) for the target property. If it is found, run the properties deletion callback **on a copy of the properties value**¹⁰, insert the properties name in A's deleted list, decrement A's nprops field and return. Note that the target property is not removed from its host property list class.

If both searches fail, H5P__do_prop() fails.

Property Value Get and Set

The public API call to get the value of a property in a property list is

```
herr t H5Pget(hid t plist id, const char *name, void *value)
```

Its internal API cognate is

```
herr t H5P get(H5P genplist t *plist, const char *name, void *value)
```

Conceptually, these routines look up the target property in the target property list, and copy its value into the supplied buffer. The actual implementation is a bit more complex.

H5Pget() looks up a pointer to the target property list (call it A) and passes this pointer into H5P get() with its other parameters.

H5P_get() calls H5P__do_prop() with the appropriate parameters to perform the lookup and then returns.

In this configuration, H5P_do_prop() first scans A's deleted list for the target name, and returns failure if this search succeeds.

If the search of A's deleted list fails, H5P__do_prop() searches first A's props skip list, and then the props skip lists of the parent property list class(es) until a property of the specified name is found.

If the search fails, H5P do prop() returns failure.

If the search succeeds, H5P do prop() tests to see if the target property has a get callback.

¹⁰ At present, I don't know why this is done. I expect that investigation of the call back functions will reveal the answer.

If it doesn't, H5P__do_prop() just memcpy's the target property's value buffer into the supplied buffer and returns.

If it does, H5P__do_prop() allocates a temporary buffer of size equal to the target property's value buffer, copies the value buffer into the temporary buffer, runs the properties get function on the temporary buffer, copies the temporary buffer into the supplied buffer¹¹, discards the temporary buffer and returns.

The public API to set the value of a property in a property list is

```
herr t H5Pset(hid t plist id, const char *name, const void *value)
```

Its private API cognate is

```
herr t H5P set(H5P genplist t *plist, const char *name, const void *value)
```

Conceptually, these routines look up the property of the supplied name in the target property list, and set its value to the supplied value. In practice, this is complicated by property specific set callbacks, and the possibility that the target property may still have its default value, and thus not reside in the target property list.

H5Pset() looks up a pointer to the target property list (call it A) and passes this pointer into H5P_set() with its other parameters.

H5P_set() calls H5P__do_prop() with the appropriate parameters to perform the lookup and then returns. Note that in this case, the supplied function pointers are different – one for the case in which the target property is in A's props skip list, and another for the case in which the target property is found in one of A's property list class(es).

In this configuration, H5P__do_prop() first scans A's deleted list for the target name, and returns failure if this search succeeds.

It then searches A's props skip list for the target property.

If the target property is found, H5P do prop()

• Tests to see if the property's set call back is defined. If it is defined, H5P__do_prop() allocates a buffer of size equal to the property's value buffer, memcpy's the supplied buffer into the temporary buffer, and runs the property's set callback on the temporary buffer¹².

¹¹ Again, the reason for this is a unknown to me. A review the property callbacks is needed to determine if this is really necessary, and if so why.

¹² Yet another epicycle whose motivation must be investigated.

- Tests to see if the property's del callback is defined, and if so calls it on the property's value.
- Memcpy's the new value into the property's value field, either from the supplied buffer (if the set callback is undefined) or from the above temporary buffer if it is.
- Frees the temporary buffer if it exists, and
- Returns

If the target property is not found in A's props skip list, H5P__do_prop() searches for a property of the specified name in the parent property list class(es). If such a property is found, H5P__do_prop()

- Checks to see if the target property's set callback is defined, and if so, set up the temporary buffer as above.
- Duplicates the property
- Inserts the duplicate property into A
- Memcpy's the new value into the duplicate property's value field, either from the supplied buffer (if the set callback is undefined) or from the above temporary buffer if it is.
- Frees the temporary buffer if it exists, and
- Returns

If both searches fail, H5P__do_prop() fails.

Property List Encode and Decode

Perhaps the only points to be made here is that the facility for encoding and decoding property lists exists, that it is restricted to property lists derived from one of the HDF5 library defined types, and that only properties with encode / decode callbacks are encoded / decoded.

To my knowledge, there is no documentation on the file format of encoded property lists. The format is very simple, so this isn't a major issue.

Getting a Property Lists Parent Property List Class

The public API

```
hid t H5Pget class(hid t plist id)
```

exists to return the id of the immediate parent property list class of the supplied property list. It has an internal API cognate

```
H5P genclass t *H5P get class(const H5P genplist t *plist)
```

which fortunately doesn't have the problems that H5Pget_class() has.

In principle, this should be simple. Property list classes are stored in the index, and are referenced by their ID when the user creates a property list based on one of the extant property list classes. Thus, it should be simple for a property list to report the ID of the property list class it is immediately derived from.

However, the policy decision to version property list classes that have immediately derived property list classes or property lists when the target property list class is modified breaks this¹³, as the relevant version of the property list class may no longer exist in the index.

H5Pget_class() solves this problem by unconditionally inserting the instance of H5P_genclass_t pointed to by its parent field into the index, and returning the newly allocated ID.

This has several knock-on effects:

- A given property list class can have multiple IDs and therefore multiple entries in the index.
- The index can contain multiple property list classes with the same name but different contingents of properties, or perhaps the same properties but with different default values.
- Since it is also possible to have multiple property list classes with identical definitions but different IDs, the process of comparing property list classes is greatly complicated. Instead of a simple comparison of IDs or revision numbers, a deep, field by field comparison is required. See H5Pequal() in the first appendix.

This introduces a level of potential confusion into the public API that seems unacceptable. If at all possible, this should be resolved.

¹³ See the section **Adding and Deleting Properties from an Existing Property List Class** above for further discussion.

Comments on the Current Implementation of Property Lists

As should be obvious from the above, the data structures used to implement property lists are complex. While I expect it is possible, implementing the mutual exclusion required to avoid data structure corruption in a multi-thread environment would be challenging, and likely slow due to the multitude of locks. More importantly, its complexity would make it hard to avoid accidentally inserting either deadlocks or holes in mutual exclusion during routine maintenance. Finally, a complex MT solution will exacerbate the lock ordering problem between packages.

The use of skip lists (implemented in H5SL) is also worthy of comment. Skip lists were once used extensively throughout the HDF5 library. However, profiling exercises indicated that the shift to skip lists was the primary cause of the slowdown in HDF5 performance since HDF5 1.6.

Much of this slowdown was located in H5P as skip lists are a fairly heavy weight data structures, property lists seldom if ever exceed 25 entries, and (at the time) properties were looked up repeatedly. The introduction of H5CX largely mitigated this issue as it (among other things) caches the values of commonly accessed property list entries. However, property list operations remain expensive, and other optimization efforts have pushed H5P back up near the top of the optimization to-do list.

Given this move away from skip lists for performance reasons, it is hard to argue for developing a MT safe implementation for use in property lists.

If the above points are not sufficient to rule out any attempt to retrofit multi-thread safety on the current property list implementation, there are also the various interesting features of the current implementation as outlined above. In particular, while one can argue the merits of the versioning approach to modifications to property list classes, the current implementation introduces too much complexity, and too much potential confusion into the public API. Further, I am not aware of any used case for it.

Given all the above, the remainder of this RFC operates on the assumption that a re-design and re-implementation of the core property list code is the only viable approach. Needless to say, this re-implementation should change the public and private API's as little as possible, and then only with prior consultation with the developer and user communities.

Multi-Thread Issues in H5P

Before outlining the design of a proposed redesign and re-implementation of property lists, it will be useful to list the issues that should be addressed.

Use of other HDF5 packages in H5P

Any implementation of property lists must use H5E (error reporting) and H5I (indexing).

At least for internal calls, H5E was was largely multi-thread safe to for internal calls – modulo its dependency on H5I. Public API calls raise a number of issues, but for the time being, these can be addressed by keeping them under the global mutex..

Since the last revision of this document, H5I has been modified to use a lock free hash table, making it fundamentally lock free. Unfortunately, there is no guarantee that its callbacks are lock free, and thus they are executed under the global lock. Further, since these callbacks can't be rolled back, it is necessary to lock the relevant index entries while these callbacks are in progress¹⁴.

The net effect of this is that at least in the context of HDF5 library proper, there shouldn't be much in the way of lock ordering concerns from H5E and H5I in H5P – as long as H5P can handle non multi-thread safe callbacks the same way as H5I.

Whether this is practical comes down to the particulars of the interactions that H5P has with the various packages that use property lists derived from HDF5 library defined property list classes both for configuration and (in a few cases) to return data to the user remains.

These packages implement property specific callbacks that must be executed when various operations are performed on the associated properties. In my experience, few if any of these callbacks do anything significant from a multi-thread safety perspective. However, all these callbacks must be reviewed, documented, and tamed where necessary. Construction of a census of these callbacks and the required analysis is in progress as of this writing.

A more subtle issue is the possibility of modifications to property lists while calls referring to them are in progress. While this is a user error, we still have to keep it from corrupting internal data structures.

After some thought, I have come to the conclusion that the problem of packages that use property lists to return data to the user is best solved by requiring the user to create thread specific copies of the property list in question. Absent this, there is a fundamental race condition that will be difficult if not impossible to address satisfactorily. Note, however, that

¹⁴ As we have not yet settled on a thread package for this work, these locks are currently implemented via atomics. Once we do choose a threading package for this work, these home brew locks will likely be replaced with recursive mutexes.

we can't force users to do this, so we must ensure that this doesn't corrupt our data structures, even if it does return garbage to the user.

Finally, there is the matter of user defined properties and property list classes. Both of these have user defined callbacks – other than asking nicely and running these callback under the global mutex unless assured that they are thread safe, we don't have any way of filtering out code that could cause deadlocks and such. Unfortunately, I don't see any practical solutions other than careful user documentation or disallowing these callbacks in the multi-thread case.

Multi-thread thread issues in H5P proper

There is the usual problem of potential public API race conditions. This is an unsolvable problem from the perspective of H5P – all H5P can do is to execute operations in some order, and to keep its data structures in an internally consistent state. It will be the responsibility of the client to either avoid race conditions of the above type, or to handle them gracefully.

Proposed Solution

In the previous version of this document, the notion of simplifying H5P by making property list classes read only if they have any derived property lists or property list classes was floated. While this would work with HDF5 proper, there are use cases for adding properties to existing property list classes that make this suggestion unworkable.

This means that, at least from an external perspective, we must maintain the support for versioning property list classes, with the requirement that any such changes must not be reflected in any preexisting property list classes or property lists.

While the following design could be modified to permit it, as presented, it does not expose old versions of property list classes to the user. As discussed above, this feature invites confusion, and should, in my opinion, be dropped if at all possible.

As per H5I, the objective of the H5P redesign is to make the property list code fundamentally lock free.

The following design replaces skip lists with lock free singly linked lists (LFSLLs). This design choice is predicated on the proposition that property lists and property list classes will be relatively short – making the cost of linear searches on sorted lists acceptable. Needless to say, it will be necessary to maintain statistics to see if this proposition is correct. If it isn't, replacing the LFSLLs with lock free hash tables will be a simple fix.

Secondly, the design replaces the current practice of creating and maintaining copies of property list classes with versioning properties. While the primary impetus behind this decision

was to allow modifications to property list classes and property lists to be effectively atomic, it should have the side benefit reducing memory footprint.

Data Structures

Properties, or more correctly versions of properties, are stored in instances of H5P_mt_prop_t. See below for definitions of this structure, and its supporting structures H5P_mt_prop_aptr_t and H5P mt prop value t.

H5P_mt_prop_t is a modified version of H5P_genprop_t, with added fields to support lock free operation and versioning. Close relatives to the lock free algorithms used in this design are discussed in "The Art of Multiprocessor Programming" by Maurice Herlihy, Victor Luchangco, Nir Shavit, and Michael Spear, and thus will be glossed over here.

The create_version field is used to record the version of the containing property list class or property list in which the represented property version was added. The delete_version field will normally be zero, but will be set to the version of the containing property list class or property list at which the property was deleted.

The chksum field contains a 32 bit checksum on the name of the property – this is done for the convenience of the LFSLL (and lock free hash table if it comes to it) and to speed up lookups in the table of inherited properties in property list (of which more later).

Both property list classes and property lists maintain LFSLLs containing instances of H5P_mt_prop_t, one for each version of each property that has appeared in the containing property list class or property list¹⁵. This list is sorted first by hash code, then by name¹⁶, and finally by creation_version in descending order. Since all searches for properties must have a target version of the containing property list or property list class, this allows easy determination of the property version (if any) present in the target version.

See the header comments on H5P_mt_prop_t., H5P_mt_prop_aptr_t and H5P mt prop value t for further details.

¹⁵ Not quite – as shall be seen, property lists refer to their parent property list classes for default values of inherited properties.

¹⁶ To allow for hash code collisions.

```
* be accessed and modified in a single atomic operations.
\ensuremath{^{*}} With padding, this structure is 128 bits, which allows true atomic operation on
* many (most?) modern CPUs. However, it this becomes a problem, we can obtain the
* same effect by stealing the low order bit of the pointer for a deleted bit -- which
* works on all CPU / C compiler combinations I have tried.
* The individual fields of the structure are discussed below:
* ptr:
         Pointer to an instance of H5P_mt_prop_t, or NULL.
* deleted: Boolean flag. If this instance of H5P_mt_prop_aptr_t appears as a
        field in an instance of H5P_mt_prop_t, the instance of H5P_mt_prop_t is
        logically deleted if this flag is TRUE, and not if the flag is FALSE.
        If this instance of H5P_mt_prop_aptr_t appears elsewhere, the flag is
        meaningless.
* dummy_bool_1:
* dummy_boot_2:
* dummy bool 3:
* dummy_bool_1: The dummy_bool_? fields exist to pad H5P_mt_prop_aptr_t out to 128 bits,
        and allow prevention of insertion of garbage into an atomic instance of
        H5P_mt_prop_aptr_t, thus avoiding spurious failures Of
        atomic_compare_exchange_strong(). They should always be set to false.
             typedef struct H5P_mt_prop_aptr_t {
 struct H5P_mt_prop_t * ptr;
 bool
               deleted;
               bool buf 1;
 bool
 bool
               bool_buf_2;
               bool_buf_3;
 hool
} H5P_mt_prop_aptr_t;
* struct H5P_mt_prop_value_t
* Properties in a property list consist of a void pointer and a size. To avoid race
* condidtions, the size and pointer must be set atomically. This structure exists
* to facilitate this.
* ptr:
         Void pointer to the value, or NULL if the value is undefined.
* size:
         size t containing the size of the buffer pointed to by the ptr field,
        or zero if ptr is NULL.
* Note: The above fields will usually have a total size of 128 bits. However, since
* the size of size_t is not fixed across all 64 bit compilers, there is the potential
^{*} for occult failures in atomic_compare_exchange_strong() when garbage gets into
* the un-used space in the structure. (recall that the sum of the sizes of the fields
* of a structure need not equal the allocation size of the structure.)
* For now, it should be sufficient to assert that sizeof(H5P_mt_prop_value_t) = 8.
* However, we will have to deal with the issue eventually. For example, I have read
* that size_t is a 32 bit value on at least some compilers targeting Windows.
```

```
typedef struct H5P_mt_prop_value_t {
  void * ptr;
  size_t size;
} H5P_mt_prop_value_t;
* struct H5P_mt_prop_t
* Struct H5P_mt_prop_t is revised version of H5_genprop_t designed for use in a
* multi-thread safe version of H5P. The data structures supporting property lists
* are lock free to the extent practical, and thus instances of H5P_mt_prop_t will
* typically appear in lock free singly linked list.
* Further, to support versioning in property list classes,instances of H5P_mt_prop_t
* in property list classes maintain reference counts of the number of property lists
* that refer to them for default values, the class revision number at which they inserted
* into the property list class, and (if deleted) the revision number at which which the
* deletion took place.
* The fields of H5P_mt_prop_t are discussed individually below.
* tag:
          Integer value set to H5P_MT_PROP_TAG when an instance of H5P_mt_prop_t
         is allocated from the heap, and to H5P_MT_PROP_INVALID_TAG just before
        it is released back to the heap. The field is used to validate pointers
        to instances of H5P_mt_prop_t,
* next:
          Atomic instance of H5P_mt_prop_aptr_t, which combines a pointer to the
         next element of the lock free singly linked list with a deleted flag.
         If there is no next element, or if the instance of H5P_mt_prop_t is
        not in a SLL, this field should be set to {NULL, false}.
* sentinel: Boolean flag. When set, this instance of H5P mt prop t is a sentinel
         node in the lock free singly linked list -- and therefore does not
        represent a property.
* in_prop_class: Boolean flag that is set to TRUE if this instance of H5P_mt_prop_t
        resides in a propterty list class, and false otherwise. Note that
        the ref count field is un-used if this field is false.
* ref_count: Atomic integer used to track the number of property list properties
        that point to this instance of H5P_mt_prop_t. This field must be
         zero if in_prop_class is false.
         Note that this ref count is only increased when a new property list
         is created, and is decremented when either a non-default value is
        set in in a derived property list, or when property list is discarded.
        Thus this instance of H5P_mt_prop_t can be safely deleted if:
             1) the ref count drops to zero, and
             2) this property has been either deleted or superceeded
               in the property list class.
* Property Chksum, Name & Value:
* Instances of H5P_mt_prop_t will typically appear in lock free singly linked lists,
* which must be sorted by property name, and then by decreasing create_version (i.e.
* highest create_version first).
```

* The lock free singly linked list used to store most instances of H5P_mt_prop_t

```
* requires sentinels at the beginning and end of the list with values (conceptually)
* on negative and positive infinity respectively. This is a bit awkward with strings,
* so for this reason, the (name, creation_version) key is augmented with a 32 bit
* checksum on the name, convering the key to a (chksum, name, creation version)
* triplet. Note that the check sum is a 32 bit unsigned value, which is stored
* in an int64_t. Thus we can use LLONG_MIN and LLONG_MAX as our negative and
* positive infinity respectively.
\ensuremath{^{*}} The addition of the chksum changes the sorting order to checksum, name, and
* then decreasing create_version. This ordering, along with the delete_version
* field, allows us to operate on specific versions of a property list classes and
* property lists -- thus allowing concurrent operations without introducing
* corruption.
* chksum: int64_t containing a 32 bit checksum computed on the name field
        below, or LLONG_MIN or LLONG_MAX if either the head or tail
         sentinel in the lock free SLL respectively.
         Since this field is constant for the life of the instance of
         H5P mt prop t, and is set before the instance is visible to more
         than one thread. Thus it need not be atomic.
* name:
            Pointer to a dynamically allocated string containing the name of the
         property. This field is not atomic, as the string should be allocated,
         and initialized, and the name field set before the instance of
        H5P mt prop t is visible to more than one thread. Since the name
         is constant for the life of the instance of H5P_mt_prop_t, this should
        be sufficient for thread safety.
           Atomic structure containing the pointer to the buffer containing the
         value of the property, and its size.
* create_version: Atomic integer which is set to the version of the containing
         property list class or property list in which this property was
         inserted.
 delete version: Atomic integer which is set to the version of the containing
         property list class or property list in which the property was
        deleted. If the property has not been deleted, this field contains
         zero.
* Property Callback Functions:
* The following fields are pointers to the callback functions associated with the
* property, combined with a boolean indicating whether all callbacks are thread safe.
* If this flag is not set, all callbacks are protected by the global mutex.
* The descritptions of the callbacks are all taken from the existing code -- and are
* completely inadequate. They must be expanded upon.
* callbacks_mt_safe: Boolean flag used to indicate whether all callbacks are
         multi-thread safe. If this field is not set, the global mutex must
         be held when the callback is called.
* create: Function to call when a property is created.
* set:
          Function to call when a property value is set.
* get:
          Function to call when a property value is retrieved.
* encode: Function to call when a property is encoded.
```

```
* decode: Function to call when a property is decoded.
* del:
        Function to call when a property is deleted.
         Function to call when a property is copied.
* copy:
* cmp:
        Function to call when a property is compared.
* close:
       Function to call when a property is closed.
              #define H5P_MT_PROP_TAG
#define H5P_MT_PROP_INVALID_TAG
typedef struct H5P_mt_prop_t {
 uint32_t
                  tag;
 _Atomic H5P_mt_prop_aptr_t next;
 bool
                sentinel;
                in_prop_class;
 _Atomic uint64_t
                     ref_count;
 int64_t
                chksum;
 char *
                name;
 _Atomic H5P_mt_prop_value_t value;
 _Atomic uint64_t create_version;
 _Atomic uint64_t
                    delete_version;
                callbacks_mt_safe;
 H5P prp create func t create;
 H5P_prp_set_func_t set;
 H5P_prp_get_func_t get;
 H5P_prp_encode_func_t encode;
H5P_prp_decode_func_t decode;
 H5P_prp_decode_func_t
 H5P_prp_delete_func_t del;
 H5P_prp_copy_func_t copy;
 H5P_prp_compare_func_t cmp;
 H5P_prp_close_func_t close;
} H5P_mt_prop_t;
```

Property list classes are stored in instances of H5P_mt_class_t. See below for the definition of this structure.

As with H5P_genprop_t, H5P_mt_class_t is a version of H5P_genclass_t modified to support multi-thread. The major changes from H5P genclass t are as follows:

Properties (or more correctly, versions of properties) are stored in a LFSLL as described above. Properties inherited from ancestor property list classes are copied into the LFSLL associated with the new property list class at creation time. Only the current versions of properties are copied. This is a matter of code simplification. The current search through the inheritance tree could be used, it would just be more complex. Note, however, that we must still execute the inherited callbacks

The current version of a property list class is stored in the curr_version field, and all read operations on the property list class must be directed at a version no greater than this value at the point at which the operation starts. This has the effect of making the read effectively atomic as any subsequent modifications to the property list will be visible to the read.

When an operation that modifies the property list¹⁷ starts, it must first obtain a version number for the change. This is done via a fetch an atomic fetch and increment on the next_version field. The returned new version number is used to tag the change.

In the event of a property insertion or modification, a new instance of of H5P_mt_prop_t is allocated and initialized as appropriate, tagged with the new version in its create_version field, and then inserted into the LFSLL of properties in sorted order. Recall that this list is sorted by hash, name, and then by decreasing creation version.

For property deletions, the version of the target property that is valid at version one less than the target version is found, and its delete version is set to the change version number.

Observe that by requiring all read operations on the property list class to target a version no greater than curr_version, we force modifications to the property list class to remain invisible until the curr_version field is incremented – thus making modifications effectively atomic. While this clearly works if no more than one modification is in progress at one time, there are issues with concurrent modifications.

If multiple operations are in progress simultaneously, it is usually sufficient to ensure that operations complete in issue order (i.e. the order in which change version numbers are issued). If, however, a modify or insert and a deleted are in progress on the same property simultaneously, they must be executed in issue order.

See the header comment on H5P mt class t for further details.

¹⁷ i.e. a property create, delete, or modify.

- * least being that it makes it possible for multiple versions of the property list * class to exist in the index, and thus be visible to the user.
- * Instead, the multi-thread version of property list classes maintains back versions
- * of all properties tagged with the property list class version in which they were
- * created (and possibly deleted). All properties are ref counted with the number of
- * properties in derived property lists that refer to them for default values. Since
- * the ref count on a version of a property can only be incremented when that property
- * version appears in the current version of the property list class, this means that
- $\ensuremath{^*}$ back versions of properties may be safely discarded once their ref counts drop to zero.
- * Note that this no longer need be the case if we allow back version of property list
- $\ensuremath{^*}$ classes to be visible outside of H5P. Note also that this is a semantic change in
- * the H5P API from the single thread version, albeit an obscure one, and probably in
- * the right direction.
- * More importantly, if all operations on a property list address a specific version,
- * and all modifications are effectively atomic, concurrent operations can occur without
- * the potential for data corruption as long as all modifications trigger an increment
- * of the property list class version number.
- * Making modifications to a property list class effectively atomic is slightly tricky,
- $\ensuremath{^*}$ as, to give an obvious example, inserting a new property and incrementing the
- * version number can't be made atomic without heroic measures. However, by
- * targeting every operation at a specific version, we can make changes in progress
- * effectively invisible since new or modified properties are represented by new
- * instances of H5P_mt_prop_t with creation property list class versions higher than
- * the current version, and thus don't become visible until the property list class
- * version is incremented to the point that they become visible.
- * However, if multiple modifications to the property list class are in progress
- * simultaneously, there is a race condition between the issue of a new version
- * number to be used to tag a modification, and the increment of the property list
- * class version number when the modification completes.
- * Conceptually, this can be handled by waiting to increment the version number until
- * the current version number is one less than the issued version number. Use of a
- * condition variable is the obvious solution here -- but we will sleep and try again
- * until we settle on a threading package.
- * There is also a potential race condition if a delete and either a modify or an
- * insert on a single property is in progress at the same time. In this case, the
- * operations must proceed in target version issue order.
- * A second fundamental difference between the single thread and the multi-thread
- * implementations of the property list class, is that properties are stored on a
- * lock free singly linked list (LFSLL) instead of a skip list. This LFSLL list is
- * sorted first by a hash on the property name, second by property name (to allow for
- * hash collisions), and finally by creation version in decreasing order.
- * Given that property lists are typically short (less that 25 properties), and that
- * the LFSLL will be searched only on property insert, delete, or modification, the
- * LFSLL should be near optimal for this application. However, if the number of
- * properties (or back versions of same) balloon and cause performance issues, it
- * will be easy enough to replace the LFSLL with a lock free hash table.
- * Finally, for code simplicity, properties inherited from the parent property list
- * class are copied into the LFSLL of properties in the derived property list class.
- * There is nothing magic about this, and we can revert to the old system if there
- * is some reason to do so.
- * Note, however, that it is still necessary for property list classes to maintain
- * pointers to their parent property list classes due to the requirement that
- * all close functions in ancestor property list classes be called on close.
- * With this outline of H5P_mt_class_t in hand, we now address individual fields.

JRM -- 5/22/24 * The fields of H5P_mt_prop_t are discussed individually below. * tag: Integer value set to H5P_MT_CLASS_TAG when an instance of H5P_mt_class_t is allocated from the heap, and to H5P_MT_CLASS_INVALID_TAG just before it is released back to the heap. The field is used to validate pointer to instances of H5P_mt_class_t, parent_id: ID assigned to the immediate parent property list class in the index. As the parent cannot be deleted until its ref counts drop to zero, it must exist at least as long as this property list class. This field is not atomic, as it is set before this property list class is inserted in the index, and thus becomes visible to to other threads. * parent_ptr: Pointer to the instance of H5P_mt_class_t that represents the immediate parent property list class in the index. As the parrent cannot be deleted until its ref counts drop to zero, it must exist and this pointer must be valid at least as long as this property list class. This field is not atomic, as it is set before this property list class is inserted in the index, and thus becomes visible to to other threads. * name: Pointer to a string containing the name of this property list class. This field is not atomic, as it is set before this property list class is inserted in the index, and thus becomes visible to to other threads. * id: Atomic instance of hid_t used to store the id assigned to this property list class in the index. This field is atomic, as it can't be set until after the instance of H5P_mt_class_t is registered, and thus visible to other threads. That said, once set, this field will not change for the life of the property list class. * type: Type of the property list class. This field is constant for the life of the property list class, and is set before the instance of H5P mt class t becomes visible to other threads. * curr_version: Atomic uint64_t containing the current version of the property list class. This version number is incremented each time a modification to the property list class is completed. A uint64_t is used, as at present there is no provision for a roll over. Given the relative infrequency of modifications to property list classes, 64 bits is probably sufficient for all reasonable cases. However, a roll over must never occur, and an error should be flagged if it does. To allow for an undefined deletion version, the curr_version must be no less than 1. * next_version: Atomic uint64_t containing the version number to be assigned to the next modification of the property list class. When no modifications to the property list class are in progress, next_version should be one greater than curr_version. When a modification to a property list class begins, it does a fetch and increment on next_version, preforms its changes and tags them with the returned version, and finally increments the curr_version. Note, that to avoid exposure of partial modifications, increments

to curr_version must be executed in next_version issue order. Thus, a

```
thread that modifies the property list class, must not increment
        curr_version until its value is one less that the version number it
        obtained when it started.
* pl_head: Atomic Pointer to the head of the LFSLL containing the list of properties
        (i.e. instances of H5P_mt_prop_t) associated with the property list class.
        Other than during setup, this field will always point to the first node
        in the list whose value will be negative infinity.
        Entries in this list are sorted first by a hash on the property name,
        second by property name (to allow for hash collisions), and finally
        by creation version in decreasing order. Other than during setup,
        The first and last entries in the list list will be sentinel entries
        with hash values (conceptually) of negative and positive infinity
        respectively.
* log_pl_len: Number of properties defined in the property list class at the
        current version. Note that, in general, this value will not be
        correct for all versions of the property list class, and will be
        briefly inaccurate even for the current version during property
        insertions and deletions. Thus when an exact value is required,
        the property list must be scanned for the correct value for the
        desired version.
 phys_pl_len: Number of instances of H5P_mt_prop_t in the property list. This
        number includes sentinel nodes, and both current an superceeded
        instances of H5P_mt_prop_t. Note that this value will be briefly
        incorrect during property insertions, deletions, and modifications.
        Modification of a property causes this value to change, and for
        modification, a new instance H5P_mt_prop_t is inserted with the
        desired changes and a new creation version.
* plc_ref_count: Number of property list classes immediately derived from this property
        list class, and still extaant.
 pl_ref_count: Number of property lists immediately derived from this property
         list class, and still extaant.
* The following fields are pointers to the callback functions associated with the
* property along with pointers to data to be passed to these functions when called.
* These are combined with a boolean indicating whether all callbacks are thread safe.
* If this flag is not set, all callbacks must be protected by the global mutex.
* The descriptions of the callbacks are all taken from the existing code -- and are
* completely inadequate. They must be expanded upon.
* callbacks_mt_safe: Boolean flag used to indicate whether all callbacks are
        multi-thread safe. If this field is not set, the global mutex must
        be held when the callbacks are called.
* create_func: Function to call when a property list is created.
* create_data: Pointer to user data to pass along to create callback.
* copy func: Function to call when a property list is copied.
* copy_data: Pointer to user data to pass along to copy callback.
* close_func: Function to call when a property list is closed.
* close_data: Pointer to user data to pass along to close callback.
* Statistics:
```

```
* TBD.
#define H5P_MT_CLASS_TAG
#define H5P_MT_CLASS_INVALID_TAG
typedef struct H5P_mt_class_t {
 uint32 r
                 tag;
 hid_t
                 parent_id;
 H5P_mt_class_t * parent_ptr;
 char *
  _Atomic hid_t *
 H5P_plist_type_t
 _Atomic uint64_t
                     curr_version;
 _Atomic uint64_t
                     next_version;
 /* List of properties, and related fields */
 H5P_mt_prop_t *
                    pl head;
 _Atomic uint32_t
                      log_pl_len;
 _Atomic uint32_t
                   phys_pl_len;
 /* reference counts */
  _Atomic uint64_t
                     plc_ref_count;
 _Atomic uint64_t
                      pl_ref_count;
 /* Callback function pointers & info */
 H5P_cls_create_func_t create_func;
                create_data;
 H5P_cls_copy_func_t copy_func;
 void *
               copy_data;
 H5P_cls_close_func_t close_func;
               close data;
 /* Stats: *;
} H5P_mt_class_t;
```

Property lists are stored in instances of H5P_mt_list_t. See below for the definition of this structure, and its supporting structures H5P mt list prop ref t and H5 mt list table entry t.

As with H5P_genclass_t, H5P_mt_list_t is a version of H5P_genlist_t modified to support multithread. The major changes from the single thread implementation are outlined as follows:

Like the single thread implementation of property lists, the multi-thread implementation refers to its parent property list class for default versions of all inherited properties, and keeps local copies of all modified or inserted properties. However, the mechanisms are quite different.

First, the modified or inserted properties (instances of H5P_mt_prop_t) are stored on a LFSLL. As with the property list class, there is one instance of H5P_mt_prop_t for each version of the property in question, marked with its creation version, and if appropriate, its delete_version.

Second, when a property list is created, an table of all inherited properties is created, stored in an array of H5P_mt_list_table_entry_t, and sorted first by hash code on the property name, and then by property name.

Each entry in this table contains a base pointer and version, and a current pointer and version. The current pointer and version are initialized to NULL and zero respectively. A base delete version field is also supplied to allow for the deletion of an unmodified, inherited property from the property list – this field is initialized to zero.

The base pointer is set to point to the instance of H5P_mt_prop_t representing the inherited property with its value at the time the new property list was created. Due to the versioning of property list classes, these instances of H5P_mt_prop_t are never modified, and will not be deleted until after all derived property lists that depend on them have been deleted. Thus the lookup of the default values of all inherited properties can be done in O(log n) time, where n is the number of inherited properties.

The base version fields of the table entries are always set to 1 - the initial version of the property list.

Third, when an inherited property is modified, a new instance of H5_mt_prot_t is created with the appropriate value and creation version, and inserted in the LFSLL of modified or inserted properties in sorted order. Then the current pointer and version fields of the appropriate entry in the table of inherited properties are set to the address and version of the new instance of H5P_mt_prop_t respectively. Finally, as per property list classes, the current version of the property list is incremented to make the new value of the property visible.

Inserted properties, or modifications of same are handled the same way, only they do not appear in the table of inherited properties, and thus must be found via a search of the LFSLL. Since the number of inserted properties is tracked, this search can be skipped when this number is zero. The presumption here is that inserted properties in property lists are rare – if this presumption proves false, a more efficient lookup mechanism should be retrofitted. See the header comments for the definitions of H5P_mt_list_t, and its supporting structures H5P mt list prop ref t and H5 mt list table entry t for further details.

```
* Second, if the default value of the property has been overwritten, to point to an
* instance of H5P_mt_prop_t in the host property list class's LFSLL of modified or
* added properties. In this case, the ver field must match the create_version field
* of the instance of H5P_mt_prop_t pointed to by ptr.
* The individual fields of the structure are discussed below:
* ptr:
         Pointer to an instance of H5P_mt_prop_t, or NULL.
* ver:
         Version number of the host property list class at which this
        this pointer was set.
typedef struct H5P_mt_list_prop_ref_t {
 H5P_mt_prop_t *
 uint64_t
} H5P_mt_list_prop_ref_t;
  ************************
* struct H5P_mt_list_table_entry_t
* An array of instances of H5P_mt_list_table_entry_t is used to create a look up
* table for properties inherited from the parent property list class.
* chksum: int64_t containing a 32 bit checksum computed on the name field
        below.
        Since this field is constant for the life of the instance of
        H5P mt prop t, and is set before the instance is visible to more
        than one thread, it need not be atomic.
* name:
           Pointer to a dynamically allocated string containing the name of the
        property. This field is not atomic, as the string should be allocated,
        and initialized, and the name field set before the instance of
        H5P mt prop t is visible to more than one thread. Since the name
        is constant for the life of the instance of H5P_mt_prop_t, this should
        be sufficient for thread safety.
* base:
          Atomic instance of H5P_mt_list_prop_ref_t. The ptr field points to
        the instance of H5P_mt_prop_t in the parent property list class, and
        the ver field should contain the initial version number of the
        property list.
* base_delete_version: Property lists derived from a property list class must not
        modify properties in the parent property list class. Thus they
        must maintain their own create and delete versions. The create
        version is simply the initial version of the proeprty list, and
        is stored in the base.ver field. However, if the property is
        deleted from the property list, we must have a detete version to
        indicate the property list version at which this took place.
        The atomic uint64_t base_delete_version exists to serve this purpose.
        if the base version of the property has not been deleted, this field
        will contain zero.
* curr:
         Atomic instance of H5P_mt_list_prop_ref_t whose ptr and ver fields
        must be initialized to NULL and 0 respectively.
        If the value of the inherited property is modified, a new instance of
```

```
H5P mt prop t is allocated, copying the tag, sentinel, chksum, name,
         and callback fields from the base version of the property pointed to
         by base.ptr.
         The in_prop_class, and ref_count fields are set to zero, and not used
        in property lists. The create_version is set to the version of the
         property list in which the modified version is set, and the
         delete version is set to 0. The value field is set to point to the
         new value of the property, and the new instance of H5P_mt_prop_t is
         inserted into the LFSLL of new / modified properties associated with
         the host property list.
         Next, curr.ptr is set to point to the new instance, and curr.ver is
        set to its creation version. Recall that both of these fields are
         set in a single atomic operation.
         Finally the version of the host property list is incremented to make
         these changes visible.
       ******************
typedef struct H5P_mt_list_table_entry_t {
  int64_t
                         chksum:
  char *
                         name:
  _Atomic H5P_mt_list_prop_ref_t base;
  _Atomic uint64_t
                              base_delete_version;
  _Atomic H5P_mt_list_prop_ref_t curr;
} H5P_mt_list_table_entry_t;
* struct H5P mt list t
* Revised version of H5P_genlist_t designed for use in a multi-thread safe version
* of the HDF5 property list module (H5P).
* At the conceptual level, a property list class is simply a properties -- i.e. name
* value pairs.
* When a property list is created, it incorporates a list of properties with default
* values from its parent property list class at the version at which the creation of
* the property list was started. At this time, the number of properties in the property
* list class is determined and stored in the nprops_inherited field.
* This done, an array of H5P mt list table entry t of length nprops inherited is
* allocated, with the base.ptr field pointing to the assocated instance of H5P_mt_prop_t
* in the parent property list classes LFSLL of properties, and the base ver field set
* to the initial version of the property list. After this array is initialized, it
* is sorted by chksum and then name, and the lkup_table field is set to point to it.
* Observe that this table allows a log n lookup of properties inherited from the
* parent property list class.
* If the value of any inherited property is modified, a new instance of H5P_mt_prop_t
* is created with the modified value and creation version, and inserted into the
* property list's LFSLL of properties. The curr.ptr field of the appropriate entry
* in the lookup table is set to point to it, and the curr.ver field is set to the
* version of the property list at which the modification was made. Finally, the
* propert list's curr_version field is incremented to make this modification visible.
* If a new property is added to the property list, it is simple inserted into the
* property list's LFSLL of instances of H5P_mt_prop_t, and the nprops_added field is
* incremented. On searches, the lookup table is searched first, with the LFSLL being
* searched only if this first search fails, and nprops_added is positive.
```

39

* As with the multi-thread version of the property list classes, property lists * maintain back versions of all properties tagged with the property list version * in which they were created (and possibly deleted). Unlike property list classes, * the properties are not reference counted. * Since all operations on a property list address a specific version, if all * modifications are effectively atomic, concurrent operations can occur without * the potential for data corruption as long as all modifications trigger an * increment of the property list version number. * As with property list classes, making modifications to a property list effectively * atomic is slightly tricky, but can be handled in much the same way. Since every * operation on a property list is targeted at a specic version, we can make changes in * progress effectively invisible since new or modified properties are represented by * new instances of H5P_mt_prop_t with creation property list class versions higher * than the current version, and thus don't become visible until the proprety list * version is incremented to the point that they become visible.. * However, as with property list classes, if multiple modifications to the property list * are in progress simultaneously, there is a race condition between the issue of a new * version number to be used to tag a modification, and the increment of the property list * version number when the modification completes. * As with property list classes, this can be handled by waiting to increment the * version number until the current version number is one less than the issued * version number. * Also as per property list classes, modified / new properties are stored on a * lock free singly linked list (LFSLL) instead of a skip list. This LFSLL list is * sorted first by a hash on the property name, second by property name (to allow for * hash collisions), and finally by creation version in decreasing order. * Since only new / modified properties are stored on this list, it should be shorter * than the similar list in property list classes. More importantly, the latest * version of each inherited property is pointed to by the appropriate entry in the * lookup table. Added properties still require a linear search through the LFSLL. * If this proves to be a performance issue, we can either keep added entries in a * different list, or allow the lookup table to be extended when new entries are added. * With this outline of H5P_mt_list_t in hand, we now address individual fields. Integer value set to H5P_MT_LIST_TAG when an instance of H5P_mt_list_t is allocated from the heap, and to H5P_MT_LIST_INVALID_TAG just before it is released back to the heap. The field is used to validate pointer to instances of H5P mt list t, pclass_ptr: Pointer to the instance of H5P_mt_class_t from which the property list was derived. This field is not atomic, as it is set before this property list is inserted in the index, and thus becomes visible to to other threads. * pclass_id: ID of the instance of H5P_mt_class_t from which the property list was derived. This field is not atomic, as it is set before this property list is inserted in the index, and thus becomes visible to to other threads. * pclass_version: Version of the parent property list class from which this property list was derived. This field is not atomic, as it is set before this property list is inserted in the index, and thus becomes visible to to other threads.

* plist_id: ID assigned to this property list. This field must be atomic, because the instance of H5P_mt_list_t becomes visible to other threads before this field can be set. That said, once it is set, it should not change for the lifetime of the property list. * curr_version: Atomic uint64_t containing the current version of the property list. This version number is incremented each time a modification to the property list is completed. A uint64_t is used, as at present there is no provision for a roll over. Given the relative infrequency of modifications to property lists, 64 bits is probably sufficient for all reasonable cases. However, a roll over must never occur, and an error should be flagged if it does. To allow for an undefined deletion version, the curr_version must be no less than 1. * next_version: Atomic uint64_t containing the version number to be assigned to the next modification of the property list. When no modifications to the property list are in progress, next_version should be one greater than curr_version. When a modification to a property list begins, it does a fetch and increment on next_version, preforms its changes and tags them with the returned version, and finally increments the curr_version. Note, that to avoid exposure of partial modifications, increments to curr version must be executed in next version issue order. Thus, a thread that modifies the property list class, must not increment curr_version until its value is one less that the version number it obtained when it started. * Ikup tbl: Pointer to an array of H5P mt list table entry t that permits fast lookup of properties inherited from the parent property list class. See the header comment for H5P mt list table entry t for further details. * nprops inherited: The number of properties inherited from the parent property list class, and also the number of entries in the lookup table (lkup_tbl) above. Note that any or all of these properties may be deleted in an arbitrary version of the property list. * nprops_added: The number of properties added to the property list after its creation. Note that these properties do not appear in the lkup tbl, and thus if a search for a property fails in lkup tbl and nprops added is positive, the LFSLL pointed to by pl_head (below) must also be searched. * nprops: Number of properties defined in the current version of the property list. Note that this value may be briefly inaccurate during property additions or deletins -- if an accurate value is required, the LFSLL pointed to by pl_head must be scanned for the target property list version. * pl head: Atomic Pointer to the head of the LFSLL containing the list of properties (i.e. instances of H5P_mt_prop_t) associated with the property list. Other than during setup, this field will always point to the first node in the list whose value will be negative infinity. Entries in this list are sorted first by a hash on the property name,

second by property name (to allow for hash collisions), and finally

```
by creation version in decreasing order. Other than during setup,
        The first and last entries in the list list will be sentinel entries
        with hash values (conceptually) of negative and positive infinity
        respectively.
* log_pl_len: Number of properties defined in the property list class at the
        current version. Note that, in general, this value will not be
        correct for all versions of the property list class, and will be
        briefly inaccurate even for the current version during property
        insertions and deletions. Thus when an exact value is required,
        the property list must be scanned for the correct value for the
        desired version.
* phys_pl_len: Number of instances of H5P_mt_prop_t in the property list. This
        number includes sentinel nodes, and both current and superceeded
        instances of H5P_mt_prop_t. Note that this value will be briefly
        incorrect during property insertions, deletions, and modifications.
        Modification of a property causes this value to change, as for
        modification, a new instance H5P_mt_prop_t is inserted with the
        desired changes and a new creation version.
* class_init: True iff the class initialization callback finished successfully.
* Statistics:
* TBD.
#define H5P_MT_LIST_TAG
#define H5P_MT_LIST_INVALID_TAG
typedef struct H5P_mt_list_t {
  uint32 t
                     tag;
  H5P_mt_class_t *
                          pclass_ptr;
                    pclass_id;
 hid t
  uint64_t
                     pclass_version;
  Atomic hid t
                        plist id;
  _Atomic uint64_t
                          curr_version;
  _Atomic uint64_t
                          next_version;
  H5P_mt_list_table_entry_t * lkup_tbl;
  uint32 t
                     nprops inherited;
  _Atomic uint32_t
                          nprops_added;
  _Atomic uint32_t
                          nprops;
  /* List of properties, and related fields */
 H5P_mt_prop_t *
                          pl_head;
  _Atomic uint32_t
                          log_pl_len;
  _Atomic uint32_t
                          phys_pl_len;
  _Atomic bool
                        class_init;
  /* Stats: */
} H5P_mt_list_t;
```

Public API Function Outlines
In this section, list the public API calls and outline their processing
Private API Function Outlines In this section, list the private API, and outline their processing where the above discussion of public API function does not make this redundant.

Next Steps

This RFC continues to be a work in progress. Next steps are:

- Finish the census and analysis of the property list and property list class callbacks.

 Document their function, and limitations on their processing required for multi-thread.
- Update the above data structure definitions to address any issues resulting from the prior task.
- Write the outlines of the public and private multi-thread H5P API calls.
- Circulate for review.
- If all goes well, design the necessary test code.
- Begin implementation

Appendix 1 – H5P public API calls

After some type and macro definitions, this appendix contains a list of all the public H5P API calls, along with call trees, relevant structure definitions, and descriptions of their processing with particular emphasis on multi-thread safety issues. Apparent bugs / design issues are documented in red. Note that this data was derived by inspection, and thus some errors and/or oversights should be expected.

The list of public API calls was taken from H5Ppublic.h. All the public API calls in this file are decorated with Doxygen code to generate user level documentation on public API calls. I have included this code as it may be a useful addition to my own documentation.

Finally, I have skipped the detailed discussion for one API call that didn't seem interesting, and started skipping the discussions of multi-thread safety issues once it became obvious that a reimplementation was likely.

```
/* Define structure to hold class information */
struct H5P genclass t {
  unsigned
                                    created since the last modification to
                                     the class */
                     classes; /* Number of classes that have been derived
  unsigned
                                    since the last modification to the class */
                     ref count; /* Number of outstanding ID's open on this
  unsigned
                                    class object */
                     deleted; /* Whether this class has been deleted and is
  hbool t
                                    waiting for dependent classes & proplists
                                     to close */
             revision; /* Revision number of a particular class
  unsigned
                                     (global) */
                     * props; /* Skip list containing properties */
  H5SL t
  /* Callback function pointers & info */
  H5P_cls_create_func_t create_func; /* Function to call when a property list
                                     is created */
  void *
                     create data; /* Pointer to user data to pass along to
                                    create callback */
  H5P_cls_copy_func_t copy_func; /* Function to call when a property list
                                     is copied */
  void *
                       copy data; /* Pointer to user data to pass along to
                                    copy callback */
  H5P cls close func t close func; /* Function to call when a property list
                                     is closed */
  void *
                       close data; /* Pointer to user data to pass along to
                                     close callback */
};
/* Define structure to hold property list information */
```

```
struct H5P genplist t {
   H5P genclass t *pclass;
                                 /* Pointer to class info */
   hid t
                   plist id;
                                 /* Copy of the property list ID (for use in
                                    close callback) */
                                 /\star Number of properties in class \star/
   size t
                    nprops;
                    class_init; /* Whether the class initialization callback
   hbool t
                                    finished successfully */
   H5SL t *
                                 /* Skip list containing names of deleted properties */
                    del;
   H5SL t *
                                 /* Skip list containing properties */
                    props;
};
/* Generic Property Class ID class */
static const H5I class t H5I GENPROPCLS CLS[1] = {{
                                     /* ID class value */
   H5I GENPROP CLS,
                                      /* Class flags */
                                      /* # of reserved IDs for class */
   (H5I free t) H5P close class cb /* Callback routine for closing objects of this
class */
} ;
/* Generic Property List ID class */
static const H5I class t H5I GENPROPLST CLS[1] = {{
                                    /* ID class value */
   H5I GENPROP LST,
   Ο,
                                    /* Class flags */
                                    /* # of reserved IDs for class */
   (H5I free t)H5P close list cb /* Callback routine for closing objects of this
class */
} } ;
/* Define structure to hold property information */
typedef struct H5P genprop t {
   /* Values for this property */
   char *
                                    /* Name of property */
                      name;
   size t
                                    /* Size of property value */
                      size;
   void *
                                    /* Pointer to property value */
                      value;
                                   /* Type of object the property is within */
   H5P_prop_within_t type;
                      shared name; /* Whether the name is shared or not */
   hbool t
   /* Callback function pointers & info */
   H5P prp create func t create; /* Function to call when a property is created */
   H5P_prp_set_func_t set; /* Function to call when a property value is set */
   H5P_prp_get_func_t
                           get;
                                    /* Function to call when a property value is
retrieved */
   H5P_prp_encode_func_t encode; /* Function to call when a property is encoded */
H5P_prp_decode_func_t decode; /* Function to call when a property is decoded */
H5P_prp_delete_func_t del; /* Function to call when a property is deleted */
                                   /* Function to call when a property is copied */
   H5P prp copy_func_t
                           copy;
                                   /* Function to call when a property is compared */
   H5P_prp_compare_func_t cmp;
   H5P_prp_close_func_t close; /* Function to call when a property is closed */
} H5P genprop t;
```

```
* \ingroup GPLO
 \brief Terminates access to a property list
* \plist id
* \return \herr t
* \details H5Pclose() terminates access to a property list. All property
           lists should be closed when the application is finished
           accessing them. This frees resources used by the property
           list.
* \since 1.0.0
* /
H5 DLL herr t H5Pclose(hid t plist id);
H5Pclose()
 +-H5I_get_type()
 +-H5I_dec_app_ref()
    +-H5I__dec_app_ref()
       +-H5I dec ref()
         +-H5I _find_id()
       | | +- ...
         +-(type_info->cls->free_func)((void *)info->object, request)
       1 1 11
         | H5P close list cb() // in this case
            +-H5P close()
                | // iterate through the plist class close functions.
                +-(tclass->close func)(plist->plist id, tclass→close data);
                +-H5SL create() // create seen list
                | // iterate through properties running the close function
                | // on each property and inserting its name in the seen list
                +-H5SL_count(plist->props)
                +-H5SL_first(plist->props)
                +-(H5P_genprop_t *)H5SL_item(curr_node)
                +-(tmp->close)(tmp->name, tmp->size, tmp→value)
                +-H5SL insert(seen, tmp->name, tmp->name)
                +-H5SL next(curr node)
                | // repeat the above process iterating through the parent
                | // plist classes.
                +-H5SL first(tclass→props)
                +-(H5P genprop t *)H5SL item(curr node);
                +-H5SL search (seen, tmp->name)
                +-H5SL search(plist->del, tmp->name)
                +-H5MM malloc()
                +-H5MM memcpy()
                +-(tmp->close)(tmp->name, tmp->size, tmp value)
                +-H5MM xfree()
                +-H5SL insert(seen, tmp->name, tmp->name)
                +-H5SL next(curr node);
                +-H5P access class(plist→pclass, H5P MOD DEC LST)
                +-\overline{\text{H5MM}} \text{ xfree()}
                | +-H5SL_destroy()
                | | +- ...
                | +-H5P access class(par class, H5P MOD DEC CLS)
```

```
H5P__free_del_name_cb()
+-H5MM xfree()
| // tprop→close is not called in this case because *make_cb
| // is FALSE.
+-(tprop->close)(tprop->name, tprop->size, tprop->value);
             | +- ... // property specific - may not exist
            +-H5P free prop(tprop);
ii
               +-H5MM xfree()
1 1
               +-H5FL FREE()
| +-H5FL_FREE(H5P_genplist_t, plist);
| +-H5SL_close(seen);
| +-H5I remove common()
+-H5I find id()
```

In a nutshell:

Decrement the ref count on the target property list. If it drops to zero, remove it from the index, and delete it.

In greater detail:

If the supplied hid_t is H5P_DEFAULT, **H5Pclose()** does nothing and returns.

If the supplied hid_t is not associated with a property list, H5Pclose() flags an error and returns. Otherwise, it calls H5I dec app ref() and returns.

H5I_dec_app_ref() is basically a pass through. It preforms some sanity checks, and the calls H5I_dec_app_ref(id, H5_REQUEST_NULL), and returns whatever value H5I_dec_app_ref() returns.

H5I__dec_app_ref() calls H5I__dec_ref() to decrement the regular ref count on the target. If H5I__dec_ref() returns a positive value (indicating that the regular reference count has not been decremented to zero), the function calls H5I__find_id() to obtain a pointer to the instance of H5I_id_info_t associated with the ID. This in hand, the function decrements the application reference count. The function returns either the value return by H5I__dec_ref() (if it is non-positive), or the application reference count after it has been decremented.

H5I__dec_ref() first calls H5I__find_id() to obtain a pointer (info) to the instance of H5I_id_info_t associated with the target index entry.

If info->count is greater that one, it decrements that value, and returns it to the caller.

If info→count is one, it accesses the H5I_type_info_array_g global to look up the pointer to the instance of H5I_type_info_t associated with the target, calls type_info→free_func() (which will be H5P__close_list_cb() in this case) to free info→object, calls H5I__remove_common() to remove *info from the index, and returns 0.

H5P_close_list_cb() calls H5P_close(), flags an error if it fails, and returns.

H5P close() is a lengthy, and involved function – it performs the following actions:

- Test to see if the property list initialization function completed (i.e. plist→class_init ==
 TRUE). If it did, execute the close function of the parent property list class (i.e.
 plist→pclass→close_func) if it exists, along with those of any property list classes from
 which the parent property list class was derived (i.e. plist→pclass→parent→close_func,
 etc).
- Create a skip list call it "seen". This is used to track the property list entries that have been encountered in the subsequent scan of the target property list, and the property list class(es) from which the property list was derived. This list is then used to ensure that the close callback for each property encountered is only called the first time it is seen.
- Scan the target property list (i.e. the plist→props skip list). It should contain only
 properties that have been modified from their default values. For each such property,
 add it to the "seen" list, and call its close callback if it exists.
- Scan the list of properties in the parent property list class. For each property, test to see if it appears in either the seen list, or the target property list's deleted list (plist→del). If it does not, add the property to the seen list, and call its close function if it exists.
 - If the parent property list class has a parent property list class, repeat the process on the parent until the root of the property list class hierarchy is reached.
- Call H5P_access_class(plist->pclass, H5P_MOD_DEC_LST) to decrement the parent property list class's dependent property list count.
- Free the skip lists associated with the target property list (plist→del and plist→props) via calls to H5SL_destroy(plist->del, H5P__free_del_name_cb, NULL) and H5SL destroy(plist->props, H5P free prop cb, &make cb) respectively.
 - Note that H5P__free_del_name_cb just discards the string containing the name of the discarded property. H5P__free_prop_cb can call the close callback for the target property, but does not in this case because *make cb is zero (i.e. FALSE).

• Finally, call H5FL_FREE() to discard the base plist structure (an instance of H5P_genplist_t – see above for definition).

Multi-thread safety concerns:

Skip list implementation is not thread safe.

Property List classes, property lists, and properties are all subject to simultaneous access and / or modification – with the obvious potential for corruption.

```
* \ingroup GPLOA
* \brief Closes an existing property list class
* \plistcls_id{plist_id}
* \return \herr t
* \details H5Pclose class() removes a property list class from the library.
          Existing property lists of this class will continue to exist,
          but new ones are not able to be created.
* \since 1.4.0
*/
H5 DLL herr t H5Pclose class(hid t plist id);
H5Pclose class()
+-H5I get type()
+-H5I_dec_app_ref()
   +-H5I__dec_app_ref()
      +-H5I__dec_ref()
      | +-H5I__find_id()
         +-(type info->cls->free func)((void *)info->object, request)
         | | H5P close class cb() // in this case
       | + + \overline{H5P} close class()
               +-H5P access_class(pclass, H5P_MOD_DEC_REF)
                 +-\overline{\text{H5}}\text{MM} \text{ xfree}()
                  +-H5SL destroy(pclass->props, H5P free prop cb, &make cb)
                 | +- ... // eventually
                 | H5P free prop cb()
                 +-(tprop->close)(tprop->name, tprop->size, tprop->value);
                 +-H5P_free_prop(tprop);
                 +-H5MM xfree()
       +-H5FL FREE()
                  +-H5FL FREE()
                 +-H5P_access_class(par_class, H5P_MOD_DEC_CLS);
                    +- ... // note recursion
         +-H5I remove common()
      +-H5I find id()
```

In a nutshell:

Decrement the reference count on the target property list class. If this reference count drops to zero, the class is removed from the index, and is marked as deleted. The class is not actually discarded until both the number of property lists that instantiate it, and the number of classes derived from it drop to zero as well.

In greater detail:

If the supplied hid_t is not associated with a property list class, **H5Pclose_class()** flags an error and returns. Otherwise, it calls H5I_dec_app_ref() and returns.

H5I_dec_app_ref() is basically a pass through. It preforms some sanity checks, and the calls H5I_dec_app_ref(id, H5_REQUEST_NULL), and returns whatever value H5I_dec_app_ref() returns.

H5I__dec_app_ref() calls H5I__dec_ref() to decrement the regular ref count on the target. If H5I__dec_ref() returns a positive value (indicating that the regular reference count has not been decremented to zero), the function calls H5I__find_id() to obtain a pointer to the instance of H5I_id_info_t associated with the ID. This in hand, the function decrements the application reference count. The function returns either the value return by H5I__dec_ref() (if it is non-positive), or the application reference count after it has been decremented.

H5I__dec_ref() first calls H5I__find_id() to obtain a pointer (info) to the instance of H5I id info t associated with the target index entry.

If info->count is greater that one, it decrements that value, and returns it to the caller.

If info→count is one, it accesses the H5I_type_info_array_g global to look up the pointer to the instance of H5I_type_info_t associated with the target, calls type_info→free_func() (which will be H5P__close_class_cb() in this case) to free info→object, calls H5I__remove_common() to remove *info from the index, and returns 0.

H5P_close_class_cb() calls H5P__close_class(), flags an error if it fails, and returns.

H5P__close_class() calls H5P__access_class(pclass, H5P_MOD_DEC_REF), flags an error if it fails, and returns.

H5P_access_class() maintains counts of the number of property lists and/or property list classes that depend on the target property list class.

In this case it is called with the H5P_MOD_DEC_REF op code (actually an instance of H5P_class_mod_t enumerated type), which directs it to decrement pclass→ref_count and set pclass→deleted to TRUE if the ref count has dropped to zero.

Regardless of op code, it also checks to see if:

(pclass->deleted && pclass->plists == 0 && pclass->classes == 0)

If so, it:

frees all class properties without calling the associated close callbacks,

- discards the skip list that contained the class properties,
- discards the instance of H5P genclass t that represented the property list class, and
- calls H5P__access_class(par_class, H5P_MOD_DEC_CLS) on the parent of the discarded class (if there was one).

The call to H5P__access_class(par_class, H5P_MOD_DEC_CLS) will decrement par_class → classes, before the check of:

```
(par class->deleted && par class->plists == 0 && par class->classes == 0)
```

is run on the parent class – possibly resulting in its deletion as well.

Multi-thread safety concerns:

Skip list implementation is not thread safe.

Property List classes, and their associated properties are all subject to simultaneous access and / or modification – with the obvious potential for corruption.

```
* \ingroup GPLO
^{\star} \brief Copies an existing property list to create a new property list
* \plist_id
* \return \hid t{property list}
* \details H5Pcopy() copies an existing property list to create a new
          property list. The new property list has the same properties
          and values as the original property list.
* \since 1.0.0
* /
H5 DLL hid t H5Pcopy(hid t plist id);
H5Pcopy()
+-H5I get type() // verify they is either H5I GENPROP LST or H5I GENPROP CLS
+-H5I_object()
| + ...
+-H5P copy plist() // if a property list
 | +-H5FL_CALLOC()
| +-H5SL_create()
 | +- ...
 | +-H5SL_count()
 | | +- ...
 | +-H5SL first()
 | +-H5MM xstrdup()
 | +-H5SL insert()
 | | + ...
 | +-H5SL next()
 | | // copy the properties from plist->props
   +-H5SL first()
   | +- ...
   +-H5SL_item()
 | +-H5FL MALLOC()
 | +-H5MM xstrdup()
 | +-(new prop->copy) (new prop->name, new prop->size, new prop->value)
 | | +- ... // property specific
 | +-H5P add prop()
 | +-H5SL insert()
       +- ...
 +-H5P__free_prop() // error recovery
 | +- ...
   +-H5SL_insert()
   | +- ...
   +-H5SL next()
   | // copy properties from parent property list class(es) if required.
 | +-H5SL first()
 | | +- ...
```

```
| +-H5SL_item()
| | +- ...
| +-H5SL search()
| | +- ...
| +-H5P do prop cb1(plist->props, tmp, tmp->copy)
| +-H5MM malloc()
| | +-cb(prop->name, prop->size, tmp value) // cb == tmp→copy
| | +- // property specific
| +-H5P__dup_prop(prop, H5P_PROP_WITHIN_LIST)
| +-H5MM memcpy()
  | +-H5P add prop()
 | + \overline{\text{H5}}\text{SL}_{insert}()
 +- ...
| | +-H5MM xfree () // error cleanup
+-H5MM_xfree()
+-H5FL_FREE()
| +-H5SL_insert()
| +- ...
+-H5SL next()
  | +- ...
+-H5P access_class(new_plist->pclass, H5P_MOD_INC_LST)
  | +-H5MM xfree() //can't happen in this case
| +-H5SL_destroy() // can't happen in this case
| | +- ...
| +-H5P access class(par class, H5P MOD DEC CLS) // can't happen in this case
 +-H5I_register(H5I_GENPROP_LST, new_plist, app_ref)
| | +- ...
1 1
| | // tclass is initialized as plist->parent, and then scans up the inheritance tree
+-(tclass->copy_func)(new_plist_id, old_plist->plist_id,
old plist→pclass→copy data)
| | +- ... // class specific
| +-H5I remove() // error cleanup
    +- ...
+-H5P copy pclass // if a property class
 +-H5P create class()
  | +-H5FL CALLOC()
  | +-H5MM xstrdup()
  | +-H5SL create()
 | | +- ...
 | +-H5P access class(par class, H5P MOD INC CLS)
| | +-H5MM xfree()
| | | +- ...
| | + ...
| | +-H5MM_xfree() // error cleanup
| +-H5SL_destroy()
      +- ... // eventually
H5P free prop cb()
```

```
+-(tprop->close)(tprop->name, tprop->size, tprop->value);
              | +- ... // property specific - may not exist
               +-H5P free_prop(tprop);
                 +-\overline{\text{H5}}\text{MM} \text{ xfree}()
                  +-H5FL FREE()
| +-H5SL first()
| | +- ...
  +-H5P__dup_prop()
   | +- // see above
  +-H5P__add_prop()
| +- // see above
  +-H5SL_next()
| +- ...
| +-H5P close_class() // error recovery
     +-H5P access class(pclass, H5P MOD DEC REF)
        +-H5MM xfree()
         +-H5SL destroy()
         | +- ...
         +-H5P access class(par class, H5P MOD DEC CLS)
+-H5I_register() // if a property class
| +- ...
+-H5P__close_class() // error cleanup on H5I_register()
  +- // see above
```

In a nutshell:

Duplicate the supplied property list or property list class, insert the duplicate in the appropriate index, and return the associated hid t.

It is interesting to note that the user documentation only discusses copying property lists – is there a reason for this?

Also, the duplicate property list need not be an exact duplicate, as its property list will contain any properties that have been deleted from the base property list. These added properties are copied from the parent property list class(es).

Is this a feature or a bug?

In greater detail:

H5Pcopy() verifies that the supplied hid_t refers to either a property list or a property list class, and verifies that the target of the ID actually exists. If any of these checks fail, H5Pcopy() fails.

H5Pcopy() then checks to see if the supplied id is that of a property list, or a property list class.

If it is a property list, it calls H5P copy plist(), flags an error it it fails, and returns.

If it is a property list class, if first calls H5P_copy_pclass(). If that function succeeds, it then calls H5I_register() to insert the new property list class in appropriate index. If H5I_register fails, it calls H5P_close_class() to discard the new property list class before returning. See H5Pclose_class() above for details on H5P_close_class().

COPY PROPERTY LIST CASE:

H5P_copy_plist() first verifies that the supplied old_plist pointer is not NULL, and then allocates a new instance of H5P gen plist t and stores its address in new plist.

It then sets new_plist→pclass = old_plist→pclass – which is to say that the new property list will be derived from the same property list class as the old property list.

It then initializes:

```
new_plist→nprops = 0; // the plist is empty to begin with new_plist→class_init = FALSE; // until the class callback completes
```

and calls H5SL_create() to create the new_plist→props and new_plist→del skip lists. Both of these lists are empty to begin with.

Similarly, it creates the "seen" skip list used to track properties that have already been seen and thus had their copy callbacks invoked – thus avoiding invoking the copy callback again on the property of the same name in a parent property list class.

It then copies the contents of the old_plist→del skip list into the new_plist→del skip list. The del skip lists contain the names of properties that have been deleted from old plist.

It then scans through old_plist→props and performs the following operations on each property it encounters:

Duplicate the property via a call to H5P__dup_prop() (specifically, new_prop = H5P_dup_prop(old_prop, H5P_PROP_WITHIN_LIST).

In this context, H5P__dup_prop() allocates a new instance of H5P_genprop_t (new_prop), copies the image of *old_prop into it, and (if old_prop->shared_name is FALSE), duplicates the string pointed to by old_prop->name and stored its address in new_prop->name. It then duplicates the buffer pointed to by old_prop->value (if it exists) storing the address of the duplicate in new_prop->value, and returns the address of the new instance of H5P_genprop_t

Note that the name would be shared if the property was copied from a class – which can't happen in this case.

Call the copy callback for the property if it exists (specifically, (new_prop->copy)(new_prop->name, new_prop->size, new_prop->value), calling H5P__free_prop() if this copy fails.

Insert the new property into new_plist -> props via a call to H5P__add_prop(), again calling H5P__free_prop() if the insertion fails. **H5P__add_prop()** simply calls H5SL_insert() to perform the insertion.

Insert the name of the new property into the "seen" skip list.

Increment nseen.

Increment new plist→nprops.

H5P_copy_plist() then scans through the properties of the parent property list class (i.e. tclass>props), and then for any property list classes that the parent property list class may be derived from. For each such property (prop) that is not in the "seen" list, the following operations are performed:

- Test to see if prop→copy is defined. If it is, duplicate the property and insert it into new_plist→props. Do this via a call to H5P__do_prop_cb1(new_plist->props, prop, prop→copy). In this context, H5P__do_prop_cb1() does the following:
 - Allocate a buffer (tmp_value) of size equal to the size of the value of the property (prop->size),
 - memcopy the value of the property (prop→value) into tmp value,
 - Call (prop→copy)(prop→name, prop→size, tmp_value),
 *** need spec on what copy is supposed to do ***
 - Call H5P__dup_prop(prop, H5P_PROP_WITHIN_LIST). In this context,
 H5P__dup_prop() allocates a new instance of H5P_genprop_t, copies the image of
 *prop into it, and (if prop->shared_name is FALSE), duplicates the string pointed to by old_prop->name and stored its address in new_prop->name. It then duplicates the buffer pointed to by prop->value (if it exists) storing the address of the duplicate in pcopy->value, and returns the address of the new instance of H5P_genprop_t
 - Memcpy tmp value into new prop→value.
 - Call H5P add prop() to insert the new property into new slist→props.

- Discard tmp value.
- On failure, call H5P__free_prop() to discard the copy of the property.

Observe that while all properties in old_plist→props are copied into new_plist→props, only properties that have copy callbacks are copied from parent property list class(es) into new_plist→props.

- 2. Add the name of the new property to the "seen" skip list
- 3. Increment nseen
- 4. Increment new plist→nprops

After the scan of the parent property list(s), H5P_copy_plist() increments the number of property lists derived from the parent property list class via a call to H5P_access_class(new_plist->pclass, H5P_MOD_INC_LST). In this context, H5P_access_class() increments pclass→plists and returns.

It then registers the new property list via a call to H5I_register(H5I_GENPROP_LST, new_plist, app_ref) where app_ref is a boolean parameter passed into H5P_copy_plist, and stores the new id in new plist->plist id.

It then calls the pclass \rightarrow copy_func() for all parent property list classes for which the call exists. If any of these calls fail, it calls H5I_remove(new_plist \rightarrow plist_id) and flags an error. If all succeed, it sets new_plist \rightarrow class_init to TRUE.

Finally, it sets the return value to the id of the new property list, and discards the "seen" skip list.

On failure, the new property list is discarded if it exists via a call to H5P_close(new_plist) – see discussion of H5Pclose() above for details of H5P_close().

COPY PROPERTY LIST CLASS CASE:

H5P_copy_pclass() first calls:

to create a new instance H5P_genclass_t. The pointer to the new instance is stored in new_pclass. In addition to allocating the the new instance, **H5P__create_pclass()** also:

```
Sets new pclass→parent = old pclass→parent
```

Duplicates the string pointed to by old_class → name, and sets new_pclass → name equal to the address of the duplicate string.

Initializes other fields of new pclass as follows:

Allocates the properties skip list and set new pclass→props to point to it.

Increments new pclass→parent→classes via a call to H5P access class().

This done, H5P__copy_pclass() scans the property list (old_pclass→props) and does the following with each property found:

 Call new_prop = H5P__dup_prop(old_prop, H5P_PROP_WITHIN_CLASS) to create a duplicate of the property.

In this context, H5P__dup_prop() allocates a new instance of H5P_genprop_t, copies the image of *old_prop into it, and duplicates the string pointed to by old_prop name and stored its address in new_prop name. Note that the unconditional duplication of the name is forced by the H5P_PROP_WITHIN_CLASS flag. It then duplicates the buffer pointed to by old_prop value (if it exists) storing the address of the duplicate in new_prop->value, and returns the address of the new instance of H5P_genprop_t

Note that unlike the copy property list case, the property specific copy call is not invoked.

- 2. Insert the new_prop into the new_class→props skip list via a call to H5P add prop(new pclass→props, new prop).
- 3. Increment new class → nprops

After the scan of the old_pclass > props completes, the function sets its return value to new_pclass and returns.

On failure, H5P__close_class(new_pclass) is called to cleanup. See discussion of H5Pclose_class() above for a description of this call.

Multi-thread safety concerns:

Skip list implementation is not thread safe.

Property list, property list classes, and their associated properties are all subject to simultaneous access and / or modification – with the obvious potential for corruption.

```
* \ingroup GPLOA
* \brief Copies a property from one list or class to another
^{\star} \param[in] dst_id Identifier of the destination property list or class
* \param[in] src_id Identifier of the source property list or class
* \param[in] name Name of the property to copy
* \return \herr_t
^{\star} \details H5Pcopy prop() copies a property from one property list or
          class to another.
          If a property is copied from one class to another, all the
          property information will be first deleted from the destination
          class and then the property information will be copied from the
          source class into the destination class.
          If a property is copied from one list to another, the property
          will be first deleted from the destination list (generating a
          call to the close callback for the property, if one exists)
          and then the property is copied from the source list to the
          destination list (generating a call to the copy callback for
          the property, if one exists).
          If the property does not exist in the class or list, this
          call is equivalent to calling H5Pregister() or H5Pinsert() (for
          a class or list, as appropriate) and the create callback will
          be called in the case of the property being copied into a list
          (if such a callback exists for the property).
* \since 1.6.0
*/
H5 DLL herr t H5Pcopy prop(hid t dst id, hid t src id, const char *name);
H5Pcopy prop()
+-H5I get type()
 | +- ...
 +-H5P copy_prop_plist()
 | +-H5I object()
 | | +- ...
 | +-H5P find prop plist()
 +- ...
 +-H5P remove()
 | +-H5P do prop(plist, name, H5P del plist cb, H5P del pclass cb, NULL)
 +-H5SL search()
         \mid // if the target property is in the property list
         +-(*plist op)(plist, name, prop, udata) // H5P del plist cb in this case
         | // if the target property is in the property class
         +-(*pclass op)(plist, name, prop, udata) // H5P del pclass cb in this case
 | +-H5P dup prop()
 | +-H5FL MALLOC()
 | +-H5MM memcpy()
 | +-H5MM xstrdup()
 | | +-H5MM xfree() // error cleanup
```

```
| | +-H5FL FREE() // error cleanup
+-(new_prop->copy)(new_prop->name, new_prop->size, new_prop->value)
| | +- ... // property specific
| +-H5P add prop()
| +-H5SL insert()
       +- ...
+-H5P__find_prop_plist()
| | +- // see above
+-H5P__create_prop()
+-H5MM memcpy()
 | +-H5MM_xfree() // error cleanup
| +-H5FL_FREE() // error cleanup
  +-(new_prop->create)(new_prop->name, new_prop->size, new_prop->value)
  | +- ... // prop. specific
  +-H5P add_prop()
 | +- // see above
| | // error cleanup
  +-H5P free prop() // error cleanup
    +-\overline{\text{H5}}\text{MM} \text{ xfree()}
     +-H5FL FREE()
+-H5P__copy_prop_pclass()
  +-H5I object()
  | +- ...
+-H5P__find_prop_pclass()
  +-H5SL_search()
  +- ...
  +-H5P exist_pclass()
  | +-H5SL search()
      +- ...
  +-H5P unregister()
  | +-H5SL search()
  | | +- ...
  | +-H5SL_remove()
  | | +- ...
  +-H5P__free_prop()
  +-H5MM xfree()
       +-H5FL FREE()
  +-H5P__register()
| | // duplicate class if required
     +-H5P create_class()
     | +-H5FL CALLOC()
    | +-H5MM xstrdup()
    | +-H5SL_create()
    | | +- ...
    | +-H5P access class(par class, H5P MOD INC CLS)
    | + + \overline{H5}MM \times free()
    | | +-H5SL_destroy()
   | | | +- ...
  // in this case
     | | + ...
     +-H5MM xfree() // error cleanup
     | +-H5SL destroy()
          +- ... // eventually
               H5P _free_prop_cb()
  +-(tprop->close)(tprop->name, tprop->size, tprop->value);
  | +- ... // property specific - may not exist
```

```
+-H5P__free_prop(tprop);
             +-H5MM xfree()
              +-H5FL FREE()
| +-H5SL_first()
| | +- ...
| +-H5P__dup_prop()
| | +- // see above
 +-H5P__add_prop()
| +- // see above
  +-H5SL next()
    +- ...
  +-H5P register real()
| | +-H5SL_search()
| | +- ...
| | +-H5P create prop()
| | +- // see above
| +-H5P close class() // error recovery
    +-H5P access class(pclass, H5P MOD DEC REF)
       +-H5MM xfree()
       +-H5SL destroy()
       | +- ...
       +-H5P _access_class(par_class, H5P_MOD_DEC_CLS)
+-H5I_subst()
| +- ...
+-H5P close class()
  +- // see above
```

In a nutshell:

Copy a property from one property list or property list class to another.

In greater detail:

H5Pcopy_prop() first verifies that the objects referred to by the source and destination ids are either both property lists, or both property list classes. The function flags an error and returns if this is not the case.

Note: No test to verify that source and destination are distinct. Subsequent review indicates that unique ids need not refer to unique property list classes. So far this doesn't seem to be the case for property lists.

If both source and destination are property lists, the function then calls:

```
H5P__copy_prop_plist(dst_id, src_id, name)
```

and returns success if that function succeeds, and failure if it fails. Otherwise, if both source and destination are property list classes, the function calls:

```
H5P copy prop pclass(dst id, src id, name)
```

again returning success if the function succeeds and failure if it fails.

PROPERTY LIST CASE:

H5P__copy_prop_plist() first makes calls to H5I_object() to obtain pointers to the source and destination property lists (src_plist and dst_plist) (Note: no test for distinctness).

This done, the function calls H5P__find_prop_plist(dst_plist, name), which calls H5SL_search() to see if the target property already exists in dst_plist.

If it does, H5P copy prop plist():

1. Calls H5P__remove(dst_plist, name) to remove the target property from the destination plist.

H5P__remove() is mostly a pass through function. It does some sanity checking, and then calls

```
H5P__do_prop(dst_plist, name, H5P__del_plist_cb, H5P__del_pclass_cb, NULL)
```

In this context, H5P__do_prop() first searches dst_plist → del to see if the target property has already been deleted – and flags an error if it has been.

It then tries to find the named property in dst plist→props via the call

```
prop = H5SL_search(dst_plist \rightarrow props, name).
```

If successful, it calls

```
H5P del plist cb(dst plist, name, prop, NULL)
```

and returns success or failure if this call succeeds or fails.

If this search fails, H5P__do_prop() searches the parent property list class(es) for the target property, and if successful calls:

```
H5P del pclass cb(dst plist, name, prop, NULL)
```

and again returns success or failure if this call succeeds or fails.

If the searches of the supplied property list and its parent property list class(es) fail, H5P__do_prop() returns failure.

H5P__del_plist_cb() calls the properties delete callback

```
(*(prop->del))(plist->plist id, name, prop->size, prop→value)
```

(What does the delete callback use the plist_id for? MT issues? Possible re-entry into H5I?)

if it exists, duplicates the property name string and inserts it into the dst_plist→del skip list, deletes the property from the dst_plist→props skip list, frees it, and decrements dst_plist→nprops.

H5P__del_pclass_cb() is similar to H5P__del_plist_cb() but subtly different.

Like H5P__del_plist_cb() it calls the properties delete callback if it exists. However, before it does so, it duplicates *(prop-value), and passes a pointer to this duplicate as the final parameter to the properties delete callback. After that, it duplicates the property name string and inserts it into the dst_plist->del skip list, and decrements dst_plist->nprops. Note, however, that since the target property is not in the dst_plist->props skip list, it doesn't attempt to remove it.

Calls prop = H5P__find_prop_plist(src_plist, name) to get a pointer to the source property.

H5P__find_prop_plist() first searches src_plist→del to see if the property has been deleted, and returns an error if it has been.

It then searches src_plist→props, and returns a pointer to the target property if this search is successful.

If this search fails, it searches for the property in the parent property list class(es), and returns a pointer to the target property if this search succeeds.

If neither search succeeds, it returns an error.

3. Calls new_prop = H5P__dup_prop(prop, H5P_PROP_WITHIN_LIST). **H5P__dup_prop()** allocates a new instance of H5P_genprop_t (new_prop), copies the image of *prop into it, and (if prop→shared_name is FALSE), duplicates the string pointed to by prop→name and stored its address in new_prop→name, duplicates the buffer pointed to by prop→value (if it exists) storing the address of the duplicate in new_prop→value, and returns the address of the new instance of H5P_genprop_t

- 4. Calls the property copy callback if it exists (new_prop->copy)(new_prop->name, new_prop->size, new_prop→value).
- 5. Calls H5P_add_prop(dst_plist->props, new_prop) to insert the new property in the destination property list. **H5P_add_prop()** does this via a call to

```
H5SL insert(dst plist->props, new prop, new prop->name)
```

6. Increments dst plist→nprops.

If, on the other hand, the target property doesn't already exist in the destination property list, H5P__copy_prop_plist() proceeds as follows:

- 1. Call prop = H5P__find_prop_plist(src_plist, name) to obtain a pointer to the target property. See discussion above.
- 2. Create the new property via the call

After some sanity checks, **H5P__create_prop()** allocates a new instance of H5P_genprop_t (new_prop), duplicates *(prop→name) and sets new_prop→name to point to it. Similarly, if prop→value is not NULL, it duplicates *(prop→value), and sets new_prop→value to point to the copy.

In this context, it initializes the remaining fields of *new_prop from its parameters as follows:

```
new_prop>shared_name = FALSE
new_prop>size = prop>size;
new_prop>type = H5P_PROP_WITHIN_LIST;
new_prop>create = prop>create;
new_prop>set = prop>set;
new_prop>get = prop>get;
new_prop>encode = prop>encode;
new_prop>decode = prop>decode;
new_prop>del = prop>del;
new_prop>create = prop>create;
new_prop>create = prop>create;
new_prop>create = prop>decode;
new_prop>create = prop>create;
new_prop>create = prop>decode;
new_prop>create = prop>create;
new_prop>create = prop>create;
new_prop>create = prop>create;
new_prop>create;
new_prop>create = prop>create;
new_prop>create = prop>create;
new_prop>create;
new_pro
```

While I don't think it can happen in this case, if prop→cmp were NULL, new prop→cmp would be set to &memcmp.

On success, H5P__create_prop() returns the pointer to the new instance of H5P_genprop_t (i.e. new_prop).

3. Call the property creation callback if it exists:

4. Insert the new property into the dst plist via the call

```
H5P add prop(dst plist->props, new prop)
```

5. Increment dst_plist→nprops

Whichever path is taken, H5P__copy_prop_plist() then returns. On error, *new_prop is discarded via a call to H5P free prop() prior to return.

PROPERTY LIST CLASS CASE:

H5P__copy_prop_pclass() first makes calls to H5I_object() to obtain pointers to the source and destination property list classes (src_pclass and dst_pclass) (No test for distinctness).

It then obtains a pointer to the target property in the source property list class via the call:

```
prop = H5P find prop pclass(src pclass, name)
```

which is essentially a pass through to H5SL search(src pclass→props, name).

H5P copy prop pclass() then calls

```
H5P exist pclass(dst pclass, name)
```

to determine whether the destination property list class already contains a property of the target name.

H5P__exist_class() does this by first running H5SL_search(dst_class→props, name). If this search fails, it repeats the process on dst_class→parent→props, and so on up the inheritance tree until a property of the specified name is found, or there are no further parent property list classes. It returns TRUE if such a property is found, and FALSE otherwise.

If H5P exist pclass() returns TRUE, H5P copy prop pclass() calls

```
H5P unregister(dst pclass, name)
```

to remove the target property from the destination property list class.

H5P__unregister() calls

```
prop = H5SL search(pclass->props, name)
```

to obtain a pointer to the target property, calls

```
H5SL remove(pclass->props, prop→name)
```

to remove it from pclass → props, calls

```
H5P free prop(prop)
```

to free it, decrements pclass in props, sets pclass-revision equal to the global variable H5P_next_rev, increments H5P_next_rev, and returns.

Note: H5P__unregister() operates only on dst_pclass, but H5P__exist_pclass() will return TRUE if either dst_pclass or any property list class that dst_pclass is derived from contains a property of the target name. Thus it appears that it is possible for H5P__exist_pclass() to return TRUE, and for H5P__unregister() to fail because it is unable to find the target property. This appears to be a bug.

After removing the target property from the destination property list class, if necessary, H5P__copy_prop_pclass() saves a copy of the pointer dst_pclass in old_dst_pclass, and then calls

```
H5P_register(&dst_pclass, name, prop->size, prop->value, prop->create, prop->set, prop->get, prop->encode, prop->decode, prop->del, prop->copy, prop->cmp, prop->close)
```

The objective of H5P__register() is to insert the new property into the target property list. However, there is a problem if there are any extant property lists, or property list classes derived from dst_pclass. Specifically, there appears to be no method for updating the derived property lists and property list classes for changes to *dst_pclass. Instead, H5P__register() duplicates *dst_pclass, inserts the new property into the duplicate, and returns a pointer to the duplicate. The duplicate later replaces the earlier version of *dst_class in the index. The original version of *dst_pclass is then is only accessible via the parent pointers in its derived property lists and property list classes (not quite – as shall be seen H5Pget_class() can insert the old version of the property list class into the index, albeit with a new id. See discussion of H5Pget_class() for further details.). It is retained until both its plists (number of derived

property lists) and classes (number of derived property list classes) fields drop to zero – at which point it is discarded.

With this background, we return to a detailed discussion of H5P_register().

H5P__register first tests to see if either dst_pclass → plists or dst_class → classes is positive. If either is, it calls

After some sanity checks, **H5P__create_class()** allocates a new instance of H5P_genclass_t, and stores its address in new_pclass. It then duplicates the string containing the name of the new property list class (dst_class → name in this case) and set new_pclass → name equal to the duplicate string.

H5P__create_class() then calls H5SL_create() to create the skip list used to store properties in the property list class, sets new_pclass→nprops to point to it, and then initializes the remaining fields of *new pclass as follows (in this case):

where H5P_next_rev is a global variable used to assign unique revision numbers to property list classes. Finally, H5P__create_class() calls

```
H5P_access_class(new_pclass-)parent, H5P_MOD_INC_CLS)
```

to increment new pclass→parent→classes, and returns new pclass.

With *new_pclass created, H5P__register must now populate it with copies of all properties that appear in dst_pclass. It does this by scanning dst_pclass → props, and performing the following operations on each property (old_prop) encountered:

1. Duplicate the property with a call to

```
new prop = H5P dup prop(old prop, H5P PROP WITHIN CLASS)
```

In this context, **H5P__dup_prop()** allocates a new instance of H5P_genprop_t, copies the image of *old_prop into it, duplicates the string pointed to by old_prop \rightarrow name and stored its address in new_prop \rightarrow name duplicates the buffer pointed to by prop \rightarrow value (if it exists) storing the address of the duplicate in pcopy \rightarrow value, and returns the address of the new instance of H5P_genprop_t.

Note that the unconditional duplication of the name is forced by the H5P_PROP_WITHIN_CLASS flag.

2. Insert new prop into new pclass via the call

```
H5P__add_prop(new_pclass->props, new_prop)
```

3. Increment new pclass->nprops

This done, H5P__register sets dst_pclass = new_pclass, completing processing for the dst_pclass → plists or dst_class → classes positive case. Note that the copy of dst_pclass made earlier is used later to detect whether a copy of dst_pclass has been created after H5P_register returns.

Whether either dst_pclass→plists or dst_class→classes is positive or not, H5P__register() next calls

```
H5P__register_real(dst_pclass, name, prop→size, prop→value, prop→create, prop→set, prop→get, prop→encode, prop→decode, prop→delete, prop→copy, prop→cmp, prop→close)
```

Recall that dst pclass may be either the original, or the duplicate at this point.

After some sanity checks, **H5P__register_real()** creates the new property via the call:

See the PROPERTY LIST CASE above for a detailed discussion of H5P__create_prop(). Note that in this case, new_prop→type is set to H5P_PROP_WITHIN_CLASS instead of H5P_PROP_WITHIN_LIST.

After new_prop is created, H5P__register_real() inserts it into dst_class via a call to

```
H5P__add_prop(dst_pclass->props, new_prop)
```

increments dst_pclass→nprops, sets dst_pclass→revision = H5P_next_rev, increments that global integer, and returns. Recall that dst_pclass may now point to a duplicate with the new property added.

Assuming no errors, H5P__register() returns immediately after H5P__register_real() returns.

After H5P__register() returns, H5P__copy_prop_pclass() compares dst_pclass with old_dst_pclass – the copy it made just before calling H5P__register(). If the two don't match, it must replace old_dst_pclass with dst_pclass in the index. It does this with the call

```
H5I subst(dst id, dst pclass)
```

and then calls

```
H5P close class(old dst pclass)
```

which decrements old_dst_pclass \rightarrow ref_count, and may delete it. See discussion in H5Pclose_class() above for further details.

Multi-thread safety concerns:

Skip list implementation is not thread safe.

Property list, property list classes, and their associated properties are all subject to simultaneous access and / or modification – with the obvious potential for corruption.

H5P_next_rev is a global used to assign unique ids. Mutual exclusion is required.

```
* \ingroup GPLO
^{\star} \brief Creates a new property list as an instance of a property list class
* \plistcls_id{cls_id}
* \return \hid t{property list}
* \details H5Pcreate() creates a new property list as an instance of
        some property list class. The new property list is initialized
        with default values for the specified class. The classes are as
        follows:
* 
  Class Identifier
    Class Name
    Comments
  #H5P ATTRIBUTE CREATE
    attribute create
    Properties for attribute creation
   #H5P DATASET ACCESS
    dataset access
    Properties for dataset access
   #H5P DATASET CREATE
    dataset create
    Properties for dataset creation
  #H5P DATASET XFER
    data transfer
    Properties for raw data transfer
   \langle t.r \rangle
    #H5P DATATYPE ACCESS
    datatype access
    Properties for datatype access
   #H5P DATATYPE CREATE
    datatype create
    Properties for datatype creation
   #H5P FILE ACCESS
    file access
    Properties for file access
   #H5P FILE CREATE
    file create
    Properties for file creation
   #H5P FILE MOUNT
    file mount
```

```
Properties for file mounting
   #H5P GROUP ACCESS
     group access
     Properties for group access
   #H5P GROUP CREATE
     group create
     Properties for group creation
   >
     #H5P LINK ACCESS
     link access
     Properties governing link traversal when accessing objects
   * 
     #H5P LINK CREATE
     link create
     Properties governing link creation
   #H5P OBJECT COPY
     object copy
     Properties governing the object copying process
   #H5P OBJECT CREATE
     object create
     Properties for object creation
   #H5P STRING CREATE
     string create
     Properties for character encoding when encoding strings or
      object names
   #H5P VOL INITIALIZE
     vol initialize
     Properties for VOL initialization
   * 
* This property list must eventually be closed with H5Pclose();
* otherwise, errors are likely to occur.
^{\star} \version 1.12.0 The <code>#H5P_VOL_INITIALIZE</code> property list class was added
* \version 1.8.15 For each class, the class name returned by
               H5Pget class name() was added.
               The list of possible Fortran values was updated.
* \version 1.8.0 The following property list classes were added at this
* release: #H5P_DATASET_ACCESS, #H5P_GROUP_CREATE,
              #H5P GROUP ACCESS, #H5P DATATYPE CREATE,
              #H5P DATATYPE ACCESS, #H5P ATTRIBUTE CREATE
* \since 1.0.0
H5_DLL hid_t H5Pcreate(hid_t cls_id);
```

```
H5Pcreate()
+-H5I object verify()
| +- ...
+-H5P create id()
  +-H5P create()
   | +-H5FL_CALLOC()
   | +-H5SL_create()
   | +- ...
     +-H5SL item()
   | | +- ...
    +-H5SL search()
   | | +- ...
   | +-H5P do prop cb1(plist->props, tmp, tmp->create)
   | +-H5MM malloc()
   | | +-cb(prop->name, prop->size, tmp_value) // cb == tmp→create
   | | +-H5P dup prop(prop, H5P PROP WITHIN LIST)
   | | +-H5MM_xfree() // error cleanup
   | | +-H5FL_FREE() // error cleanup
   | +-H5MM_memcpy()
    | +-H5P__add_prop()
    | +-H5SL_insert()
   | | +- ...
   | +-H5SL next()
   | | +- ...
   +-H5P_access_class(plist->pclass, H5P MOD INC LST)
   +-H5SL close() // error cleanup
   +-H5SL destroy() // error cleanup
     +-H5SL_close() // error cleanup
    | +- ...
   | +-H5FL FREE() // error cleanup
   +-H5I register()
   +-(tclass->create_func)(plist_id, tclass->create_data) // class specific,
                                             // may not exist
   +-H5I remove() // error cleanup only
   | +- ...
   +-H5P close() // error cleanup only
     +- // see H5Pclose() above
```

Create a new property list derived from the property list class indicated by the supplied id.

In greater detail:

H5Pcreate() first calls

```
pclass = H5I_object_verify(cls_id, H5I_GENPROP_CLS)
```

to obtain a pointer to the source property list class, calls

```
plist_id = H5P_create_id(pclass, TRUE) // discussed below
```

to create the new property list and then returns plist_id.

H5P_create_id() starts by calling

```
plist = H5P__create(pclass) // discussed below
```

to create the new property list, and then inserts it into the index with the callback

```
plist_id = H5I_register(H5I_GENPROP_LST, plist, app_ref)
```

Note that app_ref is TRUE in this case. H5P_create_id() then sets plist→plist_id = plist_id, and then scans up the property list class inheritance tree (i.e. tclass = plist→parent, tclass = plist→parent, etc), calling the create function:

```
(tclass->create func) (plist id, tclass->create data)
```

whenever it exists. This done, it sets pclass -> class init = TRUE and returns plist id.

H5P__create() is the main routine for creating a new property list. It starts by allocating a new instance of H5P genplist t and seting plist to point to it. This done, it sets:

```
plist→pclass = pclass;
plist→nprops = 0;
plist→class init = FALSE;
```

and creates the

```
plist→props
plist→del
```

skip lists with calls to H5SL_create(). The "seen" skip list is also created.

The next step is to populate the new property list. Do this by scanning the property lists of the parent property list class(es) and copying properties into the new property list. This is complicated by two factors:

First, only properties with create functions are copied into plist->props.

Second, in cases where pclass has one or more parent property list classes (i.e. pclass-) parent != NULL), it appears to be possible that two or more of these property list classes will contain properties of the same name. This is handled by first scanning the property list of pclass, then pclass-) parent (if it exists), and so forth, and for any given name, only coping the first property of that name encountered (and then only if its create function is defined). The "seen" skip list is used to track the names of properties already been considered for copying into the new property list.

For each property (prop) selected by this method, **H5P__create()** does the following:

1. Test to see if the property creation callback exists (i.e. prop→create != NULL). If it does, it calls

```
H5P__do_prop_cb1(plist->props, prop, prop->create)
```

H5P__do_prop_cb1() duplicates the property, and inserts it into plist→props. In this context, it does the following:

- Allocate a buffer (tmp_value) of size equal to the size of the value of the property (prop->size),
- memcopy the value of the property (prop→value) into tmp_value,
- Call (prop->create)(prop->name, prop->size, tmp_value),
 *** need spec on what create is supposed to do ***
- Call H5P__dup_prop(prop, H5P_PROP_WITHIN_LIST). In this context, H5P__dup_prop() allocates a new instance of H5P_genprop_t (new_prop), copies the image of *prop into it, sets new_prop→shared_name = TRUE, duplicates the buffer pointed to by prop→value (if it exists) storing the address of the duplicate in new_prop→value, and returns the address of the new instance of H5P_genprop_t.
- Memcopy tmp value into new prop→value.
- Call H5P add prop() to insert the new property into new slist→props.
- Discard tmp_value.

• On failure, call H5P__free_prop() to discard the copy of the property.

Again, note that only properties that have create callbacks are copied from parent property list class(es) into plist props.

After H5P do prop cb1() returns, increment pclass → nprops.

2. Regardless of whether prop→create != NULL, add prop→name to the "seen" skip list.

After populating plist→props, H5P__create() calls

```
H5P__access_class(plist->pclass, H5P_MOD_INC_LST)
```

which in this context increments plist→pclass→plists.

Finally, H5P create() returns plist.

Multi-thread safety concerns:

Skip list implementation is not thread safe.

Property list, property list classes, and their associated properties are all subject to simultaneous access and / or modification – with the obvious potential for corruption.

```
* \ingroup GPLOA
 \brief Creates a new property list class
* \plistcls_id{parent}
* \param[in] name
                         Name of property list class to register
* \param[in] create
                         Callback routine called when a property list is
                         created
^{\star} \param[in] create_data Pointer to user-defined class create data, to be
                         passed along to class create callback
* \param[in] copy
                         Callback routine called when a property list is
                         copied
* \param[in] copy_data
                         Pointer to user-defined class copy data, to be
                         passed along to class copy callback
* \param[in] close
                         Callback routine called when a property list is
                         being closed
* \param[in] close data Pointer to user-defined class close data, to be
                         passed along to class close callback
* \return \hid t{property list class}
* \details H5Pcreate_class() registers a new property list class with the
          library. The new property list class can inherit from an
           existing property list class, \p parent, or may be derived
           from the default "empty" class, NULL. New classes with
           inherited properties from existing classes may not remove
          those existing properties, only add or remove their own class
          properties. Property list classes defined and supported in the
          HDF5 library distribution are listed and briefly described in
          H5Pcreate(). The \p create, \p copy, \p close functions are called
          when a property list of the new class is created, copied, or closed,
          respectively.
           H5Pclose class() must be used to release the property list class
           identifier returned by this function.
* \since 1.4.0
H5 DLL hid t H5Pcreate class(hid t parent, const char *name,
                             H5P cls create func t create,
                             void *create data, H5P cls copy func t copy,
                             void *copy data, H5P cls close func t close,
                             void *close data);
H5Pcreate class()
+-H5I get type()
 | + ...
 +-H5I object()
 | +- ...
 +-H5P create class()
 | +-H5FL CALLOC()
 | +-H5MM xstrdup()
 | +-H5SL create()
 | | +- ...
   +-H5P_access_class(par_class, H5P_MOD_INC_CLS)
 | +-H5SL destroy()
 | +-H5P_access_class(par_class, H5P_MOD_DEC_CLS) // can't happen in this case
```

```
| +-H5MM xfree() // error cleanup
| +-H5SL destroy()
     +- ... // eventually
         H5P free prop cb()
           +-(tprop->close)(tprop->name, tprop->size, tprop->value);
            | +- ... // property specific - may not exist
            +-H5P _free_prop(tprop);
               +-H5MM xfree()
               +-H5FL FREE()
+-H5I register()
| +- ...
+-H5P__close_class() // error cleanup
  +-H5P access class(pclass, H5P MOD DEC REF)
     +-H5MM xfree()
     +-H5SL destroy()
     | +- ...
      +-H5P access class(par class, H5P MOD DEC CLS)
        +- // see above
```

Create a new property list class based on the supplied parent property list class, insert it in the index, and return its id.

In greater detail:

After input validations, **H5Pcreate_class()** checks to see if the parent property list class id is H5P_DEFAULT. If it is, it sets par_class = NULL. Otherwise it calls H5I_object to obtain a pointer to the parent class, and sets par_class to this value. (Note: a NULL par_class will trigger an assertion failure in H5P__create_class() in debug builds, but does not seem to trigger an error in production builds. This is probably a bug.)

This done, H5Pcreate class() calls

to create the new property list class.

H5P__create_class() is discussed in detail in the "COPY PROPERTY LIST CLASS" case of the discussion of H5Pcopy() above. Briefly, it creates a property list class with no properties and no derived property lists or property list classes, that is otherwise a duplicate of the parent property list class, and returns a pointer to it. In passing, it also increments dst_pclass->parent->classes.

When H5P__create_class() returns, H5Pcreate_class() calls

```
H5I_register(H5I_GENPROP_CLS, pclass, TRUE)
```

to insert the new property list class into the index, and returns the new property list class id.

Multi-thread safety concerns:

Skip list implementation is not thread safe.

Property list classes, and their associated properties are all subject to simultaneous access and / or modification – with the obvious potential for corruption.

```
* \ingroup GPLO
* \brief Decodes property list received in a binary object buffer and
           returns a new property list identifier
* \param[in] buf Buffer holding the encoded property list
* \return \hid tv{object}
* \details Given a binary property list description in a buffer, H5Pdecode()
          reconstructs the HDF5 property list and returns an identifier
           for the new property list. The binary description of the property
           list is encoded by H5Pencode().
           The user is responsible for passing in the correct buffer.
          The property list identifier returned by this function should be
          released with H5Pclose() when the identifier is no longer needed
           so that resource leaks will not develop.
^{\star} \note Some properties cannot be encoded and therefore will not be available
        in the decoded property list. These properties are discussed in
        H5Pencode().
* \since 1.10.0
H5 DLL hid t H5Pdecode(const void *buf);
H5Pdecode()
 +-H5P decode()
   +-H5P _new_plist_of_type()
    | +-H5I object()
    | | +- ...
      +-H5P create id()
         +-H5P create()
          | +-H5FL CALLOC()
          | +-H5SL_create()
          | | +- ...
          | +-H5SL first()
          | | +- ...
            +-H5SL item()
          | +- ...
            +-H5SL_search()
            | +- ...
            +-H5P__do_prop_cb1(plist->props, tmp, tmp->create)
          | +-cb(prop->name, prop->size, tmp_value) // cb == tmp→create
            | +-H5P dup prop(prop, H5P PROP WITHIN LIST)
            | +-H5FL MALLOC()
            | | +-H5MM xstrdup()
            | | +-H5MM_xfree() // error cleanup
            | | +-H5FL_FREE() // error cleanup
            | +-H5MM memcpy()
            | +-H5P__add_prop()
          | | +-H5SL_insert()
          1
          | | +- ...
            | +-H5MM_xfree () // error cleanup
| +-H5P_free_prop()
| +-H5P_free_prop()
```

```
| +-H5SL insert()
     | | +- ...
     | +-H5SL next()
     | | +- ...
     | +-H5P_access_class(plist->pclass, H5P_MOD_INC_LST)
     // in this case, increment the plist count in the pclass
     +-H5SL close() // error cleanup
        | +- ...
        +-H5SL_destroy() // error cleanup
      | +-H5SL_close() // error cleanup
     | | +- ...
     | +-H5FL FREE() // error cleanup
     +-H5I register()
     | +- ...
     +-(tclass->create func)(plist id, tclass->create data) // class specific,
                                                           // may not exist
     +-H5I_remove() // error cleanup only
     | +- ...
     +-H5P_close() // error cleanup only
        +- // see H5Pclose() above
+-H5I object()
| +- ...
+-HDstrlen()
+-H5P__find_prop_plist()
| +-
+-H5MM realloc()
+-(prop->decode) ((const void **)&p, value buf)
| +- // property specific
+-H5P poke()
+-H5P do prop(plist, name, H5P poke plist cb,
                 H5P__poke_pclass_cb, &udata)
     +-H5SL_search()
     | +- ...
+-H5P__poke_plist_cb()
      | +-H5MM memcpy()
     +-H5P poke pclass cb()
        +-H5P_dup_prop(prop, H5P_PROP_WITHIN_LIST)
        | +-H5FL MALLOC()
        | +-H5MM memcpy()
         | +-H5MM xstrdup()
         | +-H5MM_xfree() // error cleanup
        | +-H5FL FREE() // error cleanup
        +-H5MM memcpy()
        +-H5P__add_prop()
        | +-H5SL_insert()
            +- ...
        +-H5P__free_prop() // error cleanup
             +-H5MM xfree()
             +-H5FL_FREE()
+-H5MM xfree()
+-H5I dec ref() // error cleanup
```

Given a buffer containing an encoded property list, decode the buffer, construct the property list described in the buffer, insert it in the index, and return the id associated with the decoded property list.

Note that only property lists derived from HDF5 defined property list classes are supported. This is not mentioned in the user documentation.

In greater detail:

H5Pdecode() simply calls H5P_decode() with the supplied buffer, and returns whatever H5P_decode() returns, flagging an error in passing if H5P_decode() fails.

H5P__decode() first reads the encoding version number from the first byte of the supplied buffer and fails if it is not H5P ENCODE VERS (currently defined to be zero).

It then loads the type of the property list (another byte) and fails if

```
type <= H5P TYPE USER or type >=H5P TYPE MAX TYPE.
```

Observe that this disallows user defined property lists. H5P_TYPE_USER and H5P_TYPE_MAX_TYPE are both members of the enumerated type H5P_plist_type_t, whose definition is reproduced below:

```
typedef enum H5P plist type t {
  H5P_TYPE_USER = 0,
H5P_TYPE_ROOT = 1,
  H5P TYPE OBJECT CREATE = 2,
  H5P_TYPE_FILE_CREATE = 3,
H5P_TYPE_FILE_ACCESS = 4,
  H5P TYPE DATASET CREATE = 5,
  H5P TYPE DATASET ACCESS = 6,
  H5P_TYPE_DATASET_XFER
  H5P_TYPE_FILE_MOUNT = 8,
H5P_TYPE_GROUP_CREATE = 9,
H5P_TYPE_GROUP_ACCESS = 10,
   H5P TYPE DATATYPE CREATE = 11,
   H5P TYPE DATATYPE ACCESS = 12,
   H5P TYPE STRING CREATE = 13,
  H5P TYPE ATTRIBUTE CREATE = 14,
   H5P\_TYPE\_OBJECT\_COPY = 15,
   H5P_TYPE_LINK_CREATE = 16,
H5P_TYPE_LINK_ACCESS = 17,
   H5P TYPE ATTRIBUTE ACCESS = 18,
   H5P\_TYPE\_VOL\ INITIALIZE = 19,
   H5P_TYPE_MAP_CREATE = 20,
H5P_TYPE_MAP_ACCESS = 21,
   H5P TYPE REFERENCE ACCESS = 22,
   H5P TYPE MAX TYPE
```

```
} H5P_plist_type_t;
```

If the property list type is in range, H5P__decode() calls

```
plist_id = H5P__new_plist_of_type(type)
```

to create a new property list of the specified type, insert it in the index, and return its id. Given plist_id, H5P_decode() obtains a pointer to the new property list (plist) via a call to H5I_object(). It populates *plist by executing the following loop until the supplied buffer is exhausted.

- Test to see if the buffer is exhausted, and exit the loop if it is.
- Set name to point to the string in the buffer containing the next property name.
- Call

```
prop = H5P find prop plist(plist, name)
```

to obtain a pointer to the existing property in the newly created property list of the specified name. Since plist is a newly created property list, prop should have the default value.

- The value_buf is a buffer that is provided to prop→decode(), and must be of length greater than or equal to prop→size. Check to see if the current value_buf is large enough, and if not, realloc() it to the required size, and make note of the new size in value_buf_size.
- Call

```
prop->decode)((const void **)&p, value_buf)
```

where p is a pointer to the current location in the supplied buffer. In addition to loading the value into value_buf, prop→decode() must update p to reflect the number of bytes read from the buffer.

Call

```
H5P poke(plist, name, value buf)
```

to insert the value into the named property in the property list.

On exiting this loop, free value buf, and return plist id.

On error, test to see if the new property list has been created, and if so, discard it via a call to H5I dec ref().

After some sanity checking (which includes specifically disallowing property lists derived from user created property list classes) H5P__new_plist_of_type() runs a switch statement to map the supplied instance of H5P_plist_type_t to the id of the associated property list class. These ids are read from the appropriate global variable, and stored in the local variable class_id.

H5P__new_plist_of_type() then calls H5I_object() to obtain a pointer (pclass) to the source data set class, and then calls

```
ret_value = H5P_create_id(pclass, TRUE)
```

which creates the desired property list class, inserts it into the index, and returns the new id, which H5P__rew_plist_of_type() returns.

H5P_create_id() is discussed at length In H5Pcreate() above – please see the discussion of that API call for details. Briefly, it creates a new property list of the supplied property list class, populates it with default values, inserts it in the index, and returns the id of the new property list class.

H5P__find_prop_plist() first searches the deleted list (prop→del) for the supplied name, and flags an error and returns if the search is successful.

Failing that, it searches plist→props for a property of the supplied name, and returns a pointer to the target instance of H5P_genprop_t if the search succeeds.

Failing that, it searches the property lists of its parent property list class(es), starting with plist \rightarrow parent \rightarrow props, and then up the list of parents until it either finds a property of the supplied name – in which case it returns a pointer to the target instance of H5P_genprop_t, or it runs out of parents – in which case it returns NULL and flags an error.

All searches are done via calls to H5SL search()

H5P_poke() allocates an instance of H5P_prop_set_ud_t (definition below)

```
/* Typedef for property list set/poke callbacks */
typedef struct {
   const void *value; /* Pointer to value to set */
} H5P_prop_set_ud_t;
```

and initializes the instance (udata) as follows:

```
udata.value = value;
```

This done, it calls

```
H5P do prop(plist, name, H5P poke plist cb, H5P poke pclass cb, &udata)
```

and returns.

H5P__do_prop(plist, name, H5P__poke_plist_cb, H5P__poke_pclass_cb, &udata) first searches plist → del for the specified name, and fails if it is found.

It then tries to find the named property in dst plist→props via the call

```
prop = H5SL search(dst plist→props, name).
```

If successful, it calls

```
H5P__poke_plist_cb(plist, name, prop, udata)
```

and returns success or failure if this call succeeds or fails.

If this search fails, H5P__do_prop() searches the parent property list class(es) for the target property, and if successful calls:

```
H5P__poke_pclass_cb(dst_plist, name, prop, udata)
```

and again returns success or failure if this call succeeds or fails.

If the searches of the supplied property list and its parent property list class(es) fail, H5P__do_prop() returns failure.

H5P__poke_plist_cb() simply memcpy's the supplied buffer (udata→value) into prop→value and returns.

After some sanity checks, H5P__poke_pclass_cb() calls

```
pcopy = H5P dup prop(prop, H5P PROP WITHIN LIST)
```

to duplicate the named property, memcpy()s udata.value into pcopy -> value, and then calls

```
H5P add prop(plist->props, pcopy)
```

to insert the modified property into plist before returning.

In this context, **H5P__dup_prop()** allocates a new instance of H5P_genprop_t (pcopy), copies the image of *prop into it, sets pcopy -> shared_name = TRUE, duplicates the buffer pointed to by prop-> value (if it exists) storing the address of the duplicate in pcopy -> value, and returns the address of the new instance of H5P_genprop_t.

H5P__add_prop() simply calls H5SL_insert() to add pcopy to plist→props.

Multi-thread safety concerns:

```
/**
* \ingroup GPLO
  \brief Encodes the property values in a property list into a binary
* \plist id
* \param[out] buf
                     Buffer into which the property list will be encoded.
                     If the provided buffer is NULL, the size of the
                     buffer required is returned through \p nalloc; the
                     function does nothing more.
* \param[out] nalloc The size of the required buffer
* \fapl id
* \return \herr_t
* \details H5Pencode2() encodes the property list \p plist_id into the
           binary buffer \p buf, according to the file format setting
           specified by the file access property list \p fapl id.
           If the required buffer size is unknown, \p buf can be passed
           in as NULL and the function will set the required buffer size
           in \p nalloc. The buffer can then be created and the property
           list encoded with a subsequent H5Pencode2() call.
           If the buffer passed in is not big enough to hold the encoded
           properties, the H5Pencode2() call can be expected to fail with
           a segmentation fault.
           The file access property list \p fapl id is used to
           control the encoding via the \a libver bounds property
           (see H5Pset_libver_bounds()). If the \sqrt{a} libver_bounds
           property is missing, H5Pencode2() proceeds as if the \a
           libver_bounds property were set to (#H5F_LIBVER_EARLIEST,
           #H5F LIBVER LATEST). (Functionally, H5Pencode1() is identical to
           H5Pencode2() with \a libver bounds set to (#H5F LIBVER EARLIEST,
           #H5F LIBVER LATEST).)
           Properties that do not have encode callbacks will be skipped.
           There is currently no mechanism to register an encode callback for
           a user-defined property, so user-defined properties cannot
           currently be encoded.
           Some properties cannot be encoded, particularly properties that
           are reliant on local context.
       \b Motivation:
        This function was introduced in HDF5-1.12 as part of the \a H5Sencode
        format change to enable 64-bit selection encodings and a dataspace
        selection that is tied to a file.
* \since 1.12.0
* /
H5 DLL herr t H5Pencode2(hid t plist id, void *buf, size t *nalloc, hid t fapl id);
H5Pencode2()
+-H5I object verify()
 | +- ...
+-H5CX_set_apl()
 | +- //
 +-H5P encode()
    +-H5P iterate plist(plist, enc all prop, &idx, H5P encode cb, &udata)
```

```
+-H5SL_create()
| +- ...
| // Note different callback functions in two invocations
| // of H5SL iterate().
+-H5SL iterate(plist->props, H5P iterate plist cb, &udata int)
  | // in this case - note that arg names have been changed
  | // for clarity
  +-H5P iterate plist cb(prop, name, udata int)
      +-H5P cmp plist cb(id, prop→name, udata)
         +-H5P exist plist(udata->plist2, prop->name)
         | +-H5SL search()
             +- ...
         +-H5P find prop_plist(udata->plist2, prop->name)
         +-H5SL_search()
         +-H5P encode cb(prop, prop2)
           +-HDstrlen()
           +-HDstrcpy()
           +-prop->encode(prop->value, udata->pp, &prop_value_len)
               +- ??? // property specific
+-H5SL iterate(plist->props, H5P iterate plist pclass cb, &udata int)
  | // in this case - note that arg names have been changed
  // for clarity
  +-H5P _iterate_plist_pclass_cb(prop, name, udata_int)
     + H5SL search()
     | +- ...
     +-H5P iterate plist cb(prop, name, udata int)
        +-H5P encode cb(id, prop→name, udata)
           +-\frac{1}{2}/ see above
+-H5SL close()
  +- ...
```

Encode the indicated property list in the supplied buffer, and return the number of bytes written to buf in *nalloc. If buf is NULL, *nalloc is set to the number of bytes required in buf.

In greater detail:

H5Pencode2() calls H5I_object_verify() to obtain a pointer (plist) to the target property list, and then calls

```
H5CX set apl(&fapl id, H5P CLS FACC, H5I INVALID HID, TRUE)
```

to setup the context – in particular to make the FAPL available to the next call. This done, H5Pencode2() calls

```
H5P encode(plist, TRUE, buf, nalloc)
```

and returns the result.

Note: there appears to be no mechanism to use *nalloc to detect or prevent buffer overruns when buf is not NULL.

After some sanity checking, **H5P__encode()** tests to see if the buf parameter is NULL. If it is, it sets the local encode variable to FALSE. Otherwise, encode is TRUE. Similarly, it sets the local variable p equal to buf. p is used to point to the next location to write in buf.

If encode is TRUE, H5P__encode sets the first two bytes of buf equal to H5P_ENCODE_VERS and the type of the property list to be encoded, and updates p according. Regardless of the value of encode, the local variable encode_size (used to accumulate the number of bytes written / required in the buffer) is set to 2

It then initializes udata, an instance of H5P_enc_iter_ud_t (definition below)

as follows

```
/* Initialize user data for iteration callback */
udata.encode = encode;
udata.enc_size_ptr = &encode_size;
udata.pp = (void **)&p;
```

H5P_encode() next sets the local variable idx equal to zero and calls

```
H5P iterate plist(plist, TRUE, &idx, H5P encode cb, &udata)
```

to encode the properties in plist, After H5P__iterate_plist() returns, it sets the last byte in the buffer to zero. As mentioned above, the number of bytes either written to the buffer (if encode is TRUE) or that would be written (if encode is FALSE) is maintained in the local variable encode_size. Just before H5P__encode() returns, it sets *nalloc = encode_size.

H5P__iterate_plist() first creates the "seen" skip list that is used to track the names of properties that have already been seen in the scan of the properties.

It then initializes udata int, which is an instance of H5P iter plist ud t (definition below)

as follows:

This done, H5P iterate plist() calls

```
H5SL iterate(plist->props, H5P iterate plist cb, &udata int)
```

After this call returns, H5P__iterate_plist() tests to see if the iter_all_prop parameter is TRUE (which it is in this case). If it is, the function scans the property list(s) of the parent property list class(es) staring with plist—parent->props via the calls

```
H5SL iterate(tclass->props, H5P iterate plist pclass cb, &udata int)
```

where tclass is the parent property list class currently under scan. Note that it breaks out of this scan of the parent property list class(es) if an error is return by H5SL iterate().

Before returning, H5P__iterate_plist() sets *idx equal to *(udata_int.curr_idx) and frees the "seen" skip list.

H5SL_iterate() simply walks the skip list, calling the supplied call back function on the contents of each node until it either reaches the end of the list, or the supplied callback returns a non-zero value. In this case, it calls either

```
H5P__iterate_plist_cb(prop, name, udata_int)

Or

H5P__iterate_plist_cb(prop, name, udata_int)
```

depending on which invocation in H5P__iterate_plist() we are looking at. Here, prop is a pointer to the instance of H5P_getprop_t, and name is the name of the property pointed to by prop.

After some sanity checks, **H5P__iterate_plist_cb()** tests to see if

```
*(udata int\rightarrowcurr idx ptr) >= udata int\rightarrowprev idx
```

if it is, H5P iterate plist cb() calls:

```
ret value = (*udata int->cb func)(prop, udata int→udata)
```

or, in this case

```
ret value = H5P encode cb(prop, udata int→udata)
```

If the above test is false, or if ret_value is non-zero, H5P__iterate_plist_cb() increments *(udata_int→cur_idx_ptr) and adds name to the "seen" skip list (udata_int→seen) prior to returning.

In reading the above, recall that udata \rightarrow prev_idx is zero in this case, thus the effect is to call H5P__encode_cb() on each property in the target property list.

Finally, note that udata_int \rightarrow udata is (in this case) the instance of H5P_enc_iter_ud_t allocated on the stack of H5P encode() and initilized by that function.

If prop→encode is NULL, **H5P__encode_cb()** is a NO-OP.

Otherwise, H5P__encode_cb() calls strlen() to determine the length of the name of the supplied property. If udata >encode is TRUE, the function calls strcpy() to copy the property name into the buffer starting at udata >pp, and updates *(udata >pp) to point to the next available byte in the buffer. Regardless of the value of udata >encode, it also adds the length of property name to *(udata >enc_size_ptr).

Also regardless of the value of udata→encode, H5P__encode_cb() sets the local variable prop value len = 0, calls

(prop->encode)(prop->value, udata->pp, &prop value len)

adds prop value len to *(udata→enc size ptr) and returns.

Note: This unconditional call to prop→encode() implies that encode functions will not write to a NULL, and will update *(udata→pp) if it is not NULL Further, the decode code makes the assumption that value length is prop→size. When this is not the case, it seems that the encode and decode functions must conceal this.

Backing up a bit, **H5P__iterate_plist_pclass_cb()** first checks to see if the supplied name is in either the "seen" skip list (udata_int→seen) or the properties deleted skip list (prop→del). If it isn't, H5P__iterate_plist_pclass_cb() calls

```
ret_value = H5P__iterate_plist_cb(prop, name, udata_int)
```

and returns ret_value. See above for a discussion of H5P__iterate_plist_cb.

Multi-thread safety concerns:

```
/**
* \ingroup GPLOA
* \brief Compares two property lists or classes for equality
* \param[in] id1 First property object to be compared
* \param[in] id2 Second property object to be compared
* \return \htri_t
^{\star} \details H5Pequal() compares two property lists or classes to determine
          whether they are equal to one another.
          Either both \p id1 and \p id2 must be property lists or both
          must be classes; comparing a list to a class is an error.
* \since 1.4.0
*/
H5 DLL htri t H5Pequal(hid t id1, hid t id2);
H5Pequal()
+-H5I get type()
 | +- ...
+-H5I object()
 l +- ...
 | // parameter names have been changed for clarity
 +-H5P__cmp_plist(plist1, plist2, &cmp_ret) // if plists
 | +-H5P iterate plist(plist1, TRUE, &idx, H5P cmp plist cb, &udata)
 | +-H5SL create()
 | | +- ...
 | | // Note different callback functions in two invocations
   | | // of H5SL iterate().
   | +-H5SL iterate(plist->props, H5P iterate plist cb, &udata int)
   1 1 1
   \mid \ \mid \ \mid \ // in this case - note that arg names have been changed for clarity
      | +-H5P__iterate_plist_cb(prop, name, udata_int)
   +-H5P cmp plist cb(id, prop→name, udata)
   +-H5P_exist_plist(udata->plist2, prop->name)
   +-H5SL_search()
   +-H5P find prop plist(udata->plist2, prop->name)
  1 1
               +-\overline{\text{H5}}SL search()
                    +- ...
               +-H5P__cmp_prop(prop, prop2)
                  +-prop->cmp(prop->value, prop2->value, prop→size)
                     +- ??? // property specific
  | +-H5SL iterate(plist->props, H5P iterate plist pclass cb, &udata int)
   \mid // in this case - note that arg names have been changed for clarity
   +-H5P iterate plist pclass cb(prop, name, udata int)
            +_H5SL_search()
   +-H5P__cmp_plist_cb(id, prop→name, udata)
    +- // see above
```

```
| +-H5SL_close()
| +- ...
| +-H5P__cmp_class(plist1->pclass, plist2->pclass)
| +-strcmp()
| +-H5SL_first()
| +- ...
| +-H5SL_item()
| | +- ...
| +-H5P__cmp_prop()
| | +- // see above
| +-H5SL_next()
| +- ...
| // parameter names have been changed for clarity
+-H5P__cmp_class(pclass1, pclass2)
+- // see above
```

Compare two property list or two property list classes and return TRUE if they are identical, and FALSE otherwise.

In greater detail:

H5Pequal() first verifies that either both the supplied ids refer to property list classes, or both refer to property lists. It flags an error and returns if this is not the case.

It then calls H5I_object() to obtain pointers to both property lists or property list classes, and in passing verifies that both exist.

If both of the supplied ids refer to property lists, it calls

```
H5P cmp plist(plist1, plist2, &cmp ret)
```

sets ret value to TRUE *cpm ret = 0, and FALSE otherwise and then returns.

Alternatively, if both of the supplied ids refer to property list classes, H5Pequal() calls

```
H5P cmp_class(pclass1, pclass2)
```

and then returns TRUE if that function returns 0, and FALSE otherwise.

PROPERTY LIST CASE:

H5P__cmp_plist() first checks to see if plist1→nprops is either greater than or less than plist2→nprops, sets *cmp_ret to either +1 or -1 if this is the case and returns SUCCEED.

If the nprops fields are equal, it checks to see if plist1→class_init is either greater than or less than pclist2→class_init, again setting *cpm_ret to either +1 or -1 and returning SUCCEED if this is the case.

If neither of these tests demonstrate inequality, H5P__cmp_plist initializes udata, an instance of H5P_plist_cmp_ud_t (definition below)

as follows:

```
/* Set up iterator callback info */
udata.cmp_value = 0;
udata.plist2 = plist2;
```

This done, H5P__cmp_plist() calls

Here, idx is a local integer that is initialized to zero.

If ret_value is negative, H5P__cmp_plist() flags an error and returns. If ret_value is positive, it sets *cm_ret = udata.cmp_value. Otherwise, it calls

```
*cmp_ret = H5P__cmp_class(plist1->pclass, plist2->pclass)
```

and returns SUCCEED if cmp ret is non-zero.

Finally, if none of these tests have demonstrated inequality, it sets *cmp_ret = 0 and returns SUCCEED.

H5P__iterate_plist() is discussed in detail in the description of H5Piterate() below. Thus, only a brief outline that highlights the differences is shown here, and the reader is directed to H5Piterate() for further details.

The only significant difference between the calls to H5P__iterate_plist() here and in H5Piterate() are the call back and udata parameters, which are reflected in the initialization of udata int as shown below:

```
/* Set up iterator callback info */
udata_int.plist = plist1;
```

While these differences have no effect on the processing of H5P__iterate_plist() proper, they become key further down the calling tree.

This initialization done, H5P__iterate_plist calls:

```
ret_value = H5SL_iterate(plist1->props, H5P__iterate_plist_cb, &udata_int)
```

to scan the plist1 \rightarrow props, and, if H5SL_iterate() returns zero (indicating no differences found in this case) and if the iter_all_props parameter is TRUE (which it is in this case) it goes on to scan the property lists of the parent property list classes via (possibly) repeated calls to:

where tclass is the parent property list class currently being scanned. P5P__iterate_plist() breaks out of the scan and returns if ret_value is non-zero – which indicates (in this case) that either an error or a difference has been found.

H5SL_iterate() simply walks the skip list, calling the supplied call back function on the contents of each node until it either reaches the end of the list, or the supplied callback returns a non-zero value. In this case, it calls either

```
H5P__iterate_plist_cb(prop, name, udata_int)

or

H5P__iterate_plist_cb(prop, name, udata_int)
```

depending on which invocation in H5P__iterate_plist() we are looking at. Here, prop is a pointer to the instance of H5P_getprop_t, and name is the name of the property pointed to by prop.

H5P__iterate_plist_cb() is also discussed under H5Piterate(), and the reader is directed there for a detailed discussion. In this context, H5P iterate plist cb() simply calls:

```
ret_value = (*udata_int->cb_func)(prop, udata_int→udata)
```

or, in this case

```
ret_value = H5P__cmp_plist_cb(prop, udata_int→udata)
```

and returns ret_value. Other than maintaining the "seen" skip list, the remaining processing of the function is irrelevant to property list comparison.

H5P__cmp_plist_cb() starts by calling

```
prop2 exist = H5P exist plist(udata→plist2, prop→name)
```

to see whether plist2 contains a property of the same name as the target property.

If prop2_exist is TRUE, H5P__cmp_plist_cb() calls

```
prop2 = H5P find prop plist(udata->plist2, prop->name)
```

to obtain a pointer to the target property in plist2, and then calls

```
udata->cmp_value = H5P__cmp_prop(prop, prop2)
```

to compare the two properties. If udata→cmp_value is not zero, H5P__cmp_plist_cb() returns H5 ITER STOP.

If prop2_exist is FALSE, H5P__cmp_plist_cb() sets udata→cmp_value to 1 and again returns H5 ITER STOP.

H5P_exist_plist() first searches for the supplied property name in the deleted list (plist→del), and returns FALSE if this search is successful.

It then searches plist→props, returning TRUE if this search succeeds.

If the search of plist props fails, it searches the parent property list class(es), starting with plist props and works its way up until either the search succeeds – in which case it returns TRUE – or it runs out of parent property list classes – in which case it returns FALSE.

All searches are done via calls to H5SL search().

H5P__find_prop_plist() is essentially the same as H5P_exist_plist(), save that it returns a pointer to the target property on success, and flags an error if either the target property has been deleted or if the search fails.

H5P__cmp_prop() does a field by field comparison of the two instances of H5P_genprop_t pointed to by the prop1 and prop2 parameters. The names are compared via strcmp() and the values via the cmp call back. The function returns zero if all fields are identical, and either +1 or -1 if a difference is detected.

Backing up a bit, H5P__iterate_plist_pclass_cb() first checks to see if the supplied name is in either the "seen" skip list (udata_int→seen) or in the properties deleted skip list (prop→del). If it isn't, H5P__iterate_plist_pclass_cb() calls

```
ret_value = H5P__iterate_plist_cb(prop, name, udata_int)
```

and returns ret_value. See above for a discussion of H5P__iterate_plist_cb.

Backing up even further, **H5P__cmp_class()**, compares the supplied instances of H5P_genclass_t. If the revision fields match, the function assumes that the rest of the structures are identical, and returns zero.

Otherwise, H5P__cmp_class() does a field by field comparison of the instances of H5P_genclass_t (Note that parent fields are not compared). Names are compared via strcmp(). The contents of the property lists are compared by stepping through both property lists entry by entry, and calling H5P__cmp_prop() to compare the properties. Since skip lists sort their entries, this test appears to be correct.

H5P cmp class() returns zero if no differences are found, and either +1 or -1 otherwise.

PROPERTY LIST CLASS CASE:

The property list class case is handled by a call to H5P__cmp_class() – see above.

```
* \ingroup GPLOA
^{\star} \brief Queries whether a property name exists in a property list or
       class
* \return \htri_t
* \details H5Pexist() determines whether a property exists within a
         property list or class.
* \since 1.4.0
*/
H5 DLL htri t H5Pexist(hid t plist id, const char *name);
H5Pexist(id, name)
+-H5I_get_type()
+-H5I object()
 +-H5P exist plist()
 +-H5SL_search()
 +-H5P__exist_pclass()
  +-H5SL search()
     +- ...
```

Search for a property of the specified name in the property list or property list class associated with the supplied ID. Return TRUE if such a property exist, and FALSE otherwise.

In greater detail:

H5Pexists() first calls H5I_get_type() to verify that the supplied id refers to either a property list or a property list class. It then calls H5I_object() to get a pointer to the property list or class.

If it is property list, it calls H5P_exist_plist(plist, name) and returns the result.

If it is a property list class, it calls H5P_exist_pclass(pclass, name) and again returns the result.

H5P_exist_plist(plist, name), first searches plist → del for the target name and returns FALSE if the search succeeds.

Failing that, it searches plist→props for a property of the supplied name, and returns TRUE if the seach succeeds.

Failing that, it searches the property list classes of its parent property list class(es), starting with plist \rightarrow parent \rightarrow propes, and then works its way up the list of parents until it either finds a property of the supplied name – in which case it returns TRUE, or it runs out of parents – in which case it returns FALSE.

All searches are done via calls to H5SL_search()

H5P__exist_pclass(pclass_name) first searches pclass→props for a property of the supplied name, and returns TRUE if the search succeeds.

Failing that, it searches the property lists of its parent property list class(es), starting with pclass → parent → props, and then works its way up the list of parents until it either finds a property of the supplied name – in which case it returns TRUE, or it runs out of parents – in which case it returns FALSE.

Again, all searches are done via calls to H5SL search().

Thread safety concerns:

```
* \ingroup GPLOA
* \brief Queries the value of a property
* \plist id
* \param[in] name Name of property to query
* \param[out] value Pointer to a location to which to copy the value of
                    the property
* \return \herr_t
* \details H5Pget() retrieves a copy of the value for a property in a
           property list. If there is a \p get callback routine registered
           for this property, the copy of the value of the property will
           first be passed to that routine and any changes to the copy of
           the value will be used when returning the property value from
           this routine.
           This routine may be called for zero-sized properties with the
           \p value set to NULL. The \p get routine will be called with
           a NULL value if the callback exists.
           The property name must exist or this routine will fail.
           If the \p get callback routine returns an error, \ value will
           not be modified.
* \since 1.4.0
*/
H5_DLL herr_t H5Pget(hid_t plist_id, const char *name, void *value);
H5Pget()
+-H5I_object_verify()
 | +- ...
 +-H5P get()
    +-H5P do prop(plist, name, H5P get cb, H5P get cb, &udata)
       +-H5SL_search()
       | +- ...
       \mid // In this case, the same callback is provided for both the
       // plist op and pclass op parameters - hence simplifying the
       // call tree in this case.
       +-H5P get_cb(plist, name, prop, udata)
         +-H5MM malloc()
          +-H5MM memcpy()
          +-(*(prop->get))(plist->plist id, name, prop->size, tmp value)
```

Lookup the named property in the specified property list and copy its value into the supplied buffer.

In greater detail:

H5Pget() validates input, calls H5I_object_verify() to obtain a pointer (plist) to the supplied property, calls

```
H5P get(plist, name, value)
```

and returns success or failure depending the result.

H5P_get() is essentially a pass through. It sets udata.value = value (here, udata is an instance of H5P_prop_get_ud_t), calls

```
H5P do prop(plist, name, H5P get cb, H5P get cb, &udata)
```

and returns success or failure depending on its result.

In this context, **H5P__do_prop()** first searches plist→del to see if the target property has already been deleted – and flags an error if it has been.

It then tries to find the named property, first in plist→props via the call

```
prop = H5SL search(dst plist→props, name),
```

and if that is unsuccessful, via similar calls on the props fields of the parent property list class(es) starting with plist parent, and working its way up.

If H5P do prop() is unable to find the target property, the function returns failure.

If it succeeds, it calls

```
H5P get cb(dst plist, name, prop, udata)
```

and returns success or failure depending on whether this call succeeds or fails.

Conceptually, **H5P__get_cb()** copies the value of the target property into the supplied buffer *(udata \rightarrow value). If the property has a get callback, it calls it on this buffer before returning it to the caller.

The actual implementation is a bit more complex, as outlined below.

H5P get cb() first verifies that prop \rightarrow size > 0, and fails if this is not the case.

Note that this disagrees with the user documentation that states "This routine may be called for zero-sized properties with the value set to NULL. The get routine will be called with a NULL value if the callback exists." As H5Pget() will also fail if the value parameter is NULL, this appears to be a documentation bug (at best).

H5P__get_cb() then checks to see if prop→get is NULL.

If it is, H5P__get_cb() simply calls

```
H5MM_memcpy(udata->value, prop->value, prop->size)
```

and returns. If the get callback is defined, H5P_get_cb() duplicates prop→value and saves the duplicate's address in tmp_value. It then calls

```
(*(prop->get))(plist->plist id, name, prop->size, tmp value)
```

on the duplicate, copies *tmp_value into *value via

```
H5MM_memcpy(udata->value, tmp_value, prop->size)
```

discards *tmp_value, and returns. The comments suggest that this done to avoid corrupting prop-yalue if prop->get fails.

Multi-thread safety concerns:

```
*\ingroup GPLO
* \brief Returns the property list class identifier for a property list
* \plist id
* \return \hid_t{property list class}
 \details H5Pget class() returns the property list class identifier for
           the property list identified by the \p plist id parameter.
           Note that H5Pget class() returns a value of #hid t type, an
           internal HDF5 identifier, rather than directly returning a
           property list class. That identifier can then be used with
           either H5Pequal() or H5Pget class name() to determine which
           predefined HDF5 property list class H5Pget class() has returned.
           A full list of valid predefined property list classes appears
           in the description of H5Pcreate().
           Determining the HDF5 property list class name with H5Pequal()
           requires a series of H5Pequal() calls in an if-else sequence.
           An iterative sequence of H5Pequal() calls can compare the
           identifier returned by H5Pget class() to members of the list of
           valid property list class names. A pseudo-code snippet might
           read as follows:
           \code
           plist class id = H5Pget class (dsetA plist);
           if H5Pequal (plist_class_id, H5P_OBJECT_CREATE) = TRUE;
               [ H5P OBJECT CREATE is the property list class
               [ returned by H5Pget class.
           else if H5Pequal (plist class id, H5P DATASET CREATE) = TRUE;
               [ H5P DATASET CREATE is the property list class. ]
           else if H5Pequal (plist_class_id, H5P_DATASET_XFER) = TRUE;
               [ H5P DATASET XFER is the property list class.
               [ Continuing the iteration until a match is found. ]
           \endcode
           H5Pget_class_name() returns the property list class name directly
           as a string:
           plist class id = H5Pget class (dsetA plist);
           plist class_name = H5Pget_class_name (plist_class_id)
           \endcode
           Note that frequent use of H5Pget class name() can become a
           performance problem in a high-performance environment. The
           H5Pequal() approach is generally much faster.
* \version 1.6.0 Return type changed in this release.
 \since 1.0.0
```

```
*/
H5_DLL hid_t H5Pget_class(hid_t plist_id);

H5Pget_class(plist_id)
+-H5I_object_verify()
| +- ...
+-H5P_get_class(plist)
| +-
+-H5P__access_class(pclass, H5P_MOD_INC_REF)
| +-H5MM_xfree()
| +-H5SL_destroy()
| | +- ...
| +-H5P__access_class(par_class, H5P_MOD_DEC_CLS)
| +- // see above
+-H5I_register(H5I_GENPROP_CLS, pclass, TRUE)
| +-
+-H5P__close_class() // error cleanup
+-H5P__access_class(pclass, H5P_MOD_DEC_REF)
+- // see above
```

Return an id that maps to the property list class from which the supplied property list was derived.

In greater detail:

H5Pget_class() first calls H5I_object_verify to obtain a pointer to the target property list (plist). It then calls H5P_get_class() to obtain a pointer to the target property list's parent property list class (pclass = plist→pclass).

This done, H5Pget_class() calls **H5P__access_class(pclass, H5P_MOD_INC_REF)**. This has the effect of setting pclass—deleted back to FALSE if it was TRUE, and incrementing pclass—ref_count.

H5Pget class() then calls H5I register() to insert the property list class into the index.

Note that can result in a given property list class having multiple ids in the index. Further, if the parent property list class has been modified since plist was created, this will cause the previous version of the property list class to be inserted into the index – resulting in multiple property list classes of the same name but different structure.

This behavior is not discussed in the user documentation.

If H5I_register() fails, H5Pget_class() calls H5P__close_class(pclass) to undo the prior call to H5P__access_class().

Thread safety concerns:

```
* \ingroup GPLOA
* \brief Retrieves the name of a class
* \plistcls id{pclass id}
^{\star} \return Returns a pointer to an allocated string containing the class
       name if successful, and NULL if not successful.
^{\star} \details H5Pget class name() retrieves the name of a generic property
        list class. The pointer to the name must be freed by the user
        with a call to H5free memory() after each successful call.
        Class Name (class identifier) Returned
         Property List Class
         Expanded Name of the Property List Class
         The Class Identifier Used with H5Pcreate
         Comments
         \langle t.r \rangle
         attribute create
         acpl
         Attribute Creation Property List
         H5P ATTRIBUTE CREATE

        dataset access
         dapl
         Dataset Access Property List
         H5P DATASET ACCESS

         dataset create
         dcpl
         Dataset Creation Property List
         H5P DATASET CREATE

         data transfer
         dxpl
         Data Transfer Property List
         H5P_DATASET_XFER

         datatype access

         H5P DATATYPE ACCESS
         This class can be created, but there are no properties
             in the class currently.
         datatype create
```

```
H5P DATATYPE CREATE
This class can be created, but there
   are no properties in the class currently.
file access
fapl
File Access Property List
H5P FILE ACCESS

>
file create
fcpl
File Creation Property List
H5P FILE CREATE

file mount
fmpl
File Mount Property List
H5P FILE MOUNT

>
group access

H5P GROUP ACCESS
This class can be created, but there
   are no properties in the class currently.
group create
gcpl
Group Creation Property List
H5P GROUP CREATE

>
 link access
 lapl
 Link Access Property List
 H5P LINK ACCESS
 \langle td \rangle \langle /\overline{t}d \rangle
link create
lcpl
Link Creation Property List
H5P_LINK_CREATE
\langle td \rangle \langle \overline{t}d \rangle
<t.r>
object copy
ocpypl
Object Copy Property List
H5P OBJECT COPY
```

```
object create
        ocpl
        Object Creation Property List
        H5P OBJECT CREATE

        string create
         strcpl
         String Creation Property List
        H5P_STRING_CREATE
        * \since 1.4.0
*/
H5 DLL char *H5Pget class name(hid t pclass id);
H5Pget_class_name(pclass_id)
+-H5I_object_verify()
| +- ...
+-H5P get class name (pclass)
  +-H5MM xstrdup(pclass->name)
```

Look up the indicated property list class, allocate a string of appropriate length, copy the class's name into the new string, and return a pointer to it.

In greater detail:

Later

```
* \ingroup GPLOA
* \brief Retrieves the parent class of a property class
* \plistcls id{pclass id}
* \return \hid_t{parent class object}
* \details H5Pget class parent() retrieves an identifier for the parent
          class of a property class.
* \since 1.4.0
H5 DLL hid t H5Pget class parent (hid t pclass id);
H5Pget class parent (pclass id)
+-H5I_object_verify()
+-H5P get class parent(pclass)
+-H5P access_class(parent, H5P_MOD_INC_REF)
 | +-H5MM xfree()
 | +-H5SL_destroy()
 | +-H5P access class(par class, H5P MOD DEC CLS)
      +- // see above
 +-H5I register (H5I GENPROP CLS, pclass, TRUE)
 | +-
 +-H5P__close_class() // error cleanup
   +-H5P__access_class(pclass, H5P_MOD_DEC_REF)
      +- // see above
```

Return an id that maps to the property list class from which the supplied property list class was derived.

In greater detail:

H5Pget_class_parent() first calls H5I_object_verify to obtain a pointer to the target property list class (pclass). It then calls H5P_get_class_parent() to obtain a pointer to the target property list class's parent property list class (parent = pclass→parent).

This done, H5Pget_class_parent() calls H5P__access_class(parent, H5P_MOD_INC_REF). This has the effect of setting parent→deleted back to FALSE if it was TRUE, and incrementing parent→ref_count.

H5Pget_class() then calls H5I_register() to insert the parent property list class into the index.

Note that can result in a given property list class having multiple ids in the index. Further, if the parent property list class has been modified since pclass was created, this will cause the previous version of the property list class to be inserted into the index – resulting in multiple property list classes of the same name but different structure.

This behavior is not discussed in the user documentation.

If H5I_register() fails, H5Pget_classparent() calls H5P__close_class(pclass) to undo the prior call to H5P__access_class().

Thread safety concerns:

```
* \ingroup GPLOA
 \brief Queries the number of properties in a property list or class
* \param[in] id Identifier for property object to query
* \param[out] nprops Number of properties in object
* \return \herr_t
* \details H5Pget nprops() retrieves the number of properties in a
          property list or property list class.
          If \p id is a property list identifier, the current number of
          properties in the list is returned in \p nprops.
          If \p id is a property list class identifier, the number of
          registered properties in the class is returned in \p nprops.
* \since 1.4.0
*/
H5_DLL herr_t H5Pget_nprops(hid_t id, size_t *nprops);
H5Pget_nprops()
+-H5I_get_type()
+-H5I object()
 +-H5P get nprops plist(plist, nprops)
 +-H5P_get_nprops_pclass(pclass, nprops, FALSE)
```

Given the id of a property list or a property list class, return the number of properties in same. In the case of property list classes, this is just the number of properties defined in the target property list class, and does not include properties defined in its parents.

In greater detail:

After verifying that the supplied id refers to either a property list, or a property list class, and that the target property list or property list class actually exists, **H5Pget_nprops()** first calls either H5P__get_nprops_plist() or H5P_get_nprops_pclass() to obtain the number of properties in the target, and returns this value in *nprops.

H5P__get_nprops_plist() simply sets *nprops = plist→nprops and returns.

If its "recurse" parameter is FALSE (as it is in this case) **H5P_get_nprops_pclass()** also just sets *nprops = pclass -> nprops. However, if "recurse" is TRUE, it also walks the list of parent of pclass, and returns the sum of the nprops fields of pclass and all of its parents.

Thread safety concerns:

```
* \ingroup GPLOA
* \brief Queries the size of a property value in bytes
* \param[in] id Identifier of property object to query
* \param[in] name Name of property to query
* \param[out] size Size of property in bytes
* \return \herr_t
* \details H5Pget size() retrieves the size of a property's value in
          bytes. This function operates on both property lists and
           property classes.
           Zero-sized properties are allowed and return 0.
* \since 1.4.0
*/
H5 DLL herr t H5Pget size(hid t id, const char *name, size t *size);
H5Pget size()
+-H5I_get_type(id)
 | +- ...
+-H5I_get_object(id)
 +-H5P__get_size_plist(plist, name, size)
 +-\overline{H5P} find prop plist(plist, name)
      +-H5SL_search()
 +-H5P__get_size_pclass(pclass, name, size)
   +-H5P find prop pclass (pclass, name)
       +-H5SL search()
          +- ...
```

Look up the named property in the property list or property list class associated with the supplied id, and return the size of the value of the property in *size.

In greater detail:

After verifying that the supplied id refers to either a property list class or a property list, **H5Pget_size()** verifies that the target property list class or property list exists, and then calls either

```
H5P__get_size_plist(plist, name, size)

or

H5P__get_size_plist(plist, name, size)
```

to load the size of the target properties value in *size, and returns.

H5P get_size_plist() calls

```
prop = H5P find prop plist(plist, name)
```

to obtain a pointer to the target property. If this is successful, it sets *size = prop→size and returns.

H5P__find_prop_plist() first searches the deleted list (prop→del) for the supplied name, and flags an error and returns if the search is successful.

Failing that, it searches plist→props for a property of the supplied name, and returns a pointer to the target instance of H5P genprop t if the search succeeds.

Failing that, it searches the property lists of its parent property list class(es), starting with plist \rightarrow parent \rightarrow props, and then up the list of parents until it either finds a property of the supplied name – in which case it returns a pointer to the target instance of H5P_genprop_t, or it runs out of parents – in which case it returns NULL and flags an error.

All searches are done via calls to H5SL search()

H5P__get_size_pclass() calls

```
prop = H5P find prop pclass(pclass, name)
```

to obtain a pointer to the target property. If this is successful, it sets *size = prop→size and returns.

H5P__find_prop_pclass() searches its property list (pclass→props) via a call to H5SL_search() for a property of the supplied name, and returns a pointer to the target instance of H5P_genprop_t if successful. If the search fails, it flags an error and returns NULL.

Note that H5P__find_prop_pclass() does not search the property lists of its parent property list class(es) for the target property if it doesn't exist in pclass→props. This makes H5Pset_size() incongruent with similar calls and is probably a bug.

```
* \ingroup GPLOA
 \brief Registers a temporary property with a property list
* \plist id
* \param[in] name
                    Name of property to create
* \param[in] size
                  Size of property in bytes
* \param[in] value Initial value for the property
* \param[in] set
                    Callback routine called before a new value is copied
                    into the property's value
* \param[in] get
                    Callback routine called when a property value is
                    retrieved from the property
* \param[in] prp del Callback routine called when a property is deleted
                    from a property list
* \param[in] copy
                    Callback routine called when a property is copied
                    from an existing property list
* \param[in] compare Callback routine called when a property is compared
                    with another property list
* \param[in] close
                    Callback routine called when a property list is
                    being closed and the property value will be disposed
* \return \herr_t
 \details H5Pinsert2() creates a new property in a property
          list. The property will exist only in this property list and
          copies made from it.
          The initial property value must be provided in \p value and
          the property value will be set accordingly.
          The name of the property must not already exist in this list,
          or this routine will fail.
          The \p set and \p get callback routines may be set to NULL
          if they are not needed.
          Zero-sized properties are allowed and do not store any data
          in the property list. The default value of a zero-size
          property may be set to NULL. They may be used to indicate the
          presence or absence of a particular piece of information.
          The \p set routine is called before a new value is copied
          into the property. The #H5P prp set func t callback function
          is defined as follows:
          \snippet this H5P prp cb2 t snip
          The parameters to the callback function are defined as follows:
          >
            \ref hid t \c prop id
            IN: The identifier of the property list being
                modified
           >
            \Code{const char * name}
            IN: The name of the property being modified
           >
            \Code{size t size}
```

```
IN: The size of the property in bytes
\Code{void * value}
  IN: Pointer to new value pointer for the property
      being modified
The \p set routine may modify the value pointer to be set and
those changes will be used when setting the property's value.
If the \p set routine returns a negative value, the new property
value is not copied into the property and the \p set routine
returns an error value. The \p set routine will be called for
the initial value.
\b Note: The \p set callback function may be useful to range
check the value being set for the property or may perform some
transformation or translation of the value set. The \p get
callback would then reverse the transformation or translation.
A single \p get or \p set callback could handle multiple
properties by performing different actions based on the
property name or other properties in the property list.
The \p get routine is called when a value is retrieved from
a property value. The #H5P prp get func t callback function
is defined as follows:
\snippet this H5P prp cb2 t snip
The parameters to the above callback function are:
<t.r>
 \ref hid_t \c prop_id
 IN: The identifier of the property list being queried
 >
 \Code{const char * name}
 IN: The name of the property being queried
 </t.r>
\langle t.r \rangle
 \Code{size t size}
 In: The size of the property in bytes
\Code{void * value}
 IN: The value of the property being returned
The \p get routine may modify the value to be returned from
the query and those changes will be preserved. If the \p get
routine returns a negative value, the query routine returns
an error value.
The \p prp del routine is called when a property is being
deleted from a property list. The #H5P prp delete func t
callback function is defined as follows:
\snippet this H5P prp cb2 t snip
The parameters to the above callback function are:
```

```
>
 \ref hid t \c prop id
 In: The identifier of the property list the property is
     being deleted from
 >
 \Code{const char * name}
 IN: The name of the property in the list
 \langle t.r \rangle
 \Code{size t size}
 In: The size of the property in bytes
 \Code{void * value}
 IN: The value for the property being deleted
 </t.r>
The \p prp_del routine may modify the value passed in, but the
value is not used by the library when the \protect\operatorname{prp\_del} routine
returns. If the \p prp del routine returns a negative value,
the property list \p prp del routine returns an error value but
the property is still deleted.
The \p copy routine is called when a new property list with
this property is being created through a \p copy operation.
The #H5P prp copy func t callback function is defined as follows:
\snippet this H5P prp cb1 t snip
The parameters to the above callback function are:
\Code{const char * name}
 IN: The name of the property being copied
 \langle t.r \rangle
 \Code{size t size}
 IN: The size of the property in bytes
 \Code{void * value}
 IN/OUT: The value for the property being copied
 The \p copy routine may modify the value to be set and those
changes will be stored as the new value of the property. If the
\p copy routine returns a negative value, the new property value
is not copied into the property and the copy routine returns an
error value.
The \p compare routine is called when a property list with this
property is compared to another property list with the same
property.
The #H5P prp compare func t callback function is defined as
follows:
```

```
\snippet this H5P_prp_compare_func_t_snip
         The parameters to the callback function are defined as follows:
         \Code{const void * value1}
           IN: The value of the first property to compare
           \Code{const void * value2}
           IN: The value of the second property to compare
          \Code{size t size}
           IN: The size of the property in bytes
          The \p compare routine may not modify the values. The \p compare
         routine should return a positive value if \p value1 is greater
         than \p value2, a negative value if \p value2 is greater than
          \p value1 and zero if \p value1 and \p value2 are equal.
         The \p close routine is called when a property list with this
         property is being closed.
         The #H5P_prp_close_func_t callback function is defined as follows:
         \snippet this H5P prp cb1 t snip
         The parameters to the callback function are defined as follows:
         \Code{const char * name}
           IN: The name of the property in the list
          >
           \Code{size t size}
           IN: The size of the property in bytes
          <t.r>
           \Code{void * value}
           IN: The value for the property being closed
          The \p close routine may modify the value passed in, the
         value is not used by the library when the close routine
         returns. If the \p close routine returns a negative value,
         the property list \p close routine returns an error value
         but the property list is still closed.
         \b Note: There is no \p create callback routine for temporary
         property list objects; the initial value is assumed to
         have any necessary setup already performed on it.
* \since 1.8.0
H5 DLL herr t H5Pinsert2(hid t plist id, const char *name, size t size,
                      void *value, H5P_prp_set_func_t prp_set,
                      H5P_prp_get_func_t prp_get,
```

```
H5P prp_delete_func_t prp_del,
                            H5P prp copy func t prp copy,
                            H5P prp compare func t prp cmp,
                           H5P prp close func t prp close);
H5Pinsert2(plist id, name, size, value, prp set, prp get, prp del, prp copy,
          prp cmp, prp close)
+-H5I_object_verify()
 | +- ...
 +-H5P insert(plist, name, size, value, prp_set, prp_get, NULL, NULL,
              prp delete, prp copy, prp cmp, prp close)
    +-H5SL search()
    | +- ...
    +-H5SL_remove()
    | +- ...
    +-H5MM xfree()
    +-H5P create prop()
    +-\overline{\text{H5}}\text{FL MALLOC}()
    +-H5MM xstrdup()
    +-H5MM malloc()
    | +-H5MM_memcpy()
    | +-H5MM_xfree() // error cleanup
| +-H5FL_FREE() // error cleanup
    +-H5P__add_prop()
+-H5P__add_prop()
    | +-H5SL insert()
         +- ...
    +-H5P__free_prop() // error cleanup
        +-H5MM xfree()
        +-H5FL FREE()
```

Create a property as specified by the supplied parameters and insert it in the target property list.

In greater detail:

H5Pinsert2() calls H5I_object_verify() to obtain a pointer (plist) to the target property list. After some sanity checking, it then calls

```
H5P_insert(plist, name, size, value, prp_set, prp_get, NULL, NULL, prp_delete, prp_copy, prp_cmp, prp_close)
```

and returns whatever H5P insert() returns.

H5P insert() proceeds as follows:

• Search plist props for name. If this search is successful, a property of the supplied name already exists. In this case, H5P insert() flags an error and returns.

 Search the deleted list (plist→del) for the supplied name. If it is found, remove it from the deleted list.

If the supplied name doesn't appear in the deleted list, search the parent property list class(es) for the supplied name. If it is found, a property of the supplied name already exists. In this case as well, H5P insert() flags an error and returns.

• Create the new property via the call:

After some sanity checks, **H5P__create_prop()** allocates a new instance of H5P_genprop_t (new_prop), duplicates *name and sets new_prop→name to point to it. Similarly, if value is not NULL, it duplicates *value, and sets new_prop→value to point to the copy.

It initializes the remaining fields of *new prop from its parameters as follows:

```
new_prop⇒shared_name = FALSE

new_prop⇒size = size;

new_prop⇒create = H5P_PROP_WITHIN_LIST;

new_prop⇒create = NULL;

new_prop⇒set = prp_set;

new_prop⇒encode = prp_encode;

new_prop⇒decode = prp_decode;

new_prop⇒del = prp_delete;

new_prop⇒copy = prp_copy;

new_prop⇒chose = prp_close;
```

If prp cmp is NULL, new prop→cmp is set to &memcmp.

• Insert the new property in plist via the call

```
H5P add prop(plist->props, new prop)
```

Increment plist→nprops.

And then return. In the event of error, H5P_insert() tests for the existence of *new_prop and discards it if found prior to return.

```
/**
* \ingroup GPLOA
* \brief Determines whether a property list is a member of a class
* \plist id
* \plistcls_id{pclass_id}
* \return \htri t
* \details H5Pisa class() checks to determine whether the property list
           \p plist id is a member of the property list class
           \p pclass id.
* \see H5Pcreate()
* \since 1.6.0
*/
H5 DLL htri t H5Pisa class(hid t plist id, hid t pclass id);
H5Pisa class(plist id, pclass id)
+-H5I get type()
 | +- ...
+-H5P isa_class(plist_id, pclass_id)
   +-H5I_object_verify()
    | // pclass1 == plist→pclass, pclass2 == pclass
    +-H5P class isa(pclass1, pclass2)
      +-H5P cmp class(pclass1, pclass2)
       | +-strcmp()
       | +-H5SL first()
       | | +- ...
       +-H5SL item()
       | +- ...
         +-H5P cmp prop(prop1, prop2)
       | | +-prop->cmp(prop1->value, prop2->value, prop1→size)
         | +- ??? // property specific
         +-H5SL next()
            +- ...
       +-H5P class isa(pclass1->parent, pclass2)
          +- // recursive call - see above
```

Determine whether the the supplied property list is a member of the supplied property list class.

Note: Here "member" appears to mean that plist_id refers to a property list that is an instance of the property list class referred to by pclass_id **OR** that the immediate parent property list class of the supplied property list is a descendant of the supplied property list class. While this is standard OOP terminology, it may be asking a bit much of our users to know this. Assuming

that this interpretation is retained, this point should be made clear in the user level documentation.

In more detail:

H5Pisa_class() verifies that plist_id and pclass_id refer to a property list and a property list class respectively, calls:

```
H5P_isa_class(plist_id, pclass_id)
```

and returns whatever that function returns.

H5P_isa_class() calls H5I_object_verify() to obtain pointers (plist and pclass2) to the supplied property list and property class. To make the following discussion easier to follow, define pclass1 = plist→pclass.

Finally, H5P_isa_class() calls

```
H5P_class_isa(pclass1, pclass2)
```

and returns whatever that function returns. In what follows, keep in mind that H5P_isa_class() and H5P_class_isa() are two very different functions, and that pclass1 is the parent property list class of the supplied property list, and that pclass2 is the property list class supplied by the user.

H5P_class_isa(pclass1, pclass2) first calls

```
H5P__cmp_class(pclass1, pclass2)
```

and returns TRUE if H5P__cmp_class() returns 0. For any other return value, H5P_class_isa() sets pclass1 = pclass1→parent. If pclass1 is NULL, H5P_class_isa() returns FALSE. Otherwise, H5P_class_isa() makes the recursive call:

```
H5P class isa(pclass1, pclass2)
```

and returns whatever the recursive call returns. The effect of this recursive call is to compare all the property list classes from which pclass1 is derived to pclass2 and return TRUE if and only if one of these property list classes is identical to pclass2.

H5P__cmp_class(), compares the supplied instances of H5P_genclass_t. If the revision fields match, the function assumes that the rest of the structures are identical, and returns zero.

Otherwise, H5P__cmp_class() does a field by field comparison of the instances of H5P_genclass_t (Note that parent fields are not compared). Names are compared via strcmp(). The contents of the property lists are compared by stepping through both property lists entry

by entry, and calling H5P__cmp_prop() to compare the properties. Since skip lists sort their entries, this test appears to be correct.

H5P__cmp_class() returns zero if no differences are found, and either +1 or -1 otherwise.

H5P__cmp_prop() does a field by field comparison of the two instances of H5P_genprop_t pointed to by the prop1 and prop2 parameters. The names are compared via strcmp() and the values via the cmp call back. The function returns zero if all fields are identical, and either +1 or -1 if a difference is detected.

```
* \ingroup GPLOA
* \brief Iterates over properties in a property class or list
               id Identifier of property object to iterate over
* \param[in,out] idx Index of the property to begin with
* \param[in]
                iter func Function pointer to function to be called
                with each property iterated over
* \param[in,out] iter_data Pointer to iteration data from user
* \return On success: the return value of the last call to \p iter func if
         it was non-zero; zero if all properties have been processed.
         On Failure, a negative value
* \details H5Piterate() iterates over the properties in the property
          object specified in \p id, which may be either a property
          list or a property class, performing a specified operation
          on each property in turn.
          For each property in the object, \p iter func and the
          additional information specified below are passed to the
          #H5P iterate t operator function.
          The iteration begins with the \p idx-th property in the
          object; the next element to be processed by the operator
          is returned in \p idx. If \p idx is NULL, the iterator
          starts at the first property; since no stopping point is
          returned in this case, the iterator cannot be restarted if
          one of the calls to its operator returns non-zero.
          The operation \p iter func receives the property list or class
          identifier for the object being iterated over, \p id, the
          name of the current property within the object, \p name,
          and the pointer to the operator data passed in to H5Piterate(),
          \p iter data.
          H5Piterate() assumes that the properties in the object
          identified by \p id remain unchanged through the iteration.
          If the membership changes during the iteration, the function's
          behavior is undefined.
* \since 1.4.0
* /
H5 DLL int H5Piterate(hid t id, int *idx, H5P iterate t iter func,
                     void *iter_data);
H5Piterate(id, idx, iter func, iter data)
 +-H5I_get_type(id)
 | +- ...
+-H5I object(id)
 | +- ...
 | // iter func and iter data stored in udata
 +-H5P iterate plist((H5P genplist t *)obj, TRUE, idx, H5P iterate cb, &udata)
 | +-H5SL create()
 | +- ...
```

```
| +-H5SL iterate(plist->props, H5P iterate plist cb, &udata int)
| | // in this case - note that arg names have been changed for clarity
| | +-H5P iterate plist cb(prop, name, udata)
       +-H5P iterate cb(prop, iter data)
| +-*iter func(id, prop→name, iter data) // user supplied function
       +-H5SL_insert()
| +-H5SL_iterate(plist->props, H5P__iterate_plist_pclass_cb, &udata_int)
| // in this case - note that arg names have been changed for clarity
     +-H5P iterate plist pclass cb(prop, name, udata)
        +_H5SL search()
  | +- ...
  +-H5P iterate_plist_cb(prop, name, udata)
  +-H5P__iterate_cb(prop, iter_data)
 +-*iter_func(id, prop→name, iter_data) // user supplied function
                +- ...
           +-H5SL_insert()
  +-H5SL close()
+-H5P iterate pclass(pclass, idx, H5P iterate cb, &udata)
  +-H5SL iterate(pclass->props, H5P iterate pclass cb, &udata int)
  \mid \mid \mid // in this case - note that arg names have been changed for clarity
     +-H5P__iterate_pclass_cb(prop, name, udata)
+-*iter_func(prop, iter_data) // user supplied function
           +- ...
  +-H5SL close()
```

Starting with the *idx'th property, scan the target property list or property list class and call the supplied iter_fcn with the id of the property list or property list class, the name of the property, and the supplied user data.

In greater detail:

After verifying that the supplied id exists, and references either a property list class or a property list, **H5Piterate()** initializes an instance of H5P iter ud t (definition shown below):

```
typedef struct {
   H5P_iterate_t iter_func; /* Iterator callback */
   hid_t id; /* Property list or class ID */
   void * iter_data; /* Iterator callback pointer */
} H5P iter ud t;
```

(udata) as follows:

```
udata.iter_func = iter_func;
udata.id = id;
udata.iter data = iter data;
```

With udata initialized, H5Piterate() calls either

if id refers to a property list, or

if id refers to a property list class. Note that fake_idx is an integer that is initialized to zero. It allows the function to handle a NULL idx pointer gracefully.

In either case, H5Piterate() returns whatever value is returned.

THE PROPERTY LIST CASE:

H5P__iterate_plist() first creates the "seen" skip list that is used to track the names of properties that have already been seen in the scan of the properties. It then initializes udata int, which is an instance of H5P iter plist ud t (definition below)

as follows:

This done, H5P__iterate_plist() calls

```
H5SL iterate(plist->props, H5P iterate plist cb, &udata int)
```

After this call returns, H5P__iterate_plist() tests to see if the iter_all_prop parameter is TRUE (which it is in this case). If it is, the function scans the property list(s) of the parent property list class(es) staring with plist—parent->props via the calls

```
H5SL_iterate(tclass->props, H5P__iterate_plist_pclass_cb, &udata_int)
```

where tclass is the parent property list class currently under scan. Note that it breaks out of this scan of the parent property list class(es) if an error is return by H5SL iterate().

Before returning, H5P__iterate_plist() sets *idx equal to *(udata_int.curr_idx) and frees the "seen" skip list.

H5SL_iterate() simply walks the skip list, calling the supplied call back function on the contents of each node until it either reaches the end of the list, or the supplied callback returns a non-zero value. In this case, it calls either

```
H5P__iterate_plist_cb(prop, name, udata_int)

Or

H5P__iterate_plist_cb(prop, name, udata_int)
```

depending on which invocation in H5P__iterate_plist() we are looking at. Here, prop is a pointer to the instance of H5P_getprop_t, and name is the name of the property pointed to by prop.

After some sanity checks, H5P__iterate_plist_cb() tests to see if

```
*(udata_int→curr_idx_ptr) >= udata_int→prev_idx
```

if it is, H5P iterate plist cb() calls:

```
ret value = (*udata int->cb func)(prop, udata int→udata)
```

or, in this case

```
ret value = H5P iterate cb(prop, udata int→udata)
```

If the above test is false, or if ret_value is non-zero, H5P__iterate_plist_cb() increments *(udata_int→cur_idx_ptr) and adds name to the "seen" skip list (udata_int→seen) prior to returning.

In reading the above, recall that udata → prev_idx is either the starting index passed into H5Piterate() in *idx, or 0 if idx was NULL, and that udata int → cur idx ptr points to a local

variable in H5Piterate that was initialized to zero. Thus the initial test has the effect of skipping over the first udata int-prev idx items.

Further, note that udata_int→udata is (in this case) the instance of H5P_iter_ud_t allocated on the stack of H5Piterate() and initilized by that function.

H5P__iterate_cb() simply calls the user supplied function

```
ret_value = (*udata->iter_func)(udata->id, prop->name, udata->iter_data)
```

where udata iter_func, and udata iter_data are the iter_func and iter_data parameters passed to H5Piterate, and udata is both the id of the property list within which *prop resides, and also the id parameter passed to H5Piterate().

H5P__iterate_cb() returns ret_value unconditionally.

Backing up a bit, H5P__iterate_plist_pclass_cb() first checks to see if the supplied name is in either the "seen" skip list (udata_int→seen) or the properties deleted skip list (prop→del). If it isn't, H5P__iterate_plist_pclass_cb() calls

```
ret_value = H5P__iterate_plist_cb(prop, name, udata_int)
```

and returns ret value. See above for a discussion of H5P iterate plist cb.

THE PROPERTY LIST CLASS CASE:

H5P__iterate_pclass() is similar to H5P_iterate_plist(), but simpler.

It does not create the "seen" skip list, as only the properties of the target property list class are scaned, and thus the "seen" list is not necessary. It does initialize udata_int (an instance of H5P iter plist ud t) as follows:

```
/* Set up iterator callback info */
udata_int.cb_func = cb_func; // H5P__iterate_cb() in this case
udata_int.udata = udata; // the udata initialized by H5Piterate()
udata_int.curr_idx_ptr = &curr_idx; // curr_idx is a local integer
udata int.prev idx = *idx;
```

It then calls

```
ret_value = H5SL_iterate(pclass->props, H5P__iterate_pclass_cb, &udata_int);
```

H5P iterate pclass() returns ret value after setting *idx = *(udata int.cur idx ptr).

As discussed above, **H5SL_iterate()** simply walks the skip list, and calls the supplied call back function on the contents of each node until it either reaches the end of the list, or the supplied function returns a non-zero value. In this case, it calls:

```
H5P__iterate_pclass_cb(prop, name, udata_int)
```

Here, prop is a pointer to the instance of H5P_getprop_t, and name is the name of the property pointed to by prop.

Likewise, H5P__iterate_pclass_cb() is similar to H5P__iterate_plist_cb(), only simpler.

As per H5P__iterate_plist_cb(), H5p__iterate_pclass_cb() tests to see if

```
*(udata_int->curr_idx_ptr) >= udata_int->prev_idx
```

and calls:

```
ret value = (*udata int->cb func)(prop, udata int→udata)
```

if it is. Since udata int→cb func == H5P iterate cb() this case, the call is really:

```
ret value = H5P iterate cb(prop, udata int→udata)
```

If ret value isn't zero, H5P iterate plist() returns ret value immediately.

Otherwise, H5P__iterate_plist_cb() increments *(udata_int→curr_idx_ptr) before returning ret_value.

As discussed at the end of the PROPERTY LIST CASE above, **H5P__iterate_cb()** simply calls the user supplied function

```
ret value = (*udata->iter func)(udata->id, prop->name, udata->iter data)
```

where udata→iter_func, and udata→iter_data are the iter_func and iter_data parameters passed to H5Piterate, and udata→id is both the id of the property list within which *prop resides, and also the id parameter passed to H5Piterate().

```
* \ingroup GPLOA
 \brief Registers a permanent property with a property list class
* \plistcls id{cls id}
* \param[in] name
                       Name of property to register
 \param[in] size
                       Size of property in bytes
* \param[in] def value Default value for property in newly created
                       property lists
* \param[in] create
                       Callback routine called when a property list is
                       being created and the property value will be
                       initialized
* \param[in] set
                       Callback routine called before a new value is
                       copied into the property's value
* \param[in] get
                       Callback routine called when a property value is
                       retrieved from the property
* \param[in] prp_del
                       Callback routine called when a property is deleted
                       from a property list
* \param[in] copy
                       Callback routine called when a property is copied
                       from a property list
* \param[in] compare
                       Callback routine called when a property is compared
                       with another property list
* \param[in] close
                       Callback routine called when a property list is
                       being closed and the property value will be
                       disposed of
* \return \herr t
* \details H5Pregister2() registers a new property with a property list
           class. The \p cls_id identifier can be obtained by calling
           H5Pcreate_class(). The property will exist in all property
          list objects of \p cl_id created after this routine finishes. The
           name of the property must not already exist, or this routine
           will fail. The default property value must be provided and all
           new property lists created with this property will have the
           property value set to the default value. Any of the callback
           routines may be set to NULL if they are not needed.
           Zero-sized properties are allowed and do not store any data in
          the property list. These may be used as flags to indicate the
          presence or absence of a particular piece of information. The
           default pointer for a zero-sized property may be set to NULL.
          The property \p create and \p close callbacks are called for
           zero-sized properties, but the \p set and \p get callbacks are
          never called.
           The \protect\ p create routine is called when a new property list with
           this property is being created. The #H5P prp create func t
           callback function is defined as follows:
           \snippet this H5P prp cb1 t snip
           The parameters to this callback function are defined as follows:
           \Code{const char * name}
            IN: The name of the property being modified
           >
            \Code{size t size}
```

```
IN: The size of the property in bytes
\Code{void * value}
 IN/OUT: The default value for the property being created,
    which will be passed to H5Pregister2()
The \p create routine may modify the value to be set and those
changes will be stored as the initial value of the property.
If the \p create routine returns a negative value, the new
property value is not copied into the property and the
\p create routine returns an error value.
The \p set routine is called before a new value is copied into
the property. The #H5P prp set func t callback function is defined
as follows:
\snippet this H5P prp cb2 t snip
The parameters to this callback function are defined as follows:
\langle t.r \rangle
 \ref hid t \c prop id
 IN: The identifier of the property list being modified
\Code{const char * name}
 IN: The name of the property being modified
\Code{size t size}
 IN: The size of the property in bytes
>
 \Code{void *value}
 IN/OUT: Pointer to new value pointer for the property
     being modified
The \p set routine may modify the value pointer to be set and
those changes will be used when setting the property's value.
If the \p set routine returns a negative value, the new property
value is not copied into the property and the \p set routine
returns an error value. The \p set routine will not be called
for the initial value; only the \p create routine will be called.
\b Note: The \p set callback function may be useful to range
check the value being set for the property or may perform some
transformation or translation of the value set. The \p get
callback would then reverse the transformation or translation.
A single \p get or \p set callback could handle multiple
properties by performing different actions based on the property
name or other properties in the property list.
The \p get routine is called when a value is retrieved from a
property value. The #H5P prp get func t callback function is
defined as follows:
\snippet this H5P_prp_cb2_t_snip
```

The parameters to the callback function are defined as follows: $\ref hid t \c prop id$ IN: The identifier of the property list being queried > \Code{const char * name} IN: The name of the property being queried $\langle t.r \rangle$ \Code{size t size} IN: The size of the property in bytes \Code{void * value} IN/OUT: The value of the property being returned The \p get routine may modify the value to be returned from the query and those changes will be returned to the calling routine. If the \p set routine returns a negative value, the query routine returns an error value. The \p prp del routine is called when a property is being deleted from a property list. The #H5P prp delete func t callback function is defined as follows: \snippet this H5P prp cb2 t snip The parameters to the callback function are defined as follows: > $\ref hid t \c prop id$ In: The identifier of the property list the property is being deleted from > \Code{const char * name} IN: The name of the property in the list \Code{size t size} In: The size of the property in bytes $\langle t.r \rangle$ \Code{void * value} IN: The value for the property being deleted The \p prp del routine may modify the value passed in, but the value is not used by the library when the \p prp del routine returns. If the \p prp del routine returns a negative value, the property list delete routine returns an error value but the property is still deleted. The \p copy routine is called when a new property list with

```
this property is being created through a \p copy operation.
The #H5P prp copy func t callback function is defined as follows:
\snippet this H5P_prp_cb1_t_snip
The parameters to the callback function are defined as follows:
\Code{const char * name}
 IN: The name of the property being copied
 >
 \Code{size t size}
 In: The size of the property in bytes
\Code{void * value}
 IN/OUT: The value for the property being copied
The \p copy routine may modify the value to be set and those
changes will be stored as the new value of the property. If
the \p copy routine returns a negative value, the new
property value is not copied into the property and the \p copy
routine returns an error value.
The \p compare routine is called when a property list with this
property is compared to another property list with the same
property. The #H5P prp compare func t callback function is
defined as follows:
\snippet this H5P prp compare func t snip
The parameters to the callback function are defined as follows:
\Code{const void * value1}
 IN: The value of the first property to compare
</t.r>
>
 \Code{const void * value2}
 In: The value of the second property to compare
\Code{size t size}
 In: The size of the property in bytes
The \p compare routine may not modify the values. The \p compare
routine should return a positive value if \p value1 is greater
than \p value2, a negative value if \p value2 is greater than
\p value1 and zero if \p value1 and \p value2 are equal.
The \p close routine is called when a property list with this
property is being closed. The #H5P prp close func t callback
function is defined as follows:
\snippet this H5P_prp_cb1_t_snip
```

```
The parameters to the callback function are defined as follows:
         <t.r>
           \Code{const char * name}
           IN: The name of the property in the list
          \Code{size t size}
           IN: The size of the property in bytes
          \langle t.r \rangle
           \Code{void * value}
           IN: The value for the property being closed
          The \p close routine may modify the value passed in, but the
         value is not used by the library when the \protect\operatorname{p} close routine returns.
         If the \p close routine returns a negative value, the property
         list close routine returns an error value but the property list is
         still closed.
* \since 1.8.0
H5_DLL herr_t H5Pregister2(hid_t cls_id, const char *name, size_t size,
                        void *def value, H5P_prp_create_func_t create,
                        H5P prp set func t set, H5P prp get func t get,
                        H5P prp delete func_t prp_del,
                        H5P prp copy func t copy,
                        H5P prp compare func t compare,
                        H5P prp close func t close);
H5Pregister2(cls id, name, size, def value, create, set, get, prp del,
           copy, compare, close)
+-H5I_object_verify()
| +- ...
+-H5P register()
| | // duplicate class if required
| +-H5P create class()
| +-H5FL CALLOC()
| +-H5MM xstrdup()
| +-H5SL create()
| | +- ...
| | +-H5P access class(par class, H5P MOD INC CLS)
| | + \overline{\text{H5}MM}_x \text{free}()
| | +- ...
     +-H5MM xfree() // error cleanup
   +-H5SL destroy()
   +- ... // eventually
   H5P free prop cb()
+-(tprop->close)(tprop->name, tprop->size, tprop->value);
             | +- ... // property specific - may not exist
+-H5P free_prop(tprop);
1 1
                +-H5MM xfree()
+-H5FL_FREE()
1 1
```

```
| +-H5SL_first()
| | +- ...
| +-H5P dup prop(prop, H5P PROP WITHIN LIST)
| +-H5FL MALLOC()
| | +-H5MM_xfree() // error cleanup
| | +-H5FL_FREE() // error cleanup
 +-H5P add prop()
| +-H5SL insert()
     +- ...
 +-H5SL_next()
| | +- ...
| +-H5P register real()
| | +- ...
| | +-H5P create prop()
| +-H5P close_class() // error recovery
   +-H5P access class(pclass, H5P MOD DEC REF)
     +-H5MM xfree()
     +-H5SL destroy()
     | +- ...
     +-H5P access class(par class, H5P MOD DEC CLS)
       +- ... // see abpve
+-H5I subst()
| +- ...
+-H5P__close_class()
+- // see above
```

Insert a new property in a property list class.

If the target class has any directly derived property lists or property list classes, this will result in duplication of the target property list, with the duplicate (with the new property added) replacing the old version in the index.

In greater detail:

H5Pregister2(cls_id, name, size, def_value, prp_create, prp_set, prp_get, prp_delete, prp_copy, prp_cmp, prp_close) first calls H5I_object_verify(cls_id) to obtain a pointer to the target property list class (pclass).

After some sanity checks, it saves a copy of pclass in original pclass, and then calls:

H5P__register() is discussed at great length in the "PROPERTY LIST CLASS CASE" of the section on H5Pcopy prop(), and the reader is referred there for details.

For purposes of this discussion, perhaps the following summary will suffice.

The objective of H5P__register() is to insert the new property into the target property list class. However, if there are any extant property lists, or property list classes directly derived from dst_pclass, it must duplicate the supplied property list class, insert the new property into the duplicate, and set *pclass to point to the modified duplicate. The duplicate later replaces the earlier version of *pclass in the index. The original version of *pclass is then is only accessible via the parent pointers in its derived property lists and property list classes. It is retained until both its plists (number of derived property lists) and classes (number of derived property list classes) fields drop to zero – at which point it is discarded.

After H5P__register() returns, H5Pregister() compares pclass with orig_pclass – the copy it made just before calling H5P__register(). If the two don't match, it must replace orig_pclass with pclass in the index. It does this with the call

```
H5I_subst(cls_id, pclass)
```

and then calls

```
H5P close class(orig pclass)
```

which decrements old_dst_pclass -> ref_count, and may delete it. See discussion in H5Pclose_class() above for further details.

```
/**
* \ingroup GPLOA
 \brief Removes a property from a property list
* \plist id
* \param[in] name Name of property to remove
* \return \herr_t
^{\star} \details H5Premove() removes a property from a property list. Both
           properties which were in existence when the property list was
           created (i.e. properties registered with H5Pregister()) and
           properties added to the list after it was created (i.e. added
           with H5Pinsert1() may be removed from a property list.
           Properties do not need to be removed from a property list
           before the list itself is closed; they will be released
           automatically when H5Pclose() is called.
           If a \p close callback exists for the removed property, it
           will be called before the property is released.
* \since 1.4.0
H5 DLL herr t H5Premove(hid t plist id, const char *name);
H5Premove()
+-H5I object verify()
 | +- ...
 +-H5P remove()
    +-\overline{\text{H5P}} do prop(plist, name, H5P del plist cb, H5P del pclass cb, NULL)
       +-H5SL_search(plist->del, name)
       +-(*plist op)(plist, name, prop, udata)
       | H5P__del_plist_cb() // in this case
       +-(*(prop->del))(plist->plist_id, name, prop->size, prop->value)
         // property specific call - different for each property
         +-H5MM xstrdup(name)
         +-H5SL insert()
        | + ...
         +-H5P free_prop()
            +-H5MM xfree()
             +-H5FL FREE()
       +-(*pclass op)(plist, name, prop, udata)
         H5P__del_pclass_cb() // in this case
          +-H5MM malloc()
          +-H5MM memcpy()
          +-(*(prop->del))(plist->plist_id, name, prop->size, tmp_value)
          // property specific call - different for each property
          +-H5MM xstrdup()
          +-H5SL insert()
            +- ...
```

Remove a property from a property list.

In greater detail:

H5Premove() looks up the supplied property list id to obtain a pointer (plist) to it. It then calls H5P_remove(plist, name) to remove the named property from plist, and returns whatever that function returns.

H5P_remove() simply calls

```
H5P_do_prop(plist, name, H5P_del_plist_cb, H5P_del_pclass_cb, NULL)
```

and returns whatever that call returns.

H5P__do_prop() first searches plist→del to see if the target property has already been deleted, and fails if it has.

It then searches plist→props for the target property. If it finds it, it stores its address in prop, calls

```
H5P del plist cb(plist, name, prop, NULL)
```

and returns success or failure depending on whether this call succeeds or fails.

If the search of plist props fails, H5P_do_prop() searches the property lists of the parent property list class(es) for the target property, starting with plist property, and working its way up until it either finds the target property, or it runs out of parent property list classes. If this search is successful, it stores a pointer to the target property in prop, calls

```
H5P del pclass cb(plist, name, prop, NULL)
```

and returns success or failure depending on whether this call succeeds or fails. If the search of the parent property list class(es) fails, H5P__do_prop() returns failure.

H5P__del_plist_cb() calls the properties delete callback

```
(*(prop->del))(plist->plist_id, name, prop->size, prop→value)
```

if it exists, duplicates the property name string and inserts it into the plist \rightarrow del skip list, deletes the property from the plist \rightarrow props skip list, frees it, and decrements plist \rightarrow nprops.

H5P__del_pclass_cb() is similar to H5P__del_plist_cb() but subtly different.

Like H5P__del_plist_cb() it calls the properties delete callback if it exists. However, before it does so, it duplicates *(prop->value), and passes a pointer to this duplicate as the final parameter to the properties delete callback. After that, it duplicates the property name string and inserts it into the plist->del skip list, and decrements plist->nprops. Note, however, that since the target property is not in the plist->props skip list, it doesn't attempt to remove it.

```
* \ingroup GPLOA
* \brief Sets a property list value
* \plist id
* \param[in] name Name of property to modify
* \param[in] value Pointer to value to set the property to
* \return \herr_t
* \details H5Pset() sets a new value for a property in a property list.
           If there is a \p set callback routine registered for this
           property, the \p value will be passed to that routine and any
           changes to the \p value will be used when setting the property
           value. The information pointed to by the \p value pointer
           (possibly modified by the \p set callback) is copied into the
           property list value and may be changed by the application
           making the H5Pset() call without affecting the property value.
           The property name must exist or this routine will fail.
           If the \p set callback routine returns an error, the property
           value will not be modified.
           This routine may not be called for zero-sized properties and
           will return an error in that case.
* \since 1.4.0
* /
H5 DLL herr t H5Pset(hid t plist_id, const char *name, const void *value);
H5Pset(plist id, name, value)
+-H5I object verify(plist id)
 | +- ...
 +-H5P set(plist, name, value)
    +-H5P do prop(plist, name, H5P set plist cb, H5P set pclass cb, &udata)
       +-H5SL_search()
       | +- ...
       +-(*plist op)(plist, name, prop, udata)
       | | | | | in this case
       | H5P set plist cb(plist, name, prop, udata)
         +-H5MM malloc()
         +-H5MM memcopy()
         +-(*(prop→set))(plist→plist id, name, prop→size, tmp value)
            +- // property specific
         | // if prop→del != NULL
         +-(*(prop→del)(plist→plist-id, name, prop→size, prop→value)
         | +- // property specific
         +-H5MM xfree()
       +-(*pclass op)(plist, name, prop, udata)
         || // in this case
         H5P set pclass cb(plist, name, prop, udata)
         +-H5MM malloc()
          +-H5MM memcpy()
          +-(*(prop→set))(plist→plist id, name, prop→size, tmp value)
          | +- // property specific
```

```
+-H5P__dup_prop(prop, H5P_PROP_WITHIN_LIST)
| +-H5FL_MALLOC()
| +-H5MM_memcpy()
| +-H5MM_xstrdup()
| +-H5MM_xfree() // error cleanup
| +-H5FL_FREE() // error cleanup
+-H5P__add_prop()
| +-H5SL_insert()
| +- ...
+-H5MM_xfree()
+-H5P__free_prop() // error cleanup
+-H5MM_xfree()
+-H5FL_FREE()
```

In a nutshell:

Set the value of an existing property in a property list.

In greater detail:

After some sanity checking, **H5Pset()** calls H5I_object_verify() to obtain a pointer to the target property list, calls:

```
H5P_set(plist, name, value)
```

and returns.

H5P_set() allocates an instance of H5P prop set ud t (definition below) on its stack

```
/* Typedef for property list set/poke callbacks */
typedef struct {
   const void *value; /* Pointer to value to set */
} H5P prop set ud t;
```

and initializes it as follows:

```
udata.value = value
```

It then calls

```
H5P_do_prop(plist, name, H5P_set_plist_cb, H5P_set_pclass_cb, &udata)
```

and returns.

H5P__do_prop() first searches plist→del to see if the target property has already been deleted, and fails if it has.

It then searches plist→props for the target property. If it finds it, it stores its address in prop, calls (in this case)

```
H5P set plist cb(plist, name, prop, udata)
```

and returns success or failure depending on whether this call succeeds or fails.

If the search of plist props fails, H5P_do_prop() searches the property lists of the parent property list class(es) for the target property, starting with plist property, and working its way up until it either finds the target property, or it runs out of parent property list classes. If this search is successful, it stores a pointer to the target property in prop, calls (in this case)

```
H5P set pclass cb(plist, name, prop, NULL)
```

and returns success or failure depending on whether this call succeeds or fails. If the search of the parent property list class(es) fails, H5P do prop() returns failure.

If prop→set is not NULL, **H5P__set_plist_cb()** allocates a buffer of size prop→size, stores its address in tmp_value, memcpy's udata→value into *tmp_value, calls

```
(*(prop->set))(plist->plist id, name, prop->size, tmp value)
```

and then set prp value = tmp value.

If prop→set is NULL, it just sets prp value = udata→value.

This done, H5P set plist cb() test to see if prop→del is not NULL, and if so, calls

```
(*(prop->del))(plist->plist id, name, prop->size, prop->value)
```

Finally, it memcpy's prp_value into prop→value, and frees the buffer pointed to by tmp_value (if it exists) before returning.

Note the implication that the del callback doesn't free prop→value.

H5P__set_pclass_cb() starts by setting up prp_value as per H5P__set_plist_cb() above.

It then calls

```
pcopy = H5P__dup_prop(prop, H5P_PROP_WITHIN_LIST)
```

Here, **H5P__dup_prop()** allocates a new instance of H5P_genprop_t (pcopy), copies the image of *prop into it, and (if prop->shared_name is FALSE), duplicates the string pointed to by prop->name and stored its address in pcopy->name. It then duplicates the buffer pointed to by prop->value (if it exists) storing the address of the duplicate in pcopy->value, and returns the address of the new instance of H5P_genprop_t.

This done, H5P__set_pclass_cb() memccpy's prp_value into pcopy→value, and calls

```
H5P__add_prop(plist->props, pcopy)
```

which inserts pcopy into the skip list pointed to by plist props via a call to H5SL_insert().

Finally, H5P__set_pclass_db() deletes *tmp_value if it has been allocated, and returns. On error, it discards *pcopy via a call to H5P__free_prop() if it was created prior to the failure.

Multi-Thread safety concerns:

```
* \ingroup GPLOA
* \brief Removes a property from a property list class
* \plistcls id{pclass id}
* \param[in] name Name of property to remove
* \return \herr_t
* \details H5Punregister() removes a property from a property list class.
           Future property lists created of that class will not contain
           this property; existing property lists containing this property
           are not affected.
* \since 1.4.0
*/
H5_DLL herr_t H5Punregister(hid_t pclass_id, const char *name);
H5Punregister()
+-H5I object verify()
 | +- ...
+-H5P unregister()
   +-H5SL_search()
    | +- ...
    +-H5SL remove()
    | +- ...
+-H5P__free_prop()
      +-H5MM xfree()
       +-H5FL FREE()
```

In a nutshell:

Delete a property from the specified property list class.

According to the user documentation, this should have no effect on existing property lists – however examination of the code suggests otherwise. See detailed discussion below.

In greater detail:

H5Punregister() looks up the supplied property list class id to obtain a pointer (pclass) to it. It then calls H5P_unregister(pclass, name) to remove the named property from pclass, and returns whatever that function returns.

H5P unregister() calls

```
prop = H5SL search(pclass->props, name)
```

to obtain a pointer to the target property, calls

```
H5SL remove (pclass->props, prop→name)
```

to remove it from pclass → props, calls

```
H5P free prop(prop)
```

to free it, decrements pclass \rightarrow nprops, sets pclass->revision equal to the global variable H5P next rev, increments H5P next rev, and returns.

Note: While H5Punregister removes a property from a property list class, decrements its nprops field, and assigns a new unique revision number, it does not duplicate the property list class, apply these changes to the duplicate, and then replace the original version with the new modified version in the index as per H5P__register() (see discussion of H5Pcopy_prop() above).

This has two problematic effects:

First, the version number seen by property lists previously derived from the starting version of the property list class changes. This may or may not be an issue, but it should be noted.

Second, if the target property doesn't have a create callback, and a derived property list class never changes its value, the call to H5Punregister has the effect of removing the target property from all such property lists without decrementing the associated nprops field – recall that such properties are not copied into the property list but are instead read from the parent property list class(es) if accessed (see H5Pcreate() above).

This second issue is much more serious, as not only is it at odds with the documented behavior of the function, it also corrupts the property list data structure. I presume that this is a bug.

Multi-thread safety concerns:

Appendix 2 – H5P internal API calls

In addition to its public API, H5P also has a private API providing property list services to the HDF5 library. For the most part, these calls are similar to their cognates in the public API – but there are some differences, and also some calls which offer additional capabilities.

Since the objective of this exercise is make H5P multi-thread safe so it can be safely called by multiple threads in multi-thread safe VOL connectors, at first glance, the internal H5P API is not relevant to this effort. However, the internal H5P API is used by other packages – including some that are necessary to support multi-thread VOL connectors.

H5Iprivate.h is reproduced below, with annotations to some of the internal API calls and the some of the package initialization calls. Most entries are annotated with a reference to the relevant public API call. Those with no public API cognate have more extensive annotations or no annotation at all for calls specific to particular property lists. Annotations to the initialization calls are a work in progress.

```
* Copyright by The HDF Group.
 * Copyright by the Board of Trustees of the University of Illinois.
* All rights reserved.
* This file is part of HDF5. The full HDF5 copyright notice, including
* terms governing use, modification, and redistribution, is contained in
* the COPYING file, which can be found at the root of the source code
* distribution tree, or in https://www.hdfgroup.org/licenses.
* If you do not have access to either file, you may request a copy from
* help@hdfgroup.org.
 * This file contains private information about the H5P module
#ifndef H5Pprivate H
#define H5Pprivate H
/* Early typedefs to avoid circular dependencies */
typedef struct H5P genplist t H5P genplist t;
/* Include package's public header */
#include "H5Ppublic.h"
/* Private headers needed by this file */
#include "H5private.h" /* Generic Functions
/*********/
/* Library Private Macros */
/*********
/* ====== String creation property names ====== */
#define H5P STRCRT CHAR ENCODING NAME "character encoding" /* Character set encoding
for string */
/* If the module using this macro is allowed access to the private variables, access
them directly */
```

```
#ifdef H5P MODULE
#define H5P PLIST ID(P) ((P)->plist id)
#define H5P CLASS(P)
                        ((P)->pclass)
#else /* H5P MODULE */
#define H5P PLIST_ID(P) (H5P_get_plist_id(P))
#define H5P CLASS(P) (H5P get class(P))
\#endif /* H\overline{5}P MODULE */
#define H5 COLL MD READ FLAG NAME "collective metadata read"
/**********
/* Library Private Typedefs */
/***********
typedef enum H5P_coll_md_read_flag_t {
   H5P FORCE FALSE = -1,
    H5P USER FALSE = 0,
    H5P USER TRUE = 1
} H5P coll md read flag t;
/* Forward declarations for anonymous H5P objects */
typedef struct H5P genclass t H5P genclass t;
typedef enum H5P plist type t {
   H5P TYPE USER
   H5P TYPE ROOT
   H5P TYPE OBJECT CREATE = 2,
   H5P_TYPE_OBUECT_CREATE = 3,
H5P_TYPE_FILE_CREATE = 3,
H5P_TYPE_FILE_ACCESS = 4,
   H5P TYPE DATASET CREATE = 5,
   H5P TYPE DATASET ACCESS = 6,
   H5P TYPE DATASET XFER = 7,
   H5P_TYPE FILE MOUNT
                             = 8,
                            = 9,
= 10,
   H5P TYPE GROUP CREATE
   H5P_TYPE_GROUP_ACCESS
   H5P_TYPE_DATATYPE_CREATE = 11,
   H5P\_TYPE\_DATATYPE\_ACCESS = 12,
   H5P_TYPE_STRING_CREATE = 13,
H5P_TYPE_ATTRIBUTE_CREATE = 14,
   H5P TYPE OBJECT COPY
                           = 15,
   H5P TYPE LINK CREATE
                              = 16,
                           = 17,
   H5P TYPE LINK ACCESS
   H5P TYPE ATTRIBUTE ACCESS = 18,
   H5P TYPE VOL INITIALIZE = 19,
   H5P_TYPE_MAP_CREATE = 20,
H5P_TYPE_MAP_ACCESS = 21,
    H5P TYPE REFERENCE ACCESS = 22,
    H5P TYPE MAX TYPE
} H5P plist type t;
/* Function pointer for library classes with properties to register */
typedef herr t (*H5P reg prop func t)(H5P genclass t *pclass);
^{\star} Each library property list class has a variable of this type that contains
 ^{\star} class variables and methods used to initialize the class.
typedef struct H5P libclass t {
                    name; \overline{/}* Class name */
   const char *
   H5P plist type t type; /* Class type */
    H5P genclass_t ** par_pclass; /* Pointer to global parent class
                                           property list class */
```

```
/* Pointer to global property list class */
     H5P genclass t **
                             pclass;
     hid t *const
                                                /* Pointer to global property list class
                             class id;
                                                   ID */
                                                /* Pointer to global default property
     hid t *const
                             def plist id;
                                                    list ID */
     H5P reg prop func t reg prop func; /* Register class's properties */
     /* Class callback function pointers & info */
     H5P_cls_create_func_t create_func; /* Function to call when a property
                                                    list is created */
                                create data; /* Pointer to user data to pass along
     void *
                                                   to create callback */
                                                /* Function to call when a property list
                                copy func;
     H5P cls copy func t
                                                   is copied */
                                                /\star Pointer to user data to pass along
     void *
                                copy data;
                                                   to copy callback */
                                               /* Function to call when a property list
     H5P cls close func t close func;
                                                   is closed */
                                               /* Pointer to user data to pass along
     void *
                                close data;
                                                    to close callback */
} H5P_libclass_t;
/*********/
/* Library Private Variables */
/*************************/
/* Predefined property list classes. */
H5 DLLVAR H5P genclass t *H5P CLS ROOT g;
H5 DLLVAR H5P genclass t *H5P CLS OBJECT CREATE q;
H5 DLLVAR H5P genclass t *H5P CLS FILE CREATE g;
H5 DLLVAR H5P genclass t *H5P CLS FILE ACCESS g;
H5 DLLVAR H5P genclass t *H5P CLS DATASET CREATE g;
H5 DLLVAR H5P genclass t *H5P CLS DATASET ACCESS g;
H5 DLLVAR H5P genclass t *H5P CLS DATASET XFER g;
H5_DLLVAR H5P_genclass_t *H5P_CLS_FILE_MOUNT_g;
H5 DLLVAR H5P genclass t *H5P CLS GROUP CREATE g;
H5 DLLVAR H5P genclass t *H5P CLS GROUP ACCESS g;
H5 DLLVAR H5P genclass t *H5P CLS DATATYPE CREATE g;
H5 DLLVAR H5P genclass t *H5P CLS DATATYPE ACCESS g;
H5 DLLVAR H5P genclass t *H5P CLS MAP CREATE g;
H5 DLLVAR H5P genclass t *H5P CLS MAP ACCESS g;
H5_DLLVAR H5P_genclass_t *H5P_CLS_ATTRIBUTE CREATE g;
H5 DLLVAR H5P genclass t *H5P CLS ATTRIBUTE ACCESS g;
H5 DLLVAR H5P genclass t *H5P CLS OBJECT COPY g;
H5 DLLVAR H5P genclass t *H5P CLS LINK CREATE q;
H5 DLLVAR H5P genclass t *H5P CLS LINK ACCESS g;
H5 DLLVAR H5P genclass t *H5P CLS STRING CREATE g;
/* Internal property list classes */
H5_DLLVAR const struct H5P_libclass_t H5P_CLS_LCRT[1]; /* Link creation */
H5_DLLVAR const struct H5P_libclass_t H5P_CLS_LACC[1]; /* Link access */
H5_DLLVAR const struct H5P_libclass_t H5P_CLS_AACC[1]; /* Attribute access */
H5_DLLVAR const struct H5P_libclass_t H5P_CLS_DACC[1]; /* Dataset access */
H5_DLLVAR const struct H5P_libclass_t H5P_CLS_GACC[1]; /* Group access */
H5_DLLVAR const struct H5P_libclass_t H5P_CLS_TACC[1]; /* Named datatype access */
H5_DLLVAR const struct H5P_libclass_t H5P_CLS_MACC[1]; /* Map access */
H5 DLLVAR const struct H5P_libclass_t H5P_CLS_FACC[1]; /* File access */
H5 DLLVAR const struct H5P libclass t H5P CLS OCPY[1]; /* Object copy */
/**********
/* Library Private Prototypes */
/*********
```

```
/* Forward declaration of structs used below */
struct H50 fill t;
struct H5T t;
struct H5VL connector prop t;
/* Package initialization routines */
H5_DLL herr_t H5P_init_phase1(void);
H5_DLL herr_t H5P_init_phase2(void);
H5P init phase1()
+-H5I register type()
| +- ...
+-H5P create_class()
| +-H5FL CALLOC()
+-H5MM xstrdup()
| +-H5SL create()
| | +- ...
+-H5P access class(par class, H5P MOD INC CLS)
| | +- ...
  | +-H5P_access_class(par_class, H5P_MOD_DEC_CLS) // not in this case
   + ...
  +-H5MM xfree() // error cleanup
  +-H5SL destroy()
     +- ... // eventually
          H5P _free_prop_cb()
           +-(tprop->close)(tprop->name, tprop->size, tprop->value);
           | +- ... // property specific - may not exist
           +-H5P free prop(tprop);
             +-H5MM xfree()
             +-H5FL FREE()
+-(*lib class→reg prop func)(*lib class→pclass)
| +- ... // varies
+-H5I_register(H5I_GENPROP_CLS, *lib_class->pclass, FALSE)
| +- ...
+-H5P create id(*lib class->pclass, FALSE)
| +-H5P create()
| +-H5SL_item()
  | | +- ...
   | +-H5SL search()
  | | +- ...
  | +-H5P do prop cb1(plist->props, tmp, tmp->create)
  +-\overline{\text{H5}}\text{MM} malloc()
| | +-cb(prop->name, prop->size, tmp value) // cb == tmp->create
 | | +-H5P dup prop(prop, H5P PROP WITHIN LIST)
 +- ...
        | | +-H5MM_xfree () // error cleanup
```

```
| | +-H5P free prop()
 | | +- ...
 | | +- ...
  | +-H5P_access_class(plist->pclass, H5P_MOD_INC_LST)
| // in this case, increment the plist count in the pclass
 | +-H5S
 0
 | | +-H5SL_destroy() // error cleanup
 | | +- ...
 | | +-H5SL_close() // error cleanup
 | | +- ...
 | | +-H5FL_FREE() // error cleanup
 | +-H5I register()
 | | +- ...
 | +-(tclass->create_func)(plist_id, tclass->create_data) // class specific,
                                                      // may not exist
 +-H5I_remove() // error cleanup only
 | | +- ...
 | +-H5P close() // error cleanup only
      +- // see H5Pclose() above
+-H5I clear_type() // error cleanup only
 | +- ...
 +-H5I_dec_ref() // error cleanup only
 | +- ...
 +-H5P close class() // error cleanup only
   +- // see H5Pclose class()
H5P_init_phase2()
+-H5P__facc_set_def_driver()
   +-HDgetenv (HDF5_DRIVER)
   +-H5FD is driver registered by name()
   +-H5I inc ref()
   +-H5P__facc_set_def_driver_check_predefined(driver_env_var, &driver_id)
   +-H5FD_register_driver_by_name(driver_env_var, TRUE)
   +-H5I object()
   | +- ...
   +-H5P_class_set(def_fapclass, H5F_ACS_FILE_DRV_NAME, &driver prop)
   | +-
   +-H5P_set_driver(def_fapl, driver_prop.driver_id, driver_prop.driver_info,
   driver prop.driver config str)
   +-H5I_dec_app_ref(driver_id) // error cleanup
     +- ...
```

H5P init phase1() starts by creating the indexes for property list classes and property lists:

```
H5I_register_type(H5I_GENPROPCLS_CLS)
H5I register type(H5I_GENPROPLST_CLS)
```

The next step is to create the various property list classes used by the HDF5 library, populate their property lists setting default values in passing, and then create the default property lists. The data required to create the property list classes is stored in init_class[] – an array of pointers to constant instances of H5P_libclass_t, whose definition is reproduced below for convenience:

```
typedef struct H5P_libclass_t {
                   name; \overline{/}* Class name */
    const char *
    H5P_plist_type_t type; /* Class type */
    H5P genclass t ** par pclass;
                                      /* Pointer to global parent
                                          class property list class */
                                       /* Pointer to global property
    H5P genclass t **
                       pclass;
                                          list class */
    hid t *const
                                       /* Pointer to global property
                        class id;
                                           list class ID */
    hid t *const
                        def plist id; /* Pointer to global default
                                           property list ID ^{\star}/
    H5P reg prop func t reg prop func; /* Register class's
                                           properties */
    /* Class callback function pointers & info */
    H5P cls create func_t create_func; /* Function to call when a
                                           property list is created */
    void *
                          create data; /* Pointer to user data to pass
                                          along to create callback */
                                      /* Function to call when a
    H5P cls copy func t
                          copy func;
                                          property list is copied */
                          copy data; /* Pointer to user data to pass
    void *
                                          along to copy callback */
    H5P cls close func t close func; /* Function to call when a
                          property list is closed */
close_data; /* Pointer to user data to pass
                                           along to close callback */
} H5P libclass t;
```

init_class[] is initialized as follows:

```
/* List of all property list classes in the library */
/* (order here is not important, they will be initialized in the proper
      order according to their parent class dependencies)
static H5P_libclass_t const *const init_class[] = {
  H5P_CLS_ROOT, /* Root */
                  /* Object create */
  H5P CLS OCRT,
  H5P CLS STRCRT, /* String create */
  H5P_CLS_LACC, /* Link access */
                  /* Group create */
  H5P CLS GCRT,
  H5P CLS OCPY,
                 /* Object copy */
  H5P CLS GACC,
                 /* Group access */
                 /* File creation */
  H5P CLS FCRT,
                 /* File access */
  H5P CLS FACC,
  H5P CLS DCRT,
                 /* Dataset creation */
  H5P_CLS_DACC,
                 /* Dataset access */
  H5P_CLS_DXFR, /* Data transfer */
  H5P_CLS_FMNT, /* File mount */
H5P_CLS_TCRT, /* Datatype creation */
```

```
H5P_CLS_TACC, /* Datatype access */
H5P_CLS_MCRT, /* Map creation */
H5P_CLS_MACC, /* Map access */
H5P_CLS_ACRT, /* Attribute creation */
H5P_CLS_ACC, /* Attribute access */
H5P_CLS_LCRT, /* Link creation */
H5P_CLS_VINI, /* VOL initialization */
H5P_CLS_RACC /* Reference access */
};
```

The individual entries in the array are mostly initialized in H5Pint.c. Note that the instances of H5P_libclass_t contain references to values that are not known until run time. This is handled by initializing fields to point to global variables that are initialized at run time. The following initialization of H5P CLS FACC gives an example of this.

```
/* File access property list class library initialization object */
const H5P_libclass_t H5P_CLS FACC[1] = {{
 "file access",
                /* Class name for debugging */
 H5P TYPE FILE ACCESS, /* Class type
                                                */
 &H5P CLS ROOT g,
                           /* Parent class
 &H5P CLS FILE ACCESS g, /* Pointer to class
 &H5P CLS FILE ACCESS ID g, /* Pointer to class ID
 &H5P LST FILE ACCESS ID g, /* Pointer to default property list ID */
 H5P facc reg prop,
                         /* Default property registration routine */
 NULL, /* Class creation callback */
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
 NULL, /* Class copy callback info */
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

With the background, we can now discuss the actual initialization.

At the conceptual level, H5P_init_phase1() scans each entry in the init_class[] array. If the property list class and default property list described by this entry is uninitialized, it checks to see if all prerequisites for initialization are met, and if so, creates the indicated property list class and default property list. It repeats this scan until there is no activity for a full scan of of init_class[], verifies that the required number of initializations have occurred, and returns.

Let lib_class be a pointer to the element of init_class[] currently under examination in the above scan. Proceed as follows for each such entry before going on to the next:

If *lib_class→class_id is not equal -1, the indicated property list class has been initialized. Go on to the next entry in the scan.

Similarly, if lib_class → par_pclass is not NULL, and *lib_class → par_pclass is, the parent property list class hasn't been created yet. Go on to the next entry in the scan.

If lib_class \rightarrow par_pclass is NULL (i.e. this is the root property list class) or *lib_class->par_pclass is not NULL (i.e. the parent class has been initiaized), create the indicated property list class as follows:

Call:

```
*lib_class->pclass = H5P__create_class(par_pclass,
lib_class->name,
lib_class->type,
lib_class->create_func,
lib_class->create_data,
lib_class->copy_func,
lib_class->copy_data,
lib_class->close_func,
lib_class->close_data)
```

where par_class = NULL if lib_class → par_pclass is NULL, and *lib_class → par_pclass otherwise, This call creates the indicated property list class, but does not populate it beyond the properties inherited from its parent class. See H5Pcopy() above for further details on H5P__create_class().

Next, if lib class → reg prop func is not NULL, call:

```
(*lib_class->reg_prop_func) (*lib_class->pclass)
```

To create the properties specific to the new property list class, and insert them.

Once the new property list class is created, it is registered via the call:

```
*lib_class->class_id = H5I_register(H5I_GENPROP_CLS, *lib_class->pclass, FALSE)
```

Finally, check to see if the default property list of the new class already exists, and create it if not via the call:

```
*lib_class->def_plist_id = H5P_create_id(*lib_class->pclass, FALSE)
```

All this done, go on to the next entry in the scan.

```
/* Internal versions of API routines */
H5 DLL herr t H5P close(H5P genplist t *plist);
**** See H5Pclose() ****
H5 DLL hid t H5P create id(H5P genclass t *pclass, hbool t app ref);
**** See H5Pcreate() *****
H5 DLL hid t H5P copy plist(const H5P genplist t *old plist, hbool t app ref);
**** See H5Pcopv() ****
H5 DLL herr t H5P get(H5P genplist t *plist, const char *name, void *value);
**** See H5Pget() ****
H5 DLL herr t H5P set(H5P genplist t *plist, const char *name, const void *value);
**** See H5Pset() ****
H5_DLL herr_t H5P_peek(H5P_genplist_t *plist, const char *name, void *value);
H5P peek(plist, name, value)
| // udata.value = value
+-H5P do prop(plist, name, H5P peek cb, H5P peek cb, &udata)
   +-H5SL search()
    \mid // In this case, the same callback is provided for both the
    // plist_op and pclass_op parameters - hence simplifying the
    // call tree in this case.
   +-H5P peek cb(plist, name, prop, udata)
      +-H5MM memcpy()
```

Similar to H5P_get() – the main difference is that H5P_peek_cb simply memcpy()s prop \rightarrow value into the supplied value buffer instead of calling prop \rightarrow copy() for this purpose.

```
H5_DLL herr_t H5P_poke(H5P_genplist_t *plist, const char *name, const void *value);

**** See H5Pdecode() ****

H5_DLL herr_t H5P_insert(H5P_genplist_t *plist, const char *name, size_t size, void *value, H5P_prp_set_func_t prp_set, H5P_prp_get_func_t prp_get, H5P_prp_encode_func_t prp_encode, H5P_prp_decode_func_t prp_decode, H5P_prp_delete_func_t prp_delete, H5P_prp_copy_func_t prp_copy,
```

```
H5P_prp_compare_func_t prp_cmp,
                         H5P prp close func t prp close);
**** See H5Pinsert2() ****
H5 DLL herr t H5P remove(H5P genplist t *plist, const char *name);
**** See H5Premove() ****
H5 DLL htri t H5P exist plist(const H5P genplist t *plist, const char *name);
**** See H5Pexist() ****
H5 DLL htri t H5P class isa(const H5P genclass t *pclass1,
                             const H5P genclass t *pclass2);
**** See H5Pisa class() ****
H5 DLL char * H5P get class name(H5P genclass t *pclass);
**** See H5Pget class name() ****
/* Internal helper routines */
H5 DLL herr t
               H5P_get_nprops_pclass(const H5P_genclass_t *pclass,
                                          size t *nprops, hbool t recurse);
**** See H5Pget nprops() ****
// only used in H5P.c and H5Pint.c - make it a package function?
H5 DLL hid t
                   H5P peek driver(H5P genplist t *plist);
// used in H5FD, and H5F
H5 DLL const void *H5P peek driver info(H5P genplist t *plist);
// used in H5FD
H5 DLL const char *H5P peek driver config str(H5P genplist t *plist);
// used in H5FD, and H5F
                   H5P_set_driver(H5P_genplist_t *plist, hid_t new_driver_id,
H5 DLL herr t
                                   const void *new_driver_info,
const char *new_driver_config_str);
// used in H5FD
H5 DLL herr t
                  H5P_set_driver_by_name(H5P_genplist_t *plist,
                                           const char *driver name,
                                           const char *driver config,
                                           hbool_t app_ref);
```

```
// Only in 5Pfapl.c
H5 DLL herr t
                  H5P set driver by value (H5P genplist t *plist,
                                             H5FD class value t driver value,
                                             const char *driver_config,
                                             hbool t app ref);
// Used in H5FD
                   H5P set vol(H5P genplist t *plist, hid t vol id,
H5 DLL herr t
                                const void *vol info);
// used in H5VL
H5 DLL herr t H5P reset vol class(const H5P genclass t *pclass,
                                   const struct H5VL_connector_prop_t *vol_prop);
// Used in H5VL
H5 DLL herr t H5P set vlen mem manager(H5P genplist t *plist,
                                        H5MM_allocate_t alloc_func,
                                         void *alloc info,
                                         H5MM_free_t free_func, void *free_info);
// Used in H5D
H5 DLL herr t H5P is fill value defined (const struct H5O fill t *fill,
                                          H5D_fill_value_t *status);
// Used in H5D and H50
H5 DLL int
              H5P fill value cmp(const void *value1, const void *value2,
                                  size t size);
// Used in H5D
H5_DLL herr_t H5P_modify_filter(H5P genplist t *plist, H5Z filter t filter,
                                 unsigned flags, size t cd nelmts,
                                 const unsigned cd_values[]);
// Used in H5Z
H5_DLL herr_t H5P_get_filter_by_id(H5P_genplist_t *plist, H5Z_filter_t id, unsigned int *flags, size_t *cd_nelmts,
                                    unsigned cd_values[], size_t namelen,
                                    char name[], unsigned *filter_config);
// Used in H5Z
H5 DLL htri t H5P filter in pline(H5P genplist t *plist, H5Z filter t id);
// Used in H5Z
```

```
/* Query internal fields of the property list struct */
H5 DLL hid t H5P get plist id(const H5P genplist t *plist);
// Doesn't appear to be used in the library
H5 DLL H5P genclass t *H5P get class(const H5P genplist t *plist);
**** See H5Pget class()
// Used in H5trace.c
/* *SPECIAL* Don't make more of these! -QAK */
H5 DLL htri t H5P isa class(hid t plist id, hid t pclass id);
**** See H5Pisa_class() ****
// Used in H5CX, H5D, H5F, H5FD, H5G, H5L, H5M, H5O, H5R, H5T, and H5VL
H5 DLL H5P genplist t *H5P object verify(hid t plist id, hid t pclass id);
// Used in H5FD, H5F, H5L, H5VL, and H5Z
/* Private DCPL routines */
H5_DLL herr_t H5P_fill_value_defined(H5P genplist t *plist,
                                     H5D fill value t *status);
// Used in H5Z
H5_DLL herr_t H5P_get_fill_value(H5P_genplist_t *plist,
                                 const struct H5T t *type,
                                 void *value);
// used in H5Z
H5 DLL int
              H5P ignore cmp(const void H5 ATTR UNUSED *val1,
                             const void H5 ATTR UNUSED *val2,
                             size t H5 ATTR UNUSED size);
// Doesn't appear to be used in the library
#endif /* H5Pprivate_H */
```

Appendix 3 – Original Proposal For Generic Properties?

Thank you to Elena Pourmal for finding the following document, and bringing it to my attention. https://support.hdfgroup.org/HDF5/doc resource/H5Generic Props.html#H5Pcopy prop.

My understanding is that the original property list facility was implemented as a flat structure, supporting only a pre-defined set of properties for each type of property list.

The following document appears to be an early RFC written by Quincey Koziol for the re-write of H5P to support generic properties. Until only five or ten years ago, proposals for extensions / changes in the HDF5 library (typically referred to as RFCs) usually consisted of user level documentation for the new feature / revision along with a brief discussion of motivation. Implementation details were seldom if ever discussed. As it is dated 9/10/01, the document is consistent with this practice.

Leaving aside implementation concerns, the motivation still applies – specifically the need to allow user defined properties to configure user supplied VFDs. Indeed, the VOL layer has only accentuated this requirement.

While this is not a design document as I would use the term, it does shed light on the objectives of the current implementation of H5P – and thus makes the current implementation easier to understand.

Generic Properties Overview and Justification

It is useful to allow "drivers" (VFL, VDL, datatype conversion, etc.) to create properties for controlling features they wish to add to the library. Allowing a driver to create properties when installed at run-time will enable new features to be easily created and controlled while localizing the changes to just the section of code being modified or added. This should allow easier maintainence and evolution of the library's properties in future versions of the library code.

It would also be useful to give users the ability to create and set properties which are temporary in nature and do not need to be stored longer than the application is active. These would allow users to set application specific properties which can be set and queried during the application's execution.

Generic Properties Implementation

The existing property list classes would be modified so that the existing properties are generic properties which are registered when the library starts up. The existing property list API functions would become wrappers around the new "generic" get/set functions. This would

allow the library to become more modular, with each driver or API registering it's own properties without hard- wiring new fields in the property list class.

The library will provide a default or "empty" property list class with no property values defined for property lists of that class. A mechanism for deriving a new property list class will be defined by inheriting from an existing property list class. The existing property list classes defined by the library (file access, dataset creation, etc) will be created during library initialization and will have global constants available for applications to use. (This is similar to the way the library-defined datatypes are created at run-time)

Users may derive new property list classes from any existing property list class, including the completely new classes derived from the default "empty" property list class, or other user-derived property list classes. User-derived property list classes which are derived from the library-defined classes may be passed to API functions which expect library-defined property lists and the API functions will traverse the inherited classes to find the correct class to retrieve information.

The new generic property list API functions allow properties to be registered for each property list class (library or user defined) to create a set of initial properties for newly created property lists of that class. These registered properties can have default values for each new property list created for that class.

Temporary generic properties can also be attached to any existing property list without affecting new property lists of that class.

Property names beginning with "H5" are reserved for library use and should not be used by third-party applications or libraries.

The names and sizes of property values for each property are local to each property list and changing them in a property list class do not affect existing property lists.

API Changes for Implementing Generic Properties

New Functions:

<u>H5Pcreate_class</u> - Create a new property list class.

H5Pcreate_list - Create a new property list of a given class.

<u>H5Pregister</u> - Register a permanent property with a class.

<u>H5Pinsert</u> - Create a temporary property for a property list.

Set an existing property (permanent or temporary) to a

<u>H5Pset</u> - value.

H5Pexist - Query whether a property exists in a property list or class.

<u>H5Pget_size</u> - Query size of property value in bytes.

<u>H5Pget_nprops</u> - Query number of properties in list or class

<u>H5Pget class name</u> - Retrieve the name of a class object

<u>H5Pget class parent</u> - Retrieve a property class's parent class

<u>H5Pisa class</u> - Checks if a property list is a member of a property class

H5Pget - Retrieve property value.

Compares two property lists or classes for equality
 H5Piterate
 Iterates over properties in a property class or list

H5Pcopy prop
 Copies a property from one list to another
 Removes a property from a property list.

H5Punregister - Un-register a permanent property from a class.

H5Pclose_list - Close a property list.

<u>H5Pclose class</u> - Remove a property list class.

Removed Functions:

H5Pcreate and H5Pclose are replaced with H5Pcreate_list and H5Pclose_list.

Changes to Existing Functions:

All the existing H5Pget/set routines would need to be changed to use the new generic register/unregister and get/set routines for the properties they manage, but that shouldn't be a user-visible change. Also, H5Pget_class will change from returning a H5P_class_t to the ID of a generic property class.

New API Function Definitions

NAME

H5Pcreate class

PURPOSE

Create a new property list class

USAGE

```
hid_t H5Pcreate_class(class, name, create, copy, close)
hid_t class;

const char *name;

H5P cls create func t

IN: Callback routine called when a property list is
```

create; created.

H5P_cls_copy_func_t copy; Copied.

H5P_cls_close_func_t IN: Callback routine called when a property list is copied.

H5P_cls_close_func_t being closed.

RETURNS

Success: Valid property list class ID

Failure: negative value

DESCRIPTION

Registers a new property list class with the library. The new property list class can inherit from an existing property list class or may be derived from the default "empty" class. New classes with inherited properties from existing classes may not remove those existing properties, only add or remove their own class properties.

The *create* routine is called when a new property list of this class is being created. The H5P cls create func t is defined as:

```
typedef herr_t (*H5P_cls_create_func_t)(hid_t prop_id, void *
create_data);
```

where the parameters to the callback function are:

```
hid t prop_id; IN: The ID of the property list being created.
```

void * create_data; IN/OUT: User pointer to any class creation information needed The create routine is called after any registered create function is called for each property value. If the create routine returns a negative value, the new list is not returned to the user and the property list creation routine returns an error value.

The copy routine is called when an existing property list of this class is copied. The H5P cls copy func t is defined as:

```
typedef herr_t (*H5P_cls_copy_func_t)( hid_t prop_id, void *
copy_data );
```

where the parameters to the callback function are:

```
hid_t prop_id; IN: The ID of the property list created by copying.
```

void * copy_data; IN/OUT: User pointer to any class copy information needed The copy routine is called after any registered copy function is called for each property value. If the copy routine returns a negative value, the new list is not returned to the user and the property list copy routine returns an error value.

The *close* routine is called when a property list of this class is being closed. The H5P cls close func t is defined as:

```
typedef herr_t (*H5P_cls_close_func_t)( hid_t prop_id, void *
close_data);
```

where the parameters to the callback function are:

```
hid t prop_id; IN: The ID of the property list being closed.
```

void * close_data; IN/OUT: User pointer to any class close information needed The close routine is called before any registered close function is called for each property value. If the close routine returns a negative value, the property list close routine returns an error value but the property list is still closed.

COMMENTS, BUGS, ASSUMPTIONS

I would like to say "the property list is not closed" when a _close_ routine fails, but I don't think that's possible due to other properties in the list being successfully closed & removed from the property list. I suppose that it would be possible to just remove the properties which have successful _close_ callbacks, but I'm not happy with the ramifications of a mangled, un-closable property list hanging around... Any comments?

NAME

H5Pcreate_list

PURPOSE

Create a new property list class of a given class

USAGE

```
hid_t H5Pcreate_list(class)

hid t class; IN: Class of property list to create.
```

RETURNS

Success: Valid property list ID

Failure: negative value

DESCRIPTION

Creates a property list of a given class. If a *create* callback exists for the property list class, it is called before the property list is passed back to the user. If *create* callbacks exist for

any individual properties in the property list, they are called before the class *create* callback.

COMMENTS, BUGS, ASSUMPTIONS

[?]

NAME

H5Pregister

PURPOSE

Register a permanent property with a property list class

USAGE

herr t H5Pregister(class, name, size, default, create, set, get, close)

IN: Property list class to register permanent property hid t class; within. const char * name; IN: Name of property to register. size t size; IN: Size of property in bytes. IN: Default value for property in newly created property void * default; lists. H5P prp create func t IN: Callback routine called when a property list is being created and the property value will be initialized. create: ${\tt H5P_prp_set_func_t} \begin{tabular}{l} {\tt IN: Callback routine called before a new value is copied into the property's value.} \end{tabular}$ H5P_prp_get_func_t IN: Callback routine called when a property value is get; retrieved from the property. H5P prp delete func t IN: Callback routine called when a property is deleted delete: from a property list. H5P prp copy func t IN: Callback routine called when a property is copied from in a property list. copy; H5P prp close func t IN: Callback routine called when a property list is being close; closed and the property value will be disposed of.

RETURNS

Success: non-negative value Failure: negative value

DESCRIPTION

Registers a new property with a property list class. The property will exist in all property list objects of *class* created after this routine finishes. The name of the property must not already exist, or this routine will fail. The default property value must be provided and all new property lists created with this property will have the property value set to the default value. Any of the callback routines may be set to NULL if they are not needed.

Zero-sized properties are allowed and do not store any data in the property list. These may be used as flags to indicate the presence or absence of a particular piece of information. The 'default' pointer for a zero-sized property may be set to NULL. The property 'create' & 'close' callbacks are called for zero-sized properties, but the 'set' and 'get' callbacks are never called.

The *create* routine is called when a new property list with this property is being created. H5P prp create func t is defined as:

```
typedef herr_t (*H5P_prp_create_func_t)(const char *name, size_t
size, void *initial_value);
```

where the parameters to the callback function are:

H5P prp set func tis defined as:

```
const char *
name;

size_t size;

void *
IN: The name of the property being modified.

IN: The size of the property in bytes.

IN/OUT: The default value for the property being created. (The initial_value;

default value passed to H5Pregister)
```

The *create* routine may modify the value to be set and those changes will be stored as the initial value of the property. If the *create* routine returns a negative value, the new property value is not copied into the property and the create routine returns an error value.

```
The set routine is called before a new value is copied into the property.
```

```
hid_t prop_id; IN: The ID of the property list being modified.

const char *
name; IN: The name of the property being modified.

size_t size; IN: The size of the property in bytes.

void ** new_value; IN/OUT: Pointer to new value pointer for the property being modified.
```

The *set* routine may modify the value pointer to be set and those changes will be used when setting the property's value. If the *set* routine returns a negative value, the new property value is not copied into the property and the set routine returns an error value. The *set* routine will not be called for the initial value, only the *create* routine will be called.

The *get* routine is called when a value is retrieved from a property value.

```
H5P prp get func tis defined as:
```

```
typedef herr_t (*H5P_prp_get_func_t)( hid_t prop_id, const char
*name, size_t size, void *value);
```

where the parameters to the callback function are:

```
hid_t prop_id; IN: The ID of the property list being queried.

const char * name; IN: The name of the property being queried.

size_t size; IN: The size of the property in bytes.

void * value; IN/OUT: The value of the property being returned.
```

The *get* routine may modify the value to be returned from the query and those changes will be returned to the calling routine. If the *set* routine returns a negative value, the query routine returns an error value.

The delete routine is called when a property is being deleted from a property list. H5P prp delete func t is defined as:

```
typedef herr_t (*H5P_prp_delete_func_t)( hid_t prop_id, const char
*name, size_t size, void *value);
```

where the parameters to the callback function are:

```
hid_t prop_id; IN: The ID of the property list the property is being deleted from.

const char * name; IN: The name of the property in the list.

size_t size; IN: The size of the property in bytes.

void * value; IN: The value for the property being deleted.
```

The *delete* routine may modify the value passed in, but the value is not used by the library when the *delete* routine returns. If the *delete* routine returns a negative value, the property list delete routine returns an error value but the property is still deleted.

The copy routine is called when a new property list with this property is being created through a copy operation. H5P prp copy func t is defined as:

```
typedef herr_t (*H5P_prp_copy_func_t)( const char *name, size_t
size, void *value);
```

where the parameters to the callback function are:

```
const char * name; IN: The name of the property being copied.
```

```
size_t size; IN: The size of the property in bytes.
void * value; IN/OUT: The value for the property being copied.
```

The *copy* routine may modify the value to be set and those changes will be stored as the new value of the property. If the *copy* routine returns a negative value, the new property value is not copied into the property and the copy routine returns an error value.

The close routine is called when a property list with this property is being closed. H5P prp close func t is defined as:

```
typedef herr_t (*H5P_prp_close_func_t)( hid_t prop_id, const char
*name, size_t size, void *value);
```

where the parameters to the callback function are:

```
hid_t prop_id; IN: The ID of the property list being closed.

const char * name; IN: The name of the property in the list.

size_t size; IN: The size of the property in bytes.

void * value; IN: The value for the property being closed.
```

The *close* routine may modify the value passed in, but the value is not used by the library when the *close* routine returns. If the *close* routine returns a negative value, the property list close routine returns an error value but the property list is still closed.

COMMENTS, BUGS, ASSUMPTIONS

The *set* callback function may be useful to range check the value being set for the property or may perform some tranformation/translation of the value set. The *get* callback would then [probably] reverse the transformation, etc. A single *get* or *set* callback could handle multiple properties by performing different actions based on the property name or other properties in the property list.

I would like to say "the property list is not closed" when a *close* routine fails, but I don't think that's possible due to other properties in the list being successfully closed & removed from the property list. I suppose that it would be possible to just remove the properties which have successful *close* callbacks, but I'm not happy with the ramifications of a mangled, un-closable property list hanging around... Any comments?

NAME

H5Pinsert

PURPOSE

Register a temporary property with a property list

USAGE

herr t H5Pinsert(plid, name, size, value, set, get, close) hid t*plid*; IN: Property list id to create temporary property within. const char *name; IN: Name of property to create. size t*size*; IN: Size of property in bytes. void *value: IN: Initial value for the property. H5P_prp_set_func_t set; IN: Callback routine called before a new value is copied into the property's value. IN: Callback routine called when a property value is H5P prp get func t get; retrieved from the property. H5P prp delete func t IN: Callback routine called when a property is deleted delete: from a property list. H5P_prp_copy_func t IN: Callback routine called when a property is copied copy; from an existing property list. H5P prp close func t IN: Callback routine called when a property list is being close; closed and the property value will be disposed of.

RETURNS

Success: non-negative value Failure: negative value

DESCRIPTION

Create a new property in a property list. The property will exist only in this property list and copies made from it. The name of the property must not already exist in this list, or this routine will fail. The initial property value must be provided and the property value will be set to it. The *set* and *get* callback routines may be set to NULL if they are not needed.

Zero-sized properties are allowed and do not store any data in the property list. The default value of a zero-size property may be set to NULL. They may be used to indicate the presence or absence of a particular piece of information.

The set routine is called before a new value is copied into the property. The H5P prp set func t is defined as:

```
size_t size; IN: The size of the property in bytes.

void **new_value; IN: Pointer to new value pointer for the property being modified.
```

The *set* routine may modify the value pointer to be set and those changes will be used when setting the property's value. If the *set* routine returns a negative value, the new property value is not copied into the property and the set routine returns an error value. The *set* routine will be called for the initial value.

The *get* routine is called when a value is retrieved from a property value. The H5P prp get func t is defined as:

```
typedef herr_t (*H5P_prp_get_func_t)( hid_t prop_id, const char
*name, size_t size, void *value);
```

where the parameters to the callback function are:

```
hid_t prop_id; IN: The ID of the property list being queried.

const char *name; IN: The name of the property being queried.

size_t size; IN: The size of the property in bytes.

void *value; IN: The value of the property being returned.
```

The *get* routine may modify the value to be returned from the query and those changes will be preserved. If the *get* routine returns a negative value, the query routine returns an error value.

The delete routine is called when a property is being deleted from a property list. H5P prp delete func t is defined as:

```
typedef herr_t (*H5P_prp_delete_func_t)( hid_t prop_id, const char
*name, size_t size, void *value);
```

where the parameters to the callback function are:

```
hid_t prop_id; IN: The ID of the property list the property is being deleted from.

const char * name; IN: The name of the property in the list.

size_t size; IN: The size of the property in bytes.

void * value; IN: The value for the property being deleted.
```

The *delete* routine may modify the value passed in, but the value is not used by the library when the *delete* routine returns. If the *delete* routine returns a negative value, the property list delete routine returns an error value but the property is still deleted.

The *copy* routine is called when a new property list with this property is being created through a copy operation. H5P_prp_copy_func_t is defined as:

```
typedef herr_t (*H5P_prp_copy_func_t)( const char *name, size_t
size, void *value);
```

where the parameters to the callback function are:

```
const char * name; IN: The name of the property being copied.
```

```
size_t size; IN: The size of the property in bytes.
```

void * value; IN/OUT: The value for the property being copied.

The *copy* routine may modify the value to be set and those changes will be stored as the new value of the property. If the *copy* routine returns a negative value, the new property value is not copied into the property and the copy routine returns an error value.

The close routine is called when a property list with this property is being closed. The H5P prp close func t is defined as:

```
typedef herr_t (*H5P_prp_close_func_t)( hid_t prop_id, const char
*name, size_t size, void *value);
```

where the parameters to the callback function are:

```
hid_t prop_id; IN: The ID of the property list being closed.

const char *name; IN: The name of the property in the list.

size_t size; IN: The size of the property in bytes.

void *value; IN: The value for the property being closed.
```

The *close* routine may modify the value passed in, the value is not used by the library when the *close* routine returns. If the *close* routine returns a negative value, the property list close routine returns an error value but the property list is still closed.

COMMENTS, BUGS, ASSUMPTIONS

The *set* callback function may be useful to range check the value being set for the property or may perform some tranformation/translation of the value set. The *get* callback would then [probably] reverse the transformation, etc. A single *get* or *set* callback could handle multiple properties by performing different actions based on the property name or other properties in the property list.

There is no *create* callback routine for temporary property list objects, the initial value is assumed to have any necessary setup already performed on it.

I would like to say "the property list is not closed" when a *close* routine fails, but I don't think that's possible due to other properties in the list being successfully closed & removed from the property list. I suppose that it would be possible to just remove the properties which have successful *close* callbacks, but I'm not happy with the ramifications of a mangled, un-closable property list hanging around... Any comments?

NAME

H5Pset

PURPOSE

Set a property list value

USAGE

```
herr_t H5Pset(plid, name, value)
hid_t plid; IN: Property list id to modify
const char *name; IN: Name of property to modify.
void *value; IN: Pointer to value to set the property to.
```

RETURNS

Success: non-negative value Failure: negative value

DESCRIPTION

Sets a new value for a property in a property list. The property name must exist or this routine will fail. If there is a *set* callback routine registered for this property, the *value* will be passed to that routine and any changes to the *value* will be used when setting the property value. The information pointed at by the *value* pointer (possibly modified by the *set* callback) is copied into the property list value and may be changed by the application making the H5Pset call without affecting the property value.

If the *set* callback routine returns an error, the property value will not be modified. This routine may not be called for zero-sized properties and will return an error in that case.

COMMENTS, BUGS, ASSUMPTIONS

[?]

NAME

H5Pexist

PURPOSE

Query if a property name exists in a property list or class

USAGE

RETURNS

Success: Positive if the property exists in the property object, zero if the property does

not exist.

Failure: negative value

DESCRIPTION

This routine checks if a property exists within a property list or class.

COMMENTS, BUGS, ASSUMPTIONS

[?]

NAME

H5Pget_size

PURPOSE

Query size of property value in bytes

USAGE

```
int H5Pget_size(id, name, size)
hid_t id; IN: ID of property object to query
const char *name; IN: Name of property to query
size t *size; OUT: Size of property in bytes
```

RETURNS

Success: non-negative value Failure: negative value

DESCRIPTION

This routine retrieves the size of a property's value in bytes. Zero- sized properties are allowed and return 0. This function operates on both poperty lists and property classes

COMMENTS, BUGS, ASSUMPTIONS

NAME

```
H5Pget_nprops
```

PURPOSE

Query number of properties in property list or class

USAGE

RETURNS

Success: non-negative value Failure: negative value

DESCRIPTION

This routine retrieves the number of properties in a property list or class. If a property class ID is given, the number of registered properties in the class is returned in nprops. If a property list ID is given, the current number of properties in the list is returned in nprops.

COMMENTS, BUGS, ASSUMPTIONS

[?]

NAME

```
H5Pget_class_name
```

PURPOSE

Retrieve the name of a class

USAGE

```
char * H5Pget_class_name(pcid)
    hid t pcid; IN: Property class id to query
```

RETURNS

Success: Pointer to a malloc'ed string containing the class name

Failure: NULL

DESCRIPTION

This routine retrieves the name of a generic property list class. The pointer to the name must be free'd by the user for successful calls.

COMMENTS, BUGS, ASSUMPTIONS

[?]

NAME

```
H5Pget class parent
```

PURPOSE

Retrieve the parent class of a property class

USAGE

```
hid_t H5Pget_class_parent(pcid)
hid t pcid; IN: Property class ID to query
```

RETURNS

Success: ID of parent class object

Failure: negative

DESCRIPTION

This routine retrieves an ID for the parent class of a property class.

COMMENTS, BUGS, ASSUMPTIONS

[?]

NAME

H5Pisa_class

PURPOSE

Check if a property list is a member of a class

USAGE

```
htri_t H5Pisa_class(plist, pclass)
    hid_t plist; IN: ID of property list to compare
    hid t pclass; IN: ID of property class to compare against
```

RETURNS

Success: TRUE (positive) if equal, FALSE (zero) if unequal Failure: negative value

DESCRIPTION

This routine checks if a property list is a member of a class.

COMMENTS, BUGS, ASSUMPTIONS

[?]

NAME

H5Pget

PURPOSE

Query value of property

USAGE

```
herr_t H5Pget(plid, name, value)

hid_t plid; IN: Property list id to query

const char *name; IN: Name of property to query

void *value; OUT: Pointer to location to copy value of property retrieved into.
```

RETURNS

Success: non-negative value. Failure: negative value

DESCRIPTION

Retrieves a copy of the value for a property in a property list. The property name must exist or this routine will fail. If there is a *get* callback routine registered for this property, the copy of the value of the property will first be passed to that routine and any changes to the copy of the value will be used when returning the property value from this routine. If the *get* callback routine returns an error, *value* will not be modified. This routine may be called for zero-sized properties with the *value* set to NULL and the *get* routine will be called with a NULL value if the callback exists.

COMMENTS, BUGS, ASSUMPTIONS

[?]

NAME

H5Pequal

PURPOSE

Compare two property lists or classes for equality

USAGE

```
htri_t H5Pequal(id1, id2)

hid_t id1; IN: First property object to compare

hid_t id2; IN: Second property object to compare
```

RETURNS

Success: TRUE (positive) if equal, FALSE (zero) if unequal

Failure: negative value

DESCRIPTION

This routine determines whether two property lists or classes are equal to one another. Both id1 and id2 must be either property lists or classes, comparing a list to a class is an error.

COMMENTS, BUGS, ASSUMPTIONS

NAME

H5Piterate

PURPOSE

Iterates over properties in a property class or list

USAGE

int H5Piterate(idass_id, idx, iter_func, iter_data)

hid_t *id*; IN: ID of property object to iterate over int * *idx*; IN/OUT: Index of the property to begin with

H5P iterate t IN: Function pointer to function to be called with each

iter_func; property iterated over.

void * iter data; IN/OUT: Pointer to iteration data from user

RETURNS

Success: Returns the return value of the last call to iter func if it was non-zero, or zero if

all properties have been processed.

Failure: negative value

DESCRIPTION

This routine iterates over the properties in the property object specified with ID. The properties in both property lists and classes may be iterated over with this function. For each property in the object, the $iter_func$ and some additional information, specified below, are passed to the $iter_func$ function. The iteration begins with the idx property in the object and the next element to be processed by the operator is returned in idx. If idx is NULL, then the iterator starts at the first property; since no stopping point is returned in this case, the iterator cannot be restarted if one of the calls to its operator returns non-zero.

The prototype for H5P iterate t is:

typedef herr_t (*H5P_iterate_t)(hid_t id, const char *name, void *iter_data)
The operation receives the property list or class identifier for the object being iterated over, ID, the name of the current property within the object, name, and the pointer to the operator data passed in to H5Piterate, iter_data.

The return values from an operator are:

Zero: Causes the iterator to continue, returning zero when all properties have been

processed.

Positive: Causes the iterator to immediately return that positive value, indicating short-

circuit success. The iterator can be restarted at the index of the next property.

Negative: Causes the iterator to immediately return that value, indicating failure. The iterator

can be restarted at the index of the next property.

H5Piterate assumes that the properties in the object identified by ID remains unchanged through the iteration. If the membership changes during the iteration, the function's behavior is undefined.

COMMENTS, BUGS, ASSUMPTIONS

[?]

NAME

H5Pcopy_prop

PURPOSE

Copies a property from one list or class to another

USAGE

```
herr_t H5Pcopy_prop(dst_id, src_id, name)

hid_t dst_id; IN: ID of destination property list or class

hid_t src_id; IN: ID of source property list or class

const char *name; IN: Name of property to copy
```

RETURNS

Success: non-negative value. Failure: negative value

DESCRIPTION

Copies a property from one property list or class to another.

If a property is copied from one class to another, all the property information will be first deleted from the destination class and then the property information will be copied from the source class into the destination class.

If a property is copied from one list to another, the property will be first deleted from the destination list (generating a call to the *close* callback for the property, if one exists) and then the property is copied from the source list to the destination list (generating a call to the *copy* callback for the property, if one exists).

If the property does not exist in the class or list, this call is equivalent to calling H5Pregister or H5Pinsert (for a class or list, as appropriate) and the *create* callback will be called in the case of the property being copied into a list (if such a callback exists for the property).

COMMENTS, BUGS, ASSUMPTIONS

NAME

H5Premove

PURPOSE

Removes a property from a property list

USAGE

```
herr_t H5Premove(plid, name)

hid_t plid; IN: Property list id to modify

const char *name; IN: Name of property to remove
```

RETURNS

Success: non-negative value. Failure: negative value

DESCRIPTION

Removes a property from a property list. Both properties which were in existance when the property list was created (i.e. properties registered with H5Pregister) and properties added to the list after it was created (i.e. added with H5Pinsert) may be removed from a property list. Properties do not need to be removed a property list before the list itself is closed, they will be released automatically when H5Pclose is called. The *close* callback for this property is called before the property is release, if the callback exists.

COMMENTS, BUGS, ASSUMPTIONS

NAME

H5Punregister

PURPOSE

Removes a property from a property list class

USAGE

```
herr_t H5Punregister(class, name)

H5P_class_t class; IN: Property list class to remove permanent property from.

const char *name; IN: Name of property to remove
```

RETURNS

Success: non-negative value. Failure: negative value

DESCRIPTION

Removes a property from a property list class. Future property lists created of that class will not contain this property. Existing property lists containing this property are not affected.

COMMENTS, BUGS, ASSUMPTIONS

[?]

NAME

H5Pclose list

PURPOSE

Close a property list

USAGE

```
herr_t H5Pclose_list(plist)
hid t plist; IN: Property list to close.
```

RETURNS

Success: non-negative value Failure: negative value

DESCRIPTION

Closes a property list. If a *close* callback exists for the property list class, it is called before the property list is destroyed. If *close* callbacks exist for any individual properties in the property list, they are called after the class *close* callback.

COMMENTS, BUGS, ASSUMPTIONS

[?]

NAME

H5Pclose class

PURPOSE

Closes an existing property list class

USAGE

```
herr_t H5Pclose_class(class)

hid t class; IN: Property list class to close.
```

RETURNS

Success: non-negative value Failure: negative value

DESCRIPTION

Removes a property list class from the library. Existing property lists of this class will continue to exist, but new ones are not able to be created.

COMMENTS, BUGS, ASSUMPTIONS

[?]

Examples:

Example #1: Register a new property for future dataset creation property lists. This property uses a "set" callback to range check the values for the property. This set of features would likely be used with Virtual File or Dataset drivers. This example also shows how get/set API functions for the property registered might work.

```
/* Property "set" callback */
herr t driver set check(hid t prop, const char *name, void * value)
   int *value=(int *) value;
   /* Check that this routine is called for proper property name */
   if(strcmp(name, "property1"))
       return(-1);
   /* Range check property value */
   if(*value<0 || *value>SOME LIMIT)
       return(-1);
   /* Name and value are OK */
   return(0);
}
/* An API routine that sets the property for this driver */
herr t H5Pset driver property1(hid t prop, int value)
    * Call the generic H5Pset routine and let the "set" callback do the
    * range checking, etc.
   return(H5Pset(prop, "property1", &value));
}
/* An API routine that gets the property for this driver */
herr t H5Pget driver property1 (hid t prop, int *value)
   /* Call the generic H5Pget routine to retrieve the value */
   return(H5Pget(prop, "property1", value));
}
int setup driver()
   [Set up other driver information]
   /* Register new property with Dataset Creation property list class */
   /* Provide a "set" callback, but no "get" callback for this property */
   H5Pregister(H5P DATASET CREATE, "property1", sizeof(int), &prop1 default,
       driver set check, NULL);
}
int shutdown driver()
```

```
{
    [Shut down other driver information]

/* Unregister property from Dataset Creation property list class */
    H5Punregister(H5P_DATASET_CREATE, "property1");
}
```

QAK:9/10/01

Appendix 4: Property and Property List Class Callbacks

The callbacks supported by the properties and property list classes are an obvious source of multi-thread safety issues. My objective in this appendix is to identify all the property and property list class callbacks defined by the HDF5 library, and examine them for potential multi-thread issues.

In this appendix, I list the callbacks associated with each of the library defined property list classes, and their associated properties, review the callbacks, and note any potential difficulties.

As it is assumed that it will be necessary to maintain appropriate mutual exclusion on properties when reading or writing them, the primary focus is identifying any other places where mutual exclusion is required when executing property callbacks. While these are identified in the discussions of the individual properties, the following summary may be useful:

- Encode / decode buffer during property list encode / decode operations.
- Calls to H5Z (DXPL / Data transform property)
- Calls to H5S (DXPL / Dataset selection property)

In the case of the property list classes this is easy – none of them appear to have any callbacks. Unfortunately, properties far out number property list classes.

Per the following typedef

```
typedef enum H5P_plist_type_t {
 H5P_TYPE_USER
                    = 0.
 H5P_TYPE_ROOT
                    = 1,
 H5P_TYPE_OBJECT_CREATE = 2,
 H5P TYPE FILE CREATE = 3,
 H5P TYPE FILE ACCESS = 4,
 H5P TYPE DATASET CREATE = 5,
 H5P_TYPE_DATASET_ACCESS = 6,
 H5P TYPE DATASET XFER = 7,
 H5P_TYPE_FILE_MOUNT
 H5P_TYPE_GROUP_CREATE = 9,
 H5P TYPE GROUP ACCESS = 10,
 H5P_TYPE_DATATYPE_CREATE = 11,
 H5P TYPE DATATYPE ACCESS = 12,
 H5P TYPE STRING CREATE = 13,
 H5P_TYPE_ATTRIBUTE_CREATE = 14,
 H5P_TYPE_OBJECT_COPY = 15,
 H5P TYPE LINK CREATE = 16,
 H5P TYPE LINK ACCESS = 17,
 H5P TYPE ATTRIBUTE ACCESS = 18,
 H5P_TYPE_VOL_INITIALIZE = 19,
 H5P_TYPE_MAP_CREATE
```

```
H5P_TYPE_MAP_ACCESS = 21,
H5P_TYPE_REFERENCE_ACCESS = 22,
H5P_TYPE_MAX_TYPE
} H5P_plist_type_t;
```

the HDF5 library defines 22 property list classes, which form the following inheritance tree:

```
H5P TYPE ROOT
+-Data Transfer Property List (DXPL)
+-File Access Property List (FAPL)
+-Reference Access Property List (RACCPL) Class
+-File Mount Property List (FMPL)
+-VOL Initialization Property List (VIPL)
+-Link Access Property List (LAPL)
+-Datatype Access Property List (TAPL)
+-Attribute Access Property List (AAPL)
+-Group Access Property List (GAPL)
+-Dataset Access Property List (DAPL)
+-Map Access Property List (MAPL) Class
+-Object Creation Property List (OCRTPL)
+-Datatype Creation Property List (TCPL)
+-Dataset Creation Property List (DCRTPL)
+-Group Creation Property List (GCRTPL)
+-File Creation Property list (FCRTPL) Class
| +-Map Create Property List (MCRTPL)
+-Object Copy Property List (OCPYPL)
+-String Creation Property List (STRCRTPL)
  +-Attribute Creation Property List (ACRTPL)
  +-Link Creation Property List (LCRTPL)
```

In the following sections, I review each of these, in the order listed in the above inheritance tree.

Root Property List Class

The instance of H5P_libclass_t defining the initialization of the Root property list class is shown below.

```
/* Root property list class library initialization object */
const H5P_libclass_t H5P_CLS_ROOT[1] = {{
    "root", /* Class name for debugging */
    H5P_TYPE_ROOT, /* Class type */

    NULL, /* Parent class */
    &H5P_CLS_ROOT_g, /* Pointer to class */
    &H5P_CLS_ROOT_ID_g, /* Pointer to class ID */
    NULL, /* Pointer to default property list ID */
    NULL, /* Default property registration routine */
```

```
NULL, /* Class creation callback */
NULL, /* Class creation callback info */
NULL, /* Class copy callback */
NULL, /* Class copy callback info */
NULL, /* Class close callback */
NULL /* Class close callback info */
}};
```

As there are no callbacks associated with the Root property list class, and no default properties, it follows that the Root property list class does not introduce any multi-thread issues.

Data Transfer Property List (DXPL) Class

Inheritance: ROOT→ DXPL

The instance of H5P_libclass_t defining the initialization of the data transfer property list class is shown below.

```
/* Data transfer property list class library initialization object */
const H5P libclass t H5P CLS DXFR[1] = {{
 "data transfer", /* Class name for debugging
 H5P_TYPE_DATASET_XFER, /* Class type
                                                   */
 &H5P CLS ROOT g,
                           /* Parent class
 &H5P CLS DATASET XFER g, /* Pointer to class
                                                         */
 &H5P_CLS_DATASET_XFER_ID_g, /* Pointer to class
ID
A*/
 &H5P LST DATASET XFER ID g, /* Pointer to default property list ID */
                          /* Default property registration routine */
 H5P dxfr reg prop,
 NULL, /* Class creation callback
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
 NULL, /* Class copy callback info
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

While there are no callbacks associated with the property list class, the following properties are registered by H5P__dxfr_reg_prop(), the default property registration routine, registers the following properties:

- 1. Max. temp buffer size property
- 2. Type conversion buffer property
- 3. Background buffer property

- 4. Background buffer type property
- 5. B-Tree note splitting ratios property
- 6. Vlen allocation function property
- 7. Vlen allocation information property
- 8. Vlen free function property
- 9. Vlen free information property
- 10. Vector size property
- 11. I/O transfer mode property (H5D_XFER_IO_XFER_MODE)
- 12. I/O transfer mode property (H5D XFER MPIO COLLECTIVE OPT)
- 13. I/O transfer mode property (H5D XFER MPIO CHUNK OPT HARD)
- 14. I/O transfer mode property(H5D XFER MPIO CHUNK OPT NUM)
- 15. I/O transfer mode property (H5D XFER MPIO CHUNK OPT RATIO)
- 16. Chunk Optimization mode property
- 17. Actual I/O mode property
- 18. Local cause of broken collective I/O property
- 19. Global cause of broken collective I/O property
- 20. EDC property
- 21. Filter callback property
- 22. Type conversion callback property
- 23. Data transform property
- 24. Dataset selection property

Each of these properties is discussed below

Maximum Temp Buffer Size Property

The call used to register the Max. temp buffer size property is reproduced below with the formal parameters added as comments

```
H5P__register_real(pclass // H5P_genclass_t *pclass, H5D_XFER_MAX_TEMP_BUF_NAME, // const char *name, H5D_XFER_MAX_TEMP_BUF_SIZE, // size_t size, &H5D_def_max_temp_buf_g, // const void *def_value,
```

```
NULL,
                            // H5P prp create func t prp create,
NULL,
                            // H5P prp set func t prp set,
NULL,
                            // H5P prp get func t prp get,
H5D XFER MAX TEMP BUF ENC, // H5P_prp_encode_func_t prp_encode,
H5D XFER MAX TEMP BUF DEC, // H5P prp decode func t prp decode,
NULL,
                            // H5P prp delete func t prp delete,
NULL,
                            // H5P_prp_copy_func_t prp_copy,
                            // H5P_prp_compare_func_t prp_cmp,
NULL,
NULL);
                            // H5P prp close func t prp close
```

Observe that only the encode and decode callbacks are defined.

H5D_XFER_MAX_TEMP_BUF_ENC and H5D_XFER_MAX_TEMP_BUF_DEC resolve to H5P__encode_size_t() and H5P__decode_size_t() respectively. Their signatures appear in H5Ppkg.h, and are reproduced below:

```
herr_t H5P__encode_size_t(const void *value, void **_pp, size_t *size);
herr_t H5P__decode_size_t(const void **_pp, void *_value);
```

These two routines appear to have no potential for multi-thread issues outside of variables pointed to by their parameters. As it is assumed that appropriate mutual exclusion must be maintained on the property, the only remaining potential area of concern is the encode / decode buffer.

Type conversion buffer property

The call used to register the type conversion buffer property is reproduced below with the formal parameters added as comments

```
H5P register real(pclass
                                                          // H5P genclass t *pclass,
                       ##5D_XFER_TCONV_BUF_NAME, // const char *name,
##5D_XFER_TCONV_BUF_SIZE, // size_t size,
##5D_def_tconv_buf_g, // const void *def_value,
NULL. // #5P_prp_create_func_t.
                                                          // H5P_prp_create_func_t prp_create,
                       NULL,
                                                          // H5P_prp_set_func_t prp_set,
                       NULL,
                       NULL,
                                                          // H5P prp get func t prp get,
                       NULL.
                                                          // H5P prp encode func t prp encode,
                       NULL,
                                                         // H5P prp decode func t prp decode,
                       NULL,
                                                         // H5P prp delete func t prp delete,
                       NULL,
                                                         // H5P prp copy func t prp copy,
                       NULL,
                                                         // H5P prp compare func t prp cmp,
                       NULL);
                                                          // H5P prp close func t prp close
```

Since no callbacks are defined., there are no callback related multi-thread safety issues with this property.

Background buffer property

The call used to register the background buffer property is reproduced below with the formal parameters added as comments

```
H5P__register_real(pclass
                                                       // H5P genclass t *pclass,
                      H5D_XFER_BKGR_BUF_NAME, // const char *name, H5D_XFER_BKGR_BUF_SIZE, // size_t size, &H5D_def_bkgr_buf_g,, // const void *def_value,
                      NULL,
                                                       // H5P prp create func t prp create,
                      NULL,
                                                       // H5P_prp_set_func_t prp_set,
                      NULL,
                                                       // H5P_prp_get_func_t prp_get,
                                                       // H5P_prp_encode_func_t prp_encode,
                      NULL,
                      NULL,
                                                       // H5P_prp_decode_func_t prp_decode,
                                                       // H5P prp delete func t prp delete,
                      NULL,
                                                       // H5P prp copy func t prp copy,
                      NULL,
                                                       // H5P prp compare_func_t prp_cmp,
                      NULL,
                                                       // H5P prp close func t prp close
                      NULL);
```

Since no callbacks are defined., there are no callback related multi-thread safety issues with this property.

Background buffer type property

The call used to register the background buffer property is reproduced below with the formal parameters added as comments

```
H5P register real(pclass
                                                // H5P genclass t *pclass,
                  H5D XFER BKGR BUF TYPE NAME, // const char *name,
                  H5D_XFER_BKGR_BUF_TYPE_SIZE, // size_t size,
                  &H5D_def_bkgr_buf_type_g, // const void *def_value,
                  NULL,
                                               // H5P prp create func t prp create,
                  NULL,
                                               // H5P prp set func t prp set,
                                               // H5P prp get func t prp get,
                  NULL,
                  H5D XFER BKGR BUF TYPE ENC, // H5P prp encode func t prp encode,
                  H5D XFER BKGR BUF TYPE DEC, // H5P prp decode func t prp decode,
                  NULĪ,
                                               // H5P_prp_delete_func_t prp_delete,
                  NULL,
                                               // H5P_prp_copy_func_t prp_copy,
                                               // H5P_prp_compare_func_t prp_cmp,
                  NULL,
                  NULL);
                                                // H5P prp close func t prp close
```

Observe that only the encode and decode callbacks are defined.

H5D_XFER_BKGR_BUF_TYPE_ENC and H5D_XFER_BKGR_BUF_TYPE_DEC resolve to H5P__dxfr_bkgr_buf_type_enc() and H5P__dxfr_bkgr_buf_type_dec() respectively. Their signatures appear in H5Pdxpl.c, and are reproduced below:

```
herr_t H5P__dxfr_bkgr_buf_type_enc(const void *value, void **pp, size_t *size);
herr_t H5P__dxfr_bkgr_buf_type_dec(const void **pp, void *value);
```

These two routines appear to have no potential for multi-thread issues outside of variables pointed to by their parameters. As it is assumed that appropriate mutual exclusion must be maintained on the property, the only remaining potential area of concern is the encode / decode buffer.

B-Tree node splitting ratios property

The call used to register the B-Tree node splitting property is reproduced below with the formal parameters added as comments

```
H5P register real (pclass
                                                       // H5P genclass t *pclass,
                  H5D XFER BTREE SPLIT RATIO NAME, // const char *name,
                  H5D XFER BTREE SPLIT RATIO SIZE, // size t size,
                  H5D_def_btree_split_ratio_g, // const void *def_value,
                  NULĪ,
                                                      // H5P_prp_create_func_t prp_create,
                  NULL,
                                                      // H5P_prp_set_func_t prp_set,
                                                      // H5P_prp_get_func_t prp_get,
                  NULL,
                 H5D_XFER_BTREE_SPLIT_RATIO_ENC, // H5P_prp_encode_func_t prp_encode, H5D_XFER_BTREE_SPLIT_RATIO_DEC, // H5P_prp_decode_func_t prp_decode,
                                                      // H5P_prp_delete_func_t prp_delete,
                  NULL.
                                                      // H5P prp_copy_func_t prp_copy,
                  NULL,
                                                      // H5P_prp_compare_func_t prp_cmp,
                  NULL.
                  NULL);
                                                      // H5P prp close func t prp close
```

Observe that only the encode and decode callbacks are defined.

H5D_XFER_BTREE_SPLIT_RATIO_ENC and H5D_XFER_BTREE_SPLIT_RATIO_DEC resolve to H5P__dxfr_btree_split_ratio_enc() and H5P__dxfr_btree_split_ratio_dec() respectively. Their signatures appear in H5Pdxpl.c, and are reproduced below:

```
herr_t H5P__dxfr_btree_split_ratio_enc(const void *value, void **pp, size_t *size);
herr_t H5P__dxfr_btree_split_ratio_dec(const void **pp, void *value);
```

These two routines appear to have no potential for multi-thread issues outside of variables pointed to by their parameters. As it is assumed that appropriate mutual exclusion must be maintained on the property, the only remaining potential area of concern is the encode / decode buffer.

Vlen allocation function property

The call used to register the vien allocation function property is reproduced below with the formal parameters added as comments

```
H5P register_real(pclass
                                               // H5P genclass t *pclass,
                   H5D XFER VLEN ALLOC NAME,
                                               // const char *name,
                   H5D XFER VLEN ALLOC SIZE,
                                               // size t size,
                   &H5D_def_vlen_alloc_g,
                                               // const void *def value,
                   NULL,
                                               // H5P prp create func t prp create,
                   NULL,
                                               // H5P prp set func t prp set,
                   NULL,
                                               // H5P prp get func t prp get,
                   NULL,
                                               // H5P_prp_encode_func_t prp_encode,
                   NULL,
                                               // H5P_prp_decode_func_t prp_decode,
                   NULL,
                                               // H5P_prp_delete_func_t prp_delete,
                   NULL,
                                               // H5P_prp_copy_func_t prp_copy,
                   NULL,
                                               // H5P_prp_compare_func_t prp_cmp,
                   NULL);
                                               // H5P prp close func t prp close
```

Since no callbacks are defined., there are no callback related multi-thread safety issues with this property.

Vlen allocation information property

The call used to register the vlen allocation information property is reproduced below with the formal parameters added as comments

```
H5P register real(pclass
                                                     // H5P_genclass_t *pclass,
                   H5D_XFER_VLEN_ALLOC_INFO_NAME, // const char *name, H5D_XFER_VLEN_ALLOC_INFO_SIZE, // size_t size,
                   &H5D def vlen alloc_info_g,
                                                     // const void *def value,
                                                     // H5P_prp_create_func_t prp_create,
                   NULL.
                                                     // H5P_prp_set_func_t prp_set,
                   NULL,
                   NULL,
                                                      // H5P prp get func t prp get,
                                                      // H5P prp_encode_func_t prp_encode,
                   NULL
                                                     // H5P prp decode func t prp decode,
                   NULL,
                                                     // H5P prp delete func_t prp_delete,
                   NULL.
                   NULL,
                                                     // H5P prp copy func t prp copy,
                   NULL,
                                                      // H5P prp compare func t prp cmp,
                   NULL);
                                                      // H5P prp close func t prp close
```

Since no callbacks are defined., there are no callback related multi-thread safety issues with this property.

Vlen free function property

The call used to register the vien free function property is reproduced below with the formal parameters added as comments

```
H5P register real(pclass
                                                 // H5P genclass t *pclass,
                  H5D XFER VLEN FREE NAME, // const char *name,
                  H5D XFER VLEN FREE SIZE, // size t size,
                  &H5D_def_vlen_free_g, // const void *def_value,
                  NULL,
                                                 // H5P prp create func t prp create,
                  NULL,
                                                 // H5P prp set func t prp set,
                  NULL,
                                                 // H5P prp get func t prp get,
                  NULL,
                                                 // H5P prp encode func t prp encode,
                  NULL,
                                                 // H5P prp decode func t prp decode,
                                                 // H5P prp delete func t prp delete,
                  NULL,
                                                 // H5P_prp_copy_func_t prp_copy,
                  NULL,
                  NULL,
                                                 // H5P_prp_compare_func_t prp_cmp,
                  NULL);
                                                 // H5P prp close func t prp close
```

Since no callbacks are defined., there are no callback related multi-thread safety issues with this property.

Vlen free information property

The call used to register the vlen free information property is reproduced below with the formal parameters added as comments

```
H5P_register_real(pclass // H5P_genclass_t *pclass, H5D_XFER_VLEN_FREE_INFO_NAME, // const char *name, H5D_XFER_VLEN_FREE_INFO_SIZE, // size_t size, &H5D_def_vlen_free_info_g, // const void *def_value,
```

```
NULL,
                               // H5P prp create func t prp create,
                               // H5P prp set func t prp set,
NULL.
NULL,
                               // H5P prp get func t prp get,
NULL,
                               // H5P prp encode func t prp encode,
NULL,
                               // H5P prp decode func t prp decode,
NULL,
                               // H5P prp delete func t prp delete,
NULL.
                               // H5P prp copy func t prp copy,
NULL,
                               // H5P_prp_compare_func_t prp_cmp,
NULL);
                               // H5P prp close func t prp close
```

Since no callbacks are defined., there are no callback related multi-thread safety issues with this property.

Vector size property

The call used to register the vector size property is reproduced below with the formal parameters added as comments

```
H5P register real(pclass
                                                   // H5P genclass t *pclass,
                H5D XFER HYPER VECTOR SIZE NAME, // const char *name,
                H5D XFER HYPER VECTOR SIZE SIZE, // size t size,
                &H5D_def_hyp_vec_size_g, // const void *def_value,
                NULL,
                                                 // H5P_prp_create_func_t prp_create,
                NULL,
                                                 // H5P_prp_set_func_t prp_set,
                NULL, // H5P_prp_get_func_t prp_get, H5D_XFER_HYPER_VECTOR_SIZE_ENC, // H5P_prp_encode_func_t prp_encode,
                H5D_XFER_HYPER_VECTOR_SIZE_DEC, // H5P_prp_decode_func_t prp_decode,
                                                  // H5P_prp_delete_func_t prp_delete,
                NULL,
                NULL,
                                                  // H5P_prp_copy_func_t prp_copy,
                                                  // H5P prp compare_func_t prp_cmp,
                NULL,
                NULL);
                                                  // H5P_prp_close_func_t prp_close
```

Observe that only the encode and decode callbacks are defined.

H5D_XFER_HYPER_VECTOR_SIZE_ENC and H5D_XFER_HYPER_VECTOR_SIZE_DEC resolve to H5P__encode_size_t() and H5P__decode_size_t() respectively. Their signatures appear in H5Ppkg.h, and are reproduced below:

```
herr_t H5P__encode_size_t(const void *value, void **_pp, size_t *size);
herr t H5P decode size t(const void ** pp, void * value);
```

These two routines appear to have no potential for multi-thread issues outside of variables pointed to by their parameters. As it is assumed that appropriate mutual exclusion must be maintained on the property, the only remaining potential area of concern is the encode / decode buffer.

I/O transfer mode property (H5D_XFER_IO_XFER_MODE)

The call used to register the I/O transfer mode property (H5D_XFER_IO_XFER_MODE) is reproduced below with the formal parameters added as comments

```
H5P__register_real(pclass
                                                         // H5P genclass t *pclass,
                   H5D_XFER_IO_XFER_MODE_NAME,
H5D_XFER_IO_XFER_MODE_SIZE,
                                                        // const char *name,
                                                       // size t size,
                                                        // const void *def value,
                   &H5D def io xfer mode g,
                   NULL,
                                                        // H5P prp create_func_t prp_create,
                                                         // H5P_prp_set_func_t prp_set,
                   NULL,
                   NULL,
                                                         // H5P_prp_get_func_t prp_get,
                                                        // H5P_prp_encode_func_t prp_encode,
// H5P_prp_decode_func_t prp_decode,
// H5P_prp_delete_func_t prp_delete,
                   H5D XFER IO XFER MODE ENC,
                   H5D XFER IO XFER MODE DEC,
                   NULL,
                   NULL,
                                                         // H5P prp copy func t prp copy,
                                                         // H5P prp compare func t prp cmp,
                   NULL,
                                                         // H5P prp close func t prp close
                   NULL);
```

Observe that only the encode and decode callbacks are defined.

H5D_XFER_IO_XFER_MODE_ENC and H5D_XFER_IO_XFER_MODE_DEC resolve to H5P__dxfr_io_xfer_mode_enc() and H5P__dxfr_io_xfer_mode_dec() respectively. Their signatures appear in H5Pdxpl.c, and are reproduced below:

```
herr_t H5P__dxfr_io_xfer_mode_enc(const void *value, void **pp, size_t *size);
herr t H5P    dxfr io xfer mode dec(const void **pp, void *value);
```

These two routines appear to have no potential for multi-thread issues outside of variables pointed to by their parameters. As it is assumed that appropriate mutual exclusion must be maintained on the property, the only remaining potential area of concern is the encode / decode buffer.

I/O transfer mode property (H5D_XFER_MPIO_COLLECTIVE_OPT)

The call used to register the I/O transfer mode property (MPI Collective Optimization) is reproduced below with the formal parameters added as comments

```
H5P register real(pclass
                                                  // H5P genclass t *pclass,
              H5D XFER MPIO COLLECTIVE OPT NAME,
                                                  // const char *name,
              H5D XFER MPIO COLLECTIVE OPT SIZE, // size t size,
              &H5D def mpio collective opt mode g,// const void *def value,
                                                  // H5P prp create func t prp create,
              NULL,
              NULL,
                                                  // H5P prp set func t prp set,
              NULL,
                                                  // H5P prp get func t prp get,
                                                  // H5P_prp_encode_func_t prp_encode,
              H5D XFER MPIO COLLECTIVE OPT ENC,
              H5D XFER MPIO COLLECTIVE OPT DEC,
                                                  // H5P_prp_decode_func_t prp_decode,
                                                  // H5P_prp_delete_func_t prp_delete,
              NULL,
              NULL,
                                                  // H5P prp copy func t prp copy,
              NULL,
                                                  // H5P prp compare func t prp cmp,
                                                  // H5P prp close func t prp close
              NULL);
```

Observe that only the encode and decode callbacks are defined.

H5D_XFER_MPIO_COLLECTIVE_OPT_ENC and H5D_XFER_MPIO_COLLECTIVE_OPT_DEC resolve to H5P__dxfr_mpio_collective_opt_enc() and H5P__dxfr_mpio_collective_opt_dec() respectively. Their signatures appear in H5Pdxpl.c, and are reproduced below:

```
herr_t H5P__dxfr_mpio_collective_opt_enc(const void *value, void **pp, size_t *size);
herr_t H5P__dxfr_mpio_collective_opt_dec(const void **pp, void *value);
```

These two routines appear to have no potential for multi-thread issues outside of the variables pointed to by their parameters. As it is assumed that appropriate mutual exclusion must be maintained on the property, the only remaining potential area of concern is the encode / decode buffer.

I/O transfer mode property (H5D_XFER_MPIO_CHUNK_OPT_HARD)

The call used to register the I/O transfer mode property (H5D_XFER_MPIO_CHUNK_OPT_HARD) is reproduced below with the formal parameters added as comments

```
H5P register real(pclass
                                                     // H5P genclass t *pclass,
              H5D XFER MPIO CHUNK OPT HARD NAME,
                                                     // const char *name,
               H5D XFER MPIO CHUNK OPT HARD SIZE, // size t size,
               &H5D def mpio chunk opt mode q,
                                                     // const void *def value,
                                                     // H5P prp create func t prp create,
              NULL,
                                                     // H5P_prp_set_func_t prp_set,
              NULL,
                                                     // H5P_prp_get_func_t prp_get,
               H5D XFER MPIO CHUNK OPT HARD ENC,
                                                     // H5P_prp_encode_func_t prp_encode,
                                                     // H5P_prp_decode_func_t prp_decode,
// H5P_prp_delete_func_t prp_delete,
               H5D XFER MPIO CHUNK OPT HARD DEC,
               NULL.
               NULL,
                                                     // H5P prp copy func t prp copy,
               NULL,
                                                     // H5P prp compare func t prp cmp,
                                                     // H5P_prp_close_func_t prp_close
              NULL);
```

Observe that only the encode and decode callbacks are defined.

H5D_XFER_MPIO_CHUNK_OPT_HARD_ENC and H5D_XFER_MPIO_CHUNK_OPT_HARD_DEC resolve to H5P__dxfr_mpio_chunk_opt_hard_enc() and H5P__dxfr_mpio_chunk_opt_hard_dec() respectively. Their signatures appear in H5Pdxpl.c, and are reproduced below:

```
herr_t H5P__dxfr_mpio_chunk_opt_hard_enc(const void *value, void **pp, size_t *size);
herr_t H5P__dxfr_mpio_chunk_opt_hard_dec(const void **pp, void *value);
```

These two routines appear to have no potential for multi-thread issues outside of the variables pointed to by their parameters. As it is assumed that appropriate mutual exclusion must be maintained on the property, the only remaining potential area of concern is the encode / decode buffer.

I/O transfer mode property(H5D_XFER_MPIO_CHUNK_OPT_NUM)

The call used to register the I/O transfer mode property (H5D_XFER_MPIO_CHUNK_OPT_NUM) is reproduced below with the formal parameters added as comments

```
NULL,
                                     // H5P prp create func t prp create,
NULL,
                                     // H5P prp set func t prp set,
NULL,
                                     // H5P prp get func t prp get,
H5D XFER MPIO CHUNK OPT NUM ENC,
                                    // H5P prp encode func t prp encode,
H5D XFER MPIO CHUNK OPT NUM DEC,
                                    // H5P prp decode func t prp decode,
                                     // H5P_prp_delete_func_t prp_delete,
NULL,
NULL,
                                     // H5P_prp_copy_func_t prp_copy,
                                     // H5P_prp_compare_func_t prp_cmp,
NULL,
NULL);
                                     // H5P prp close func t prp close
```

Observe that only the encode and decode callbacks are defined.

H5D_XFER_MPIO_CHUNK_OPT_NUM_ENC and H5D_XFER_MPIO_CHUNK_OPT_NUM_DEC resolve to H5P__encode_unsigned() and H5P__decode_unsigned() respectively. Their signatures appear in H5Ppkg.h, and are reproduced below:

```
herr_t H5P__encode_unsigned(const void *value, void **_pp, size_t *size);
herr_t H5P__decode_unsigned(const void **_pp, void *value);
```

These two routines appear to have no potential for multi-thread issues outside of the variables pointed to by their parameters. As it is assumed that appropriate mutual exclusion must be maintained on the property, the only remaining potential area of concern is the encode / decode buffer.

I/O transfer mode property (H5D_XFER_MPIO_CHUNK_OPT_RATIO)

he call used to register the I/O transfer mode property (H5D_XFER_MPIO_CHUNK_OPT_RATIO) is reproduced below with the formal parameters added as comments

```
H5P register real(pclass
                                                  // H5P genclass t *pclass,
              H5D XFER MPIO CHUNK OPT RATIO NAME, // const char *name,
              H5D XFER MPIO CHUNK OPT RATIO SIZE, // size t size,
              &H5D def mpio chunk opt ratio g,
                                                  // const void *def value,
              NULL,
                                                  // H5P_prp_create_func_t prp_create,
              NULL,
                                                  // H5P_prp_set_func_t prp_set,
              NULL,
                                                  // H5P_prp_get_func_t prp_get,
              H5D XFER MPIO CHUNK OPT RATIO ENC,
                                                  // H5P_prp_encode_func_t prp_encode,
                                                  // H5P_prp_decode_func_t prp_decode,
              H5D XFER MPIO CHUNK OPT RATIO DEC,
                                                  // H5P_prp_delete_func_t prp_delete,
              NULL.
              NULL,
                                                  // H5P prp copy func t prp copy,
                                                  // H5P prp_compare_func_t prp_cmp,
              NULL.
                                                  // H5P prp close func t prp close
              NULL);
```

Observe that only the encode and decode callbacks are defined.

H5D_XFER_MPIO_CHUNK_OPT_RATIO_ENC and H5D_XFER_MPIO_CHUNK_OPT_RATIO_DEC resolve to H5P__encode_unsigned() and H5P__decode_unsigned() respectively. Their signatures appear in H5Pdxpl.c, and are reproduced below:

```
herr_t H5P__encode_unsigned(const void *value, void **_pp, size_t *size);
herr t H5P decode unsigned(const void ** pp, void *value);
```

These two routines appear to have no potential for multi-thread issues outside of the variables pointed to by their parameters. As it is assumed that appropriate mutual exclusion must be maintained on the property, the only remaining potential area of concern is the encode / decode buffer.

Chunk Optimization mode property

The call used to register the chunk optimization mode property is reproduced below with the formal parameters added as comments

```
H5P register real(pclass
                                                  // H5P genclass t *pclass,
           H5D MPIO ACTUAL CHUNK OPT MODE NAME, // const char *name,
           H5D MPIO ACTUAL CHUNK OPT MODE SIZE, // size t size,
           &H5D_def_mpio_actual_chunk_opt_mode_g, // const void *def value,
           NULL,
                                                  // H5P prp create func t prp create,
           NULL.
                                                  // H5P_prp_set_func_t prp_set,
                                                  // H5P_prp_get_func_t prp_get,
           NULL,
                                                  // H5P_prp_encode_func_t prp_encode,
           NULL,
           NULL.
                                                  // H5P_prp_decode_func_t prp_decode,
                                                  // H5P_prp_delete_func_t prp_delete,
           NULL,
                                                  // H5P prp copy func t prp copy,
           NULL,
                                                  // H5P prp compare_func_t prp_cmp,
           NULL,
                                                  // H5P prp close func t prp close
           NULL);
```

Since no callbacks are defined., there are no callback related multi-thread safety issues with this property.

Actual I/O mode property

The call used to register the actual I/O mode property is reproduced below with the formal parameters added as comments

```
// H5P_genclass_t *pclass
H5D_MPIO_ACTUAL_IO_MODE_NAME, // const char *name,
H5D_MPIO_ACTUAL_IO_MODE_SIZE, // size_t size,
&H5D_def_mpio_actual_io_mode_g, // const void *def_value,
NULL, // USD
H5P register real(pclass
                                                              // H5P genclass t *pclass,
             NULL,
                                                                // H5P_prp_create_func_t prp_create,
             NULL,
                                                                // H5P_prp_set_func_t prp_set,
                                                                // H5P_prp_get_func_t prp_get,
             NULL,
                                                                // H5P prp encode_func_t prp_encode,
             NULL,
                                                                // H5P prp_decode_func_t prp_decode,
             NULL.
                                                                // H5P prp delete func t prp delete,
             NULL.
                                                                // H5P prp copy func t prp copy,
             NULL,
              NULL,
                                                                // H5P prp compare func t prp cmp,
                                                                // H5P prp close func t prp close
```

Since no callbacks are defined., there are no callback related multi-thread safety issues with this property.

Local cause of broken collective I/O property

The call used to register the local cause of broken collective I/O property is reproduced below with the formal parameters added as comments

```
H5D MPIO LOCAL NO COLLECTIVE CAUSE NAME, // const char *name,
H5D_MPIO_NO_COLLECTIVE_CAUSE_SIZE, // size_t size,
&H5D def_mpio_no_collective_cause_g,
                                        // const void *def value,
NULL.
                                        // H5P prp create func t prp create,
NULL,
                                         // H5P prp set func t prp set,
                                         // H5P_prp_get_func_t prp_get,
NULL,
NULL,
                                         // H5P_prp_encode_func_t prp_encode,
                                         // H5P_prp_decode_func_t prp_decode,
NULL,
                                         // H5P_prp_delete_func_t prp_delete,
NULL.
NULL,
                                         // H5P_prp_copy_func_t prp_copy,
NULL,
                                         // H5P prp compare func t prp cmp,
                                         // H5P prp close func t prp close
NULL);
```

Since no callbacks are defined., there are no callback related multi-thread safety issues with this property.

Global cause of broken collective I/O property

The call used to register the global cause of broken collective I/O property is reproduced below with the formal parameters added as comments

```
H5P register real(pclass
                                                  // H5P genclass t *pclass,
       H5D MPIO GLOBAL NO COLLECTIVE CAUSE NAME, // const char *name,
       H5D MPIO_NO_COLLECTIVE_CAUSE_SIZE, // size_t size,
       &H5D def mpio no collective cause g,
                                                 // const void *def value,
       NULL,
                                                  // H5P_prp_create_func_t prp_create,
                                                  // H5P_prp_set_func_t prp_set,
       NULL,
                                                  // H5P_prp_get_func_t prp_get,
       NULL,
       NULL,
                                                  // H5P_prp_encode_func_t prp_encode,
                                                  // H5P prp decode func t prp decode,
       NULL,
                                                  // H5P_prp_delete_func_t prp_delete,
       NULL.
                                                  // H5P_prp_copy_func_t prp_copy,
       NULTI
                                                  // H5P_prp_compare_func_t prp_cmp,
       NULL,
                                                  // H5P prp close func t prp close
```

Since no callbacks are defined., there are no callback related multi-thread safety issues with this property.

EDC property

The call used to register the EDC property is reproduced below with the formal parameters added as comments

```
H5P register real(pclass
                                                  // H5P_genclass_t *pclass,
        H5D_XFER_EDC_NAME,
                                                  // const char *name,
        H5D_XFER_EDC_SIZE,
                                                  // size t size,
        &H5D def enable edc q,
                                                  // const void *def value,
                                                  // H5P prp create_func_t prp_create,
        NULL,
                                                  // H5P prp set func t prp set,
       NULL.
                                                  // H5P_prp_get_func_t prp_get,
       NULL.
        H5D XFER EDC ENC,
                                                  // H5P_prp_encode_func_t prp_encode,
        H5D XFER EDC DEC,
                                                  // H5P_prp_decode_func_t prp_decode,
                                                  // H5P prp_delete_func_t prp_delete,
        NULL,
        NULL.
                                                  // H5P_prp_copy_func_t prp_copy,
        NULL,
                                                  // H5P prp compare func t prp cmp,
        NULL);
                                                  // H5P prp close func t prp close
```

Observe that only the encode and decode callbacks are defined.

H5D_XFER_EDC_ENC and H5D_XFER_EDC_DEC resolve to H5P__dxfr_edc_enc() and H5P__dxfr_edc_dec() respectively. Their signatures appear in H5Pdxpl.c, and are reproduced below:

```
herr_t H5P__dxfr_edc_enc(const void *value, void **pp, size_t *size)
herr t H5P__dxfr_edc_dec(const void **pp, void *value);
```

These two routines appear to have no potential for multi-thread issues outside of the variables pointed to by their parameters. As it is assumed that appropriate mutual exclusion must be maintained on the property, the only remaining potential area of concern is the encode / decode buffer.

Filter callback property

The call used to register the filter callback property is reproduced below with the formal parameters added as comments

```
// H5P genclass t *pclass,
H5P register real(pclass
        H5D XFER FILTER CB NAME,
                                                  // const char *name,
        H5D XFER FILTER CB SIZE,
                                                  // size t size,
        &H5D def filter cb g,
                                                   // const void *def value,
       NULL,
                                                   // H5P_prp_create_func_t prp_create,
        NULL,
                                                   // H5P_prp_set_func_t prp_set,
                                                   // H5P_prp_get_func_t prp_get,
        NULL,
                                                   // H5P_prp_encode_func_t prp_encode,
        NULL.
                                                   // H5P_prp_decode_func_t prp_decode,
        NULL,
                                                   // H5P_prp_delete_func_t prp_delete,
        NULL,
                                                   // H5P prp copy func t prp copy,
        NULL,
                                                   // H5P prp compare func t prp cmp,
        NUT T.
        NULL);
                                                   // H5P prp close func t prp close
```

Since no callbacks are defined., there are no callback related multi-thread safety issues with this property.

Type conversion callback property

The call used to register the type conversion callback property is reproduced below with the formal parameters added as comments

```
H5P register real(pclass
                                                      // H5P_genclass_t *pclass,
        H5D XFER CONV CB NAME,
                                                     // const char *name,
                                                     // size_t size,
        H5D_XFER_CONV_CB_SIZE,
        &H5D def_conv_cb_g,
                                                     // const void *def value,
        NULL,
                                                     // H5P_prp_create_func_t prp_create,
                                                     // H5P_prp_set_func_t prp_set,
// H5P_prp_get_func_t prp_get,
        NULL,
        NULL,
                                                     // H5P_prp_encode_func_t prp_encode,
        NULL.
                                                     // H5P prp decode func t prp decode,
        NULL.
        NULLI
                                                     // H5P_prp_delete_func_t prp_delete,
                                                     // H5P prp copy func t prp copy,
        NULL,
        NULL,
                                                     // H5P prp compare func t prp cmp,
        NULL);
                                                      // H5P prp close func t prp close
```

Since no callbacks are defined., there are no callback related multi-thread safety issues with this property.

Data transform property

The call used to register the data transform property is reproduced below with the formal parameters added as comments

With the exception of create, all the property callbacks are set. The following table shows the mapping of the macros to actual function names:

H5D_XFER_XFORM_SET	H5Pdxfr_xform_set()
H5D_XFER_XFORM_GET	H5Pdxfr_xform_get()
H5D_XFER_XFORM_ENC	H5Pdxfr_xform_enc()
H5D_XFER_XFORM_DEC	H5Pdxfr_xform_dec()
H5D_XFER_XFORM_DEL	H5Pdxfr_xform_del()
H5D_XFER_XFORM_COPY	H5Pdxfr_xform_copy()
H5D_XFER_XFORM_CMP	H5Pdxfr_xform_cmp()
H5D_XFER_XFORM_CLOSE	H5Pdxfr_xform_close()

All of the above functions are defined in H5Pdxpl.c. The function signatures are reproduced below:

```
herr_t H5P__dxfr_xform_set(hid_t prop_id, const char *name, size_t size, void *value);
herr_t H5P__dxfr_xform_get(hid_t prop_id, const char *name, size_t size, void *value);
herr_t H5P__dxfr_xform_enc(const void *value, void **pp, size_t *size);
herr_t H5P__dxfr_xform_dec(const void **pp, void *value);
herr_t H5P__dxfr_xform_del(hid_t prop_id, const char *name, size_t size, void *value);
herr_t H5P__dxfr_xform_copy(const char *name, size_t size, void *value);
int H5P__dxfr_xform_cmp(const void *value1, const void *value2, size_t size);
herr_t H5P__dxfr_xform_close(const char *name, size_t size, void *value);
```

All of these functions make calls into H5Z – must evaluate for thread safety.

Dataset selection property

The call used to register the dataset selection property is reproduced below with the formal parameters added as comments

```
H5P register real (pclass
                                                      // H5P genclass t *pclass,
        H5D XFER DSET IO SEL NAME,
                                                      // const char *name,
        H5D_XFER_DSET_IO_SEL_SIZE,
                                                      // size_t size,
        &H5D def dset io sel g,
                                                      // const void *def value,
                                                      // H5P_prp_create_func_t prp_create,
        NUT T.
        NULL,
                                                      // H5P_prp_set_func_t prp_set,
        NULL,
                                                      // H5P_prp_get_func_t prp_get,
                                                      // H5P_prp_encode_func_t prp_encode,
// H5P_prp_decode_func_t prp_decode,
        NULL.
        NULL,
                                                      // H5P_prp_delete_func_t prp_delete,
        NULL.
        H5D XFER DSET IO SEL COPY,
                                                      // H5P prp copy_func_t prp_copy,
        H5D XFER DSET IO SEL CMP,
                                                     // H5P_prp_compare_func_t prp_cmp,
        H5D XFER DSET IO SEL CLOSE);
                                                     // H5P_prp_close_func_t prp_close
```

Note that the copy, compare, and close callbacks are set. The following table shows the mapping of the macros to actual function names:

H5D_XFER_DSET_IO_SEL_COPY	H5Pdxfr_dset_io_hyp_sel_copy()
H5D_XFER_DSET_IO_SEL_CMP	H5Pdxfr_dset_io_hyp_sel_cmp()
H5D_XFER_DSET_IO_SEL_CLOSE	H5Pdxfr_dset_io_hyp_sel_close()

All of the above functions are defined in H5Pdxpl.c. The function signatures are reproduced below:

All of these functions make calls into H5S. While we must make H5S thread safe eventually, that may be a while. We will need some interim solution.

File Access Property List (FAPL) Class (ROOT → FAPL)

```
/* File access property list class library initialization object */
const H5P_libclass_t H5P_CLS_FACC[1] = {{
    "file access", /* Class name for debugging */
    H5P_TYPE_FILE_ACCESS, /* Class type */

&H5P_CLS_ROOT_g, /* Parent class */
&H5P_CLS_FILE_ACCESS_g, /* Pointer to class */
&H5P_CLS_FILE_ACCESS_ID_g, /* Pointer to class ID */
&H5P_LST_FILE_ACCESS_ID_g, /* Pointer to default property list ID */
    H5P_facc_reg_prop, /* Default property registration routine */
```

```
NULL, /* Class creation callback */
NULL, /* Class creation callback info */
NULL, /* Class copy callback */
NULL, /* Class copy callback info */
NULL, /* Class close callback */
NULL /* Class close callback info */
}};
```

the File Access Property List Class has no callbacks – and hence no multi-thread safety issues.

File Mount Property List (FMPL) Class (ROOT → FMPL)

As seen from the initialization below:

```
/* File mount property list class library initialization object */
const H5P libclass t H5P CLS FMNT[1] = {{
 "file mount".
                 /* Class name for debugging
                                                */
 H5P_TYPE_FILE_MOUNT, /* Class type
 &H5P CLS ROOT g,
                          /* Parent class
 &H5P_CLS_FILE_MOUNT_g, /* Pointer to class
 &H5P_CLS_FILE_MOUNT_ID_g, /* Pointer to class ID
 &H5P LST FILE MOUNT ID g, /* Pointer to default property list ID */
                        /* Default property registration routine */
 H5P fmnt reg prop,
 NULL, /* Class creation callback
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
 NULL, /* Class copy callback info
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

the File Mount Property List Class has no callbacks – and hence no multi-thread safety issues.

VOL Initialization Property List (VIPL) Class (ROOT ->VIPL)

```
/* VOL initialization property list class library initialization object */
/* (move to proper source code file when used for real) */
const H5P_libclass_t H5P_CLS_VINI[1] = {{
    "VOL initialization", /* Class name for debugging */
    H5P_TYPE_VOL_INITIALIZE, /* Class type */

&H5P_CLS_ROOT_g, /* Parent class */
&H5P_CLS_VOL_INITIALIZE_g, /* Pointer to class */
&H5P_CLS_VOL_INITIALIZE_ID_g, /* Pointer to class ID */
&H5P_LST_VOL_INITIALIZE_ID_g, /* Pointer to default property list ID */
```

```
NULL, /* Class creation callback */
NULL, /* Class creation callback info */
NULL, /* Class creation callback info */
NULL, /* Class copy callback */
NULL, /* Class copy callback info */
NULL, /* Class close callback */
NULL, /* Class close callback info */
NULL /* Class close callback info */
}};
```

the VOL Initialization Property List Class has no callbacks – and hence no multi-thread safety issues.

Link Access Property List (LAPL) Class (ROOT → **LAPL)**

As seen from the initialization below:

```
/* Link access property list class library initialization object */
const H5P libclass t H5P CLS LACC[1] = {{
 "link access", /* Class name for debugging
 H5P_TYPE_LINK_ACCESS, /* Class type
                                                 */
 &H5P CLS ROOT g,
                           /* Parent class
 &H5P_CLS_LINK_ACCESS_g, /* Pointer to class
 &H5P_CLS_LINK_ACCESS_ID_g, /* Pointer to class ID
 &H5P LST LINK ACCESS ID g, /* Pointer to default property list ID */
                         /* Default property registration routine */
 H5P lacc reg prop,
 NULL, /* Class creation callback
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
 NULL, /* Class copy callback info */
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

the Link Access Property List Class has no callbacks – and hence no multi-thread safety issues.

Object Creation Property List (OCRTPL) Class (ROOT \rightarrow OCRTPL)

```
/* Object creation property list class library initialization object */
const H5P_libclass_t H5P_CLS_OCRT[1] = {{
    "object create", /* Class name for debugging */
    H5P_TYPE_OBJECT_CREATE, /* Class type */
```

```
&H5P_CLS_ROOT_g, /* Parent class */
&H5P_CLS_OBJECT_CREATE_g, /* Pointer to class //
&H5P_CLS_OBJECT_CREATE_ID_g, /* Pointer to class ID */
NULL, /* Pointer to default property list ID */
H5P__ocrt_reg_prop, /* Default property registration routine */
NULL, /* Class creation callback */
NULL, /* Class creation callback info */
NULL, /* Class copy callback info */
NULL, /* Class copy callback info */
NULL, /* Class close callback info */
NULL /* Class close callback info */
NULL /* Class close callback info */
NULL /* Class close callback info */
};
```

the Object Creation Property List Class has no callbacks – and hence no multi-thread safety issues.

Object Copy Property List (OCPYPL) Class (ROOT → OCPYPL)

As seen from the initialization below:

```
/* Object copy property list class library initialization object */
const H5P_libclass_t H5P_CLS_OCPY[1] = {{
 "object copy",
                  /* Class name for debugging
 H5P TYPE OBJECT COPY, /* Class type
                                                 */
 &H5P CLS ROOT g,
                           /* Parent class
 &H5P CLS OBJECT COPY g, /* Pointer to class
 &H5P CLS OBJECT COPY ID g, /* Pointer to class ID
 &H5P_LST_OBJECT_COPY_ID_g, /* Pointer to default property list ID */
                         /* Default property registration routine */
 H5P ocpy reg prop,
 NULL, /* Class creation callback
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
 NULL, /* Class copy callback info
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

the Object Copy Property List Class has no callbacks – and hence no multi-thread safety issues.

String Creation Property List (STRCRTPL) Class (ROOT→ STRCRTPL)

```
/* String creation property list class library initialization object */
const H5P_libclass_t H5P_CLS_STRCRT[1] = {{
 "string create",
                   /* Class name for debugging
 H5P TYPE STRING CREATE, /* Class type
                                                    */
 &H5P CLS ROOT g,
                            /* Parent class
 &H5P CLS STRING CREATE g, /* Pointer to class
 &H5P_CLS_STRING_CREATE_ID_g, /* Pointer to class ID
 NULL,
                    /* Pointer to default property list ID */
 H5P strcrt reg prop,
                            /* Default property registration routine */
 NULL, /* Class creation callback
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
 NULL, /* Class copy callback info
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

the String Creation Property List Class has no callbacks – and hence no multi-thread safety issues.

Datatype Access Property List (TAPL) Class (ROOT → LAPL → TAPL)

```
/* Datatype access property list class library initialization object */
/* (move to proper source code file when used for real) */
const H5P libclass t H5P CLS TACC[1] = {{
 "datatype access",
                      /* Class name for debugging
 H5P_TYPE_DATATYPE_ACCESS, /* Class type
 &H5P CLS LINK ACCESS g,
                                /* Parent class
 &H5P_CLS_DATATYPE_ACCESS_g, /* Pointer to class
 &H5P CLS DATATYPE ACCESS ID g, /* Pointer to class ID
 &H5P_LST_DATATYPE_ACCESS_ID_g, /* Pointer to default property list ID */
                     /* Default property registration routine */
 NULL,
 NULL, /* Class creation callback
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
                                  */
 NULL, /* Class copy callback info
                                   */
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

the Datatype Access Property List Class has no callbacks – and hence no multi-thread safety issues.

Attribute Access Property List (AAPL) Class (ROOT → LAPL → AAPL)

As seen from the initialization below:

```
/* Attribute access property list class library initialization object */
/* (move to proper source code file when used for real) */
const H5P libclass t H5P CLS AACC[1] = {{
 "attribute access",
                      /* Class name for debugging
 H5P_TYPE_ATTRIBUTE_ACCESS, /* Class type
 &H5P CLS LINK ACCESS g,
                                 /* Parent class
 &H5P CLS ATTRIBUTE ACCESS g, /* Pointer to class
 &H5P_CLS_ATTRIBUTE_ACCESS_ID_g, /* Pointer to class ID
 &H5P LST ATTRIBUTE ACCESS ID g, /* Pointer to default property list ID */
                     /* Default property registration
 NULL,
                    routine */
 NULL, /* Class creation callback
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
 NULL, /* Class copy callback info
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

the Attribute Access Property List Class has no callbacks – and hence no multi-thread safety issues.

Group Access Property List (GAPL) Class (ROOT \rightarrow LAPL \rightarrow GAPL)

```
/* Group access property list class library initialization object */
/* (move to proper source code file when used for real) */
const H5P_libclass_t H5P_CLS_GACC[1] = {{
    "group access", /* Class name for debugging */
    H5P_TYPE_GROUP_ACCESS, /* Class type */

&H5P_CLS_LINK_ACCESS_g, /* Parent class */
    &H5P_CLS_GROUP_ACCESS_g, /* Pointer to class */
    &H5P_CLS_GROUP_ACCESS_ID_g, /* Pointer to class ID */
    &H5P_LST_GROUP_ACCESS_ID_g, /* Pointer to default property list ID */
    NULL, /* Default property registration routine */
```

```
NULL, /* Class creation callback */
NULL, /* Class creation callback info */
NULL, /* Class copy callback */
NULL, /* Class copy callback info */
NULL, /* Class close callback */
NULL /* Class close callback info */
}};
```

the Group Access Property List Class has no callbacks – and hence no multi-thread safety issues.

Datatype Creation Property List (TCPL) Class (ROOT → OCPL → TCPL)

As seen from the initialization below:

```
/* Datatype creation property list class library initialization object */
/* (move to proper source code file when used for real) */
const H5P_libclass_t H5P_CLS_TCRT[1] = {{
 "datatype create",
                     /* Class name for debugging
 H5P TYPE DATATYPE CREATE, /* Class type
 &H5P_CLS_OBJECT_CREATE_g, /* Parent class
 &H5P CLS DATATYPE CREATE g, /* Pointer to class
 &H5P CLS DATATYPE CREATE ID g, /* Pointer to class ID
 &H5P_LST_DATATYPE_CREATE_ID_g, /* Pointer to default property list ID */
 NULL,
                    /* Default property registration routine */
 NULL, /* Class creation callback
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
 NULL, /* Class copy callback info */
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

the Datatype Creation Property List Class has no callbacks – and hence no multi-thread safety issues.

Dataset Creation Property List (DCRTPL) Class (ROOT → OCPL → DCRTPL)

```
/* Dataset creation property list class library initialization object */
const H5P_libclass_t H5P_CLS_DCRT[1] = {{
 "dataset create", /* Class name for debugging
 H5P_TYPE_DATASET_CREATE, /* Class type
                                                     */
 &H5P CLS OBJECT CREATE g, /* Parent class
                                                         */
 &H5P_CLS_DATASET_CREATE_g, /* Pointer to class
 &H5P_CLS_DATASET_CREATE_ID_g, /* Pointer to class ID
 &H5P_LST_DATASET_CREATE_ID_g, /* Pointer to default property list ID */
                           /* Default property registration routine */
 H5P dcrt reg prop,
 NULL, /* Class creation callback
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
 NULL, /* Class copy callback info
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

the Dataset Creation Property List Class has no callbacks – and hence no multi-thread safety issues.

Dataset Access Property List (DAPL) Class (ROOT → LAPL → DAPL)

```
/* Dataset access property list class library initialization object */
const H5P libclass t H5P CLS DACC[1] = {{
 "dataset access", /* Class name for debugging
                                                    */
 H5P_TYPE_DATASET_ACCESS, /* Class type
 &H5P CLS LINK ACCESS g,
                               /* Parent class
 &H5P_CLS_DATASET_ACCESS_g, /* Pointer to class
 &H5P CLS DATASET ACCESS ID g, /* Pointer to class ID
 &H5P_LST_DATASET_ACCESS_ID_g, /* Pointer to default property list ID */
                            /* Default property registration routine */
 H5P dacc reg prop,
 NULL, /* Class creation callback */
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
 NULL, /* Class copy callback info
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

the Dataset Access Property List Class has no callbacks – and hence no multi-thread safety issues.

Group Creation Property List (GCRTPL) Class (ROOT → OCRTPL → GCRTPL)

As seen from the initialization below:

```
/* Group creation property list class library initialization object */
const H5P_libclass_t H5P_CLS_GCRT[1] = {{
 "group create",
                  /* Class name for debugging
                                                   */
 H5P TYPE GROUP CREATE, /* Class type
 &H5P_CLS_OBJECT_CREATE_g, /* Parent class
 &H5P_CLS_GROUP_CREATE_g, /* Pointer to class
 &H5P_CLS_GROUP_CREATE_ID_g, /* Pointer to class ID
 &H5P LST GROUP CREATE ID g, /* Pointer to default property list ID */
                        /* Default property registration routine */
 H5P__gcrt_reg_prop,
 NULL, /* Class creation callback
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
 NULL, /* Class copy callback info
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

the Group Creation Property List Class has no callbacks – and hence no multi-thread safety issues.

Attribute Creation Property List (ACRTPL) Class (ROOT → STRCRTPL → ACRTPL)

```
/* Attribute creation property list class library initialization object */
const H5P_libclass_t H5P_CLS_ACRT[1] = {{
    "attribute create", /* Class name for debugging */
    H5P_TYPE_ATTRIBUTE_CREATE, /* Class type */

&H5P_CLS_STRING_CREATE_g, /* Parent class */
    &H5P_CLS_ATTRIBUTE_CREATE_g, /* Pointer to class */
    &H5P_CLS_ATTRIBUTE_CREATE_ID_g, /* Pointer to class ID */
    &H5P_LST_ATTRIBUTE_CREATE_ID_g, /* Pointer to default property list ID */
    NULL, /* Default property registration
```

routine */

```
NULL, /* Class creation callback */
NULL, /* Class creation callback info
NULL, /* Class copy callback */
NULL, /* Class copy callback info
NULL, /* Class close callback */
NULL /* Class close callback info
*/
};
```

the Attribute Creation Property List Class has no callbacks – and hence no multi-thread safety issues.

Link Creation Property List (LCRTPL) Class (ROOT \rightarrow STRCRTPL \rightarrow LCRTPL)

As seen from the initialization below:

```
/* Link creation property list class library initialization object */
const H5P libclass t H5P CLS LCRT[1] = {{
 "link create", /* Class name for debugging
 H5P_TYPE_LINK_CREATE, /* Class type
 &H5P_CLS_STRING_CREATE_g, /* Parent class
                                                        */
 &H5P_CLS_LINK_CREATE_g, /* Pointer to class
 &H5P_CLS_LINK_CREATE_ID_g, /* Pointer to class ID
 &H5P LST LINK CREATE ID g, /* Pointer to default property list ID */
 H5P | Icrt reg prop, /* Default property registration routine */
 NULL, /* Class creation callback
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
 NULL, /* Class copy callback info */
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

the Link Creation Property List Class has no callbacks – and hence no multi-thread safety issues.

Map Create Property List (MCRTPL) Class (ROOT → OCRTPL → MCRTPL)

```
/* Map create property list class library initialization object */
const H5P_libclass_t H5P_CLS_MCRT[1] = {{
                 /* Class name for debugging
 "map create",
 H5P TYPE MAP CREATE, /* Class type
                                                 */
 &H5P CLS OBJECT CREATE g, /* Parent class
                                                       */
 &H5P CLS MAP CREATE g, /* Pointer to class
 &H5P_CLS_MAP_CREATE_ID_g, /* Pointer to class ID
 &H5P_LST_MAP_CREATE_ID_g, /* Pointer to default property list ID */
                         /* Default property registration routine */
 H5P mcrt reg prop,
 NULL, /* Class creation callback
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
 NULL, /* Class copy callback info
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

the Map Creation Property List Class has no callbacks – and hence no multi-thread safety issues.

Map Access Property List (MAPL) Class (ROOT → LAPL → MAPL)

As seen from the initialization below:

```
/* Map access property list class library initialization object */
const H5P_libclass_t H5P_CLS_MACC[1] = {{
 "map access",
                 /* Class name for debugging
                                                 */
 H5P TYPE MAP ACCESS, /* Class type
                                                     */
 &H5P CLS LINK ACCESS g, /* Parent class
 &H5P_CLS_MAP_ACCESS_g, /* Pointer to class
 &H5P_CLS_MAP_ACCESS_ID_g, /* Pointer to class ID
 &H5P LST MAP ACCESS ID g, /* Pointer to default property list ID */
                         /* Default property registration routine */
 H5P__macc_reg_prop,
 NULL, /* Class creation callback
 NULL, /* Class creation callback info */
 NULL, /* Class copy callback
 NULL, /* Class copy callback info
 NULL, /* Class close callback
 NULL /* Class close callback info */
}};
```

the Map Access Property List Class has no callbacks – and hence no multi-thread safety issues.

Reference Access Property List (RACCPL) Class (Root → FAPL →RACCPL)

As seen from the initialization below:

```
/* Reference access property list class library initialization object */
/* (move to proper source code file when used for real) */
const H5P_libclass_t H5P_CLS_RACC[1] = {{
 "reference access", /* Class name for debugging
 H5P_TYPE_REFERENCE_ACCESS, /* Class type
 &H5P CLS FILE ACCESS g,
                               /* Parent class
                                                            */
 &H5P_CLS_REFERENCE_ACCESS_g, /* Pointer to class
 &H5P CLS REFERENCE_ACCESS_ID_g, /* Pointer to class ID
 &H5P LST REFERENCE ACCESS ID g, /* Pointer to default property list ID */
 NULL.
                     /* Default property registration routine*/
 NULL, /* Class creation callback
                                       */
 NULL. /* Class creation callback info
 NULL, /* Class copy callback
 NULL, /* Class copy callback info
                                        */
 NULL, /* Class close callback
 NULL /* Class close callback info
}};
```

the Reference Access Property List Class has no callbacks – and hence no multi-thread safety issues.

File Creation Property List (FCRTPL) Class (ROOT → OCRTPL → GCRTPL → FCRTPL)

```
/* File creation property list class library initialization object */
const H5P_libclass_t H5P_CLS_FCRT[1] = {{
    "file create", /* Class name for debugging */
    H5P_TYPE_FILE_CREATE, /* Class type */

&H5P_CLS_GROUP_CREATE_g, /* Parent class */
    &H5P_CLS_FILE_CREATE_g, /* Pointer to class */
    &H5P_CLS_FILE_CREATE_ID_g, /* Pointer to class ID */
    &H5P_LST_FILE_CREATE_ID_g, /* Pointer to default property list ID */
    H5P__fcrt_reg_prop, /* Default property registration routine */

NULL, /* Class creation callback */
```

```
NULL, /* Class creation callback info */
NULL, /* Class copy callback */
NULL, /* Class copy callback info */
NULL, /* Class close callback */
NULL /* Class close callback info */
}};
```

the File Creation Property List Class has no callbacks – and hence no multi-thread safety issues.