


QNMnonreciprocal_resonators: an openly available toolbox for computing the QuasiNormal Modes of nonreciprocal resonators

Tong Wu, Philippe Lalanne LP2N, Institut d'Optique d'Aquitaine, IOGS, Univ. Bordeaux, CNRS

> wutong1121@sina.com philippe.lalanne@institutoptique.fr

> > Last revision: June, 2021



QNMnonreciprocal_resonators is copyright (c) 2019-2029, Institut d'Optique-CNRS.

QNMnonreciprocal_resonators is an openly available COMSOL application; you can redistribute it and/or modify it under the terms of the GNU General PublicLicense as published by the Free Software Foundation, either version 3 of the License, or (at your option) any later version. It is composed of

- the present user guide document,
- QNM_Dolmen_multipole.mph(.m), a COMSOL model provided under. mph or .m extensions.

The COMSOL application is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details http://www.gnu.org/license/.

Table of contents

1. QNI	Mnonreciprocal_resonators	3
1.1 Hc	ow to acknowledge and cite	3
1.2 Ur	nits and conventions of input/output data for QNMnonreciprocal_resonators	3
1.3 Ou	utline of the theoretical background	3
2. The	permittivity and permeability of Yttrium iron garnet	5
3. A Tu	utorial: Computing QNMs for a YIG wire in AIR	5
2.1 Mc	odeling Instructions	5
4. Refe	erences	16

1. QNMNONRECIPROCAL_RESONATORS

QNMnonreciprocal_resonators is an extension (posted in 2021) of the **QNMEig** solver of the freeware package **MAN**. It provides a comprehensive presentation of the computation and normalization of electromagnetic quasinormal modes (QNMs) of resonators composed of nonreciprocal materials. It features a theoretical background on the topic and a COMSOL model that illustrates how to put into practice the theory on the example of a Yttrium iron garnet wire in a homogenous background. This document provides the necessary details on how the model is built so that the interested readers may easily modify it for computing QNMs of other nonreciprocal resonators.

The present model has been successfully tested with another COMSOL model operating with **QNMpole**, the second QNM solver of **MAN** that performs a pole search gradient descent algorithm to compute and normalize QNMs [1]. The corresponding COMSOL model and Matlab programs used in the **QNMpole** are also included in the version 7.2 of MAN and following ones.

1.1 How to acknowledge and cite

We kindly ask that you reference the **MAN** package from IOGS-CNRS and its authors in any publication/report for which you used it. The preferred citation for **QNMnonreciprocal_resonators** is the following paper:

Wu, T.; Gurioli, M.; Lalanne, P. "Nanoscale Light Confinement: the Q's and V's", *ACS Photonics* **2021**, (https://doi.org/10.1021/acsphotonics.1c00336).

1.2 Units and conventions of input/output data for QNMnonreciprocal_resonators

Unit. All the input information is required to be in the **SI unit**. Accordingly, the output information is given in the SI unit as well.

Convention. The time-dependent terms $\exp(i\omega t)$ are used in the COMSOL model provided in this toolbox. We use $\exp(-i\omega t)$ convention for the formulas in Sections 1.3 and 2.

1.3 Outline of the theoretical background

The Section is organized as follows. It starts with the classical derivation of a general form of the Lorentz reciprocity theorem. The theorem is then used to normalize the modes and introduce the definition of the mode volume. Unlike our previous work [2,3], we do not assume reciprocity, namely, the formulas are valid for systems with $\bar{\mu}^T \neq \bar{\mu}$ or $\bar{\epsilon}^T \neq \bar{\epsilon}$ (the uperspcript T being the transpose operator). The theory presented here can be viewed as an extension of Supplementary Material 1 of ref. [2]. Related works may also be found in refs. [4,5].

1.3.1 Unconjugated form of Lorentz reciprocity theorem for nonreciprocal systems

We consider systems satisfying the following Maxwell's equations:

$$\nabla \times \mathbf{E}_{i} = i\omega_{i}\bar{\mu}_{i}\mathbf{H}_{i}$$

$$\nabla \times \mathbf{H}_{i} = -i\omega_{i}\bar{\varepsilon}_{i}\mathbf{E}_{i} - i\omega_{i}\mathbf{p}_{i},$$
which features a source term $-i\omega_{i}\mathbf{p}_{i}$. (1)

Lorentz reciprocity theorem relates two different solutions of Maxwell's equations, $(\mathbf{E}_1, \mathbf{H}_1, \omega_1, \mathbf{p}_1, \bar{\epsilon}_1, \bar{\mu}_1)$ and $(\mathbf{E}_2, \mathbf{H}_2, \omega_2, \mathbf{p}_2, \bar{\epsilon}_2, \bar{\mu}_2)$ labeled by indices 1 and 2. It is derived by applying the divergence theorem to the vector $\mathbf{E}_2 \times \mathbf{H}_1 - \mathbf{E}_1 \times \mathbf{H}_2$ and by using Eq. (1),

$$\iint_{\Sigma} (\mathbf{E}_{2} \times \mathbf{H}_{1} - \mathbf{E}_{1} \times \mathbf{H}_{2}) \cdot d\mathbf{S} = i \iiint_{\Omega} \mathbf{H}_{1} \cdot [\omega_{2} \bar{\mu}_{2} - \omega_{1} \bar{\mu}_{1}^{T}] \cdot \mathbf{H}_{2} - \mathbf{E}_{1} \cdot [\omega_{2} \bar{\varepsilon}_{2} - \omega_{1} \bar{\varepsilon}_{1}^{T}] \cdot \mathbf{E}_{2} + (\omega_{1} \mathbf{p}_{1} \cdot \mathbf{E}_{2} - \omega_{2} \mathbf{p}_{2} \cdot \mathbf{E}_{1}) dV,$$
(2)

where Σ is an arbitrarily closed surface defining a volume Ω .

1.3.2 QNM orthogonality

Lorentz reciprocity theorem can also be used to show that the QNMs satisfy an unconjugated orthogonality relation.

For that purpose, we set the second solution as the n^{th} QNM of a system with a permittivity $\bar{\epsilon}$ and permeability $\bar{\mu}$, that is $(\mathbf{E}_2,\mathbf{H}_2,\omega_2,\mathbf{p}_2,\bar{\epsilon}_2,\bar{\mu}_2)=(\tilde{\mathbf{E}}_n^{(R)},\tilde{\mathbf{H}}_n^{(R)},\tilde{\omega}_n^{(R)},\mathbf{0},\bar{\epsilon},\bar{\mu})$, whereas the first solution corresponds to the m^{th} QNM of a system with a permittivity $\bar{\epsilon}^T$ and permeability $\bar{\mu}^T$, that is $(\mathbf{E}_1,\mathbf{H}_1,\omega_1,\mathbf{p}_1,\bar{\epsilon}_1,\bar{\mu}_1)=(\tilde{\mathbf{E}}_m^{(L)},\tilde{\mathbf{H}}_m^{(L)},\tilde{\omega}_m^{(L)},\mathbf{0},\bar{\epsilon}^T,\bar{\mu}^T)$. QNMs have divergent fields far away from the resonator and their treatment in a "generalized" Hilbert space requires regularization. We chose to regularize QNM with perfectly matched layers (PMLs) [2]. Thus, we choose the integral domain Ω to be

the whole space including the PML regions so that Σ represents the outer surfaces of PMLs, which are made of perfect electric/magnetic conductors in practice. Perfect electric/magnetic conductors impose zero tangential components of electric/magnetic fields on Σ . As a result, the surface integral on the left-hand-side of Eq. (2) vanishes [3], and this leads to a simple volume integral relation

$$\iiint_{\Omega} \widetilde{\mathbf{H}}_{m}^{(L)} \cdot [\widetilde{\omega}_{n} \bar{\bar{\mu}}(\widetilde{\omega}_{n}) - \widetilde{\omega}_{m} \bar{\bar{\mu}}(\widetilde{\omega}_{m})] \cdot \widetilde{\mathbf{H}}_{n}^{(R)} - \widetilde{\mathbf{E}}_{m}^{(L)} \cdot [\widetilde{\omega}_{n} \bar{\bar{\epsilon}}(\widetilde{\omega}_{n}) - \widetilde{\omega}_{m} \bar{\bar{\epsilon}}(\widetilde{\omega}_{m})] \cdot \widetilde{\mathbf{E}}_{n}^{(R)} dV = 0.$$
(3)

Note that, for nonreciprocal systems, $\widetilde{\mathbf{H}}_n^{(L)} \neq \widetilde{\mathbf{H}}_n^{(R)}$ and $\widetilde{\mathbf{E}}_n^{(L)} \neq \widetilde{\mathbf{E}}_n^{(R)}$, but they share the same eigenvalues, that is $\widetilde{\omega}_n^{(R)} = \widetilde{\omega}_n^{(L)} = \widetilde{\omega}_n$ [5]. In the following part of the document, we refer to $(\widetilde{\mathbf{H}}_m^{(L)}, \widetilde{\mathbf{E}}_m^{(L)})$ as the left QNM and $(\widetilde{\mathbf{H}}_n^{(R)}, \widetilde{\mathbf{E}}_n^{(R)})$ as the right QNM.

Equation (3) is the orthogonality relation. Note that the permittivity and permeability are those of the actual (real) system without transposition. However, the orthogonality requires two fully independent computations, one for the real system QNMs and a second one for the transposed system. This is not the case for reciprocal materials.

1.3.3 The modal excitation coefficients and mode volumes

With the knowledge of the orthogonality of QNMs, we now discuss how to compute the QNM excitation coefficients. We consider a single electric dipole $\bf p$ located at $\bf r_0$ in the vicinity of a resonator. The dipole radiates a field ($\bf E, \bf H$) at the real frequency ω . Owning to the completeness [3], we are able to expand the field everywhere in the PMLized space

$$\mathbf{E}(\mathbf{r},\omega) = \sum_{m} \alpha_{m}(\omega) \tilde{\mathbf{E}}_{m}^{(R)}(\mathbf{r}), \tag{4}$$

where α_m are complex coefficients to be determined.

By applying Eq. (2) to the total field (**E**, **H**) created by the dipole at the frequency ω and to the n^{th} left QNM ($\tilde{\mathbf{E}}_n^{(L)}$, $\tilde{\mathbf{H}}_n^{(L)}$), and using the modal expansion of Eq. (4), we obtain a linear system of equations $\sum_m B_{nm}(\omega) \alpha_m(\omega) = -\omega \mathbf{p} \cdot \tilde{\mathbf{E}}_n^{(L)}(\mathbf{r}_0)$, where the frequency-dependent coefficient B_{nm} is given by

$$B_{nm} = \iiint_{\Omega} \widetilde{\mathbf{H}}_{n}^{(L)} \cdot [\widetilde{\omega}_{n} \bar{\bar{\mu}}(\widetilde{\omega}_{n}) - \omega \bar{\bar{\mu}}(\omega)] \cdot \widetilde{\mathbf{H}}_{m}^{(R)} - \widetilde{\mathbf{E}}_{n}^{(L)} \cdot [\widetilde{\omega}_{n} \bar{\bar{\varepsilon}}(\widetilde{\omega}_{n}) - \omega \bar{\bar{\varepsilon}}(\omega)] \cdot \widetilde{\mathbf{E}}_{m}^{(R)} dV.$$
 (5)

In the absence of dispersion, all the non-diagonal terms are vanished according to Eq. (3) and the expansion coefficient is analytically given by

$$\alpha_n(\omega) = -\frac{\omega_{\mathbf{p}} \tilde{\mathbf{E}}_n^{(L)}(\mathbf{r}_0)}{(\omega - \tilde{\omega}_n) \iiint_{\Omega} \tilde{\mathbf{E}}_n^{(L)} \cdot \bar{\mathbf{e}} \cdot \tilde{\mathbf{E}}_n^{(R)} - \tilde{\mathbf{H}}_n^{(L)} \cdot \bar{\boldsymbol{\mu}} \cdot \tilde{\mathbf{H}}_n^{(R)} dV}.$$
(6)

In the general case of dispersive media, the off-diagonal coefficients B_{nm} are not equal to zero. One thus has to solve a linear system of equations to obtain α_m . To guarantee a safe and accurate numerical implementation, we note that B_{nm} is null for $\omega = \widetilde{\omega}_m$, and we introduce $A_{nm} = (\omega - \widetilde{\omega}_m)^{-1}B_{nm}$, so that the linear system of equations can be rewritten as

$$\sum_{m} A_{nm}(\omega) x_{m}(\omega) = -\omega \mathbf{p} \cdot \tilde{\mathbf{E}}_{n}^{(L)}, \tag{7}$$

where the unknowns are now $x_m(\omega) = (\omega - \widetilde{\omega}_m)\alpha_m(\omega)$.

The linear system Eq. (7) is not diagonal, and it is not possible in general to derive a closed-form expression. However, we can still show that α_m has a pole and use this property to derive an approximate analytical expression. For $\omega \approx \widetilde{\omega}_n$, since $A_{nm}(\widetilde{\omega}_n) = 0$ for $n \neq m$ according to Eq. (3), we therefore find

$$\alpha_n(\omega) \approx -\frac{\omega_{\mathbf{p}} \tilde{\mathbf{E}}_n^{(L)}(\mathbf{r}_0)}{(\omega - \tilde{\omega}_n) \iiint_{\Omega} \tilde{\mathbf{E}}_n^{(L)} \frac{\partial (\omega \bar{\mathbf{p}})}{\partial \omega} \cdot \tilde{\mathbf{E}}_n^{(R)} - \tilde{\mathbf{H}}_n^{(L)} \frac{\partial (\omega \bar{\mathbf{p}})}{\partial \omega} \cdot \tilde{\mathbf{H}}_n^{(R)} dv}.$$
(8)

We thus obtain an approximate closed-form expression for α_n valid in the vicinity of $\widetilde{\omega}_n$. To derive Eqs. (6-8), we have strictly followed the approach in [2]. The approximate Eq. (8) has been successfully used in many earlier works starting with [2]. It is convenient, but it could also be set into a rigorous format. Using auxiliary fields to linearize the nonlinear eigenvalue problem of Eq. (1) (which is nonlinear in ω for dispersive material), we may derive an exact analytical expression for the excitation coefficients. This machinery that is described in [3] is not provided here for the sake of simplicity.

1.3.4 Mode volume

The Purcell factor is the modification of the spontaneous decay rate due to the resonance. Following [2], it is easily shown that the non-Hermitian Purcell factor F_n of the resonance $\tilde{\mathbf{E}}_n^{(R)}$ (i.e. the) is

$$F_n = \frac{3}{4\pi^2} \left(\frac{\lambda_n}{n_b}\right)^3 \operatorname{Re}\left(\frac{Q_n}{\widetilde{V}_n}\right) \frac{\Omega_n^2}{\omega^2} \frac{\Omega_n^2}{4Q_m^2(\omega - \Omega_n)^2 + \Omega_n^2} \left[1 + 2Q_n \frac{\omega - \Omega_n}{\Omega_n} \frac{\operatorname{Im}(\widetilde{V}_n)}{\operatorname{Re}(\widetilde{V}_n)}\right],\tag{9}$$

and that the mode volume is given

$$\tilde{V}_{n} = \frac{\iiint_{\Omega} \tilde{\mathbf{E}}_{n}^{(L)} \frac{\partial (\omega \bar{\mathbf{E}})}{\partial \omega} \cdot \tilde{\mathbf{E}}_{n}^{(R)} - \tilde{\mathbf{H}}_{n}^{(L)} \frac{\partial (\omega \bar{\mathbf{E}})}{\partial \omega} \tilde{\mathbf{H}}_{n}^{(R)} dV}{2\varepsilon(\mathbf{r}_{0}) \left[\mathbf{p} \cdot \tilde{\mathbf{E}}_{n}^{(L)}\right] \left[\mathbf{p} \cdot \tilde{\mathbf{E}}_{n}^{(R)}\right]}.$$
(10)

The Purcell factor takes a form similar to that of the classical expression derived in a Hermitian framework, except for the last bracketed term. $Q_n = \Omega_n/\Gamma_n$ is the quality factor of the mode with complex eigenfrequency $\widetilde{\omega}_n = \Omega_n - i\Gamma_n/2$. n_b is the background refractive index at the dipole position. $\lambda_n = 0$ $2\pi c/\Omega_n$ is the resonance wavelength.

We, therefore, can define the normalization factor as

$$QN = \iiint_{\Omega} \widetilde{\mathbf{E}}_{n}^{(L)} \cdot \frac{\partial(\omega\bar{\varepsilon})}{\partial\omega} \cdot \widetilde{\mathbf{E}}_{n}^{(R)} - \widetilde{\mathbf{H}}_{n}^{(L)} \cdot \frac{\partial(\omega\bar{\mu})}{\partial\omega} \cdot \widetilde{\mathbf{H}}_{n}^{(R)} dV. \tag{11}$$

Equation (10) is very similar to that derived for reciprocal resonators in [2]. Note that the expression is unchanged by scaling either $[\mathbf{\tilde{E}}_{n}^{(L)},\,\mathbf{\tilde{H}}_{n}^{(L)}]$ or $[\mathbf{\tilde{E}}_{n}^{(R)},\,\mathbf{\tilde{H}}_{n}^{(R)}]$ by any multiplicative factor, as expected.

Note that Eq. (10) is identical to the expression given at the end of the 'Summary and Perspectives' Section in [6]; the present document thus provides a demonstration of the expression that was not demonstrated in [6] for compactness.

2. THE PERMITTIVITY AND PERMEABILITY OF YTTRIUM IRON GARNET

In this toolbox, we consider a simple case of a 2D Yttrium iron garnet (YIG) wire in a homogenous background. The users may easily extend it for studying resonators with other materials, dimensions, and geometries following the steps given in the next Tutorial section.

Under an external dc magnetic field along the z direction, the YIG exhibits a strong gyromagnetic anisotropy, with the relative permeability tensor taking the form

$$\bar{\bar{\mu}} = \begin{bmatrix} \mu_r & -i\kappa_r & 0\\ i\kappa_r & \mu_r & 0\\ 0 & 0 & \mu_{\infty} \end{bmatrix} \mu_0, \tag{12}$$

where the matrix elements μ_r and κ_r are determined by the Landau-Lifshitz-Gilbert equation and can be expressed as [7]

$$\mu_r = \mu_{\infty} \left[1 + \frac{(\omega_H - i\alpha\omega)\omega_M}{(\omega_H - i\alpha\omega)^2 - \omega^2} \right],\tag{13}$$

and
$$\kappa_r = \frac{\mu_\infty \omega \omega_M}{(\omega_H - i\alpha\omega)^2 - \omega^2}, \tag{14}$$

where $\mu_{\infty}=1$, α is the damping parameter, $\omega_{H}=\gamma H_{0}$, $\omega_{M}=\gamma M_{s}$ with γ and M_{s} being the gyromagnetic ratio and saturated magnetization, respectively, H_0 being the external static magnetic field which leads to broken time-reversal symmetry. On the other hand, the YIG permittivity is taken as a constant scalar $\bar{\varepsilon} = \varepsilon_r \varepsilon_0 \operatorname{diag}(1,1,1)$.

At last, note the simple relation [8]

$$\bar{\mu}^{-1} = \begin{bmatrix} d & -ib & 0 \\ ib & d & 0 \\ 0 & 0 & \mu_{\infty}^{-1} \end{bmatrix} \mu_0^{-1},\tag{15}$$

where $d = \mu_r/(\mu_r^2 - \kappa_r^2)$ and $b = -\kappa_r/(\mu_r^2 - \kappa_r^2)$, which may help to derive the weak form expression

3. A TUTORIAL: COMPUTING QNMs FOR A YIG WIRE IN AIR

In this part, we provide details on how to compute the QNMs of a classical nonreciprocal resonator, a YIG wire in a homogenous background. Note that in QNMEig, there are already several welldocumented examples for computing modes for dispersive resonators. However, they are all limited to systems with reciprocal materials, and QNMnonreciprocal resonators can be considered as an extension of the **QNMEig** for non-reciprocal systems.

2.1 Modeling Instructions

Open COMSOL Multiphysics. From its File menu, choose New.


NEW

In the New window, click Model Wizard.

MODEL WIZARD

Since we need to compute both the left and right QNMs, unlike the other models in **QNMEig**, here we need two emws and two weak form PDEs.

- 1. In the Model Wizard window, click 2D.
- 2. In the Select physics tree, select Radio Frequency->Electromagnetic Waves, Frequency Domain (emw).
- Click Add.
- 4. In the Select physics tree, select Mathematics->PDE Interfaces, Weak Form PDE (w).
- 5. Click Add.
- 6. In the Select physics tree, select Radio Frequency->Electromagnetic Waves, Frequency Domain (emw).
- 7. Click Add.
- 8. In the Select physics tree, select Mathematics->PDE Interfaces, Weak Form PDE (w).
- 9. Click Add.
- 10. Click Study
- 11. In the Select Study tree, select Preset Studies for Selected Physics Interfaces>Eigenfrequency
- 12. Click Done



Here the 'emw2' and 'w2' are built for computing the left QNM.

GLOBAL DEFINITIONS

Define the model geometric and material parameters.

Parameters 1

- 1. In the Model Builder window, under Global Definitions click Parameters 1.
- 2. In the **Settings** window for the **Parameters**, locate the **Parameters** section.
- 3. In the table, enter the following settings:

Name	Expression	Description
Lair	a*1.5	Geom: air background width
r	0.35*a	Geom: wire radius
Lpml	a/4	Geom: PML thickness
а	26[mm]	Geom: length of the air domain
epsrinf	15	Material: permittivity of YIG
murinf	1	Material: mu_inf given in section 2
epsilonb	1	Material: permittivity of the background medium
lambda_pml	c_const/freqg	Material: typical absorbing wavelength of PMLs
freqg	8.8466 [GHz]	Freq: frequency to search for QNMs
Nomega	(freqg*2*pi)	Freq: normalization factor for the weak form

The Nomega can be set as an arbitrary value but should be of the same order of freqg*2*pi. It is used in the auxiliary-field equation of the Weak Form PDE module (see later) to make the two equations of the quadratic polynomial eigenproblem [3] have similar magnitudes, thereby increasing the numerical stabilities.

Parameters 2

- 4. In the Model Builder window, right-click Global Definitions and select Parameters.
- 5. Type YIG materials in the Label text field.
- 6. In the Settings window for Parameters 2, locate the Parameters section.
- 7. In the table, enter the following settings:

Name	Expression	Description
omegam1	175[mT]*gamma1	Material: omega_m given in section 2
omega01	gamma1*Hs1*mu0_const	Material: omega_0 given in section 2
Hs1	900[Oe]	Material: H0 given in section 2
gamma1	2*pi*28[GHz/T]	Material: gamma given in section 2
alpha1	3e-4	Material: alpha given in section 2

This table gives the parameters which are used to compute the $\bar{\mu}$ of YIG.

GEOMETRY


The geometry consists of a YIG wire in air background, surrounded by a PML.

Circle 1

- 1. In the Geometry toolbar, click Circle.
- 2. In the **Settings** window for **Circle**, locate the **Size and Shape** section.
- 3. In the Radius text field, type r.

Rectangle 1

- 4. In the **Geometry** toolbar, click **Rectangle**.
- 5. In the **Settings** window for **Rectangle**, locate the **Size and Shape** section.
- 6. In the Width text field, type Lair+Lpml*2.
- 7. In the **Height** text field, type Lair+Lpml*2.
- 8. Locate the **Position** section. From the **Base** list, select **Center**.
- 9. Locate the **Layers** section. In the **Layer 1** text field, type Lpml.
- 10. Choose Layers to the left, Layers to the right, Layers on bottom, and Layers on top checkboxes.
- 11. Click the Build All Objects.



The geometry of the system: a YIG wire in air background, surrounded by a PML.

DEFINITIONS

Define PML domains and PML types. Define the resonator and background. Define different variables used for normalizing the QNMs.

Explicit 1

- 1. In the **Definitions** toolbar, click **Explicit**.
- 2. In the **Settings** window for **Explicit**, type PML in the **Label** text field.
- 3. Set Domains 1, 2, 3, 4, 6, 7, 8, 9.

Explicit 2

- 4. In the **Definitions** toolbar, click **Explicit**.
- 5. In the **Settings** window for Explicit, type sca in the **Label** text field.
- 6. Set Domain 10 only.

Explicit 3

- 7. In the **Definitions** toolbar, click **Explicit**.
- 8. In the **Settings** window for **Explicit**, type Air background and its attached PML in the **Label** text field.
- 9. Set Domains 1, 2, 3, 4, 5, 6, 7, 8, 9.

Perfectly matched layers

We model the PML as a non-dispersive material.

- 10. In the **Definitions** toolbar, click **Perfectly Matched Layer**.
- 11. In the Settings window for Perfectly Matched Layer, locate the Domain Selection section.
- 12. From the Selection list, choose PML.
- 13. Locate the **Geometry** section. From the **Type** list, select **Cartesian**.
- 14. Locate the Scaling section. From the Typical wavelength from list, choose User defined.
- 15. In **Typical wavelength** text field, type lambda_pml.

Variables 1

Here we define the complex eigenfrequencies that will be used in the weak form later.

- 16. On the **Definitions** toolbar, click **Variables**.
- 17. In the **Settings** window for Variables, locate the **Geometric Entity Selection** section.
- 18. Locate the **Variables** section. In the table, enter the following settings:

Name	Expression	Description
QNM_omega	emw.iomega/i	Complex eigenfrequency of E^L
QNM_omega2	emw2.iomega/i	Complex eigenfrequency of E^R

Variables 2

Just like in the post-processing step, we are going to use values of the auxiliary fields everywhere, thereby defining them to be 0 outside the resonator.

- 19. In the **Definitions** toolbar, click **Variables**.
- 20. In the Settings window for Variables, locate the Geometric Entity Selection section.
- 21. From the Geometric entity level list, choose Domain.
- 22. From the Selection list, choose Air background and its attached PML.
- 23. Locate the Variables section. In the table, enter the following settings:

Name	Expression	Description
M1x	0[V/m^2]	Auxiliary field M1x in Air domain
M1y	0[V/m^2]	Auxiliary field M1y in Air domain
N1x	0[V/m^2]	Auxiliary field N1x in Air domain
N1y	0[V/m^2]	Auxiliary field N1y in Air domain

Variables 3

Define the analytical expression of $\partial(\omega\bar{\mu})/\partial\omega\widetilde{\mathbf{H}}_n^{(R)}$. Its three components are given by dwudwH_x, dwudwH_y, and dwudwH_z. These values will be used later to compute QN.

- 24. In the **Definitions** toolbar, click **Variables**.
- 25. In the Settings window for Variables, locate the Geometric Entity Selection section.
- 26. From the **Geometric entity level** list, choose **Domain**.
- 27. From the **Selection** list, choose **sca**.
- 28. Locate the **Variables** section. In the table, enter the following settings:

Name	Expression	Description
fac1	i*alpha1*w2+omega01+omegam1	
fac3	i*w2*omegam1	
fac2	i*alpha1*w2+omega01	
lowduinvu	(w2^2-fac1^2)*(w2^2-fac2^2)	
fac4	(2*omega01+omegam1)*w2*(1+alpha1^2)	
fac5	i*alpha1*((1+alpha1^2)*w2^2-omega01*(omega01+omegam1))	
upduinvu11	omegam1*(fac4+fac5)	
upduinvu12	i*omegam1*((1+alpha1^2)*w2^2+omega01*(omega01+omegam1))	
dwudw11	1/w2+upduinvu11/lowduinvu	
dwudw12	upduinvu12/lowduinvu	
dwudw21	-upduinvu12/lowduinvu	
dwudw22	1/w2+upduinvu11/lowduinvu	
dwudwH_x	(dwudw11*cERx+dwudw12*cERy)/(-i)/mu0_const	
dwudwH_y	(dwudw21*cERx+dwudw22*cERy)/(-i)/mu0_const	
dwudwH_z	cERz/w2/(-i)/mu0_const	

Variables 4

Define the analytical expression of $\partial(\omega \bar{\mu})/\partial\omega \tilde{\mathbf{H}}_n^{(R)}$ outside the resonator.

- 29. In the **Definitions** toolbar, click **Variables**.
- 30. In the **Settings** window for Variables, locate the **Geometric Entity Selection** section.
- 31. From the Geometric entity level list, choose Domain.
- 32. From the Selection list, choose Air background and its attached PML.
- 33. Locate the **Variables** section. In the table, enter the following settings:

Name	Expression	Description
dwudwH_x	HRx	
dwudwH_y	HRy	
dwudwH_z	HRz	
Variables 5		

Since we have changed the weak form, emw(2).Hx, emw(2).Hy, and emw(2).Hz no longer give the correct magnetic fields. HLx, HLy, and HLz are the correct magnetic field for the left QNMs. HRx, HRy, and HRz are the correct magnetic field for the right QNMs. We also give the curl of $\tilde{\mathbf{E}}_n^{(R)}$, cERx, cERy, and cERz.

- 34. On the **Definitions** toolbar, click **Variables**.
- 35. In the Settings window for Variables, locate the Geometric Entity Selection section.
- 36. Locate the **Variables** section. In the table, enter the following settings:

Name	Expression	Description
W	emw.iomega/i	
w2	emw2.iomega/i	
HLx	1/(-i*w*mu0_const)*(M1x+emw.curlEx*invmuinf)	
HLy	1/(-i*w*mu0_const)*(M1y+emw.curlEy*invmuinf)	
HLz	1/(-i*w*mu0_const)*(emw.curlEz*invmuinf)	
invmuinf	(murinf)^(-1)	
cERx	emw2.curlEx	
cERy	emw2.curlEy	
cERz	emw2.curlEz	
HRx	1/(-i*w2*mu0_const)*(N1x+emw2.curlEx*invmuinf)	
HRy	1/(-i*w2*mu0_const)*(N1y+emw2.curlEy*invmuinf)	
HRz	1/(-i*w2*mu0_const)*(emw2.curlEz*invmuinf)	

Variables 6

Define the numerical expression of $\partial(\omega\bar{\mu})/\partial\omega\widetilde{\mathbf{H}}_n^{(R)}$. In contrast to **Variables 3**, here these values are computed numerically.

- 37. In the **Definitions** toolbar, click **Variables**.
- 38. In the **Settings** window for Variables, locate the **Geometric Entity Selection** section.
- 39. From the Geometric entity level list, choose Domain.
- 40. From the **Selection** list, choose **sca**.
- 41. Locate the **Variables** section. In the table, enter the following settings:

Name	Expression	Description
mur_YIG	murinf+murinf*omegam1*(omega01+i*alpha1*w2)/((ome ga01+i*alpha1*w2)/2-w2^2)	
kappa_YIG	omegam1*w2/((omega01+i*alpha1*w2)^2-w2^2)*murinf	
dwkappa_YIG	d(kappa_YIG*w2,w2)	
dmur_YIG	d(mur_YIG*w2,w2)	
dmu11	dmur_YIG	
dmu12	dwkappa_YIG*i	
dmu21	-dwkappa_YIG*i	
dmu22	dmur_YIG	
duwHx	dmu11*HRx+dmu12*HRy	
duwHy	dmu21*HRx+dmu22*HRy	
duwHz	HRz	

Variables 7

Define the numerical expression of $\partial(\omega \bar{H}_n)/\partial\omega \tilde{H}_n^{(R)}$ outside the resonator.

- 42. In the **Definitions** toolbar, click **Variables**.
- 43. In the **Settings** window for Variables, locate the **Geometric Entity Selection** section.
- 44. From the Geometric entity level list, choose Domain.
- 45. From the Selection list, choose Air background and its attached PML.
- 46. Locate the **Variables** section. In the table, enter the following settings:

Name	Expression	Description
duwHx	HRx	
duwHy	HRy	
duwHz	HRz	

ELECTROMAGNETIC WAVES, FREQUENCY DOMAIN (emw)

emw and w are used to solve for the left QNMs. Here we only consider the case where the electric field component of the QNM is polarized along z axis.

- In the Settings window for Electromagnetic Waves, Frequency Domain, locate the Components section.
- 2. From the Electric field components solved for list, choose Out-of-plane vector.
- 3. On the top of the **Modal Builder** window, click **Show** option (the one with an eye icon), select at least **Advanced Physics and Discretization options**.
- 4. In the Physics toolbar, select Electromagnetic Waves, Frequency Domain (emw).
- 5. In the **Settings** window for **Electromagnetic Waves**, **Frequency Domain (emw)**, locate the Domain Selection section.
- 6. From the **Selection** list, choose **All Domains**.

Weak contribution 1

Here we define the weak contribution. Inside the resonator COMSOL solve the integration equation: $\int_{V} \nabla \times \mathbf{F}(\mathbf{r}) \cdot \mu_{\infty}^{-1} \nabla \times \widetilde{\mathbf{E}}_{n}^{(L)}(\mathbf{r}) - \widetilde{\omega}_{n}^{2} \mathbf{F} \cdot \varepsilon \widetilde{\mathbf{E}}_{n}^{(L)}(\mathbf{r}) + \nabla \times \mathbf{F}(\mathbf{r}) \cdot \mathbf{M} \ (\mathbf{r}) dV = 0 \quad \text{with} \quad \mathbf{M}(\mathbf{r}) = ((\bar{\mu}^{T})^{-1} - \mu_{\infty}^{-1}) \nabla \times \widetilde{\mathbf{E}}_{n}^{(L)}(\mathbf{r}).$ The first and second terms are defined in **Wave Equation, Electric**, whereas the third term is difined in **Weak contribution 1**.

- 7. In the Physics toolbar, from the Domains section list, choose Weak Contribution.
- 8. From the **Selection** list, choose **sca**.
- 9. In **Weak expression** text field, type -M1x*test(emw.curlEx)-M1y*test(emw.curlEy).

Wave Equation, Electric 1

The weak expression for the resonator domain.

- 10. In the **Settings** window for **Wave Equation, Electric 1**, locate the **Electric Displacement Field** section.
- 11. From the Electric displacement field model list, choose Relative permittivity.
- 12. From Relative permittivity list, choose User defined. In the text field, enter epsrinf.
- 13. In the **Settings** window for **Variables**, locate the **Magnetic Field** section.
- 14. From the Constitutive relation, choose Relative permeability.
- 15. From Relative permeability list, choose User defined. In the text field, enter murinf.
- 16. In the Settings window for Variables, locate the Conduction Current section.
- 17. From the Electric conductivity, choose User defined. In the text field, enter 0.

Wave Equation, Electric 2

The weak expression for the background domain.

- 18. In the Physics toolbar, from the Domains section list, choose Wave Equation, Electric.
- 19. In the Settings window for Wave Equation, Electric 2, locate Domain Selection section.
- 20. From the Selection list, choose Air background and its attached PML.
- 21. From the Electric displacement field model list, choose Relative permittivity.
- 22. From Relative permittivity list, choose User defined. In the text field, enter epsilonb.
- 23. In the Settings window for Variables, locate the Magnetic Field section.
- 24. From the Constitutive relation, choose Relative permeability.
- 25. From Relative permeability list, choose User defined. In the text field, enter 1.
- 26. In the Settings window for Variables, locate the Conduction Current section.
- 27. From the Electric conductivity, choose User defined. In the text field, enter 0.

Weak Form PDE (w)

The weak expression for the auxiliary fields M1x and M1y. $\mathbf{M}(\mathbf{r}) \cdot \mathbf{F} = ((\bar{\mu}^T)^{-1} - \mu_{\infty}^{-1}) \nabla \times \tilde{\mathbf{E}}_n^{(L)}(\mathbf{r}) \cdot \mathbf{F}$.

- 1. In the Physics toolbar, select Weak Form PDE.
- 2. In the Settings window for Weak Form PDE, locate the Domain Selection section.
- 3. From the **Selection** list, choose: **sca**.
- 4. Locate the Discretization section. From the Shape function type list, choose Lagrange.
- 5. Locate the **Dependent Variables** section. In the **Field name** text field, enter M1. In the **Number of dependent** variables text field, enter 2. In the **Dependent variables** text field, enter M1x, M1y.

Weak Form PDE 1

- 6. In the Modal Builder window, under the Weak Form PDE (w) module, click Weak Form PDE 1.
- 7. In the **Settings** window for **Weak Form PDE 1**. Locate the **Weak Expressions** section, enter the following expression:

(test(M1x)*emw.curlEx+test(M1y)*emw.curlEy)*(omegam1*(i*alpha1*QNM_omega+omega01+omega m1))/nomega^2+(test(M1x)*emw.curlEy-test(M1y)*emw.curlEx)*(-i)*(QNM_omega*omegam1)/nomega^2-(test(M1x)*M1x+test(M1y)*M1y)*((1+alpha1^2)*QNM_omega^2-2*i*alpha1*QNM_omega*(omega01+omegam1)-(omega01+omegam1)^2)*murinf/nomega^2

ELECTROMAGNETIC WAVES, FREQUENCY DOMAIN (emw2) emw and w are used to solve for the right QNMs.

Repeat what has been done in **ELECTROMAGNETIC WAVES**, **FREQUENCY DOMAIN** (emw1) but replace all the M1x and M1y with N1x and N1y. Note that $\mathbf{N}(\mathbf{r}) = (\bar{\bar{\mu}}^{-1} - \mu_{\infty}^{-1})\nabla \times \tilde{\mathbf{E}}_{n}^{(R)}(\mathbf{r})$, which is different from $\mathbf{M}(\mathbf{r})$.

Weak Form PDE (w2)

Repeat what has been done in **Weak Form PDE (w)** but replace all the M1x and M1y with N1x and N1y and in the **Settings** window for **Weak Form PDE 1**. Locate the **Weak Expressions** section, enter the following expression:

(test(N1x)*emw2.curlEx+test(N1y)*emw2.curlEy)*(omegam1*(i*alpha1*QNM_omega2+omega01+omegam1))/nomega^2+(test(N1x)*emw2.curlEy-test(N1y)*emw2.curlEx)*(i)*(QNM_omega2*omegam1)/nomega^2-

(test(N1x)*N1x+test(N1y)*N1y)*((1+alpha1^2)*QNM omega2^2-

2*i*alpha1*QNM_omega2*(omega01+omegam1)-(omega01+omegam1)^2)*murinf/nomega^2

Mesh 1

Free Triangular 1


- 1. In the Model Builder window, right-click Mesh 1 and choose Free Triangular.
- 2. In the Settings window for Free Triangular locate the Domain Selection section.
- 3. From the **Geometric** entity level list, choose **Domain**.
- 4. From the **Selection** list, choose **sca**.
- 5. Right-click Free Triangular 1 and choose Size.
- 6. In the Settings window for Size 1, Locate the Element Size section and choose Custom.
- 7. From the Geometric entity level list, choose Domain.
- 8. From the **Selection** list, choose **sca**.
- 9. Locate the Element Size section, In the Maximum element size text field, type r/10.

Free Triangular 2

- 10. In the Model Builder window, right-click Mesh 1 and choose Free Triangular.
- 11. In the Settings window for Free Triangular locate the Domain Selection section.
- 12. From the **Geometric** entity level list, choose **Domain**.
- 13. Select Domain 5 only.
- 14. Right-click Free Triangular 1 and choose Size.
- 15. In the Settings window for Size 1, locate the Element Size section and choose Custom.
- 16. From the Geometric entity level list, choose Domain.
- 17. Select Domain 5 only.
- 18. Locate the Element Size section, In the Maximum element size text field, type r/2.

Mapped 1

- 19. In the Model Builder window, right-click Mesh 1 and choose Mapped.
- 20. In the Settings window for Mapped locate the Domain Selection section.
- 21. From the **Geometric** entity level list, choose **Remaining**.
- 22. Right-click Mapped 1 and choose Distribution.
- 23. In the **Settings** window for **Distribution 1**, locate the **Distribution** section.
- 24. From the **Distribution** type list, choose **Fixed number of elements**.
- 25. In the **Number of elements** field, type 5.
- 26. Click Build All.



The mesh of the system.

Study 1

Search for the left QNMs.

- 1. In the Model Builder window, click **Study 1>>Step 1: Eigenfrequency**.
- 2. Activate the **Desired number of eigenfrequencies** check box. Type the number of modes.
- 3. From the **Unit** list, choose **GHz**.
- 4. In the Search for eigenfrequencies around, type freqg.
- 5. Locate the Physics and Variables Selection section, clear the ELECTROMAGNETIC

WAVES, FREQUENCY DOMAIN 2 (emw2) and Weak Form PDE 2 (w2) checkboxes.

6. Click Compute.

Study 2

Search for the right QNMs.

- 7. In the **Study** toolbar, select **Add study**.
- 8. In the Add study window, click General Studies>> Eigenfrequency.
- 9. In the Model Builder window, click Study 2>>Step 1: Eigenfrequency.
- 10. Activate the **Desired number of eigenfrequencies** check box. Type the number of modes and make sure it is equal to that in **Study 1**.
- 11. From the Unit list, choose GHz.
- 12. In the Search for eigenfrequencies around, type freqg.
- 13. Locate the **Physics and Variables Selection** section, clear the **ELECTROMAGNETIC WAVES, FREQUENCY DOMAIN (emw)** and **Weak Form PDE (w)** checkboxes.
- 14. Click Compute.

Data Sets

Join 1

Because we need both the left QNMs computed with Study 1 and the right QNM computed with Study 2, we need to join two data sets.

- 1. In the Study toolbar, select More Data Sets>>Base Data Det>>Join.
- 2. In the Model Builder window, click Join 1.
- 3. In the **Settings** window for **Join 1**, locate the **Data 1** section.
- 4. From the Data list, choose Study 1/Solution 1 (sol1).
- 5. From the **Solutions** list, choose **One**.
- 6. From the **Eigenfrequency list**, choose a mode which we are concerned about.
- 7. In the **Settings** window for **Join 1**, locate the **Data 2** section.
- 8. From the Data list, choose Study 2/Solution 2 (sol2).
- 9. From the **Solutions** list, choose **One**.
- 10. From the Eigenfrequency list, choose the mode which has the same frequency as that in Data 1.
- 11. In the **Settings** window for **Join 1**, locate the **Combination** section.
- 12. From the Combination list, choose Explicit.

Join Plot			
Label: Join 1			
▼ Data 1			
Data:	Study 1/Solution 1 (sol1) ▼		
Solutions:	One	•	
Eigenfrequency:	9.7908+0.16432i GHz	•	
▼ Data 2			
Data:	Study 2/Solution 2 (sol2) ▼		
Solutions:	One	•	
Eigenfrequency:	9.7908+0.16432i GHz	•	
▼ Combination			
Method: Explic	it	•	
Help: Use the	data1() and data2() operators to refer	to tl	

Derived Values

Surface integral

Evaluate the QN defined in Eq. (11).

- 1. In the Study toolbar, select More Derived Values>>Integration>>Surface integration.
- 2. In the Model Builder window, click Surface integration 1.
- 3. From the Data set list, choose Join 1.
- 4. Locate the **Expressions** section. In the table, enter the following settings:

Expression	Description
(data1(emw.Ex)*data2(emw2.Dx)+data1(emw.Ey)*data2(emw2.Dy) +data1(emw.Ez)*data2(emw2.Dz))*data1(pml1.detInvT)	QN_E
-(data1(HLx)*data2(dwudwH_x)+data1(HLy)*data2(dwudwH_y) +data1(HLz)*data2(dwudwH_z))*data1(pml1.detInvT)*mu0_const	QN_H
(data1(emw.Ex)*data2(emw2.Dx)+data1(emw.Ey)*data2(emw2.Dy) +data1(emw.Ez)*data2(emw2.Dz))*data1(pml1.detInvT)- (data1(HLx)*data2(dwudwH_x)+data1(HLy)*data2(dwudwH_y)	QN=QN_E+QN_H
+data1(HLz)*data2(dwudwH_z))*data1(pml1.detlnvT)*mu0_const -(data1(HLx)*data2(duwHx)+data1(HLy)*data2(duwHy) +data1(HLz)*data2(duwHz))*mu0_const*data1(pml1.detlnvT)	QN_H (Method 2)

5. Click Evaluate>>New table.


2D Plot Group

Plot the map for $\operatorname{Re}(\tilde{\mathbf{E}}_m^{(R)} \cdot \tilde{\mathbf{E}}_m^{(L)}/QN)$.

- 1. In the Study toolbar, select 2D Plot Group.
- 2. From the **Data set** list, choose **Join 1**.
- 3. In the Model Builder window, right-click 2D Plot Group 2, select Surface.

Surface 1

- 4. In the Model Builder window, click Surface.
- 5. Locate the **Expressions** section. In the table, enter the following settings: real(data1(emw.Ez) *data2(emw2.Ez)/X) with X being the value of QN=QN_E+QN_H computed in the previous step.



 $\operatorname{Re}(\tilde{\mathbf{E}}_{m}^{(R)}\cdot \tilde{\mathbf{E}}_{m}^{(L)}/QN)$

4. REFERENCES

- 1. Bai, Q.; Perrin, M.; Sauvan, C.; Hugonin, J. P.; Lalanne, P. "Efficient and intuitive method for the analysis of light scattering by a resonant nanostructure", *Opt. Express* **2013**, 21, 27371.
- 2. Sauvan, C.; Hugonin, J. P.; Maksymov, I. S.; Lalanne, P. "Theory of the spontaneous optical emission of nanosize photonic and plasmon resonators", *Phys. Rev. Lett.* **2013**, 110, 237401.
- 3. Yan, W.; Faggiani, R.; Lalanne, P. "Rigorous modal analysis of plasmonic nanoresonators", *Phys. Rev. B* **2018**, 97, 205402.
- 4. Vial, B.; Nicolet, A.; Zolla, F.; Commandré, M. "Quasimodal expansion of electromagnetic fields in open two-dimensional structures", *Phys. Rev. A* **2014**, 89, 023829.
- 5. Pick, A.; Zhen, B.; Miller O.D.; Hsu C.W.; Hernandez F.; Rodriguez A.W.; Soljačić M.; Johnson S.G. "General Theory of Spontaneous Emission Near Exceptional Points", *Opt. Express* **2017**, 25, 12325.
- 6. Wu, T.; Gurioli, M.; Lalanne, P. "Nanoscale Light Confinement: the Q's and V's", *ACS Photonics* **2021**, (https://doi.org/10.1021/acsphotonics.1c00336).
- 7. Rameshti, B. Z.; Bauer, G. E. "Indirect coupling of magnons by cavity photons", *Phys. Rev. B* **2018**, 97, 014419.
- 8. Yang, B.; Wu, T; Zhang, X. "Topological properties of nearly flat bands in two-dimensional photonic crystals", *J. Opt. Soc. Am. B* **2017**, 34, 831.