

Chapter 9: Virtual Memory





Chapter 9: Virtual Memory

- Background
- Demand Paging
- Copy-on-Write
- Page Replacement
- Allocation of Frames
- Thrashing
- Memory-Mapped Files
- Allocating Kernel Memory
- Other Considerations
- Operating-System Examples





Objectives

- □ To describe the benefits of a virtual memory system
- □ To explain the concepts of demand paging, page-replacement algorithms, and allocation of page frames
- ☐ To discuss the principle of the working-set model
- □ To examine the relationship between shared memory and memory-mapped files
- □ To explore how kernel memory is managed






Background

- Code needs to be in memory to execute, but entire program rarely used
 - Error code, unusual routines, large data structures
- Entire program code not needed at same time
- Consider ability to execute partially-loaded program
 - Program no longer constrained by limits of physical memory
 - Each program takes less memory while running -> more programs run at the same time
 - Increased CPU utilization and throughput with no increase in response time or turnaround time
 - Less I/O needed to load or swap programs into memory -> each user program runs faster







Background

- □ Virtual memory separation of user logical memory from physical memory
 - Only part of the program needs to be in memory for execution
 - Logical address space can therefore be much larger than physical address space
 - Allows address spaces to be shared by several processes
 - Allows for more efficient process creation
 - More programs running concurrently
 - Less I/O needed to load or swap processes
- □ Virtual address space logical view of how process is stored in memory
 - Usually start at address 0, contiguous addresses until end of space
 - Meanwhile, physical memory organized in page frames
 - MMU must map logical to physical
- □ Virtual memory can be implemented via:
 - Demand paging
 - Demand segmentation





Virtual Memory That is Larger Than Physical Memory








Virtual-address Space


- Usually design logical address space for stack to start at Max logical address and grow "down" while heap grows "up"
 - Maximizes address space use
 - Unused address space between the two is hole
 - No physical memory needed until heap or stack grows to a given new page
- ☐ Enables **sparse** address spaces with holes left for growth, dynamically linked libraries, etc
- System libraries shared via mapping into virtual address space
- Shared memory by mapping pages read-write into virtual address space
- Pages can be shared during fork(), speeding process creation







Shared Library Using Virtual Memory








Demand Paging

- Could bring entire process into memory at load time
- Or bring a page into memory only when it is needed
 - Less I/O needed, no unnecessary I/O
 - Less memory needed
 - Faster response
 - More users
- Similar to paging system with swapping (diagram on right)
- \square Page is needed \Rightarrow reference to it
 - □ invalid reference ⇒ abort
 - □ not-in-memory ⇒ bring to memory
- Lazy swapper never swaps a page into memory unless page will be needed
 - Swapper that deals with pages is a pager







Basic Concepts

- □ With swapping, pager guesses which pages will be used before swapping out again
- ☐ Instead, pager brings in only those pages into memory
- □ How to determine that set of pages?
 - Need new MMU functionality to implement demand paging
- □ If pages needed are already memory resident
 - No difference from non demand-paging
- ☐ If page needed and not memory resident
 - Need to detect and load the page into memory from storage
 - Without changing program behavior
 - Without programmer needing to change code





Valid-Invalid Bit

- With each page table entry a valid–invalid bit is associated
 (v ⇒ in-memory memory resident, i ⇒ not-in-memory)
- ☐ Initially valid—invalid bit is set to i on all entries
- Example of a page table snapshot:

Frame #	valid-invalid bit	
	V	
	V	
	V	
	V	
	i	
	i	
	i	


page table


During MMU address translation, if valid–invalid bit in page table entry is i ⇒ page fault







Page Table When Some Pages Are Not in Main Memory













Page Fault

- ☐ If there is a reference to a page, first reference to that page will trap to operating system:
 - page fault
- 1. Operating system looks at another table to decide:
 - □ Invalid reference ⇒ abort
 - Just not in memory
- Find free frame
- 3. Swap page into frame via scheduled disk operation
- 4. Reset tables to indicate page now in memory Set validation bit = **v**
- 5. Restart the instruction that caused the page fault





Steps in Handling a Page Fault






Aspects of Demand Paging


- Extreme case start process with no pages in memory
 - OS sets instruction pointer to first instruction of process, non-memory-resident -> page fault
 - And for every other process pages on first access
 - Pure demand paging
- Actually, a given instruction could access multiple pages -> multiple page faults
 - Consider fetch and decode of instruction which adds 2 numbers from memory and stores result back to memory
 - Pain decreased because of locality of reference
- Hardware support needed for demand paging
 - Page table with valid / invalid bit
 - Secondary memory (swap device with swap space)
 - Instruction restart






Instruction Restart

- Consider an instruction that could access several different locations
 - block move



- auto increment/decrement location
- Restart the whole operation?
 - What if source and destination overlap?



Performance of Demand Paging

- ☐ Stages in Demand Paging (worse case)
- 1. Trap to the operating system
- 2. Save the user registers and process state
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal and determine the location of the page on the disk
- 5. Issue a read from the disk to a free frame:
 - 1. Wait in a queue for this device until the read request is serviced
 - 2. Wait for the device seek and/or latency time
 - 3. Begin the transfer of the page to a free frame
- 6. While waiting, allocate the CPU to some other user
- 7. Receive an interrupt from the disk I/O subsystem (I/O completed)
- 8. Save the registers and process state for the other user
- 9. Determine that the interrupt was from the disk
- 10. Correct the page table and other tables to show page is now in memory
- 11. Wait for the CPU to be allocated to this process again
- 12. Restore the user registers, process state, and new page table, and then resume the interrupted instruction




- ☐ Three major activities
 - Service the interrupt careful coding means just several hundred instructions needed
 - Read the page lots of time
 - Restart the process again just a small amount of time
- □ Page Fault Rate $0 \le p \le 1$

 - if p = 1, every reference is a fault
- □ Effective Access Time (EAT)

```
EAT = (1 - p) x memory access
+ p (page fault overhead
+ swap page out
+ swap page in
```





Demand Paging Example

- ☐ Memory access time = 200 nanoseconds
- □ Average page-fault service time = 8 milliseconds


EAT =
$$(1 - p) \times 200 + p$$
 (8 milliseconds)
= $(1 - p \times 200 + p \times 8,000,000$
= $200 + p \times 7,999,800$

☐ If one access out of 1,000 causes a page fault, then EAT = 8.2 microseconds.

This is a slowdown by a factor of 40!!

- ☐ If want performance degradation < 10 percent
 - 220 > 200 + 7,999,800 x p20 > 7,999,800 x p
 - p < .0000025
 - < one page fault in every 400,000 memory accesses</p>






Demand Paging Optimizations

- □ Swap space I/O faster than file system I/O even if on the same device
 - Swap allocated in larger chunks, less management needed than file system
- Copy entire process image to swap space at process load time
 - Then page in and out of swap space
 - Used in older BSD Unix
- Demand page in from program binary on disk, but discard rather than paging out when freeing frame
 - Used in Solaris and current BSD
 - Still need to write to swap space
 - Pages not associated with a file (like stack and heap) anonymous memory
 - Pages modified in memory but not yet written back to the file system
- Mobile systems
 - Typically don't support swapping
 - Instead, demand page from file system and reclaim read-only pages (such as code)






Copy-on-Write

- Copy-on-Write (COW) allows both parent and child processes to initially share the same pages in memory
 - If either process modifies a shared page, only then is the page copied
- COW allows more efficient process creation as only modified pages are copied
- ☐ In general, free pages are allocated from a pool of zero-fill-on-demand pages
 - Pool should always have free frames for fast demand page execution
 - Don't want to have to free a frame as well as other processing on page fault
 - Why zero-out a page before allocating it?
- vfork() variation on fork() system call has parent suspend and child using copy-on-write address space of parent
 - Designed to have child call exec()
 - Very efficient







Before Process 1 Modifies Page C








After Process 1 Modifies Page C








What Happens if There is no Free Frame?

- Used up by process pages
- □ Also in demand from the kernel, I/O buffers, etc
- How much to allocate to each?
- □ Page replacement find some page in memory, but not really in use, page it out
 - Algorithm terminate? swap out? replace the page?
 - Performance want an algorithm which will result in minimum number of page faults
- Same page may be brought into memory several times






Page Replacement


- Prevent over-allocation of memory by modifying page-fault service routine to include page replacement
- ☐ Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory large virtual memory can be provided on a smaller physical memory







Need For Page Replacement














Basic Page Replacement


- 1. Find the location of the desired page on disk
- 2. Find a free frame:
 - If there is a free frame, use it
 - If there is no free frame, use a page replacement algorithm to select a victim frame
 - Write victim frame to disk if dirty
- 3. Bring the desired page into the (newly) free frame; update the page and frame tables
- 4. Continue the process by restarting the instruction that caused the trap


Note now potentially 2 page transfers for page fault – increasing EAT





Page Replacement






Page and Frame Replacement Algorithms


- □ Frame-allocation algorithm determines
 - How many frames to give each process
 - Which frames to replace
- Page-replacement algorithm
 - Want lowest page-fault rate on both first access and re-access
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
 - String is just page numbers, not full addresses
 - Repeated access to the same page does not cause a page fault
 - Results depend on number of frames available
- □ In all our examples, the **reference string** of referenced page numbers is

7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1





Graph of Page Faults VersusThe Number of Frames








First-In-First-Out (FIFO) Algorithm


- Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1
- □ 3 frames (3 pages can be in memory at a time per process)




15 page faults

- □ Can vary by reference string: consider 1,2,3,4,1,2,5,1,2,3,4,5
 - Adding more frames can cause more page faults!
 - Belady's Anomaly
- How to track ages of pages?
 - Just use a FIFO queue






FIFO Illustrating Belady's Anomaly








Optimal Algorithm

- Replace page that will not be used for longest period of time
 - 9 is optimal for the example
- How do you know this?
 - Can't read the future
- ☐ Used for measuring how well your algorithm performs






Least Recently Used (LRU) Algorithm

- □ Use past knowledge rather than future
- Replace page that has not been used in the most amount of time
- Associate time of last use with each page


reference string



page frames

- 12 faults better than FIFO but worse than OPT
- Generally good algorithm and frequently used
- But how to implement?






LRU Algorithm (Cont.)

- Counter implementation
 - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
 - When a page needs to be changed, look at the counters to find smallest value
 - Search through table needed
- Stack implementation
 - Keep a stack of page numbers in a double link form:
 - Page referenced:
 - move it to the top
 - requires 6 pointers to be changed
 - But each update more expensive
 - No search for replacement
- □ LRU and OPT are cases of **stack algorithms** that don't have Belady's Anomaly



Use Of A Stack to Record Most Recent Page References






stack before a

stack after b

4






LRU Approximation Algorithms

- □ LRU needs special hardware and still slow
- □ Reference bit
 - □ With each page associate a bit, initially = 0
 - When page is referenced bit set to 1
 - □ Replace any with reference bit = 0 (if one exists)
 - We do not know the order, however
- □ Second-chance algorithm
 - Generally FIFO, plus hardware-provided reference bit
 - Clock replacement
 - If page to be replaced has
 - Reference bit = 0 -> replace it
 - reference bit = 1 then:
 - set reference bit 0, leave page in memory
 - replace next page, subject to same rules





Second-Chance (clock) Page-Replacement Algorithm








Enhanced Second-Chance Algorithm

- Improve algorithm by using reference bit and modify bit (if available) in concert
- ☐ Take ordered pair (reference, modify)
- 1. (0, 0) neither recently used not modified best page to replace
- 2. (0, 1) not recently used but modified not quite as good, must write out before replacement
- 3. (1, 0) recently used but clean probably will be used again soon
- 4. (1, 1) recently used and modified probably will be used again soon and need to write out before replacement
- When page replacement called for, use the clock scheme but use the four classes replace page in lowest non-empty class
 - Might need to search circular queue several times






Counting Algorithms

- ☐ Keep a counter of the number of references that have been made to each page
 - Not common
- □ Lease Frequently Used (LFU) Algorithm: replaces page with smallest count
- Most Frequently Used (MFU) Algorithm: based on the argument that the page with the smallest count was probably just brought in and has yet to be used





Page-Buffering Algorithms


- ☐ Keep a pool of free frames, always
 - Then frame available when needed, not found at fault time
 - Read page into free frame and select victim to evict and add to free pool
 - When convenient, evict victim
- Possibly, keep list of modified pages
 - □ When backing store otherwise idle, write pages there and set to non-dirty
- Possibly, keep free frame contents intact and note what is in them
 - If referenced again before reused, no need to load contents again from disk
 - Generally useful to reduce penalty if wrong victim frame selected





- ☐ All of these algorithms have OS guessing about future page access
- ☐ Some applications have better knowledge i.e. databases
- Memory intensive applications can cause double buffering
 - OS keeps copy of page in memory as I/O buffer
 - Application keeps page in memory for its own work
- Operating system can given direct access to the disk, getting out of the way of the applications
 - Raw disk mode
- □ Bypasses buffering, locking, etc






Allocation of Frames

- Each process needs *minimum* number of frames
- □ Example: IBM 370 6 pages to handle SS MOVE instruction:
 - instruction is 6 bytes, might span 2 pages
 - 2 pages to handle from
 - 2 pages to handle to
- Maximum of course is total frames in the system
- Two major allocation schemes
 - fixed allocation
 - priority allocation
- Many variations





Fixed Allocation

- □ Equal allocation For example, if there are 100 frames (after allocating frames for the OS) and 5 processes, give each process 20 frames
 - Keep some as free frame buffer pool
- □ Proportional allocation Allocate according to the size of process
 - Dynamic as degree of multiprogramming, process sizes change

$$-s_i = \text{size of process } p_i$$

$$-S = \sum s_i$$

$$-m = total number of frames$$

$$-a_i =$$
allocation for $p_i = \frac{s_i}{S} \times m$

$$m = 64$$

$$s_1 = 10$$

$$s_2 = 127$$

$$a_1 = \frac{10}{137} \cdot 62 \gg 4$$

$$a_2 = \frac{127}{137} \cdot 62 \gg 57$$






Priority Allocation

- ☐ Use a proportional allocation scheme using priorities rather than size
- If process P_i generates a page fault,
 - select for replacement one of its frames
 - select for replacement a frame from a process with lower priority number






Global vs. Local Allocation

- ☐ Global replacement process selects a replacement frame from the set of all frames; one process can take a frame from another
 - But then process execution time can vary greatly
 - But greater throughput so more common
- □ Local replacement each process selects from only its own set of allocated frames
 - More consistent per-process performance
 - But possibly underutilized memory






Non-Uniform Memory Access

- So far all memory accessed equally
- Many systems are NUMA speed of access to memory varies
 - Consider system boards containing CPUs and memory, interconnected over a system bus
- Optimal performance comes from allocating memory "close to" the CPU on which the thread is scheduled
 - And modifying the scheduler to schedule the thread on the same system board when possible
 - Solved by Solaris by creating Igroups
 - Structure to track CPU / Memory low latency groups
 - Used my schedule and pager
 - When possible schedule all threads of a process and allocate all memory for that process within the Igroup







Thrashing

- ☐ If a process does not have "enough" pages, the page-fault rate is very high
 - Page fault to get page
 - Replace existing frame
 - But quickly need replaced frame back
 - This leads to:
 - Low CPU utilization
 - Operating system thinking that it needs to increase the degree of multiprogramming
 - Another process added to the system
- □ Thrashing = a process is busy swapping pages in and out





Thrashing (Cont.)









Demand Paging and Thrashing


- Why does demand paging work?
 Locality model
 - Process migrates from one locality to another
 - Localities may overlap
- Using Why does thrashing occur? Σ size of locality > total memory size
 - Limit effects by using local or priority page replacement






Locality In A Memory-Reference Pattern









Working-Set Model


- Δ = working-set window = a fixed number of page references Example: 10,000 instructions
- USS_i (working set of Process P_i) = total number of pages referenced in the most recent Δ (varies in time)
 - if Δ too small will not encompass entire locality
 - if Δ too large will encompass several localities
 - if $\Delta = \infty \Rightarrow$ will encompass entire program
- $D = \Sigma WSS_i \equiv \text{total demand frames}$
 - Approximation of locality
- □ if $D > m \Rightarrow$ Thrashing
- \square Policy if D > m, then suspend or swap out one of the processes

page reference table

...2615777751623412344434344413234443444...








Keeping Track of the Working Set


- □ Approximate with interval timer + a reference bit
- \square Example: $\Delta = 10,000$
 - ☐ Timer interrupts after every 5000 time units
 - Keep in memory 2 bits for each page
 - Whenever a timer interrupts copy and sets the values of all reference bits to 0
 - If one of the bits in memory = $1 \Rightarrow$ page in working set
- □ Why is this not completely accurate?
- ☐ Improvement = 10 bits and interrupt every 1000 time units





Page-Fault Frequency


- More direct approach than WSS
- Establish "acceptable" page-fault frequency (PFF) rate and use local replacement policy
 - If actual rate too low, process loses frame
 - If actual rate too high, process gains frame






Working Sets and Page Fault Rates

- n Direct relationship between working set of a process and its page-fault rate
- Morking set changes over time
- n Peaks and valleys over time







Memory-Mapped Files


- Memory-mapped file I/O allows file I/O to be treated as routine memory access by mapping a disk block to a page in memory
- A file is initially read using demand paging
 - A page-sized portion of the file is read from the file system into a physical page
 - Subsequent reads/writes to/from the file are treated as ordinary memory accesses
- Simplifies and speeds file access by driving file I/O through memory rather than read() and write() system calls
- Also allows several processes to map the same file allowing the pages in memory to be shared
- But when does written data make it to disk?
 - Periodically and / or at file close() time
 - For example, when the pager scans for dirty pages






- □ Some OSes uses memory mapped files for standard I/O
- ☐ Process can explicitly request memory mapping a file via mmap () system call
 - Now file mapped into process address space
- □ For standard I/O (open(), read(), write(), close()), mmap anyway
 - But map file into kernel address space
 - Process still does read() and write()
 - Copies data to and from kernel space and user space
 - Uses efficient memory management subsystem
 - Avoids needing separate subsystem
- □ COW can be used for read/write non-shared pages
- Memory mapped files can be used for shared memory (although again via separate system calls)






Memory Mapped Files




Silberschatz, Galvin and Gagne ©2013



Shared Memory via Memory-Mapped I/O








Shared Memory in Windows API

- ☐ First create a file mapping for file to be mapped
 - □ Then establish a view of the mapped file in process's virtual address space
- □ Consider producer / consumer
 - Producer create shared-memory object using memory mapping features
 - Open file via CreateFile(), returning a HANDLE
 - Create mapping via CreateFileMapping() creating a named shared-memory object
 - Create view via MapViewOfFile()
- □ Sample code in Textbook





Allocating Kernel Memory

- Treated differently from user memory
- Often allocated from a free-memory pool
 - Kernel requests memory for structures of varying sizes
 - Some kernel memory needs to be contiguous
 - ▶ I.e. for device I/O






Buddy System


- Allocates memory from fixed-size segment consisting of physically-contiguous pages
- Memory allocated using power-of-2 allocator
 - Satisfies requests in units sized as power of 2
 - Request rounded up to next highest power of 2
 - When smaller allocation needed than is available, current chunk split into two buddies of next-lower power of 2
 - Continue until appropriate sized chunk available
- □ For example, assume 256KB chunk available, kernel requests 21KB
 - □ Split into A_{L and} A_R of 128KB each
 - One further divided into B_L and B_R of 64KB
 - One further into C_L and C_R of 32KB each one used to satisfy request
- □ Advantage quickly **coalesce** unused chunks into larger chunk
- Disadvantage fragmentation





Buddy System Allocator

physically contiguous pages








Slab Allocator

- Alternate strategy
- □ Slab is one or more physically contiguous pages
- Cache consists of one or more slabs
- □ Single cache for each unique kernel data structure
 - Each cache filled with objects instantiations of the data structure
- ☐ When cache created, filled with objects marked as **free**
- ☐ When structures stored, objects marked as used
- ☐ If slab is full of used objects, next object allocated from empty slab
 - If no empty slabs, new slab allocated
- □ Benefits include no fragmentation, fast memory request satisfaction






Slab Allocation








Slab Allocator in Linux

- □ For example process descriptor is of type struct task_struct
- □ Approx 1.7KB of memory
- New task -> allocate new struct from cache
 - □ Will use existing free struct task struct
- ☐ Slab can be in three possible states
 - Full all used
 - 2. Empty all free
 - 3. Partial mix of free and used
- ☐ Upon request, slab allocator
 - 1. Uses free struct in partial slab
 - 2. If none, takes one from empty slab
 - 3. If no empty slab, create new empty
- □ Slab started in Solaris, now wide-spread for both kernel mode and user memory in various OSes
- ☐ Linux 2.2 had SLAB, now has both SLOB and SLUB allocators
 - SLOB for systems with limited memory
 - Simple List of Blocks maintains 3 list objects for small, medium, large objects
 - SLUB is performance-optimized SLAB removes per-CPU queues, metadata stored in page structure




Other Considerations -- Prepaging

Prepaging

- To reduce the large number of page faults that occurs at process startup
- Prepage all or some of the pages a process will need, before they are referenced
- But if prepaged pages are unused, I/O and memory was wasted
- \square Assume s pages are prepaged and α of the pages is used
 - Is cost of s * α save pages faults > or < than the cost of prepaging s * (1- α) unnecessary pages?</p>
 - α near zero ⇒ prepaging loses






Other Issues – Page Size

- Sometimes OS designers have a choice
 - Especially if running on custom-built CPU
- Page size selection must take into consideration:
 - Fragmentation
 - Page table size
 - Resolution
 - I/O overhead
 - Number of page faults
 - Locality
 - TLB size and effectiveness
- Always power of 2, usually in the range 2^{12} (4,096 bytes) to 2^{22} (4,194,304 bytes)
- □ On average, growing over time






Other Issues – TLB Reach

- □ TLB Reach The amount of memory accessible from the TLB
- ☐ TLB Reach = (TLB Size) X (Page Size)
- □ Ideally, the working set of each process is stored in the TLB
 - Otherwise there is a high degree of page faults
- □ Increase the Page Size
 - This may lead to an increase in fragmentation as not all applications require a large page size
- Provide Multiple Page Sizes
 - This allows applications that require larger page sizes the opportunity to use them without an increase in fragmentation





Other Issues – Program Structure

- Program structure
 - int[128,128] data;
 - Each row is stored in one page
 - Program 1

```
for (j = 0; j < 128; j++)
for (i = 0; i < 128; i++)
data[i,j] = 0;
```


 $128 \times 128 = 16,384$ page faults

Program 2

```
for (i = 0; i < 128; i++)
    for (j = 0; j < 128; j++)
        data[i,j] = 0;</pre>
```


128 page faults






Other Issues – I/O interlock

- I/O Interlock Pages must sometimes be locked into memory
- Consider I/O Pages that are used for copying a file from a device must be locked from being selected for eviction by a page replacement algorithm
- Pinning of pages to lock into memory







Operating System Examples

- Windows
- Solaris





Windows

- □ Uses demand paging with **clustering**. Clustering brings in pages surrounding the faulting page
- Processes are assigned working set minimum and working set maximum
- □ Working set minimum is the minimum number of pages the process is guaranteed to have in memory
- A process may be assigned as many pages up to its working set maximum
- □ When the amount of free memory in the system falls below a threshold, automatic working set trimming is performed to restore the amount of free memory
- Working set trimming removes pages from processes that have pages in excess of their working set minimum






Solaris

- Maintains a list of free pages to assign faulting processes
- □ Lotsfree threshold parameter (amount of free memory) to begin paging
- Desfree threshold parameter to increasing paging
- Minfree threshold parameter to being swapping
- Paging is performed by pageout process
- Pageout scans pages using modified clock algorithm
- Scanrate is the rate at which pages are scanned. This ranges from slowscan to fastscan
- Pageout is called more frequently depending upon the amount of free memory available
- Priority paging gives priority to process code pages





Solaris 2 Page Scanner



Silberschatz, Galvin and Gagne ©2013

End of Chapter 9

