

# Introduction

In this chapter, we shall consider some fundamental concepts of linear systems analysis and use the power of MATLAB to undertake system analysis.

# Basic Discrete-Time Sequences

## The Delta Sequence - - - $\delta$ [n]

The delta sequence plays an important role in the characterization of discrete-time linear time-invariant systems. The delta sequence, written as  $\delta$  [n], is defined as

$$\delta[n] = \begin{cases} 1, & n = 0 \\ 0, & n \neq 0 \end{cases}$$

### **Practice**

### -The Delta Sequence-

>> n=-30:30; % specify index n

>>delta=(n==0); % define the delta sequence

>>stem(n,delta, 'filled') % plot the delta sequence

## The Unit-step Sequence - - - u[n]

The unit-step sequence, written as u[n], is defined as

 $u[n] = \begin{cases} 1, & n \ge 0 \\ 0, & n < 0 \end{cases}$ 

- The Unit-step Sequence-

**(1)** 

### **Practice**

-The Unit-step Sequence-

**(2)** 

Provide a MATLAB code to sketch the discrete-time sequence x[n] specified by

$$x[n] = 2\delta[n] + 3\delta[n-1] - 5\delta[n-3]$$

$$>> xn=2*(n==0)+((n-1)==0)-5*((n-3)==0);$$
 % define the sequence x[n]

## The Ramp Sequence - - r[n]

The ramp sequence, r[n] is defined as follows:

$$r[n] = \begin{cases} n, & n \ge 0 \\ 0, & n < 0 \end{cases}$$

## **Practice**

- The Ramp Sequence-

**(1)** 

- The Ramp Sequence-


**(2)** 

Generate and plot a shifted version of a ramp sequence, r[n-5]

>>n=-10:15; % define index n

>> x=(n-5).\*((n-5)>=0); % define shifted version of ramp

>>stem(n,x,'filled');grid % plot the shifted version of ramp



## The Exponential Sequence

## **Practice**

- The Exponential Sequence -

Define and sketch the discrete-time exponential sequence given by

 $x[n] = (0.8)^n u[n]$ 

>>%exponential sequence

>>n=-30:30;

>>n=(0.8).^n.\*(n>=0);

>>stem(n,x);grid

% specify index n

% define the sequence x[n]

% plot the exponential sequence

## Periodic Signals

A discrete-time signal x[n] is said to be periodic if there exist a positive constant N (the period) for which x[n+N]=x[n], for all n. We can easily generate periodic signal in MATLAB.

```
Practice
- Periodic Signals-
Use MATLAB to create a periodic extension of the sequence x[n]={1,1,0,0,-1,-1};

>>N=4;
>>x=[1 1 0 0 -1 -1];
>>xp=repmat(x,1,N);
>>stem(n,xp)


NOTE: The repmat creates a duplicate of a matrix or vector.
```

## Square, Sawtooth & Sinusoidal Waves

## **Square & Sawtooth Waves**

The MATLAB build-in functions **square** and **sawtooth** make it possible to generate a square wave and sawtooth wave, respectively.

```
Practice
                           - Square & Sawtooth Waves-
>>t=(0:0.001:1)
                                                % time base
>>x=square(2*pi*5*t);
                                                % squarewave generator
>>subplot(2,1,1);plot(t,x,'LineWidth',2);grid
                                                % plot squarewave
                                                % scale axes
>>axis([0 1 -1.2 1.2]);
                                                % add title
>>title('Square-wave')
>>ylabel('Amplitude');
                                                % label the vertical axis
>>%y=max(0,x);
                                                % squarewave ranging from 0 to 1
>>z=sawtooth(2*pi*5*t);
                                                % sawtooth wave
>>subplot(2,1,2); plot(t,z,'LineWidth',2);grid
                                                % plot sawtooth wave
                                                % add title
>>title('Sawtooth-wave')
>>ylabel('Amplitude')
                                                % label the vertical axis
>>xlabel('Time')
                                                % label the horizontal axis
>>axis([0 1 -1.2 1.2])
                                             % scale the axes
                      (The plots are shown on the next page)
```



# Sinusoidal Wave

<u>Practice</u>	
-Sinusoidal Wave-	
Generate a 50 Hz sinusoidal signal.	
>>Fs=1000;	% sampling frequency
>>Ts=1/Fs;	% sampling interval
>>t=0:Ts:0.1;	% sampling instants
$>> x = \sin(2*pi*50*t);$	% signal vector
>>plot(t,x);grid	% plot the signal
>>xlabel('Time (sec)')	% add label to the horizontal axis
>>ylabel('Amplitude')	% add label to the vertical axis
>>Title('Sinusoidal wave')	% add title to the plot
Sinusoidal wave	
0.8	
0.6	
0.4	
Amplitude	
₹ -0.2	
-0.4	-f\\\\\\\\\\\\\
-0.6	
	/ VI IVI IVI
0 0.01 0.02 0.03 0.04 0.05 0.06 0.07 0.08 0.09 0.1 Time(sec)	

# Circle

```
Practice
                                     -Circle-
>>function [x,y]=circle(r)
>>%This function outputs the x and y coordinates of a circle of radius
>>% r and plots the circle
>>theta=0:0.01:2*pi;
>> x=r*cos(theta);
>>y=r*sin(theta);
>>plot(x,y,'m','LineWidth',3);grid
>>axis('square')
>>b=num2str(r);
>>title(['circle of radius=',b])
>>xlabel('x')
>>ylabel('y')
Alternative procedure
>>%Draw a circle
>>+=0:pi/20:2*pi;
>>plot(sin(t),cos(t))
>>axis square
>>title('unit circle')
```

# Periodic Signal Generator for Time Response Simulations

## - The "gensig" Command

The function **gensig** produces signals of different types.

## **Function Synopsis**

```
>>[u,t]=gensig(type,per)
>>type='sin'
>>type='square'
```

- >>type='pulse'
- >>t=vector of time samples
- >>u=vector of singal values at these samples
- >>per=period
- >>[u,t]=gensig(type,per,Tf,Ts)
- >>Tf=time duration
- >>Ts=spacing of the time samples

-The "gensig" Command-

Generate a squarewave.

- >>[u,t]=gensig('square',4,20,0.01);
- >>plot(t,u);
- >>axis([0 20 -0.3 1.2])

# Signal Energy

The energy of a discrete-time signal x[n] is given by  $E_x = \sum_{n=-\infty}^{\infty} |x(n)|^2$ 

### **Practice**

-Signal Energy-

Use MATLAB to determine the energy of the sequence  $x[n]=2n, -4 \le n \le 4$ 

- >>n=-4:1:4;
- >> x=2\*n;
- >>Ex=sum(abs(x).^2)

# Convolution

## **Convolution Sum**

The Convolution sum of two sequences x[n] and h[n], written as y[n]=x[n]\*h[n], is defined by

$$y[n] = x[n] * h[n] = \sum_{k=-\infty}^{\infty} x[k]h[n-k]$$

MATLAB has a built-in function, **conv**, to perform convolution on finite-length sequences of values. This function assumes that the two sequences have been defined as vectors and it generates an output sequence that is also a vector. Convolving a sequence x[n] of length N with a sequence h[n] with length M results in a sequence of length L=N+M-1. The extent of x[n]\*h[n] is equal to the extent of x[n] plus the extent of h[u].

#### **Syntax** □ Syntax

```
>>y=conv(x,h)
```

where x and h are finite sequences written in vector form

## **Practice**

- Convolution Sum-

Determine the convolution of the sequences x[n] and h[n] specified below.

>>x=[1 2 2 1 2]; nx=[-2:2]; % define sequence x[n] and its range >>h=[2 2 -1 1 2 2 1]; nh=[-3:3]; % define sequence h[n] and its range

>>nmin=min(nx)+min(nh); % specify the lower bound of convolved sequences >>nmax=mzx(nx)+max(nh); % specify the upper bound of convolved sequences

>>y=conv(x,h); n=[nmin:nmax]; % compute convolution and spec its range


>>stem(n,y,'filled');grid % plot the resulting sequence y[n]

>>title('convolution of two sequence') % add title to the plot >>ylabel('y[n]=x[n]\*h[n]') % label the y-axis

>>xlabel('index,[n]') % label the horizontal axis

>>[n'y'] <enter> % print index and sequence y[n] as column vectors

(Continue on the next page)



## **Numerical Convolution**

The other form of convolution is known as the convolution integral. If x(t) and h(t) are two continuous-time signals, then the convolution integral is defined by

$$y(t) = x(t) * h(t) = \int_{0}^{t} x(\tau)h(t-\tau)d\tau$$

Since computers have a hard time integrating, we shall consider evaluation y(t) numerically. Let t=kT

$$\therefore y(kT) = \int_{0}^{kT} x(\tau)h(kT-\tau)d\tau \cong T\sum_{i=0}^{k} x(iT)h((k-i)T) = Tx(kT)*h(kT)$$

where T is the integration step size. This equation is the convolution sum and can be found using the **conv** function.

#### - Numerical Convolution-

```
Evaluate the convolution of x(t) = \sin(2t) with h(t) = e^{-0.1t} from t=0 to 5 with T=0.1.

>>t=0:0.15:5; % define t=KT

>>x=\sin(2*t); % define x(kt)

>>h=\exp(-0.1*t); % define h(kT)

>>0.1*\conv(x,h); % evaluate convolution
```

# Sequence Folding

### - The "flplr" Command

A number of signal processing operation involve taking the mirror image of a sequence about the vertical axis passing through the origin. The **flplr** function flips a sequence left to right. The following scrip illustrates the process of folding via MATLAB.

```
Practice
-Sequence Folding: The "flplr" Command

>>n=-2:4;

>>x=[1 1 0 0 1 1 1];

>>y=fliplr(x);

>m=-fliplr(n);

>>subplot(2,1,1);stem(n,x,'filled');grid

>>title('original sequence')

>>axis([-3 5 0 1.2])


>>subplot(2,1,2);stem(m,y,'filled');grid

>>title('folded sequence')

>>axis([-5 3 0 1.2])

The following plots show the original sequence and its folded version.
```

(The plots are shown on the next page)



# Ordinary Differential Equations (ODE)

## **Ordinary Differential Equations**

- Commands: "ode23" & "ode45"

MATLAB has built-in routines for solving ordinary differential equations, namely, ode23, and ode45. The function ode45 is more accurate, but a bit slower than ode23.

## **Check List**

In order to solve a differential equation using MATLAB, the following items are required:

- ✓ You need to make a separate function file that contains the differential equation or system of differential equations.
- ✓ Specify the time range over which the solution is desired.
- ✓ Specify the initial conditions.

## -Ordinary Differential Equations-

(1)

Use MATLAB to solve the following ordinary differential equation

$$\begin{cases} \frac{dy}{dt} + 3ty = 0\\ y(0) = 2 \end{cases}$$

## **Check List**

- ✓ Create the function function ydot=yprime(t,y) ydot=-3\*t\*y;
- ✓ Time Range: We want the solution, say, over the interval [0 6]
- ✓ Initial Condition: initial=2

Typing the following at the command prompt will solve the ODE.

```
>>initial=3
>>[t,y]=ode23('yprime',[0 6],initial)
>>plot(t,y,'LineWidth',2)
```

# **Higher Order Differential Equations**

We shall now consider the solution of second-order differential equations. Higher order ordinary differential equations require conversion to two or more first order ordinary differential equations.

- Ordinary Differential Equations: Higher Order Equations(2)

Solve the following second order ordinary differential equation:

$$\begin{cases} \frac{d^2y}{dt^2} + 3t\frac{dy}{dt} + 7y = 0\\ y(0) = 0, & y'(0) = 1 \end{cases}$$

To convert to first-order differential equations, we proceed as follows:

$$y_1 = y$$

$$y_2 = y$$

$$\therefore y_2 = -3ty_2 - 7y_1$$

This yields a system of two first-order differential equations

$$\begin{cases} y_1 = y_2 \\ y_2 = -3ty_2 - 7y_1 \end{cases}$$

Function ydot=yprime(t,y) ydot=[y(2);-7\*y(1)-3\*t\*y(2)];

Typing the following at the command prompt will solve the ODE.

>>initial=[0;1];


>>[t,y]=ode45('yprime',[0 6],initial)

>>plot(t,y,'LineWidth',3);grid

## -Ordinary Differential Equations-

(3)

For the voltage divider depicted below, sketch the power dissipated in RL as RL varies from 10 ohms to 150 ohms. Deduce the value of RL yielding a maximum power transfer.



$$I = \frac{V}{R_i + R_L} \Rightarrow P = R_L \left(\frac{V}{R_i + R_L}\right)^2 = V^2 \frac{R_L}{\left(R_i + R_L\right)^2}$$

```
>>close all; clear all; clc;
```

>>v=0.010;

>>RI=40

>>RL=10:1:150;

>>for i=1:length(RL)

 $P(i)=(v^2*RL(i))/(RI+RL(i))^2;$ 

end

>>plot(RL,P,'LineWidth',2,'Color',[0.2 0.3 0.1]);grid

>>set(gca,'Xtick',0:10:150);

>>axis([0 max(RL) min(P) max()])

>>xlabel('Values of RL (ohms)')

>>ylabel('Power dissipated in RL')

>>title('Maximum power transfer')


>>k=find(P==max(P));

>>fprintf('\n');

>>disp([Value of RL for max. power transfer: ', num2str(RL(k)),' ohms'])

>>fprint('\n');

(The plot is shown on the next page)



# Transfer Function

A transfer function H(s) characterizes fully a linear time-invariant system. There are two forms of transfer function representation in MATLAB. The most typical form is the polynomial form where

$$H(s) = \frac{num(s)}{den(s)} = \frac{b_m s^m + b_{m-1} s^{m-1} + \dots + b_0}{a_n s^n + a_{n-1} s^{n-1} + \dots + a_0}$$

When expressed in this form, it may be possible to solve for the roots of the two polynomials. The roots of the numerator are called the zeros, and the roots of the denominator are called the poles. An alternative form of representation for transfer function is the **factored** form. The poles and zeros are expressed explicitly,

$$H(s) = \frac{k(s-z_1)(s-z_2)....(s-z_m)}{(s-p_1)(s-p_2)....(s-p_n)}$$

A transfer function can be entered into MATLAB in a number of ways:

# The "tf(num,den)" Command

The **tf** command is used to create MATLAB representations of systems characterized by transfer functions. We can use the command **tf(num,den)**, where **num** and **den** are vectors of coefficients of the numerator and denominator polynomials, respectively.

-Transfer Function: The "tf(num,den)" Command(1)

Consider the system transfer function

$$H(s) = \frac{S^4 - 3S^3 + 5S^2 + 2S}{2S^7 + 5S^5 - 3S^4 + S^3 - 2S^2 + 3S - 1}$$

Find the factored form of the transfer function using the MATLAB function [z,p,k] = tf2zp(num,den)

#### **Practice**

-Transfer Function: The "tf(num,den)" Command-

**(2)** 

$$H(s) = \frac{s+1}{s^2 + 5s + 6}$$

>>num=[1 1]; % specify the numerator of H(s)

>>den=[1 5 6]; % specify the denominator of H(s)

>>sys=tf(num,den); % specify the transfer function of the system

>>sys % print the transfer function on the screen

## The "zpk(zeros, poles, gain)" Command

An alternative approach is to use the command **zpk(zeros, poles, gain)**, where **zeros**, **poles** and **gain** are vectors of zeros, poles and gain of the transfer function.

#### **Practice**

- Transfer Function: The "zpk(zeros, poles, gain) Command-

$$H(s) = \frac{5(s+3)}{(s+4)(s+11)}$$

>>zeros=[-3]; % specify the zeros of H(s)

>>poles=[-4-11]; % specify the poles of H(s)

>>gain=5; % specify the gain

>>sys=zpk(zeros,ploes,gain); % specify the transfer function H(s)

>>sys % print the transfer function on the screen

## The "tfdata" Command

The **TFDATA** command returns the coefficient polynomials for the numerator and the denominator from a given transfer function model.

where "v" returns the polynomial coefficients of the numerator and the denominator as vectors.

# The "zpkdata" Command

The **ZPKDATA** returns information about the zero-pole model created by the **zpk** command. The syntax for **ZPKDATA** is

$$>>[z,p,k]=zpkdata(sys,'v')$$

## **Defining Transfer Function**

Consider a system with transfer function given by

$$H(s) = \frac{4s}{s^2 + 9s + 8}$$

We define the transfer function first, then we declare to MATLAB that we will be using "s" as the variable for transfer function and "H" as a rational function of "s".

To obtain the poles of H and store them in poles H, we proceed as follows:

Similarly, the zeros of H are obtained as follows:

## - Transfer Function: Defining Transfer Function-

An LTI system is characterized by its transfer function given by

$$H(S) = \frac{3S^2 + 5S + 7}{2S^3 + 9S + 5}, \text{ Where S=} \sigma + JW$$
Plot  $|H(S)|$  over the region -10<5<10 , -5>[sigma,omega]=meshgrid(-10:0.1:10, -5:0.1:5);

>>S=Sigma+J\*omega;

>>X=(3\*S.^2+S\*S+7)./(2\*S.^3+9\*S+5);

>>surf(omega,sigma,abs(x))

>>axis([-5 5 -10 0 0 10])

>>view(-24,40);

>>set(gca, 'xdir', 'reverse', 'ydir', 'reverse')

>>xlabel('\omega');

>>ylabel('\sigma');

# Step Response & Impulse Response

## **Continuous-time System**

>>zlabel('|H(s)|')

### A. The "step" Command

We shall now take a look at the step response of a linear time-invariant system (LTI) specified by its transfer function. The step response is simply the output of an LTI system driven by a unit step function. The command **step** provides the step response of continuous-time LTI system.

## -Continuous-time System-

A. The "step" Command

A linear time-invariant system is modeled by its transfer function given by

$$H(s) = \frac{num(s)}{den(s)} = \frac{s+1}{s^2 + 3s + 3}$$

## Find the step response

>>% Step response of a continuous-time LTI system

>>num=[1 1]; % specify the numerator of H(s) >>den=[1 3 3]; % specify the denominator of H(s)

>>sys=tf(num,den) % LTI system model created with transfer function (tf)

>>step(sys) % plot the step response of given sstem

### Alternatively, a similar result cabe obtained through the following steps:

>>%Step response of a continuous-time LTI system

>>num=[1 1]; % specify the numerator of H(s) >>den=[1 3 3]; % specify the denominator of H(s)

>>sys=tf(num,den); % LTI system model >>t=0:0.01:10; % specify time vector

>>step(sys,t) % plot the step response of given system

#### A third alternative involves the determination of the response before plotting

>>%Step response of a continuous0time LTI system

>>t=0:0.01:10; % specify a time vector >>sys=tf([1 1],[1 3 3]); % specify model of system >>[y,t]=step(sys,t); % compute the step response >>plot(t,y);grid; % plot the step response

#### B. The "impulse" Command

The inverse Laplace transform of the transfer function H(s) is the impulse response of the system. The command **impulse** determines the impulse response of an LTI system.

- Continuous-time Systems-B. The "impulse" Command

Determine the impulse response of a system governed by the transfer function given by

$$H(s) = \frac{num(s)}{den(s)} = \frac{s+1}{s^2 + 3s + 3}$$

>>%Impulse response of a continuous-time LTI system

>>num=[1 1]; % specify the numerator of H(s)

>>den=[1 3 3]; % specify the denominator of H(s)

>>sys=tf(num,den); % specify model of system

>>t=0:0.01:10; % define a time vector

>>impulse(sys,t); % plot the impulse response

An alternative method involves the determination of the impulse response before plotting the result.

>>%Impulse response of a continuous-time LTI system

>>t=0:0.01:10; % specify time vector

>>sys=tf([1 1]),[1 3 3]); % model of the system

>>[y,t]=impulse(sys,t); % compute the impulse response

>>plot(t,y) % plot the impulse response

#### C. The "lsim" Command

The **lsim** command is used to simulate and plot the response of linear time invariant (LTI) systems to arbitrary inputs. The syntax for **lsim** is

>>lsim(sys,u,t)

where "sys" is a transfer function model, "u" is a vector of inputs and must be the same length as t, and "t" is a vector of time samples.

126

- Continuous-time Systems-C. The "Isim" Command (1)

Given the LTI System:  $H(s) = \frac{3s+2}{2s^3+4s+5s+1}$ 

Plot the following response for

- (a) The impulse response using the impulse command
- (b) The step response using the **step** command
- (c) The response to the input  $x(t)=\sin(0.5t)$  calculated using both the **lsim** and the **residue** commands

>>clear all; close all; clc;

>>num=[3 2]; den=[2 4 5 1];

>>sys=tf(num,den);

>>t=0:0.01:10;

>>impulse(sys,t) % impulse response

>>figure(1); step(sys,t) % step response

 $>>u=\sin(0.5*t);$ 

>>figure(2); lsim(sys,u,t)

#### **Practice**

- Continuous-time Systems-

C. The "lsim" Command

(2)

Given the LTI system:  $H(s) = \frac{s+5}{s^2+2s+5}$ 

Plot the response to a square wave having period T=1 and duration 10.

>>num=[1 5];

>>den=[1 2 5];

>>sys=tf(num,den);

>>[u,t]=gensig('square',1,10);

>>subplot(2,1,1); plot(t,u)


>>set(gca, 'Ylim', [-0.1 1.1])

>>subplot(2,1,2); lsim(sys,u,t)


## **Discrete-time Systems**

The discrete counterparts of the commands **step** and **impulse** are **dstep** and **dimpulse**. We shall illustrate these commands with few examples:

## A. The "dstep" Command



## B. The "dimpulse" Command



# Pole-zero Plots

## - The "pzmap" Command

The command **pzmap** displays the poles and zeros of the continuous- or discrete-time linear system in the complex plane. The multiplicity of poles and zeros is not specified by **pzmap**. The poles are depicted as crosses (x's), and zeros by (0's).

-Pole-zero Plots: The "pzmap" Command-

Consider a linear time-invariant system modeled by the following transfer function:

$$H(s) = \frac{s^3 + 2s^2 + 3s + 4}{s^4 + 5s^3 + 2s^2 + 2s + 9}$$

Sketch the pole-zero plot of the system specified by H(s).

>>%Pole-zero plot of the system specified by H(s)


>>num=[1 2 3 4]; %specify the numerator of H(s)

>>den=[1 5 2 2 9]; % specify the denominator of H(s)

>>sys=tf(num,den); % model of the system

>>pzmap(sys) % plot the pole-zero plot

>>[p,z]=pzmap(sys); % return the system poles and zeros



# The Z-Plane

### - The "zplane" Command

The command **zplane** displays the poles and zeros of a linear time-invariant system in the complex plane with a unit circle as a reference. The relative location of the poles and zeros, with respect to the unit circle, is an important aspect in the analysis and design of digital filters. Multiple order poles and zeros are indicated by the multiplicity number shown to the upper right of the zeros or poles.

-The Z-plane: The "zplane" Command-

(1)

A linear time-invariant discrete-time system is modeled by its transfer function given by

$$H(z) = \frac{num(z)}{den(z)} = \frac{z^2 + 3z + 1}{z^4 + 3z^3 + 7z^2 + 3z + 9} = \frac{z^{-2} + 3z^{-3} + z^{-4}}{1 + 3z^{-1} + 7z^{-2} + 3z^{-3} + 9z - 4}$$

Plot the zero-pole plot of the system.

>>num=[0 0 1 3 1];


% specify numerator of H(z)

>>den=[1 3 7 3 9];

% specify denominator of H(z)

>>zplane(num,den)

% plot of zero-pole plot



### **Practice**

- The Z-Plane: The "zplane" Command-

(2)

Find the poles and zeros of the following transfer function and plot them onto the z-plane.

$$H(z) = \frac{1 - 0.1z^{-1}}{1 - 0.1z^{-1} - 0.02z - 2}$$

>>num=[1 -0.1];

>>den=[1 -0.1 -0.2];

>>poles=roots(den)

>>zeros=roots(num)

>>zplane(num,den)

**Question**: Is this system stable? Why?

**Answer:** Yes, the system is stable, since all of its poles lie inside the unit circle on the z-plane.

- The Z-Plane: The "zplane" Command(3)

$$H(z) = \frac{1 - 1.6180z^{-1} + z^{-2}}{1 - 1.5161z^{-1} + 0.878z^{-2}}$$

>>num=[1 -1.6180 1];

>>den=[1 -1.5161 0.878];

>>roots(den)

>>zplane(num,den)

### **Practice**

- The Z-Plane: The "zplane" Command(4)

An LTI system is described by the following difference equation:

$$y[n] + 0.2y[n-1] + 0.8y[n-2] = 0.3x[n] + 0.6x[n-1] + 0.2x[n-2]$$

- 1. Find the poles and zeros of the system
- 2. Plot the pole-zero diagram
- 3. Is the system stable? (BIBO stability implies the convergence of the cumulative sum of the absolute value of the impulse response.)
- 4. Plot the magnitude and phase responses

```
>>b=[1 \ 0.2 \ 0.8];
```

>>a=[0.3 0.6 0.2];

>>zero=roots(b);

>>pole=roots(a);

>>zplane(b,a);

>>delta=[1 zeros(1,30)];

>>h=filter(b,a,delta);

>>cumsum(h)

 $>> N=512; F_S=8000;$ 

>>freqz(b,a,N,Fs)

# Stability Design via Routh-Hurwitz

It is possible to use MATLAB to find the gain, K, for the system so that it becomes stable. Following is an illustration of the design of gain of transfer function:

```
Practice
                   -Stability Design via Routh-Hurwitz-
>>K=1:2000;
                                  % specify the range of K
>>for m=1:length(K)
                                  % number of K values to test
      denH=[1 18 77 K(m)];
                                  % specify the denominator of H(s)
      poles=roots(denH);
                                  % evaluate poles
      r=real(poles);
                                  %vector containing real values
      if max(r) \ge 0
                                  % test poles for real parts
                                  % display poles with real part positive
      poles
                                  % display the corresponding value of K
      K=K(m)
                                  % stop loop if rhp poles are found
      break
                                  % end if
      end
                                  % end for
end
```

## Partial-fraction Expansion

If the analysis of continuous-time and discrete-time systems, one very useful method of solving the inverse Laplace transform and the inverse Z transform is to perform partial fraction expansion on the transfer function H(s) and H(z). MATLAB has built-in functions called **residue** and **residuez** that return the partial fraction expansions of the transfer function H(s) and H(z), respectively. MATLAB is very helpful in eliminating the tedious computations required to compute partial fraction expansion (PFE) coefficients for rational transforms.

## Partial-fraction Expansion on H(s)

### A. Simple Poles

$$H(s) = \frac{num(s)}{den(s)} = \frac{s^{m} + b_{m-1}s^{m-1} + \dots + b_{1}s + b_{0}}{s^{n} + a_{n-1}s^{n-1} + \dots + a_{1}s + a_{0}} = \frac{r(1)}{s - p(1)} + \frac{r(2)}{s - p(2)} + \dots + \frac{r(n)}{s - p(n)} + k(s)$$

where p(k) are the poles of the transfer function, r(k) are the coefficients of the partial fraction terms (called the residues of the poles) and k(s) is a remainder polynomial which is usually empty.

### □ Syntax

>>[r,p,k]=residue(num,den); % perform partial fraction expansion of H(s)

>>[num,den]=residue(r,p,k); % convert partial fraction back to polynomial form

The "residue" command gives three pieces of information, namely

- (1) the residues are given in output column vector r.
- (2) the poles are given in output column vector p.
- (3) the direct terms are given in output row vector k.
- (a) when the order of the numerator polynomial is smaller than the order of the denominator polynomial, there will be no direct terms.
- (b) When the order of the numerator equals the order of the denominator, there will be one direct term.
- (c) When the order of the numerator is greater than the order of the denominator, there will be two direct terms; etc.

## Partial-fraction Expansion on H(s): Simple Poles

A linear time-invariant (LTI) system is governed by the transfer function H(s) given by

$$H(s) = \frac{s^2 + 2s + 3}{s^3 + 5s^2 + 2s + 7}$$

Use the residue command to obtain the partial fraction expansion of H(s)

>>Partial-fraction expansion via MATLAB

>>num=[1 2 3]; % specify numerator of H(s)

>>den=[1 5 2 7]; % specify denominator of H(s)

>>[r,p,k]=residue(num,den) % perform partial fraction expansion

r =

0.6912

0.1544 - 0.1645i

0.1544 + 0.1645i

p =

-4.8840

-0.0580 + 1.1958i

-0.0580 - 1.1958i

k =

[]

$$\therefore H(s) = \frac{0.6912}{s + 4.8840} + \frac{0.1544 - 0.1645j}{s + 0.0580 - 1.1958j} + \frac{0.1544 + 0.1645j}{s + 0.0580 + 1.1958j}$$

## **B.** Multiple Poles

$$H(s) = \frac{num(s)}{den(s)} = \frac{r(1)}{s-p} + \frac{r(2)}{(s-p)^2} + ... + \frac{r(m)}{(s-p)^m}$$

### **Practice**

-Partial-fraction Expansion on H(s): Multiple Poles-

$$H(s) = \frac{8s+10}{(s+1)(s+2)^3} = \frac{B_1}{s+2} + \frac{B_2}{(s+2)^2} + \frac{B_3}{(s+2)^3} + \frac{A}{s+1}$$

>>num=[8 10];

% specify numerator

>>den=con([1 1],[1 6 12 8]);

% specify denominator

>>[r,p,k]=residue(num,den)

% perform partial fraction expansion

r =

- 2.0000
- -2.0000

6.0000

2.0000

p =

- -2.0000
- -2.0000
- -2.0000
- -1.0000

k =

[]

$$\therefore H(s) = -\frac{2}{s+2} - \frac{2}{(s+2)^2} + \frac{6}{(s+2)^3} + \frac{2}{s+1}$$

## Partial-fraction Expansion on H(z)

In this section, we shall consider the Z Transform in the MATLAB environment. A key concept is the representation of polynomials and transfer functions. As we indicated in previous chapters, MATLAB treats polynomials as a vector of coefficients in descending powers of the polynomial variable. Thus, to represent

$$f(x) = x^2 - 3x + 2$$
, we write

$$>>f=[1 -3 2]$$

With Z Tranforms, we tend to have negative powers of the polynomial variable z. We still write a vector of coefficients in descending power of z so the farther right you go in a vector, the smaller the power of z. "Smaller" means -2<-1. For example, the polynomial  $f(z) = 1 - 2z^{-1} + 3z^{-2}$  would be written in MATLAB as

$$>> f=[1 -2 3]$$

In MATLAB transfer functions are always assumed to be of the form:

$$H(z) = \frac{num(z)}{den(z)} = \frac{b_1 + b_2 z^{-1} + b_3 z^{-3} + \dots + b_{(M+1)} z^{-M}}{a_1 + a_2 z^{-1} + a_3 z^{-2} + \dots + a_{(N+1)} z^{-N}}$$

where the numerator polynomial num(z) is represented by the length-(M+1) row vector

$$>> N = [b_1 \ b_2 \ b_3 \dots b_{M+1}]$$

and the denominator polynomial den(z) is represented by the length-(N+1) row vector

>>D=[
$$a_1 \ a_2 \dots a_{N+1}$$
]

#### A. Simple Poles

$$H(z) = \frac{num(z)}{den(z)} = \frac{r(1)}{1 - p(1)z^{-1}} + \frac{r(2)}{1 - p(2)z^{-1}} + \dots + \frac{r(n)}{1 - p(n)z^{-1}} + k(1) + k(2)z^{-1} + \dots + k(m - n + 1)z^{-(m - n)}$$

where **num** and **den** are the numerator and denominator polynomial coefficients, respectively, in ascending powers of  $z^{-1}$ , **r** and **p** are column vectors containing the residues and poles, respectively, **k** contains the direct terms in a row vector.

## □ Syntax

- >>[r,p,k]=residuez(num,den); % perform partial fraction expansion of H(z)
- >>[num,den]=residuez(r,p,k); % convert the partial fraction back to polynomial form

### **Practice**

## -Partial-fraction Expansion on H(z): Simple Poles

(1)

A linear time-invariant system is governed by the transfer function H(z) given by

$$X(z) = \frac{1 + 2z^{-1} + z^{-2}}{1 - z^{-1} + 0.3561z^{-2}}$$

- >> num=[1 2 1];
- >>den=[1 -1 0.3561];
- >>[r,p,k]=residuez(num,den)

$$r =$$

- -0.9041 5.9928i
- -0.9041 + 5.9928i

- 0.5000 + 0.3257i
- 0.5000 0.3257i

#### k =

2.8082

### **Practice**

-Partial-fraction Expansion on H(z): Simple Poles

(2)

$$H(z) = \frac{2+3z^{-1}+4z^{-2}}{1+3z^{-1}+3z^{-2}+z^{-3}} = \frac{2z^3+3z^2+4z}{z^3+3z^2+3z+1}$$

- >> num=[2 3 4];
- >>den=[1 3 3 1];
- >>q=roots(den)
- >>p=roots(num)
- >>k=num(1)/den(1)
- >>bb=k\*poly(q)
- >>aa=poly(p)

## -Partial-fraction Expansion on H(z): Simple Poles

$$H(z) = \frac{-4 + 8z^{-1}}{1 + 6z^{-1} + 8z^{-2}}$$

>>num=[-4 8];

>>[r p k]=residuez(num,den)

-12

[]

## **B.** Multiple Poles

If  $p_1$  is a pole of multiplicity m, then H(z) has terms of the form:

$$H(z) = \frac{num(z)}{den(z)} = \frac{r(1)}{1 - p_1 z^{-1}} + \frac{r(2)}{(1 - p_1 z^{-1})^2} + \dots + \frac{r(m)}{(1 - p_1 z^{-1})^m}$$

### **Practice**

- Partial-fraction Expansion: Multiple Poles-

Use the **residuez** command to find the partial fraction expansion of H(z).

$$H(z) = \frac{num(z)}{den(z)} = \frac{2 + 3z^{-1} + 4z^{-2}}{1 + 3z^{-1} + 3z^{-2} + z^{-3}}$$

>>num=[2 3 4]; >>den=[1 3 3 1]; % specify the numerator of H(z)

% specify the denominator of H(z)

>>[r,p,k]=residuez(num,den) % perform partial fraction expansion

(The results are shown on the next page)

r = 4.0000 - 0.0000i -5.0001 + 0.0000i 3.0000 - 0.0000i p = -1.0000 -1.0000 + 0.0000i -1.0000 - 0.0000i k =  $\begin{bmatrix} \end{bmatrix}$   $\therefore H(z) = \frac{4}{1+z^{-1}} - \frac{5}{\left(1+z^{-1}\right)^2} + \frac{3}{\left(1+z^{-1}\right)^3}$ 

# Power Series Expansion with MATLAB

### - The "deconv" Command

The **deconv** function is used to perform the long division required in power series method. For the following z-tranform x(z)

$$X(z) = \frac{b_0 + b_1 z^{-1} + \dots + b_n z^{-n}}{a_0 + a_1 z^{-1} + \dots + a_m z^{-m}}$$

The matlab command is

$$>>[a,r]=deconv(a,b)$$

- Power Series Expansion with MATLAB: The "deconv" Command-

```
X(z) = \frac{1 + 2z^{-1} + z^{-2}}{1 - z^{-1} + 0.3561z^{-2}}
>>num=[1 2 1];
>>den=[1 -1 0.3561];
>>n=5;
>>num=[num zeros(1,n-1)];
>>[x,r]=decony(num,den)
```

# Bode Plots

#### -The "bode" Command

If a system has a transfer function H(s), its frequency response,  $H(j\omega)$ , is in general complex, and it's typically represented in two separate plots, one for its magnitude and the other for its phase, both as functions of frequency  $\omega$ . These two plots together are called the Bode plot of the system. The command **bode** produces both the magnitude and the phase response.

## □ Syntax

>>bode(sys)

Draw automatically the magnitude and phase plots of a system modeled by the transfer function H(s), specified by sys. The frequency is on a logarithmic scale, the phase is given in degree, and the magnitude is given as the gain in decibels.

This function returns the magnitude and phase of system specified in terms of its transfer function H(s). The magnitude and phase are evaluated at a frequency vector w specified by the user. The obtain a plot with the magnitude expressed in decibels over a logarithmic frequency axis use semilogx(w,20\*log10(mag)). Similarly, the

phase (in degrees) over a logarithmic frequency axis is obtained via semilogx(w, phase). Finally, if it is desired to have a frequency axis in HZ, use x/(2\*pi) instead of w.

>>[mag,phase,w]=bode(sys);

This function returns the magnitude, phase, and a vector w that contains the values of the frequency in rad/s where the frequency response has been calculated.



In order to plot the magnitude and phase you need to remove singleton dimensions from mag and phase. This is done using the **squeeze** function or **reshape** function. This is carried out as follows:

- >>[mag, phase]=bode(sys,w);
- >>mag=squeeze(mag);
- >>phase=squeeze(phase);
- >>semilogx(w,20\*log10(mag))

#### **Practice**

-Bode Plots-(1)


Consider a linear time-invariant system governed by its transfer function given by

$$H(s) = \frac{num(s)}{den(s)} = \frac{78(s+8)}{s^2 + 25s + 625}$$

Draw the bode plot

(The matlab codes are shown on the next page)

```
>>%Bode plot with MATLAB
>>num=78*[1 8];
                                          % specify the numerator of H(s)
>>den=[1 25 625];
                                          % specify the denominator of H(s)
>>H=tf(num,den);
                                          % specify the transfer function model
>>[mag,phase,w]=bode(H)
                                          % compute magnitude and phase
>>%The output arguments of mag and phase are 3-D arrays. We need to alter the
>>%size of both via the reshape function, before plotting can be made possible.
>>subplot(2,1,1);semilogx(w,reshape(mag,length(w),1));grid
>>ylabel('|H(\omega)|')
>>subplot(2,1,2);semilogx(w,reshape(phase,length(w),1));grid
>>ylabel('\theta(\omega)')
>>xlabel('\omega')
```



#### Alternatively, the same results can be obtained as follows:

>>subplot(2,1,2);semilogx(w,phase);grid

```
>>%Bode plot with MATLAB
>>num=78*[1 8];
                                       % specify the numerator of H(s)
>>den=[1 25 625];
                                       % specify the denominator of H(s)
>>H=tf(num,den);
                                       % model of the system
>>w=1:0.02:100;
                                       % specify a frequency vector
>>[mag,phase]=bode(H,w);
                                       % compute magnitude and phase
                                       % reshape mag into a column vector
>>mag=reshape(mag,size(w));
>>phase=reshape(phase,size(w));
                                       % reshape phase into a column vector
>>subplot(2,1,1);semilogx(w,20*log10(mag));grid
```

-Bode Plots-

**(2)** 

1. Simulate the response of the system

$$H(s) = \frac{10(s+6)}{s^2 + 5s + 4}$$

to the sinusoidal input  $x(t) = 3\cos(6t + 30^\circ)$  over the interval  $o \le t \le 5$ , assuming the system is in zero state.

- 2. Find the frequency response  $H(j\omega)$  at  $\omega = 6$  rad/s
- 3. Calculate the steady-state output,  $y_{ss}(t)$
- 4. Sketch x(t), y(t) and yss(t) in a single plot

```
>>t=[0:0.05:5]';

>>x=3*cos(6*t+30*pi/180);

>>y=lsim(num,den,x,t);

>>[mag,phase]=bode(num,den,6);

>>yss=3*mag*cos(6*t+(30+phase)*pi/180);

>>subplot(2,1,1);plot(t,x,t,y,'r',t,yss,'k','LineWidth',2);

>>set(gca,'XTick',[0:0.5:5])

>>title('Sinusoidal steady-state response')

>>xlabel('Time (secs)')

>>ylabel('Amplitude')
```

# Interconnection of Systems

- The Commands: "series", "parallel", "feedback" & "cloop"

## **Three Interconnect Ways**

Systems may be interconnected in various ways to form larger systems. Conversely, one might break down larger systems into smaller ones to facilitate design and analysis. There are three major ways in which systems can be interconnected, namely,

□ Series interconnection (or cascade)

- □ Parallel interconnection
- ☐ Feedback interconnection (positive feedback or negative feedback)

The MATLAB commands, **series**, **parallel**, **feedback**, and **cloop**, provide the overall transfer function of systems that are connected in series, parallel, feedback, and a close-loop (unity feedback) system description given an open-loop system, respectively.

#### **Practice**

#### -Interconnection of Systems-

(1)

Two systems are governed by the following transfer functions:

$$H_1(s) = \frac{s}{s^2 + 2s + 3}, \ H_2(s) = \frac{s + 3}{s^2 + 5s + 1}$$

- 1. Find the overall transfer function of the cascaded systems
- 2. Repeat part (1) if the systems are connected in parallel
- 3. Repeat part (1) for a feedback connection

>>%systems connected in cascade

>>num1=[1 0]; % specify numerator of system 1

>>den1=[1 2 3]; % specify denominator of system 1

>>sys1=tf(num1,den1); % specify system 1

>>num2=[1 3]; % specify numerator of system 2

>>den2=[1 5 1]; % specify denominator of system 2

>>sys2=tf(num2,den2); % specify system 2

>>sys=series(sys1,sy2) % specify the overall cascaded system

#### **Transfer function**

$$s^2 + 3s$$

-----

>>sys=parallel(sys2,sys2) % specify overall system in parallel

(Continue on the next page)

#### **Transfer function**

-----

- >> sign=-1 % sign=-1 (negative feedback), sign=+1 (positive feedback)
- >>sys=feedback(sys1, sys2, sign) % specify model for the closed-loop feedback system

#### **Transfer function**

$$s^3+5s^2+s$$

-----


s^4+7s^3+15s^2+20s+3

#### **Practice**

- Interconnection of Systems-

**(2**)

Find the overall transfer function of the system shown below.



- >>numg=[1 2];
- >>deng=conv([1 3], [1 6]);
- >>numh=[1 7];
- >>denh=[1 10];
- >>[num,den]=feedback(numg,deng,numh,denh);
- >>sys=tf(num,den)

#### **Transfer function**

$$s^2+12s+20$$


-----

s^3+20x^2+117s+194

- Interconnection of Systems-

(3)

Find the transfer function of the feedback system depicted below



- >>numg=[1 2];
- >>deng=conv([1 4], [1 6]);
- >>[num,den]=cloop(numg,deng);
- >>sys=tf(num,den)

#### **Transfer function**

s+2

-----


s^2+11s+26

#### **Practice**

- Interconnection of Systems-

**(4)** 

Determine the transfer function of the system shown below:



(The matlab codes and the answer are shown on the next page)

```
>>num1=[1 0.6], den1=[1 -1 0.5]; sys1=tf(num1,den1);

>>num2=[1 0]; den2=[1 0 1]; sys2=tf(num2,den2);

>>num3=[2 0]; den3=[1 2 1]; sys3=tf(num3,den3);

>>sys23=parallel(sys2,sys3);

>>sys123=series(sys1,sys23)

Ans: H(s) = \frac{y(s)}{x(s)} = \frac{s^5 + 2.6s^4 + 3.2s^3 + 4.2s^2 + 1.8s}{s^7 - s^6 + 3.5s^5 + 2s^4 + 2.5s^3 - 0.5s^2 + 0.5}
```

## Frequency Response Plots

#### **Continuous-time LTI Models**

The command **freqs** and **freqz** provide the frequency response in the s-domain the frequency response in the z-domain, respectively. Several MATLAB commands are used in conjunction with frequency plots, namely, **abs**, **angle**, and **upwrap**. The **abs** and **angle** extract the magnitude and phase response, respectively, and **unwrap** removes jumps of size  $2\pi$  prior to plotting the phase.

We begin with the frequency response of continuous-time linear time-invariant system. The system function of a continuous-time system can be written in the form:

$$H(s) = \frac{num(s)}{den(s)} = \frac{s^m + b_{m-1}s^{m-1} + \dots + b_1s + b_0}{s^n + a_{n-1}s^{n-1} + \dots + a_1s + a_0}$$

#### ☐ Syntax

#### >>[H,w]=freqs(num,den);

Given the transfer function, H(s), specified by its numerator and denominator coefficients **num** and **den** in vector form. The function **freqs** returns the complex frequency response **H**, and a set of 200 frequencies **w** (in rad/s) where the frequency response has been calculated.

#### >>freq(num,den,w);

This function returns the complex frequency response **H** of an **LTI** system specified in terms of its transfer function H(s). The complex frequency response is evaluated at a frequency vector **w** specified by the user.

#### >>freqs(num,den);

Draws automatically the magnitude (in dB) and phase (in degrees) plots of a system modeled by the transfer function H(s).

#### **Practice**

#### Frequency Response Plots: Continuous-time LTI Models

Plot the s-domain frequency response of a system governed by the following transfer function:

$$H(s) = \frac{10}{s^2 + 11s + 10}$$

>>%The transfer function must be entered as vectors of descending powers of s

>> num=10; % specify numerator of H(s)

>>den=[1 11 10]; % specify denominator of H(s)

>>w=-15:0.05:15; % specify a frequency vector

>>H=freqs(num,den,w); % provide the frequency vector

>>mag=abs(H); % compute the magnitude response

>>phase=angle(H)\*180/pi; % compute the phase response in degrees

>>line 3dB=0.07\*ones(size(w))\*max(mag); % draw the 3-dB line

>>subplot(2,1,1);plot(w,mag,w,line 3dB,'ro'); % plot magnitude response and 3-dB line

>>subplot(2,1,2);plot(w,phase); % pot the phase response

#### **Discrete-time LTI Models**

We shall now consider the frequency response of discrete-time systems, which is also known as the discrete-time Fourier transform (DTFT). In general, the transfer function of a discrete-time system can be written in the form,

$$H(z) = \frac{num(z)}{den(z)} = \frac{b_1 + b_2 z^{-1} + \dots + b_{nb+1} z^{-nb}}{a_1 + a_2 z^{-1} + \dots + a_{na+1} z^{-na}}$$

#### □ Syntax

#### 1. >>[H,w]=freqz(num,den,n,'whole');

This function returns the complex frequency response **H**, and a frequency vector **w** (in radians per sample) containing the n frequency points spaced around the **whole** unit circle  $(0 \le \omega \le 2\pi)$ . If n is not specified, it defaults to 512.

#### 2. >>[H,w]=freqz(num,den,n);

Evaluates the complex frequency response **H** at **n** equally spaced points around the upper half of the unit circle. The frequency vector w has values ranging from 0 to  $\pi$  radians per sample. When you don't specify the integer n, or you specify it as the empty vector [], the frequency response is computed using the default value of 512 samples.

#### 3. >>H=freqz(num,den,w);

Returns the frequency response vector H calculated at the frequencies (in radians per sample) supplied by the vector w. The vector w can have an arbitrary length.

#### 4. >>freqz(num,den);

Returns the magnitude response (in dB) and the **unwrapped** phase response (in degrees) against the normalized frequency from 0 to 1.

#### 5. >>[H,f]=freqz(num,den,n, Fs);

Returns the frequency response vector **H** and the corresponding frequency vector **f** for the digital filter whose transfer function is determined by the (real or complex) numerator and denominator polynomials represented in the vector **num** and **den**, respectively. The frequency vector **f** is computed in units of Hz. The frequency vector **f** has values ranging from 0 to Fs/2.

#### 6. >>[H,f]=freqz(num,den,n,'whole',Fs);

Uses n points around the whole unit circle (from 0 to  $2\pi$ , or from 0 to Fs), to calculate the frequency response. The frequency vector  $\mathbf{f}$  has length n and has values ranging from 0 to Fs Hz.

#### 7. >>H=freqz(num,den,f,Fs);

Returns the frequency response vector  $\mathbf{H}$  calculated at the frequencies (in Hz) supplied in the vector  $\mathbf{f}$ . The vector  $\mathbf{f}$  can have an arbitrary length.

#### 8. >>[h,f,units]=freqz(num,den,n,'whole',Fs);

Returns the optional string argument **units**, specifying the units for the frequency vector f. The string returned in **units** is Hz.

#### **Practice**

#### Frequency Response Plots: Discrete-time LTI Models

- (1) Compute 512 samples of the complex frequency response  $H(e^{j\omega})$  for  $0 \square w \square 2\pi$  using **freqz**.
- (2) Plot the magnitude spectrum  $\left|H\left(e^{j\omega}\right)\right|$  for  $0 \le w < 2\pi$  as well as a scaled version  $10 \ H\left(e^{j\omega}\right)$  for  $\frac{\pi}{2} \le w \le \frac{3\pi}{2}$  using axis ('square') in that case. Note the symmetry of  $H\left(e^{j\omega}\right)$  with respect to the real axis.
- (3) Plot  $|H(e^{j\omega})|$  and the phase  $H(e^{j\omega})$  for  $0 \le w < \pi$  with the normal axis.

(The matlab codes are shown on the next page)

```
>>[num,den]=ellip(3,1,20,0.4)
>> N=512;
>>[H,W]=freqz(num,den,N,'whole');
>>figure(1); plot(w/pi, abs(H1);
>>xlabel('Normalized frequency,[rad/pi]');grid
>>title('Magnitude'), ylabel('\(\subseteq H(e^{2\omega})\subsete ')
>>range=(w>=pi/2)&(w<=3*pi/2);
>>figure(2)
>>plot([-0.4 0.6],[0 0],'k');hold on
>>plot([0 0], [-1 1],'k') %draw x-y axis
>>plot(10*H(range)); hold off
>>axis('square'); grid
>>xlabel('Re(10H(e^{2\omega}))')
>>ylabel('Im(10(e^{2\omega}))')
>>w1=w(1:N/2+1);
>>H1=H(1:N/2+1);
>>figure(3)
>>subplot(211), plot(w/pi,abs(H1))
>>title('magnitude phase'), ylabel('|H(e^{2\omega})|')
>>subplot(212); plot(w1/pi, unwrap(angle(H1)))
>>xlabel('normalized freq[rad/pi]);
>>ylabel('angle H(e^{2\omega})')
```

# Fourier Synthesis

Fourier series is often used to model periodic signals. By truncating the Fourier series, signals can be approximated accurately enough for applications. The computation and study of Fourier series is known as harmonic analysis. The process of expanding a periodic signal in Fourier series is termed **analysis**, while the process of reconstructing a waveform from its Fourier series is termed **Fourier synthesis**. It is well known that around a discontinuity of a function, the partial sum of the Fourier series exhibit oscillatory behavior (ringing) known as the **Gibbs phenomenon**. The **Gibbs phenomenon** is caused by the difficulty to represent sharp discontinuities with smooth trigonometric functions.

-Fourier Synthesis-

**(1)** 

The Fourier series of a pulse waveform is given by

$$y(t) = \frac{1}{2\pi} + \sum_{n\pi}^{\infty} \frac{2}{n\pi} \sin\left(\frac{1}{2}n\right) \cos(nt)$$

Write a script file to synthesize an approximation of the pulse wave. Experiment with the number of terms in the partial sum and describe your observations as the number of terms increase. The error caused by using only a finite number of terms (truncated series) is called the truncation error.

>>t=3\*pi:0.02:3\*pi;

>>N=input('Enter the number of terms:')

>>x=zeros(size(t));

>>for n=1:N

>>x=x+(2/(n\*pi))\*sin(0.5\*n)\*cos(n\*t);

end

>>y=x+1/(2\*pi);

>>plot(t,y);grid

>>s=int2str(N);

>>title(['Fourier synthesis of a pulse wave:,'s', terms'])

>>xlabel('time,[s]')

>>xlabel('Approximation of y(t)')

% specify time span

% input the number of terms

% initialization

% time index

% form the partial sum

% end of loop

% add dc component


% plot the partial sum

% convert N into a string

% add title to the resulting plot

% label the horizontal axis

% label the vertical axis



# - Fourier Synthesis-

**(2)** 

Write a script file to synthesize a square wave whose complex Fourier series coefficients are given by

$$x(t) = \sum_{n=-\infty}^{\infty} c_n e^{jn\frac{2\pi}{T}1 = t} \to C_n = \frac{1}{2} \sin c \left(\frac{n}{2}\right)$$

N=input ('Enter the number of terms:');

t=[-1:0.001:1];

n=-N:N;

cn=1/2\*sinc(n/2);

 $B = \exp(j*2*pi*t, '*n);$ 

C=ones(length(t),1)\*cn;

P=B.\*C;

xtrunc=(sum(P.'0).';

subplot(2,1,1);plot(t,real(strunc),'LineWidth',2);grid

title('Fourier synthesis of a squarewave')


ylabel('Approximation of x(t)')

subplot(2,1,2);h=stem(n,cn,'filled');grid

set(h,'LineWidth',2);

title('Discrete line spectrum of x(t)')

ylabel('Amplitude spectrum')



# The Discrete Time Fourier Transform

The discrete time Fourier transform of a sequence x[n] is defined by

$$X(e^{j\omega}) = X(\omega) = \sum_{n=-\infty}^{\infty} x[x]e^{-j\omega n}$$

#### **Practice**

#### - The Discrete Time Fourier Transform-

1. Generate the following signal

$$x[n] = 1 + \cos \frac{25\pi n}{100}, \quad 0 \le n \le 99$$

- 2. compute the DTFT of x[n] for  $\omega = 0.0.01.2 \times \pi$
- 3. Plot the real part, the imaginary part, the amplitude and phase of  $X(\omega)$

```
>>x=1+\cos(25*pi/100)*(0:99));
                                                    % generate signal
>>w=0:0.01:2*pi;
                                                    % frequency vector
>> X = \exp(-j*w((:)*(0:99))*x(:);
                                                    % dtft
>>figure(1);
>>plot(w,real(X),w, imag(x));
                                                    % plot real and imaginary components
>>xlabel('\omega');
>>title('Re(\itX\rm(\omega)),Im(\it\X\rm(\omega))')
>>figure(2);
>>plot(w,abs(X));
                                                    % plot magnitude
>>figure(3);
>>plot(w,angle(X));
                                                    % plot phase
```

## The Discrete Fourier Transform (DFT)

#### **Introduction of DFT**

In a variety of applications, we want to interpret data as signals of different frequencies. One way to accomplish this task is through the Discrete Fourier Transform (DFT). The DFT is a well-known tool to analyze the spectral content of a time series. The DFT is a very computationally intensive procedure.

#### **Introduction of FFT**

In 1965, Cooley and Tukey published a numerical algorithm to evaluate the DFT with a significant reduction in the amount of calculation required. The Fast Fourier Transform, or FFT, is a general name for a class of algorithms that allow the Discrete Fourier Transform of a sampled signal to be obtained rapidly and efficiently. Keep in mind that FFT is not a new transform, but a computationally efficient method to compute the DFT. A common use of the FFT is to find the frequency components buried in a noisy time domain signal.

#### The Commands

- "fft" & "ifft"

The **fft** command of MATLAB allows the computation of the Discrete Fourier Transform (DFT) of an N element vector x representing N samples of a discrete time signal. The function **ifft** defines the inverse discrete Fourier transform. For any x[n], the value **ifft(fft(x))** equals x to within roundoff errors.

#### □ Syntax

>>X=fft(x); % compute the DFT of x

>>x=ifft(X); % compute the inverse DFT of X



For the fastest possible FFTs, you will want to pad your data with enough zeros to make its length power of two. The **fft** function does this automatically if you provide a second argument specifying the overall length of the FFT as follows:

$$>> X = fft(x,N);$$
 % compute an N-point DFT

The next highest power of 2 greater than or equal to the length of the given sequence x[n] can be found using the MATLAB command **nextpow2**.

- The Discrete Fourier Transform-

**(1)** 

Find the next highest power of 2 of 235-point sequence x[n]

>>N=235; % length of the sequence x[n] >>NFFT=2^nextpow2(N) % make the length a power of 2

NFFT =

256

The result of **fft** is generally an array of complex numbers. The command **abs** and **angle** can be used to compute the magnitude and agnle of the complex values respectively.

#### The Command

- "fftshift"

For plotting a two-sided transform, the command *fftshift* will rearrange the output of **fft** to move the zero component to the center of the spectrum, as the following code demonstrates.

#### **Practice**

- The Discrete Fourier Transform-

**(2)** 

 $>> x=[1 \ 2 \ 3 \ 4];$  % define a vector x

>>y=fftshift(x) % swap the first and second halves of x

v =

3 4 1 2

- The Discrete Fourier Transform-

**(3)** 

Find the 4-point DFT of the sequence x[0]=1, x[1]=2, x[2]=3, x[3]=4, and x[n]=0 for all other n.

>>n=0:3; % index

>> xn=[1 2 3 4]; % sequence x[n]

>> Xk = fft(xn) % compute the FFT of x[n]

Xk =

10.0000 -2.0000 + 2.0000i -2.0000 -2.0000 - 2.0000i

#### **Practice**

- The Discrete Fourier Transform-

**(4)** 

#### **Circular convolution subroutine**

#### **Cirshift subroutine**

function y=circonv(x1,x2) function y=circshift(x,m)

L1=length(x1); %Develops a sequence y obtained by

L2=length(x2); %circularly shifting a finite length if L1~=L2, error('sequences of unequal length'),end %sequence x by M samples

y=zeros(1,L1); If abs(M)>length(x)

x2tr=[x2(1) x2(L2:-1:2)]; M=rem(M,length(x));

for k=1:L1 end sh=circshift(x2tr,1-k); If M<0

sh=circshift(x2tr,1-k); If M<0 h=x1.\*sh; M=M+length(x);

y(k)=sum(h); end

end y=[x(M+1:length(x)) x(1:M)];

## -The Discrete Fourier Transform-

(5)

We form a signal containing 40 Hz and 150 Hz frequency components and corrupt it with gaussian noise having zero mean and unity standard deviation.

- 1. Sketch the corrupted signal in the time-domain
- 2. Determine the spectrum of the corrupted signal and sketch it

>>Fs=1000; % specify the sampling frequency

>>t=0:1/Fs:1; % define a time base >>sig=cos(2\*pi\*40\*t)+cos(2\*pi\*150\*t); % signal component

>>noise=randn(size(sig)); % noise component

>>signal=sig+noise; % corrupted signal

>>subplot(2,1,1);plot(t,signal);grid % plot corrupted signal

>>title('Signal in the presence of noise') % add title

>>spec=fft(signal, 512); % compute the spectrum of corrupted signal


>>mag=fftshift(abs(spec)); % center the spectrum around dc

>>f=Fs\*(-255:256)/512; & frequency vetor

>>subplot(2,1,2);plot(f,mag);grid % plot spectrum

>>title('Spectrum of corrupted signal') % add title

>>xlabel('Frequency, [Hz]) % label the horizontal axis





The DFT results in an evaluation of the spectrum at evenly spaced frequencies. For an N-sample record and sampling frequency Fs, the frequency resolution (spacing) is  $\Delta f = Fs / N$ .

Obviously, it is difficult to identify the frequency components by looking at the original signal in the time domain. On the other hand, the identification of the spectral components is straightforward in the frequency domain.

## Timing

#### The Commands

- "tic" & "toc"

The functions **tic** and **toc** provide a means of finding the time taken to execute a segment of code. The statement **tic** starts the timing and **toc** gives the elapsed time since the last tic. The timing will vary depending on the model of computer being used and its current load.

```
Practice
-Timing-
(1)

>>x=[1 2 3 4 5 6 7 8];
>>tic,fft(x),toc

elapsed_time=

0.0900
```



A sampled record is of finite length and is therefore usually a truncated version of the actual signal. In essence, it is obtained by multiplying the signal by a rectangular pulse of height 1 over the time occupied by the record.

- Timing-

**(2)** 

Obtain the amplitude spectrum of the signal  $x(t) = \sin(2\pi f_1 t) + 0.06\sin(2\pi f_2 t)$  using 64 samples 125  $\mu s$  apart; apply a Hamming window to the data set.

Ts=0.000125; % sampling interval

 $F=[1062.5 \ 1625];$  % frequency tones of x(t)

t=(0.63)\*Ts; % time base  $x=\sin(2*pi*F(1)*t)+0.06*\sin(2*pi*F(2)*t)$ ; % signal

wham=hamming(64); % hamming window xham=wham'.\*x; % windowed signal subplot(2,1,1);stem(t,xham) % plot windowed signal

f=(0:63)/(64\*Ts); % frequency vector subplot(2,1,2); stem(f,abs(fft(xham))); %plot spectrum xlabel('Frequency (Hz)');ylabel(FFTmag'); %label axes

# Zero-Padding

Zero padding refers to the operation of extending a sequence of length M to length N>M by appending N-M zero samples to the given sequence. This operation may be performed on any sequence x[n], prior to computing its transform with a DFT.

#### **Practice**

- Zero-Padding-

>>x=[1 2 3 4 5]; % sequence x[n] >>xp=[1 2 3 4 5 **0 0 0**]; % padded sequence

# The Discrete-Time Fourier Series (DTFS)

#### The "fft" Command

The DTFS is a frequency domain representation for periodic discrete-time sequences. The built-in function **fft** may be used to evaluate the DTFS. If x is an N-point vector containing x[n] for the single period  $0 \le n \le N-1$ , then the DTFS of x[n] can be computed by

>> x = fft(x)/N

#### The "ifft" Command

Where the N-point vector X contains the DTFS coefficients, X[k] for  $0 \le k \le N-1$ . MATLAB assumes the summation in the DTFS formula run from 0 to N-1, so the first elements of x and X correspond to x[0] and X[0], respectively, while the last elements correspond to x[N-1] and X[N-1]. Similarly, given DTFS coefficients in a vector X, the command **ifft** may be used to recover the original sequence x[n].

$$>> x = ifft(X)*N$$

returns a vector x that represents one period for the time vector.

#### **Practice**

- The Discrete-Time Fourier Series-

Determine the DTFS coefficients for the following signal.

$$x[n] = 1 + \sin\left(\frac{\pi}{12}n + \frac{3\pi}{8}\right);$$
 N=24 (period)

>>x=ones(1,24)+sin([1:23]\*pi/12+3\*pi/8); % specify the sequence x[n]>>X=fft(x)/24 % compute the DTFS of x[n]

# Circular Convolution

## 

# DTMF (Multi-Tone Dialing Procedure)

#### **DTMF Scheme**

Dual-tone-multi-frequency (DTMF) also known as touch-tone is the standard in the telecommunication systems used in encoding digits for transmission between the customer and the central office. In the DTMF scheme, a telephone is equipped with a keypad as depicted in Figure 1. The A, B, C, and D keys are usually not present on a regular telephone keypad. In DTMF there are 16 distinct tones. Each tone consists of two simultaneous frequencies mixed together (added amplitudes), for example, pressing '1' will send a tone made of 1209 Hz and 697 Hz to the other end of the line. The frequencies were selected to avoid harmonics (no frequency is a multiple of another, the difference between any two frequencies does not equal any of the frequencies, likewise for the sum of two frequencies). At the central office, the telephone switch decodes the tones. Decoding can be done using a bank of eight bandpass filters, one for each of the eight possible tones. If two of these tones are detected, it is assumed that the key associated with both of these tones was pressed. DTMF "Touch" tones are defined in CCITT volume VI.




Figure 1: Touch-Tone Telephone Pad

# Telephone Tones

## **How Does a Telephone Work?**

A telephone keypad has 12 buttons, a microphone and a speaker. The phone is connected to the central office through a single pair of wires. The phone company office supplies –48 volts at 80 ma to power the telephone. When the phone company wants to ring your phone, they generate a 20 Hz, 90 volt RMS signal that pulses on for 2 seconds, then off for 4 seconds. Each time a user presses a button on their phone, the phone turns on a pair of oscillators. The frequency of these oscillators change, based on the button you pressed as shown in Figure 1.


<u>Practice</u> -Telephone Tones-				
function [s,t]=tone(test,N)				
%				
%	Freq(Hz)	1209	1336	1477
%	697	1	2	3
%	770	4	5	6
%	852	7	8	9
%	941	*	0	#
%				
% Example: [s,t]=tone('test', 200)				
(More matlab codes continue on the next page)				

```
Fs=80000;
                                     % sampling frequency
dt=1/Fs;
                                     % time interval
t=(0:(N-1))*dt;
                                     % time base
fr=[697 770 852 941];
                                     % row frequencies
fc=[1209 1336 1477];
                                     % column frequencies
if test=='1',r=1;c=1;
elseif test==^{2},r=1;c=2;
elseif test=='3',r=1;c=3;
elseif test=^4',r=^2;c=^1;
elseif test==^{5},r=2;c=2;
elseif test==^{\circ}6^{\circ},r=2;c=3;
elseif test=^{7},r=^{3};c=^{1};
elseif test==^{8},r=^{3};c=^{2};
elseif test=^{9},r=^{3};c=^{3};
elseif test=='*',r=4;c=1;
elseif test='0',r=4;c=2;
elseif test='#',r=4;c=3;
else disp('test not valid'); return;
end
s=[\sin(fr)*2*pi*t)+\sin(fc(c)*2*pi*t)]/2;
subplot(2,1,1);plot(t,2);grid
title('\itAmplitude');
spec=fftshift(abs(fft(s,N)));
f=[-N/2:N/2-1]*Fs/N;
subplot(2,1,2);plot(f,spec,'LineWidth',2);grid
title('\itDTMF spectrum')
xlabel('\itFrequency (Hz)')
ylabel('\itMagnitude spectrum')
return
```

# DTMF Decoder

In this programming exercise, we will implement a decoder to indicate which DTMF tone is being generated. This can be done in a variety of ways. We will use a simple FIR filter bank. The filter bank consists of seven bandpass filter, each passing only one of the seven possible DTMF frequencies. When the input to the filter bank is a

DTMF signal, the outputs from two of the bandpass filters would be larger than the rest. If we detect which two are the largest, then we know the corresponding frequencies. These frequencies are then used to determine the DTMF code. A good measure of the output levels is the average power of the outputs.



```
Practice
                                 -DTMF Decoder-
clear all, clc;
fs=8000;
ft=[679 770 852 941 1209 1336 1477];
Nf=50;
N=input("Enter the value of N:');
T=(N-1)/fs;
disp('Observation time');
disp(T);
t=[0: (N-1)/fs;
x=\sin(2*pi*t*ft(1)+\sin(2*pi*t*ft(6));
for I=1:7
f1=ft(i)-1;
f2=ft(i)-1;
b(i,:)=fir1(Nf,[f1 f2]*2/fs);
y(i,:)filter(b(i,:),1,x);
p(i)=1/N*sum(y(i,:).^2);
end
                   (More matlab codes continue on the next page)
```

```
subplot(2,1,1); bar(ft,p);
subplot(2,1,2); hold on
for i=1:7
[H,f]=freqz(b(i,:),1,256,fs);
c=['b','c','m','k','g','y'];
plot(f,20*log10(abs(H),c(i));
title('Magnitude response of filter bank')
xlabel('Frequency')
ylabel('Magnitude')
end
hold off
```

## Speech Processing

Digital speech and audio processing have many popular applications today. Some of them are: cell phones, CD players, MP3 players, and Internet radio. Digital signal processing algorithms are used to compress, enhance, modify, or transmit digital audio signals. MATLAB is useful in implementing such applications.

#### **Minimum Hardware**

In this section, we look at some basic speech processing within the MATLAB environment. Toward this end, we recommend the following minimum hardware:

- □ 16-bit sound card
- □ Microphone (for recording), with better than −60 dBm sensitivity
- ☐ Headphones or a set of loudspeakers

#### Sound

- Commands: "wavread" & "sound"

There are various ways to get sound into MATLAB as vectors of data. A ".wav" file produced by any windows editing/recording utility can be read into a MATLAB array using the wavread function. However, the command is limited to 8-bit PCM format. To playback a sound as samples in a vector, use the sound function.

#### □ Syntax

#### >>[y,Fs,bits]=wavread('africa.wav');

Returns a vector **y** that contains the audio samples (digitized human voice), **Fs** is the sampling frequency, and **bits** is the number of bits used to quantize the samples. This information is all contained in the header of the **.wav** file, and **wavread** strips it out before assigning the audio data to **y**. The file **africa.wav** is a short recording of speech. The range of data values in **y** should lie between -1 and 1, with saturation of the sound equipment occurring for values outside this range.

Make sure to use the semi-colon at the end of the statement; the file might have over hundreds of thousands samples in length.

#### >>sound(y,Fs);

This function plays back the sound stored in vector **y**. The second argument of the **sound** command tells MATLAB how fast to send the samples of **y** to the speakers (Try different values for **Fs** if you want to hear the sound played back at different rates). The default value of **Fs** is 8192 Hz.

```
Practice
-Speech Processing-
(1)

>>t=440; % signal frequency in Hz
>>Fs=48000; % sampling frequency in Hz
>>tspan=0.4; % signal duration in seconds
>>t=0;1/Fs:tspan; % time base
>>x=sin(2*pi*f*t); grid; % signal x(t)
>>sound(x,Fs) % play sound
```

## Wave (.wav) Files

The WAVE file format is an uncompressed audio file format that contains samples of an audio signal. WAVE files take up a lot of memory because of the fact that they are uncompressed. A WAVE file contains both sampled audio data along with other useful information about the file itself, such as the sampling rate, etc. Since WAVE files are binary, you cannot just open them up in a text editor and expect to be able to read it.

```
Practice
- Speech Processing-
(3)

>>N=400;
>>h=ones(N,1);
>>h=h/sum(h);
>>[x,Fs]=wavread('*.wav');
>>y=conv(x,h);
>>soundsc(y,Fs);
```

#### - Speech Processing-

**(4)** 

- 1. Design a low-pass Butterworth filter with a passband from 0 to 0.3\*pi, and a stopband from 0.5\*pi to pi. Allow at most 1 dB loss in the passband, and at least 25 dB loss in the stopband.
- 2. Read the file **messy.wav**, filter the signal using the designed filter, and play it over the speaker.

```
>>[x,Fs]=wavread('c:\messy.wav'); % load the wave file
```

>>[N,Wn]=buttord(0.3,0.5,1,20); % estimate filter order and cutoff frequency

>>[num,den]=butter(N,Wn); % design the Butterworth filter >>y=filter(num,den,x); % generate a filtered output

>>sound(y,Fs); % play the sound

## The Spectrogram

## A Presentation of Sound Signal

A spectrogram is a visual representation of the frequencies that make up a particular sound signal. A complex signal such as the voice can be viewed as the sum of simple sinusoidal signals. In a spectrogram, the horizontal dimension corresponds to time, and the vertical dimension corresponds to frequency (or pitch). The relative intensity of the sound at any particular time and frequency is indicated by colors. Each horizontal line on the graph represents a harmonic in the signal and their relative strengths can be read by changes in color and brightness. Colors represent a range of signal intensities. Blue represents the lowest level and red represents the highest level. In MATLAB, we can use the **specgram** function to display the spectrogram of a sound signal.

#### □ Svntax

>>[y,f,t]=specgram(x,nfft,Fs, window, noverlap)

where **x** is the time-varying signal, **nfft** is the number of samples used in the DFT, **Fs** is the sampling rate, **window** specifies the time window being used for FFT, and the **noverlap** specifies the amount of sample overlap. This function returns spectrogram in matrix **y**, the **f** and **t** are vectors representing frequency and time respectively.

#### **Practice** - The Specgram-Use the **specgram** command to display the spectrogram of a dual-tone given by $x(t) = 3\cos(2\pi 500t) + 7\cos(2\pi 3000t)$ >>Fsamp=8000; % sampling rate >>inc=1/Fsamp; % time increment >>dur=2; % time duration >>t=0:inc:dur; % time vector $>> x=3*\cos(2*pi*500*t)+7*\cos(2*pi*3000*t);$ % dual-tone >>specgram(x, 256,Fsamp); % spectrogram 4000 3000 Frequency 2000 1000 0 0.2 0.4 0.6 0.8 1.2 1.4 1.6 1.8 Time

# Chirp Signals

## What Are Chirp Signals?

A chirped sinusoidal signal is a sinewave of increasing frequency over some prescribed period. In other words, a chirped sinusoid begins at one frequency and smoothly moves to another frequency over a time interval. Chirp signals have been used in radar development since the 1960's because of their advantages over single frequency signals.

## **How Is A Chirp Signal Written?**

A typical chirped sinusoidal signal can be written as

$$c(t) = \cos(2\pi\mu t^2 + 2\pi f_0 t + \Psi)$$

where  $f_0$  is the initial frequency, t is time, and  $\mu$  is a constant.

The instantaneous frequency of the chirp is found by taking the time derivative of the phase:

$$f_i(t) = \frac{1}{2\pi} \frac{d}{dt} (2\pi\mu t^2 + 2\pi f_0 t + \Psi) = 2\mu t + f_0$$

which clearly reflects a linear frequency variation with time. Since the linear variation of the frequency can produce an audible sound similar to a siren or a bird chirp; the linear-FM signals are also called "chirp" signals or simply "chirps"

#### **Practice**

-Chirp Signals-(1)

Use the following parameters to define a chirp signal:

- $\Box$   $f_{min} = 200$  Hz (lower frequency)
- $\Box$   $f_{\text{max}} = 2000$  Hz (upper frequency)
- $\Box$  T = 2 Sec (time range)

Specify  $\mu$  and  $f_0$  to define the signal c(t) so that it sweeps the specified

frequency range.


#### **Solution:**

Because the time range for the frequency sweep is 2 seconds, we obtain a system of two equations and two unknowns,

$$\Box 200 = 2\mu(0) + f_0 \Rightarrow f_0 = 200 \text{ Hz}$$

$$\Box 2000 = 2\mu(2) + f_0 \Rightarrow \mu = 450 \text{ Hz/sec}$$

(Continue on the next page)



## The "Chirp" Command


MATLAB has a built-in function **chirp** to generate chirp signals. The command syntax is as follows:

Generates samples of a linear swept-frequency cosine signal y at the time instances defined in array t, where f0 is the instantaneous frequency at time 0, and f1 is the instantaneous frequency at time t1. The frequencies f0 and f1 are both expressed in Hertz. If unspecified, f0 is 0, t1 is 1, and f1 is 100.

# Goertzel Algorithm

One method of calculating the DFT is the Goertzel algorithm. The computation of the DFT may be implemented using a first-order complex recursive structure, which consists of one complex addition and one complex multiply.

```
Practice
                            - Goertzel Algorithm-
Fs=8000;
f=[697 770 852 941 1209 1336 1447 1633];
t=[0:4000]'*1/Fs;
x=0.4*\sin(2*pi*f(2)*t)+0.4*\sin(2*pi*f(7)*t);
subplot(2,1,1); psd(x,[],Fs);
N=length(x);
omega=2*pi*f*(1/Fs);
B=1; x2=[];
for m=1:length(f)
   A=[1, -2*\cos(omega(m)), 1];
   v=filter(B,A,x);
   x2(m)=v(N).^2+v(N-1).^2-2*cos(omega(m))*v(N)*v(N-1);
end
subplot(2,1,2); plot(f,x2,f,x2,'o'); xlabel('Frequency,(Hz)'); ylabel('|X k|^2);
title('Dual-tone multi-frequency')
set(gca,'Ylim',[-3e4,7e5])
                     (The plots are shown on the next page)
```




# Quantization

## What Is Quantization?


Quantization of a signal is the process of converting a continuous signal to one that is discrete in amplitude. For example, a five level uniform quantizer maps the input sequence values into five distinct output levels. A finite number of bits are required to represent the discrete amplitudes, as a result this representation lacks full precision and it is irreversible.

```
Practice
                                  -Quantization-
                                        (1)
>>t=0:0.001: 5*pi;
                                          %time base
>> x = fix(5 + 4 * sin(t));
                                          %quantize signal to integer values
>>plot(t,x, 'LineWidth',3);
                                          %plot quantized signal
>>xlabel('Time'); ylabel('Amplitude');
                                            %label axes
                                          %add title
>>title('Quantized signal')
                                          %scale axes
>> axis([0 14 0 max(x)+1])
                      (The graph is shown on the next page)
```



## **Pre- & Post- Scaling**

It is possible to adjust the quantization step size by pre-scaling and post-scaling the function values. The following yields functional values limited to one digit to the right of the decimal point.



## **Digit Limitation**

In digital communication, the data format is typically limited by the number of binary digits (bits). Common computer hardware utilizes 8 or 16 bits in the signal value representation. For example, a signal restricted to 8-bit format could consist of a sequence of integers lying between –256 and +255. MATLAB for constructing a single cycle of an 8-bit sinusoid at full amplitude scale might proceed as follows:

```
Practice
- Quantization-
(3)
>>n=0:1000;
>>x=fix(255*sin(2*pi*n/1000));
>>plot(n,x)
```

## **Signal Value Restriction**

Finally, to produce an audio signal, which is compatible with MATLAB **sound** function, we must restrict the signal values to real values lying between -1 and +1 inclusive. The following MATLAB piece of code plays a quantization of a pure 1 kHz tone 3 seconds in duration, sampling rate of 8192 Hz.

```
Practice
- Quantization-
(4)
%5-bit quantization
n=0:(3*8192)-1;
y=((2^(5-1))-1)*sin(2*pi*1000/8192*n);
y=fix(y)/(2^(5-1));
sound(y,8192)
```

## Zero-crossings

Suppose we are given a signal  $x(t) = \sin(2\pi 2t)$ . We shall consider counting the number of zero-crossings.

# Practice - Zero-crossings >>t=0:0.01:2; >>x=sin(2\*pi\*2\*t); >>prod=x(1:length(x)-1).\*x(2:length(x)); >>crossings=length(find(prod<0)) crossings= 7

# Audio Effects

#### Introduction

In this section, we shall turn into some audio effects that will prove useful in digital signal processing. We will briefly cover:


- □ Delay
- □ Echo
- □ Reverberation (reverb)
- □ Chorus

## **Delay**

A delay is one of the simplest effects, but very valuable if used properly. Simply stated, a delay takes an audio signal, and plays it back after the delay time. The delay time can range from several milliseconds to several seconds.

#### **Echo Effect**

A basic echo effect can be implemented according to the block diagram depicted below:



The difference equation describing this model is

$$y[n] = x[n] + ax[n-D]$$
  

$$\therefore H(z) = 1 + az^{-D}$$

```
Practice
-Audio Effect: Echo Effect-

clear all;

[x, fs,bits]=wavread('test.wav');

a=input ('Enter the value of attenuation:');

dealy=0.3; % number of samples in the delay

D=round(delay*fs);

num=[1 zeros(1,D) a];

den=[1];


x_delay=filter(num,den,x);

y=x+x_delay;

sound(y,fs)
```

#### Reverberation

This is by far the most heavily used effect in music. Reverberation is the result of many reflections of a sound that take place in a room. A reflected sound wave will arrive a little later than the direct sound, and is typically little weaker. The series of delayed and attenuated sound waves is termed reverb.



#### **Chorus**

Just as a chorus is a group of singers, the chorus effect can make a single instrument sound like there are actually several instruments being played.