# 实验十 OSPF 动态路由

### 一、实验目的

- 1. 深入掌握动态路由原理;
- 2. 掌握动态路由 OSPF 配置方法;
- 3. 掌握 OSPF 路由工作原理。

## 二、应用背景

OSPF(Open Shortest Path First,OSPF)动态路由,英文名称的意思是最短路径优先协议,它是一种典型的链路状态路由协议,它是一个内部网关协议。OSPF 网络中的每个路由 器维护一个相同的链路状态数据库(LSDB),即每台路由器都保存了整个网络的拓扑结构。依据链路状态数据库,利用SPF 算法,路由器就能构造路由表。

OSPF 路由协议有以下特点:

- (1)可适应大规模网络,不受物理跳数的限制。对于小规模网络,RIP 是首先路由协议,当网络规模扩大,具有10台以上路由器时,就需要OSPF路由协议了。
  - (2) OSPF 路由变化收敛速度快,协议自身网络开销较小。
  - (3) 最短路径采用 SPF 算法, 避免了路由环路。
  - (4) 以开销作为度量值,带宽越高,开销越小。
  - (5) 支持区域划分。

OSPF 划分区域的目的是为了控制链路状态信息 LSA 泛洪的范围、减小链路状态数据库 LSDB 的大小、改善网络的可扩展性、快速地收敛。当网络包含多个区域时,OSPF 协议规定, 必须有一个 Area 0 区域,通常也叫做骨干区域,其他所有区域都必须与骨干区域物理或逻 辑上相连。


配置OSPF 路由,(1) 创建一个OSPF 路由进程,每个路由器创建一个自身的进程号,范围是1-65535。(2) 配置Router ID, RID 是一个32 比特无符号整数,用于标识路由器,要求全局唯一,RID 可以手工配置,也可以自动生成。(3) 定义关联的IP 地址范围及区域。

查看邻居表,特权模式下使用 show ip ospf neighbor; 使用命令 show ip ospf database, 查看链路状态数据库。

# 三、实验设备

Router路由器(2台)、主机(2台)、三层交换机(1台)。

## 四、实验拓扑



## 五、实验步骤

### 第1步 线缆连接

为路由器添加串口模块,按照拓扑图正确组网。RouterA 和RouterB 之间采用串口连接, 关闭路由器电源,将 HWIC-2T 模块拖拽到空卡槽,为路由器添加串口模块,开启电源,并 连线组网。



### 第2步 配置路由器接口地址

路由器 RouterA 的 Gi0/0 以太网口地址为 192.168.10.1 255.255.255.0;

路由器 RouterA 的串口Se0/1/0 地址为 192.168.1.2 255.255.255.0;

路由器RouterB 的配置与RouterA 类似。

配置完成后,使用 show ip interface brief 命令进行检查。

#### RouterA> enable

RouterA# configure terminal

RouterA (config)# interface Gi 0/0

RouterA (config-if)# ip address 192.168.10.1 255.255.255.0

RouterA (config-if)# no shutdown

RouterA (config)# interface Se0/1/0

RouterA (config-if)# ip address 192.168.1.2 255.255.255.0

RouterA(config-if)#clock rate 64000

RouterA (config-if)# no shutdown

#### 第3步 三层交换机的配置

Switch(config)#interface f0/1

Switch(config-if)#switch port access vlan 20

Switch(config-if)#exit

Switch(config)#interface f 0/24

Switch(config-if)#switchport access vlan 200

Switch(config-if)#exit

Switch(config)#interface vlan 20

Switch(config-if)#ip address 192.168.2.2 255.255.255.0

Switch(config-if)#no shut

Switch(config-if)#exit

Switch(config)#interface vlan 200

Switch(config-if)#ip address 192.168.20.1 255.255.255.0

Switch(config-if)#no shut

配置完成后,使用命令show vlan、show ip interface brief 命令进行检查。

#### 第4步 PC 机IP 地址配置

配置PC0 的IP 地址为192.168.10.11/24, 网关接口为192.168.10.1;

配置PC1 的IP 地址为192.168.20.11/24, 网关接口为192.168.20.1;

在PC 机的命令行状态下执行ipconfig 命令查看配置是否生效。

#### 第5步 动态路由协议 OSPF 的设置。

路由器RouterA上的2个网段都在Area0区域。

RouterA(config)#router ospf 10

RouterA(config-router)#network 192.168.1.0 0.0.0.255 area 0

RouterA(config-router)#network 192.168.10.0 0.0.0.255 area 0

路由器RouterB 左侧在Area0 区域,右侧在Area1 区域.。

Router(config)#router ospf 10

Router(config-router)#network 192.168.1.0 0.0.0.255 area 0

Router(config-router)#network 192.168.2.0 0.0.0.255 area 1

交换机上的2个网段都在Areal区域。

Switch(config)#router ospf 10

Switch(config-router)#network 192.168.2.0 0.0.0.255 area 1

Switch(config-router)#network 192.168.20.0 0.0.0.255 area 1

Switch(config-router)#end

#### 第6步 查看路由表

LSDB 数据库同步之后,会出现下面的提示信息。

#### Router#

00:07:04: %OSPF-5-ADJCHG: Process 10, Nbr 192.168.2.1 on Serial0/1/0 from LOADING to FULL, Loading Done

路由器或交换机上使用 show ip route 命令,查看路由器或交换机上的路由表,截图显示。如果配置成功,每台设备上的路由表都有4个网段。下图是 RouterA 上的路由表,192.168.2.0 网段和192.168.20.0 网段,是 RouterA 的非直连网段,它是通过OSPF 路由协议 学习到的。

```
Router#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B -
BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
      i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS
inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
    192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks
C
        192.168.1.0/24 is directly connected, Serial0/1/0
        192.168.1.2/32 is directly connected, Serial0/1/0
O IA 192.168.2.0/24 [110/65] via 192.168.1.1, 00:02:24, Serial0/1/0
     192.168.10.0/24 is variably subnetted, 2 subnets, 2 masks
C
        192.168.10.0/24 is directly connected, GigabitEthernet0/0
        192.168.10.1/32 is directly connected, GigabitEthernet0/0
O IA 192.168.20.0/24 [110/66] via 192.168.1.1, 00:02:24, Serial0/1/0
```

### 第7步 查看 OSPF 信息

在 RouterA 上查看 OSPF 邻居,使用命令 show ip ospf neighbor,在区域 Area0 里面,RouterA 只有一个邻居,那就是 RouterB ,邻居的状态为 full,因为两个路由器之间是点对点的链路,所以没有选举 DR 和 BDR ,邻居存活时间为 35 秒,邻居 IP 地址和 RouterA 的连接 端口也列出来了。


在 RouterA 上查看 OSPF 数据库,使用命令 show ip ospf database,RouterA 的 ID 为 192.168.10.1,RouterB 的 ID 为 192.168.2.1,因为没有配置 OSPF ID,路由器选择活动中端口 地址中 IP 最大的作为自己的 ID。

Router Link States(Area0)发布的是5类LSA中的第1类,路由器LSA,描述自己的链路状态和开销。下图中第1行表示RouterA的通告路由器是它自己,它连接3个网段;第2行表示RouterB的通告路由器也是它自己,它连接2个网段,这部分信息告诉我们,Area0区域一共有2台路由器,连接5个网段。

```
RouterA#show ip ospf database
            OSPF Router with ID (192.168.10.1) (Process ID 10)
               Router Link States (Area 0)
Link ID
               ADV Router
                                                     Checksum Link count
                                          Seq#
192.168.10.1
               192.168.10.1
                               301
                                          0x80000006 0x00e927 3
192.168.2.1
               192.168.2.1
                               301
                                          0x80000006 0x001885 2
               Summary Net Link States (Area 0)
              ADV Router
Link ID
                             Age
                                         Segs
                                                     Checksum
192.168.2.0
               192.168.2.1
                               301
                                          0x80000001 0x00abda
192.168.20.0 192.168.2.1
                                         0x80000002 0x00ec85
```

Summary Net Link States (Area 0),发布的是5 类LSA 中的第3 类,由边界路由ABR 发出,用于通告不同区域之间的路由,本实验中RouterB 为边界路由器,它发出2 行路由信息,192.168.2.0 和192.168.20.0,这两个网段通过边界路由器RouterB 可以到达。

第8步 ping 命令测试连通性



# 六、总结与分析

- 1. 本实验拓扑图一共包含4个网段,划分了Area0和Area1两个区域,尝试修改OSPF路由配置,将4个网段同时划入一个区域,看看PC0和PC1是否能够连通?注意清除前面的配置命令,需要在命令行前面加no。
- 2. 怎样理解和验证,同一网络中的路由器拥有一个相同的链路状态数据库(LSDB)?
- 3. 二层交换机是普通交换机,不能识别 IP地址,只具备在端口之间进行数据转发功能; 三层交换机具备路由功能,可以配置 IP地址,可以根据 IP地址进行数据转发。

三层交换机开启路由功能有2种模式,一种模式是划分VLAN,为VLAN添加端口,然后为VLAN配置IP地址,步骤3给出了详细配置指令。另外一种模式,直接开启端口的的路由功能,指令为:

Switch(config)#int vlan 20

Switch(config-if)#no ip address !去掉 VLAN20 的 IP 地址,防止 IP 地址冲突

Switch(config-if)#exit

Switch(config)#int f 0/1

Switch(config-if)#no switchport ! 关闭交换模式

Switch(config-if)#ip routing !开启路由功能

Switch(config-if)#ip address 192.168.2.2 255.255.255.0

Switch(config-if)#no shutdown

请尝试删除 VLAN200 的 IP 地址,将 F0/24 端口直接开启路由功能,将 VLAN200 的 IP 地址,赋给端口 F0/24。

# 实验十一 基于思科模拟器的路由重分布实验

### 一、实验目的

- 1. 掌握路由配置方法
- 2. 掌握不用路由协议之间转换的原则
- 3. 掌握静态路由或直连路由在动态路由重分布的方法

### 二、应用背景

某企业拥有3台路由器和1台三层交换机,企业内部采用了RIP和OSPF两种动态路由协议,同时网络中有去往192.168.5.0/24网段的静态路由,PC1所在末梢网络,有去往外部网络的默认路由,请正确配置网络设备,使得网络内部的每台设备都能通信。

路由重分布能让路由器交换路由信息,从而实现多种路由协议之间的路由信息共享。 实施路由重分布的路由器为边界路由器(ASBR),该路由器上启用了多种路由协议,它们位于2个或多个自治系统的边界上。因路由协议自身的差异,在路由重分布时需要考虑不同路由协议的度量值和管理距离,度量值主要用于确定最佳路径,管理距离主要确定路由的来源。RIP路由以跳数作为路径的度量值,OSPF路由以链路状态作路径的度量值,路由重分布的原则,就是度量值要进行合理的转换。OSPF在RIP中重分布时,要用metric折合成跳数,RIP在OSPF中重分布时,跳数也折合成链路状态的度量值。如果度量值分配不正确,路由重分布将会失败。

静态路由在 RIP 中重分布时,如果不指定度量值,默认是 1 跳。直连路由在 RIP 中重分布时,如果不指定度量值,默认也是 1 跳。静态路由和直连路由在 OSPF 中重分布时,如果不指定度量值,默认是 20,类型为 2,默认子网不进行重分布,所以一般要加上参数 subnets,子网也可以重分布。

▶ 静态重分布到RIP 默认种子度量为1;

R(config)#router rip

R(config-router)#redistribute static

▶ 直连重分布到RIP 默认种子度量为1;

R(config-router)#redistribute connected

▶ 静态重分布到ospf

R(config)#router ospf 1

R(config-router)#redistribute static subnets

▶ 直连路由重分布到ospf

R(config)#router ospf 1

R(config-router)#redistribute connected subnets

➤ OSPF 重分布到RIP

OSPF 路由重分布到 RIP, 默认 metric 为无穷大, 需要指定度量值。全局配置模式下, 打 开 RIP 路由, 指定 OSPF 10 进程度量值为3, 折合成3 跳, 命令为:

R(config)# router rip

R(config-router)# redistribute ospf 10 metric 3

➤ RIP 重分布到OSPF,


RIP 路由在OSPF 中重分布时,默认度量值为20, 默认度量值类型为2, 默认不重分布 子网。全局配置模式下, 打开 OSPF 路由, 指定 RIP 度量类型为1, 重分布子网。命令为:

R(config)# router ospf 10

### 三、实验设备

路由器 3 台, 三层交换机 1 台, 直连线若干, 主机 2 台。

# 四、实验拓扑



# 五、实验步骤


### 第1步连线

选择路由器和交换机,按照实验拓扑图正确连线。

第2步配置主机网卡地址,选择Desktop,采用静态地址。

配置 PC0 网卡的 IP地址为: 192.168.1.11,掩码 255.255.255.0, 网关为 192.168.1.1; 配置 PC1 网卡的 IP地址为: 192.168.5.11,掩码 255.255.255.0, 网关为 192.168.5.1。





#### 第3步路由器的端口地址配置,R0、R2参照进行配置

R1 (config)#interface Gi0/1

R1 (config-if)#ip address 192.168.1.1 255.255.255.0

R1 (config-if)#no shutdown

R1 (config-if)#exit

R1 (config)#interface Gi0/0

R1 (config-if)#ip address 192.168.2.1 255.255.255.0

R1 (config-if)#no shutdown

R1 (config-if)#exit

#### 第 4 步 交换机的端口地址配置

switch(config)#interface F0/1

switch(config-if)#no switchport !关闭交换功能

switch(config-if)#ip address 192.168.4.2 255.255.255.0

switch(config-if)#no shutdown

switch(config-if)#exit

switch(config)#vlan 20

switch(config-vlan)#exit

switch(config)#interface F0/2

switch(config-if)#switchpor access vlan 20

switch(config)#interface vlan 20

switch(config-if)#ip address 192.168.5.1 255.255.255.0

switch(config-if)#no shutdown

switch(config-if)#exit

switch(config)#ip routing !

!开启交换机路由功能

switch#show ip route !查看交换机上的路由表,只有直连网段 Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

\* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is not set

C 192.168.4.0/24 is directly connected, FastEthernet0/1

C 192.168.5.0/24 is directly connected, Vlan20

#### 第5步路由配置(重分布之前)

Router1(config)#router ospf 100

Router1(config-router)#network 192.168.1.0 0.0.0.255 area 0

Router1(config-router)#network 192.168.2.0 0.0.0.255 area 0

Router1(config-router)#exit

```
Router0(config)#router ospf 100
  Router0(config-router)#network 192.168.2.0 0.0.0.255 area 0
  Route0r(config-router)#exit
  Router0(config)#router rip
  Route0r(config-router)#no auto-summary
  Router0(config-router)#version 2
  RouteOr(config-router)#network 192.168.3.0
  Router0(config-router)#exit
  Router2(config)#router rip
  Router2(config-router)#no auto-summary
  Router2(config-router)#version 2
  Router2(config-router)#network 192.168.3.0
  Router2(config-router)#exit
  Router2(config)#ip route 192.168.5.0 255.255.255.0 192.168.4.2
  Switch(config)#ip route 0.0.0.0 0.0.0.0 192.168.4.1
                                         ! 查看R1 路由表, 有2 个网段
Router1#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
Gateway of last resort is not set
192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks
          192.168. 1.0/24 is directly connected, GigabitEthernet0/1
          192.168.1.1/32 is directly connected, GigabitEthernet0/1
192.168.2.0/24 is variably subnetted, 2 subnets, 2 masks
          192.168.2.0/24 is directly connected, GigabitEthernet0/0
\mathbf{C}
L
          192.168.2. 1/32 is directly connected, GigabitEthernet0/0
Router0#show ip route
                                    ! 查看R0路由表,有3个网段
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
Gateway of last resort is not set
      192.168. 1.0/24 [110/2] via 192.168.2. 1, 00:07:21, GigabitEthernet0/0
192.168.2.0/24 is variably subnetted, 2 subnets, 2 masks
          192.168.2.0/24 is directly connected, GigabitEthernet0/0
C
          192.168.2.2/32 is directly connected, GigabitEthernet0/0
L
192.168.3.0/24 is variably subnetted, 2 subnets, 2 masks
```

192.168.3.0/24 is directly connected, GigabitEthernet0/1

192.168.3. 1/32 is directly connected, GigabitEthernet0/1

C

L

```
! 查看R2路由表,有3个网段
Router2#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
Gateway of last resort is not set
192.168.3.0/24 is variably subnetted, 2 subnets, 2 masks
          192.168.3.0/24 is directly connected, GigabitEthernet0/0
C
          192.168.3.2/32 is directly connected, GigabitEthernet0/0
192.168.4.0/24 is variably subnetted, 2 subnets, 2 masks
C
          192.168.4.0/24 is directly connected, GigabitEthernet0/1
          192.168.4. 1/32 is directly connected, GigabitEthernet0/1
L
S
      192.168.5.0/24 [1/0] via 192.168.4.2
Switch#show ip route
                                   ! 查看交换机路由表, 存在默认路由
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
Gateway of last resort is 192.168.4.1 to network 0.0.0.0
      192.168.4.0/24 is directly connected, FastEthernet0/1
C
C
      192.168.5.0/24 is directly connected, Vlan20
S^*
     0.0.0.0/0 [1/0] via 192.168.4.1
第6步路由重分布
  Router0(config)#router rip
  Router0(config-router)#redistribute ospf 100 metric 1
  Router0(config-router)#exit
  Router0(config)#router ospf 100
  Router0(config-router)#redistribute rip metric 10 metric-type 1 subnets
  Router0(config-router)#exit
  Router2(config)#router rip
```

Router1#show ip route ! 查看R1 的路由表,有5个网段Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGPD - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2 E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGPi - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area \* - candidate default, U - per-user static route, o - ODRP - periodic downloaded static route Gateway of last resort is not set 192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks

Router2(config-router)#redistribute static metric 2 ! 重分布静态路由
Router2(config-router)#redistribute connected metric 1 ! 重分布直连网段

```
C
          192.168. 1.0/24 is directly connected, GigabitEthernet0/1
L
          192.168. 1. 1/32 is directly connected, GigabitEthernet0/1
192.168.2.0/24 is variably subnetted, 2 subnets, 2 masks
          192.168.2.0/24 is directly connected, GigabitEthernet0/0
C
          192.168.2. 1/32 is directly connected, GigabitEthernet0/0
O E1 192.168.3.0/24 [110/11] via 192.168.2.2, 00:06:05, GigabitEthernet0/0
O E1 192.168.4.0/24 [110/11] via 192.168.2.2, 00:00:58, GigabitEthernet0/0
O E1 192.168.5.0/24 [110/11] via 192.168.2.2, 00:03:13, GigabitEthernet0/0
                           ! 查看R0 的路由表, 有5个网段
Router0#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
Gateway of last resort is not set
      192.168.1.0/24 [110/2] via 192.168.2.1, 00:21:19, GigabitEthernet0/0
192.168.2.0/24 is variably subnetted, 2 subnets, 2 masks
C
          192.168.2.0/24 is directly connected, GigabitEthernet0/0
          192.168.2.2/32 is directly connected, GigabitEthernet0/0
L
192.168.3.0/24 is variably subnetted, 2 subnets, 2 masks
          192.168.3.0/24 is directly connected, GigabitEthernet0/1
C
          192.168.3.1/32 is directly connected, GigabitEthernet0/1
L
R
      192.168.4.0/24 [120/1] via 192.168.3.2, 00:00:22, GigabitEthernet0/1
R
      192.168.5.0/24 [120/2] via 192.168.3.2, 00:00:22, GigabitEthernet0/1
Router2#show ip route
                           ! 查看R0 的路由表, 有5个网段
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
Gateway of last resort is not set
R
      192.168.1.0/24 [120/1] via 192.168.3.1, 00:00:19, GigabitEthernet0/0
      192.168.2.0/24 [120/1] via 192.168.3.1, 00:00:19, GigabitEthernet0/0
R
192.168.3.0/24 is variably subnetted, 2 subnets, 2 masks
          192.168.3.0/24 is directly connected, GigabitEthernet0/0
\mathbf{C}
          192.168.3.2/32 is directly connected, GigabitEthernet0/0
L
192.168.4.0/24 is variably subnetted, 2 subnets, 2 masks
C
          192.168.4.0/24 is directly connected, GigabitEthernet0/1
          192.168.4.1/32 is directly connected, GigabitEthernet0/1
L
S
      192.168.5.0/24 [1/0] via 192.168.4.2
                             ! 查看交换机的路由表, 有默认路由
Switch#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
```

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

\* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is 192.168.4.1 to network 0.0.0.0

C 192.168.4.0/24 is directly connected, FastEthernet0/1

C 192.168.5.0/24 is directly connected, Vlan20

S\* 0.0.0.0/0 [1/0] via 192.168.4.1

第7步 测试连通性

在R1 进行,按照从左到右的顺序进行,每一个节点都能连通。

Router1#ping 192.168.1.11

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 192.168.1.11, timeout is 2 seconds: .!!!!

Success rate is 80 percent (4/5), round-trip min/avg/max = 0/0/1 ms

Router1#ping 192.168.2.2

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 192.168.2.2, timeout is 2 seconds:

Success rate is 100 percent (5/5), round-trip min/avg/max = 0/0/1 ms

Router1#ping 192.168.3.1

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 192.168.3.1, timeout is 2 seconds: !!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 0/0/1 ms

Router1#ping 192.168.3.2

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 192.168.3.2, timeout is 2 seconds: .!!!!

Success rate is 80 percent (4/5), round-trip min/avg/max = 0/0/0 ms

Router1#ping 192.168.4.1

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 192.168.4.1, timeout is 2 seconds: !!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 0/0/1 ms

Router1#ping 192.168.5.1

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 192.168.5.1, timeout is 2 seconds:

Success rate is 80 percent (4/5), round-trip min/avg/max = 0/0/1 ms

Router1#ping 192.168.5.22

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 192.168.5.22, timeout is 2 seconds:

Success rate is 80 percent (4/5), round-trip min/avg/max = 0/1/4 ms 第 8 步 debug 命令测试

```
Router0#debug ip ospf events
```

OSPF events debugging is on

Router0#

01:10:41: OSPF: Rcv hello from 192.168.2.1 area 0 from GigabitEthernet0/0 192.168.2.1 01:10:41: OSPF: End of hello processing

01:10:51: OSPF: Rcv hello from 192.168.2.1 area 0 from GigabitEthernet0/0 192.168.2.1 01:10:51: OSPF: End of hello processing

01:11:01: OSPF: Rcv hello from 192.168.2.1 area 0 from GigabitEthernet0/0 192.168.2.1 01:11:01: OSPF: End of hello processing

Router0# debug ip ospf adj

OSPF adjacency events debugging is on

Router0#

01:12:42: OSPF: Build AS External LSA router ID 192.168.3.1, seq 0xfffffff80000001

01:12:42: OSPF: Build router LSA for area 0, router ID 192.168.3.1, seq 0xffffffff80000005 01:12:42: OSPF: Build AS External LSA router ID 192.168.3.1, seq 0xfffffff80000001 01:12:42: OSPF: Build router LSA for area 0, router ID 192.168.3.1, seq 0xffffffff80000005 01:13:10: OSPF: Build AS External LSA router ID 192.168.3.1, seq 0xffffffff80000001

01:13:10: OSPF: Build router LSA for area 0, router ID 192.168.3.1, seq 0xfffffff80000005

### Router0#debug ip rip events

RIP event debugging is on

Router0#RIP: sending v2 update to 224.0.0.9 via GigabitEthernet0/1 (192.168.3.1)

RIP: build update entries

192.168.1.0/24 via 0.0.0.0, metric 1, tag 0

192.168.2.0/24 via 0.0.0.0, metric 1, tag 0

RIP: received v2 update from 192.168.3.2 on GigabitEthernet0/1

192.168.4.0/24 via 0.0.0.0 in 1 hops

192.168.5.0/24 via 0.0.0.0 in 2 hops

RIP: sending v2 update to 224.0.0.9 via GigabitEthernet0/1 (192.168.3.1)

RIP: build update entries

192.168.1.0/24 via 0.0.0.0, metric 1, tag 0

192.168.2.0/24 via 0.0.0.0, metric 1, tag 0

# 六、思考题

1、实验是否实现了全网全通?遇到了哪些问题,你是怎样解决的?

# 实验十二 基于思科模拟器的 NAT 实验

### 一、实验目的

- 1. 掌握如何向外网发布内网的服务器;
- 2. 掌握 NAT 源地址转换和目的地址转换的区别;

# 二、应用背景

网络地址转换NAT(Network Address Translation),能帮助解决IP 地址资源紧缺的问题,而且使得内外网隔离,提高一定的网络安全保障。NAT 将网络划分为内部网络(inside )和 外部网络(outside )两部分。局域网主机利用 NAT 访问网络时,是将局域网内部的本地地 址转换为了全局地址(互联网合法IP 地址)后转发数据包。

NAT 分为两种类型: 网络地址转换 NAT 和网络地址端口转换 NAPT (Network Address Port Translation)。 NAT 是实现转换后一个本地 IP 地址对应一个全局地址。 NAPT 是实现转换后多 个本地 IP 地址对应一个全局 IP 地址,并用不同的端口号进行区分。


在传统的路由交换网络中可以使用路由器实现 NAT 转换,近年来大多使用防火墙来完成。使用路由器实现 NAT 时,常常会发现路由器的性能下降,这是因为每一个经过路由器的数据包都要进行 NAT 地址转换,这必然消耗系统的 CPU 资源,而且转换的中间结果还要暂时保存在内存中以便于回应数据的恢复。防火墙的主要功能就是完成这种复杂任务,它的性能不像路由器那样下降明显。

本实验要实现内网网段192.168.1.0/24 的地址转换,假设只有50 个公网地址,地址池是200.1.1.100/24-200.1.1.150/24,假设外网服务器地址为100.1.1.X/16。

# 三、实验设备


路由器(R1762)2台,二层交换机1台,V.35线缆(DTE/DCE)1对,主机4台。

# 四、实验拓扑



## 五、实验步骤

第1步关闭电源,将HWIC-2T模块拖拽到空卡槽,为路由器添加串口,并连线组网。



路由器 R1 和 R2 之间的串口,用 V.35 线缆连结,思科模拟器可以采用自动连线模式;将内网主机所在交换机与路由器 R1 的 Gi0/0 口相连;将另一台主机和 R2 的 Gi0/0 相连。

### 第2步配置网卡地址

内网主机配置网卡地址为 192.168.1.0/24, 网关设为 192.168.1.1;

外网服务器网卡地址设为 100.1.1.5/16, 网关设为 100.1.1.1。

### 第 3 步 路由器的基本配置

### R0(config)#

- R0 (config)#interface Gi0/0
- R0 (config-if)#ip address 192.168.1.1 255.255.255.0
- R0 (config-if)#no shutdown
- R0 (config-if)#exit
- R0 (config)#interface serial 0/1/0
- R0 (config-if)#ip address 200.1.1.1 255.255.255.0
- R0 (config-if)#clock rate 64000
- R0 (config-if)#no shutdown
- R0 (config-if)#exit

另一台路由器上的配置

- R1 (config)#interface Gi0/0
- R1 (config-if)#ip address 100.1.1.1 255.0.0.0
- R1 (config-if)#no shutdown
- R1 (config-if)#exit
- R1 (config)#interface serial 0/1/0
- R1 (config-if)#ip address 200.1.1.2 255.255.255.0
- R1 (config-if)#clock rate 64000
- R1 (config-if)#no shutdown
- R1 (config-if)#end

查看 R0 的端口状态

R0#show ip interface brief

Interface	IP-Address	OK?	Method Status	Protocol
GigabitEthernet0/0	192.168.1.1	YES manual	up	up
GigabitEthernet0/1	unassigned	YES unset	administratively down	down
Serial0/1/0	200.1.1.1	YES manual	up	up
Serial0/1/1	unassigned	YES unset	administratively down	down
Vlan1	unassigned	YES unset	administratively down	n down

### 查看R1 的端口状态

### R1#show ip interface brief

Interface	IP-Address	OK?	Method Status	Protocol
GigabitEthernet0/0	100.1.1.1	YES manual	up	up
GigabitEthernet0/1	unassigned	YES unset	administratively down	down
SerialO/1/0	200.1.1.2	YES manual	up	up
Serial0/1/1	unassigned	YES unset	administratively down	down
Vlan1	unassigned	YES unset	administratively down	down

第 4 步: R0 上配置默认路由,注意 R1 为外部路由器,它不知道企业内部网络结构以及企业内部使用的 IP 地址,因此 R1 上不需要配置任何路由。

### **R0(config)#ip route** 0.0.0.0 0.0.0.0 200.1.1.2

查看 R1 上的路由表

R0#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level- 1, L2 - IS-IS level-2, ia - IS-IS inter area

\* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is 200.1.1.2 to network 0.0.0.0

192.168.1.0/24 is variably sub netted, 2 subnets, 2 masks

C 192.168.1.0/24 is directly connected, GigabitEthernet0/0

L 192.168.1.1/32 is directly connected, GigabitEthernet0/0

200.1.1.0/24 is variably sub netted, 2 subnets, 2 masks

C 200.1.1.0/24 is directly connected, Serial0/ 1/0

L 200.1.1.1/32 is directly connected, Serial 0/1/0

S\* 0.0.0.0/0 [ 1/0] via 200.1.1.2

#### 查看 R1 上的路由表

R1#show ip route ! 只有直连网段

Router#show ip rou

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level- 1, L2 - IS-IS level-2, ia - IS-IS inter area

\* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is not set

100.0.0.0/8 is variably sub netted, 2 subnets, 2 masks

C 100.1.1.0/24 is directly connected, GigabitEthernet0/0

L 100.1.1.1/32 is directly connected, GigabitEthernet0/0

200.1.1.0/24 is variably sub netted, 2 subnets, 2 masks

C 200.1.1.0/24 is directly connected, Serial 0/1/0

L 200.1.1.2/32 is directly connected, Serial0/ 1/0

#### 第5步: 在路由器 R0 上配置 NAT

R0(config)#interface Gi 0/0

R0(config-if)#ip nat inside ! 定义内部接口

R0(config-if)#exit

R0(config)#interface serial 0/1/0

R0(config-if)#ip nat outside ! 定义外部接口

R0(config-if)#exit

R0(config)# ip nat pool net50 200.1.1.100 200.1.1.150 netmask 255.255.255.0

! 定义转换的地址池范围,并命名为 net50

**R0(config)**#access-list 1 permit 192.168.1.0 0.0.0.255 ! 定义内部地址网段,使用

ACl 表示

R0(config)#ip nat inside source list 1 pool net50 ! 定义内部源地址调用公网地址池

#### 第6步:验证测试

如果从 PC 上进行测试,首先保证 PC 机能连通自己的网关,再从网关 出发,由近及远地进行测试。本实验内部主机能访问外部网络和外部服务器,但是外部服务器并不能访问内部网络。

R0#ping 200.1.1.2

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 200.1.1.2, timeout is 2 seconds :

!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/ max = 2/7/27 ms

R0#ping 100.1.1.1

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 100.1.1.1, timeout is 2 seconds :

!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/ max = 2/2/5 ms

R0#ping 100.1.1.5

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 100.1.1.5, timeout is 2 seconds:

1111

Success rate is 80 percent (4/5), round-trip min/avg/ max = 1/2/3 ms

R2#ping 192.168.1.1 ! 不能连通

Sending 5, 100-byte ICMP Echoes to 192.168.1.1, timeout is 2 seconds:

< press Ctrl+C to break >

••••

Success rate is 0 percent (0/5)

R1#ping 192.168.1.22 ! 不能连通

Sending 5, 100-byte ICMP Echoes to 192.168.1.22, timeout is 2 seconds:

< press Ctrl+C to break >

. . . . .

Success rate is 0 percent (0/5)

第7步: 查看配置

PC端 ping外部服务器之后,在3分钟内查看地址转换的情况。

## R0#show ip nat translations

第

第

	Pro Inside global	Inside local	Outside local	Outside global	
	icmp 200.1.1.100:1	192.168.1.11:1	100.1.1.5:1	100.1.1.5:1	
	icmp 200.1.1.100:2	192.168.1.11:2	100.1.1.5:2	100.1.1.5:2	
	icmp 200.1.1.100:3	192.168.1.11:3	100.1.1.5:3	100.1.1.5:3	
	icmp 200.1.1.100:4	192.168.1.11:4	100.1.1.5:4	100.1.1.5:4	
	icmp 200.1.1.101:1	192.168.1.22:1	100.1.1.5:1	100.1.1.5:1	
	icmp 200.1.1.101:2	192.168.1.22:2	100.1.1.5:2	100.1.1.5:2	
	icmp 200.1.1.101:3	192.168.1.22:3	100.1.1.5:3	100.1.1.5:3	
	icmp 200.1.1.101:4	192.168.1.22:4	100.1.1.5:4	100.1.1.5:4	
	icmp 200.1.1.102:1	192.168.1.33:1	100.1.1.5:1	100.1.1.5:1	
	icmp 200.1.1.102:2	192.168.1.33:2	100.1.1.5:2	100.1.1.5:2	
	icmp 200.1.1.102:3	192.168.1.33:3	100.1.1.5:3	100.1.1.5:3	
	icmp 200.1.1.102:4	192.168.1.33:4	100.1.1.5:4	100.1.1.5:4	
j	8步: 查看地址转换的约	充计情况			
	R0#show ip nat statistics	s (思科路由器指令	)		
	Total translations: 0 (0 s	tatic, 0 dynamic, 0 ex	tended)		
	Outside Interfaces: Seria				
	Inside Interfaces: Gigabi Hits: 12 Misses: 41	itEthernet0/0			
	Expired translations: 12				
	Dynamic mappings:				
	Inside Source				
	access-list 1 pool net50				
	pool net50: netmask 255.255.255.0				
	start 200.1.1.100 end 20 type generic, total addre		0%) misses 0		
ī	9步: 路由 R0 上的参 <sup>5</sup>		070), misses 0		
•	R0#show running	3 HOLL			
	Ruijie#show running-co	_			
	Building configuration				
	Current configuration . (	192 hytes			
	Current configuration: 9	765 bytes			
	version 15.1				
	no service timestamps lo	og datetime msec			
	no service timestamps de	_			
	no service password-enc	ryption			
	! hostname Router				
	!				
	no ip cef				
	no ipv6 cef				
	license udi pid CISCO19	941/ K9 sn FTX15244	582		
	! spanning-tree mode pvst				
	!	•			
	interface GigabitEtherne	et0/0			
	ip address 192.168.1.1 2				
	ip nat inside				

```
duplex auto
speed auto
interface GigabitEthernet0/1
no ip address
duplex auto
speed auto
shutdown
interface Serial 0/1/0
ip address 200.1.1.1 255.255.255.0
ip nat outside
clock rate 64000
interface SerialO/ 1/1
no ip address
clock rate 2000000
shutdown
interface Vlan1
no ip address
shutdown
ip nat pool net50 200.1.1.100 200.1.1. 150 netmask 255.255.255.0
ip nat inside source list 1 pool net50
ip classless
ip route 0.0.0.0 0.0.0.0 200.1.1.2
ip flow-export version 9
access-list 1 permit 192.168.1.0 0.0.0.255
line con 0
line aux 0
line vty 0 4
login
End
```

# 六、思考题

- 1. 什么情况下使用静态 NAT? 什么情况下使用动态 NAT? 为什么?
- 2. 是否需要将内网所在网段或路由在外部网络的边界路由器上共享?为什么?