Python telnetlib模块实验

1、搭建网络环境

现有一台网络设备作为Telnet服务器,需要实现使用Python telnetlib作为Telnet客户端登录此设备。


• 网络拓扑

在本地主机(Win10操作系统)上安装华为eNSP模拟器,搭建下面的网络拓扑:



通过 Cloud1 连接本地主机和CE12800,下图中 VirtualBox Host-Only Network - IP: 192.168.56.1 是安装华为eNSP模拟器 后自动在本地主机(Win10)上产生的虚拟网卡,且在本地主机上的 IP 地址为: 192.168.56.1。Cloud1 的作用就是将本地主机通过 这个虚拟网卡连接到CE12800。

cloud1的设置如下:



2、配置CE12800管理IP


- # 华为CE12800是数据中心交换机,所有端口默认都处于vlan 1中,配置vlanif 1接口IP地址 192.168.56.100,用于连接本地主机。 <HUAWEI>system-view immediately Enter system view, return user view with return command. [HUAWEI]sysname CE1
 - 5 [CE1]interface Vlanif 1
 - 6 [CE1-Vlanif1]ip add 192.168.56.100 24

```
[CE1-Vlanif1]quit
8
   [CE1]
9
10
   # 华为CE12800,默认所有端口都是 shutdown 状态,需要进入端口,通过 undo shutdown 打开
   [CE1]interface GE1/0/0
11
12
   [CE1-GE1/0/0]undo shutdown
13
   # 在本地主机(Win10)上 ping 192.168.56.100,测试连通性
14
15
   C:\Users\Administrator>ping 192.168.56.100
16
17
   正在 Ping 192.168.56.100 具有 32 字节的数据:
18
   来自 192.168.56.100 的回复: 字节=32 时间=12ms TTL=255
   来自 192.168.56.100 的回复: 字节=32 时间=7ms TTL=255
19
20
   来自 192.168.56.100 的回复: 字节=32 时间=3ms TTL=255
   来自 192.168.56.100 的回复: 字节=32 时间=7ms TTL=255
21
22
23
   192.168.56.100 的 Ping 统计信息:
       数据包: 已发送 = 4, 已接收 = 4, 丢失 = 0 (0% 丢失),
24
25
   往返行程的估计时间(以毫秒为单位):
       最短 = 3ms, 最长 = 12ms, 平均 = 7ms
26
27
```

到此, 网络环境已经达成成功。

3、配置CE12800 telnet

- 配置思路
 - ☑ 完成设备Telnet预配置:配置Telnet密码,开启Telnet功能和允许Telnet登录。
 - ☑ 编写Python脚本:调用telnetlib登陆设备,然后查看配置。



```
# 1.配置CE12800的Telnet配置
2
3
   <huawei>system-view immediately
4
    [Huawei]user-interface vty 0 4
    [Huawei-ui-vty0-4]authentication-mode aaa
 5
 6
    [Huawei-ui-vty0-4]protocol inbound telnet
7
    [Huawei-ui-vty0-4]user privilege level 3
    [Huawei-ui-vty0-4]quit
8
9
    [Huawei]aaa
    [HUAWEI-aaa]local-user python password irreversible-cipher Huawei12#$
10
11
    Info: A new user is added.
    [HUAWEI-aaa]local-user python service-type telnet
12
13
14
   # 可以直接拷贝下列命令完成配置
15
   system-view immediately
16
   user-interface vty 0 4
    authentication-mode aaa
17
     protocol inbound telnet
18
```

```
user privilege level 3
quit
aaa
local-user python password irreversible-cipher Huawei12#$
local-user python service-type telnet
quit

24
quit
```

```
1 # 2.配置管理IP地址 192.168.56.100
2
   [HUAWEI]int Vlanif 1
3
   [HUAWEI-Vlanif1]ip address 192.168.56.100 255.255.255.0
   [HUAWEI-Vlanif1]quit
4
5
6
   [HUAWEI]int g1/0/0
7
   [HUAWEI-GE1/0/0]undo shutdown
   [HUAWEI-GE1/0/0]port link-type access
9
   [HUAWEI-GE1/0/0]port default vlan 1
10
11
   # 可以直接拷贝下列命令完成配置
12
   int Vlanif 1
13
    ip address 192.168.56.100 255.255.255.0
14
    quit
15
16 int g1/0/0
17
    undo shutdown
18
   port link-type access
19
    port default vlan 1
20
   quit
21
22
   # 在主机上 ping 192.168.56.100
   C:\Users\Administrator>ping 192.168.56.100
23
24
25
   正在 Ping 192.168.56.100 具有 32 字节的数据:
26 来自 192.168.56.100 的回复: 字节=32 时间=17ms TTL=255
   来自 192.168.56.100 的回复: 字节=32 时间=8ms TTL=255
27
28
   来自 192.168.56.100 的回复: 字节=32 时间=7ms TTL=255
   来自 192.168.56.100 的回复: 字节=32 时间=3ms TTL=255
29
30
31
   | 192.168.56.100 的 Ping 统计信息:
32
       数据包: 已发送 = 4, 已接收 = 4, 丢失 = 0 (0% 丢失),
33
   往返行程的估计时间(以毫秒为单位):
       最短 = 3ms, 最长 = 17ms, 平均 = 8ms
34
35
```

测试 telnet 192.168.56.100

```
1
     <huak<br/>HUAWEI>telnet 192.168.56.100
2
     Trying 192.168.56.100 ...
3
     Press CTRL+K to abort
     Connected to 192.168.56.100 ...
4
5
     Warning: Telnet is not a secure protocol, and it is recommended to use
   Stelnet.
6
7
     Username:python
8
     Password:
```

```
Warning: The initial password poses security risks.
The password needs to be changed. Change now? [Y/N]:n
Info: The max number of VTY users is 5, the number of current VTY users online i
s 1, and total number of terminal users online is 2.
The current login time is 2021-03-21 17:25:42.
First login successfully.
```

4、telnetlib登录CE12800

```
1 # 1、导入telnetlib 模块。telnetlib模块是Python自带的模块,无需安装。
       导入 time 模块。Python默认无间隔按顺序执行所有代码,在使用telnet向交换机发送配置命
   令时候可能会遇到响应
                                   不及时或者设备回显信息显示不全。此时,可以使用
   time模块下的sleep方法来人为暂停程序。
   import telnetlib
3
4
   import time
5
   # 2、设置要登录的CE12800的管理IP地址、telnet 用户名和telnet密码
6
7
   host = '192.168.56.100'
   Username = "python"
8
9
   password = 'Huawei12#$'
10
   # 3、实例化一个Telnet对象,并连接主机
11
   tn = telnetlib.Telnet(host)
12
13
14
   # 4、等待输入telnet用户名
15
   tn.read_until(b"Username:")表示读取到显示 "Username:"为止。其中字符
16
   串"Username:"前的"b"表示将Python3中默认的unicode编码变为bytes。这是函数对输入数据的要
   求,具体内容可以查看telnetlib官方文档,若不携带则程序会报错。
17
18
   Username.encode('ascii') 和b"\n"。Username.encode('ascii')表示转换Username代表
   的字符串"Huawei@123"的编码类型为ASCII。"+"表示将该符号前后的字符串连接。"\n"为换行符,
   相当于输入后敲击回车键。所以本行代码含义为输入用户名"python"并换行。
19
   tn.read_until(b"Username:")
20
21
   # 5、使用write()向设备输入用户名
22
23
   tn.write(Username.encode('ascii') + b"\n")
24
   #6、同理输入密码
25
26
   tn.read_until(b"Password:")
   tn.write(password.encode('ascii') + b"\n") # 使用write()向设备输入命令
27
28
29
   # 7、 正常 telnet CE12800 时,会提示是否要修改密码,回答 n 即可
30
31
   telnet 192.168.56.100
32
   Warning: Telnet is not a secure protocol, and it is recommended to use
   Stelnet.
33
   Username:python
34
35
   Password:
36
   Warning: The initial password poses security risks.
37
   The password needs to be changed. Change now? [Y/N]:n
   Info: The max number of VTY users is 5, the number of current VTY users
   online is 1, and total number of terminal users online is 2.
```

```
The current login time is 2021-03-21 17:39:21.
39
40
         The last login time is 2021-03-21 17:34:12 from 192.168.56.1 through
   Telnet.
41
   <HUAWEI>
   0.00
42
43
   # 使用write()向设备输入"n"
44
   tn.write(b"n\n")
45
46
47
   # 8、向设备发送取消分页显示的命令
48
   tn.write(b"screen-length 0 temporary\n")
49
50
   # 9、使用write()向设备输入命令display cu int vlanif 1 的配置
   tn.write(b'display cu int vlanif 1 \n')
51
52
53
   # 10、time.sleep(1)的作用是将程序暂停1秒。用于等待交换机回显信息,然后再执行后续代码。如
   果没有设置等待时间,则程序会直接执行下一行代码,导致没有数据可供读取。
54
   time.sleep(1)
55
56
   # 11、tn.read_very_eager() 表示读取当前的尽可能多的数据, decode('ascii'))表示将读取
   的数据解码为ASCII
57
   print(tn.read_very_eager().decode('ascii'))
58
59 # 12、关闭连接
60
   tn.close()
61
```

```
1 # 执行输出
    D:\Python_workplace\imagesite\imagesite_env\Scripts\python.exe
    D:/NetAutomatic/tenet.py
 3
4
    warning: The initial password poses security risks.
    The password needs to be changed. Change now? [Y/N]:n
    Info: The max number of VTY users is 5, the number of current VTY users
    online is 3, and total number of terminal users online is 4.
 7
          The current login time is 2021-03-21 17:34:12.
          The last login time is 2021-03-21 17:33:41 from 192.168.56.1 through
8
    Telnet.
    <HUAWEI>screen-length 0 temporary
    Info: The configuration takes effect on the current user terminal interface
10
    only.
11
    <HUAWEI>display cu int vlanif 1
12
13
    interface Vlanif1
    ip address 192.168.56.100 255.255.255.0
14
15
16
    return
17
    <HUAWEI>
18
    Process finished with exit code 0
19
```