CS3723 Pgm Assignment #1: Storage Management in C (50 pts) — Due Monday Sept 24<sup>th</sup>, 2018 at 11:59pm. © Copyright 2018 Larry Clark, this document must not be copied to any other website

In this assignment, you will create **heap storage management functions** based on using reference counts and understanding metadata. You will write functions which manage free memory lists and the reference counts for user data nodes:

- When a node is created, it sets the count to 1 (this is like a variable referencing data causing the count to be 1).
- A node (i.e., from node) can be associated with another node (i.e., to node) by changing a pointer attribute in the from node. This will cause the to node to have its reference count increased. If the from node was already referencing another node via that particular pointer attribute, that original referenced node should have its reference count decreased. If the new to node value is NULL, don't attempt to increase its reference count.
- We can also add references to nodes similar to a node having another variable referencing it.

Your code must be able to understand the metadata for any nodes. If you hard-code your program to only handle the two referenced node types, you will lose at least 80% of the points. To better understand the metadata, please examine the sample partial output below.

It is likely that a question on the midterm exam will be easier if you do this programming assignment. Total points: 50 (for this assignment) + (apprx) 20 \* 3 = (apprx) 110 pts

To help reduce the code that you have to write and reduce debugging difficulty, I have provided a **driver program** which has many capabilities. Initially, it will set up metadata and the heap. It also has functions to print the metadata, process commands from an input file, print the contents of user nodes, and print the heap. The driver program also provides multiple examples of pointer manipulation.

Files that I provided (located in /usr/local/courses/clark/cs3723/2018Fa):

cs3723p1Driver.c - reads the input file, calls your reference count storage management functions, and uses a hash table to store the addresses of allocated memory (so that those can be subsequently associated with other nodes or freed). An important function is the setData function which uses metadata to set attributes in a node. The driver also provides functions for printing the heap memory to help with debugging.

**cs3723p1.h** - include file for this program. Some important typedefs:

**MetaAttr** – describes one attribute in a node type: name, type, size in bytes, and offset **NodeType** – describes one node type: name, beginning subscript in metaAttrM array, total

**AllocNode** - contains the node's size, allocated/free flag, reference count, node type, and the user's data.

**FreeNode** – used for nodes that have been freed (and not yet reallocated). It contains a pointer to the next free node in a linked list of free nodes.

**StorageManager** - a structure that contains the address of the heap (pBeginStorage), free memory pointer, an array of pointers to free lists (one for each node type), an array of NodeType entries, and an array of MetaAttr entries. It does not have a count of the number of entries in those arrays. Instead, sentinels are used to mark the end of the arrays.

**SMResult** - used by many of the storage management functions to specify whether they executed successfully.


hashApi.cpp - C++ code to integrate C with the C++ Hash Table Class (unordered\_map). This supports functions getHash, putHash, eraseAll, and printAll. This is only used by the driver.

p1Input.txt - Input text file suitable for the driver. The driver uses **stdin** so redirect input from this file. printNode.o - object code for printing a node.

makefile - Please use this makefile to create your **p1** executable. Note that you should not use the hen servers. The makefile uses **g++** instead of gcc. To build the executable (with it automatically

## building the other pieces), type make p1

In C, malloc() returns a pointer to *user data* and we pass **free**() a pointer to *user data*. As you know from lecture, malloc() actually allocated more bytes than you requested, including an attribute for the total size. The following diagram shows that our allocated nodes(for this assignment) contain an allocated size, allocated/free flag (cAF), reference count, and node type:



When integrating with a **user** of the storage management functions, the storage management software uses pUserData (a pointer to the user data). The function **userAllocate** allocates a node, but returns a pointer to the user data portion of the node. Similarly, the other user integration functions (names begin with "user") are passed pointers to user data instead of a pointer to the beginning of the allocated node.

**You will need to code** the following functions; however, due to modularity concerns, you may want to create extra functions. Your code should be placed in <a href="mailto:cs3723p1.c">cs3723p1.c</a>.

void \* userAllocate(StorageManager \*pMgr, short shUserDataSize, short shNodeType
 , char sbUserData[], SMResult \*psmResult)

- Purpose: allocates an AllocNode from our heap, copies the binary sbUserData into that node, and returns a pointer to the user data portion of the node.
- It is passed:
  - pMgr a pointer to the StorageManager structure. (See cs3723p1.h for more information.)
  - o shUserDataSize the size of the user data. This does not include the four storage management prefix attributes. The size of the allocated node will actually be this plus at least the pMgr->shPrefixSize.
  - o shNodeType this is a subscript into the storage manager's nodeTypeM array.
  - sbUserData this is storage buffer containing the actual user data which needs to be placed in the allocated node. This data can contain integer and double values; therefore, it is not a zero-terminated string.
  - o psmResult a pointer to a SMResult structure. (See cs3723p1.h for more information.)
- This function first checks to see if there is a node type-specific free node available in pMgr -> pFreeHeadM[shNodeType]. If there is, it is used and the free list is updated. If there is not, it uses the driver-provided utilAllocate to allocate memory from the top of the heap. Note that your code will not use malloc().
- Initializes an AllocNode:
  - Set its reference count to 1.
  - Set its node type.
  - Set its allocated size which is bigger than shUserDataSize.
  - Sets its cAF to indicate that it is allocated.
  - Set its sbData. Why can't you use strcpy for this?
- Sets the psmResult information.
- Returns a pointer (from the user's perspective) to the allocated memory (i.e., a pointer to where the user data is in the node). This is not the address of the AllocNode! (See the diagram.) If memory was not allocated, it should return NULL.

void userRemoveRef(StorageManager \*pMgr, void \*pUserData, SMResult \*psmResult)

- Purpose: removes a reference to the specified data.
- It is passed:

- o pMgr a pointer to the StorageManager structure. (See cs3723p1.h for more information.)
- o pUserData a pointer to the user data within an allocated node.
- o psmResult a pointer to a SMResult structure. (See cs3723p1.h for more information.)
- Decrements the reference count for the corresponding AllocNode.
- If the reference count reaches zero, it must "free" the AllocNode:
  - If the user node type references pointers, decrement the ref count on any directly referenced user data nodes. (This will be a recursive call to userRemoveRef.)
  - Frees the AllocNode which reached a ref count of 0 by calling **memFree**. Note that memFree keeps the "freed" node around . It does not do a C free().

void userAssoc(StorageManager \*pMgr, void \*pUserDataFrom, char szAttrName[]
 , void \*pUserDataTo, SMResult \*psmResult)

- Purpose: logically, it is setting a pointer in a user node to point to another node (or NULL) and correspondingly updating reference counts.
- It is passed:
  - o pMgr a pointer to the StorageManager structure. (See cs3723p1.h for more information.)
  - o pUserDataFrom a user data pointer to the *from node* which contains the pointer attribute. This is the *from node*.
  - o szAttrName the name of the attribute which is used to determine where the pointer is located within the *from node*.
  - o pUserDataTo a user data pointer to the *to node*.
  - o psmResult a pointer to a SMResult structure. (See cs3723p1.h for more information.)
- The referenced attribute must be a pointer. If not, set psmResult->rc to RC\_ASSOC\_ATTR\_NOT\_PTR.
- If that specified pointer attribute in the *from node* is already referencing something, that referenced user data node needs to have its reference count decremented (how should you do that? could it reach 0?)
- Unless it is NULL, the new referenced user data node needs to have its ref count increased.
- Change the user pointer in the specified user data node to point to the new referenced user data node or NULL (if that was specified).
- Set the psmResult information.

void userAddRef(StorageManager \*pMgr, void \*pUserDataTo, SMResult \*psmResult)

- Purpose: logically, it is adding a reference to the specified *to node*. This is similar to adding a variable's reference to the *to node*.
- It is passed:
  - o pMgr a pointer to the StorageManager structure. (See cs3723p1.h for more information.)
  - o pUserDataTo a user data pointer to the to node.
  - o psmResult a pointer to a SMResult structure. (See cs3723p1.h for more information.)
- Increase the reference count for the *to node* by one.

void memFree(StorageManager \*pMgr, AllocNode \*pAlloc, SMResult \*psmResult)

- Purpose: This is adding the specified allocated node to the free list for that node's node type.
- It is passed:
  - o pMgr a pointer to the StorageManager structure. (See cs3723p1.h for more information.)
  - o pAlloc a pointer to an allocated node. This is NOT a user data pointer.
  - o psmResult a pointer to a SMResult structure. (See cs3723p1.h for more information.)
- Verify that the node is in fact an allocated node. If not return an error via psmResult.
- Add this node to the front of the free list for this node's node type.

## Notes:

- 1. In this program, your code must not use malloc(), calloc() or free().
- 2. To help understand how to use the metadata, examine the driver's **setData** function.
- 3. Your code must follow my **programming standards**.
- 4. You must make certain your code works on a fox server and can be compiled by the specified makefile.

- 5. To simplify grading, please include turn in a zip file (named LastnameFirstname.zip). It should contain:
  - o cs3723p1.c your C source code
  - o p1Output.txt your output
- 6. For Microsoft Visual Studio Users:
  - If you need a wider Console Window:
    - Once the console window displays (you may want a break point in your code so that it doesn't disappear), click the top left corner of the console window.
    - Properties
    - Layout
    - o Change the Screen Buffer Size to 120
    - Change the Window Size to 120
  - Unfortunately, you will have to create your own printNode.
- 7. Make certain your code runs correctly on a **fox** server.
- 8. Via BlackBoard, turn in a zip file (named LastnameFirstname.zip) which contains:
  - Your cs3723p1.c source file
  - Your output named p1Output.txt

## **Sample Partial Output:**

```
Metadata
Node Type Beg Attr Sub Total Sz
Customer
                     56
            0
            Attribute Name Type Offset Size
            customerId
                          S
                                0 12
            name
                                 12
                                      20
            pFirstItem
                                 32
                                     8
            pNextCust
                                 40
                                      8
            balance
                         D
                                 48
                     32
LineItem
            Attribute Name Type Offset Size
            productId S
                                0 10
            iQtyReq
                                 12
                                      4
                                      8
            dCost
                                 16
                         P 24
            pNextItem
>>> ALLOC C111 Customer 111, Sal A Mander, NULL, NULL, 100.00
>>> PRTNODE C111
      Alloc Address Size NodeType RefCnt DataAddress
      0x1def070
                     64 0 1
                                         0x1def078
                   Attr Name
                               Type Value
                               S 111
                   customerId
                   name
                                S Sal A Mander
                   pFirstItem
                                 P (nil)
                                P (nil)
                   pNextCust
                                D 100.000000
                   balance
>>> ALLOC C222 Customer 222, Barb Wire, NULL, NULL, 200.00
>>> PRTNODE C222
      Alloc Address Size NodeType RefCnt DataAddress
      0x1def0b0
                    64 0 1
                                         0x1def0b8
                   Attr Name
                               Type Value
                              S 222
                   customerId
                   name
                                S Barb Wire
                   pFirstItem
                                 P (nil)
                   pNextCust
balance
                               P (nil)
                                D 200.000000
>>> ALLOC PPF001 LineItem PPF001,5,9.95,NULL
>>> PRTNODE PPF001
      Alloc Address Size NodeType RefCnt DataAddress
                     40 1
      0x1def0f0
                                1
                                         0x1def0f8
                   Attr Name
                               Type Value
                               S PPF001
                   productId
                   iQtyReq
                                I 5
                   dCost
                                 D 9.950000
```

```
P (nil)
                    pNextItem
* #1 associate customer 111 with a next pointing to 222
>>> ASSOC C111 pNextCust C222
* customer 111's ref cnt should still be 1, but its pNextCust should point to 222
>>> PRTNODE C111
      Alloc Address Size NodeType RefCnt DataAddress
                     64 0
      0x1def070
                                   1
                                         0x1def078
                    Attr Name
                                 Type Value
                                  S 111
                    customerId
                                   S Sal A Mander
                    name
                                   P (nil)
                    pFirstItem
                                   P 0x1def0b8
                    pNextCust
                                   D 100.000000
                    balance
* customer 222's ref cnt should now be 2
>>> PRTNODE C222
      Alloc Address Size NodeType RefCnt DataAddress
      0x1def0b0
                     64 0
                                  2 0x1def0b8
                    Attr Name
                                 Type Value
                                   S 222
                    customerId
                                   S Barb Wire
                    name
                                   P (nil)
                    pFirstItem
                                   P (nil)
                    pNextCust
                                   D 200.000000
                    balance
* associate customer 111 to PPF001
>>> ASSOC C111 pFirstItem PPF001
>>> PRTNODE C111
      Alloc Address Size NodeType RefCnt DataAddress
      0x1def070
                     64 0
                                 1 0x1def078
                    Attr Name
                                 Type Value
                                   S 111
                    customerId
                                   S Sal A Mander
                    name
                                  P 0x1def0f8
                    pFirstItem
                                   P 0x1def0b8
                    pNextCust
                                   D 100.000000
                    balance
* associate customer 222 to 333
>>> ALLOC C333 Customer 333, Misty Wind, NULL, NULL, 70.00
>>> ASSOC C222 pNextCust C333
* #2 111 should point to 222 which points to 333
    111 should also point to PPF001
>>> PRTALL
PPF001:0x1def0f8
      Alloc Address Size NodeType RefCnt DataAddress
      0x1def0f0
                     40 1 2 0x1def0f8
                                 Type Value
                    Attr Name
                    productId
                                  S PPF001
                                  I 5
                    iQtyReq
                                  D 9.950000
                    dCost
                                  P (nil)
                    pNextItem
C333:0x1def120
      Alloc Address Size NodeType RefCnt DataAddress
      0x1def118
                       64 0
                                  2
                                          0x1def120
                    Attr Name
                                  Type Value
                    customerId
                                   S 333
                                   S Misty Wind
                    name
                    pFirstItem
                                   P (nil)
                                  P (nil)
                    pNextCust
                                  D 70.000000
                    balance
C222:0x1def0b8
                    Size NodeType RefCnt DataAddress
      Alloc Address
```

0x1def0b0

64

Attr Name customerId

2 0x1def0b8

Type Value

S 222

name	S	Barb Wire
pFirstItem	Р	(nil)
pNextCust	Р	0x1def120
balance	D	200.000000

## C111:0x1def078

Size NodeType	RefCnt	DataAddress
64 0	1	0x1def078
Attr Name	Type Va	lue
customerId	S 11	1
name	S Sa	l A Mander
pFirstItem	P 0x	1def0f8
pNextCust	P 0x	1def0b8
balance	D 10	0.000000
	64 0 Attr Name customerId name pFirstItem pNextCust	Attr Name Type VacustomerId S 11 name S SapFirstItem P 0x pNextCust P 0x

- \* add another customer
- >>> ALLOC C444 Customer 444, Emory Board, NULL, NULL, 44.44
- >>> ADDREF PC444 C444
- \* #3 Customer 444 should have a ref count of 2
- >>> PRTNODE C444

INODE C444					
Alloc Address	Size NodeType		RefC	nt D	ataAddress
0x1def158	64	0		2	0x1def160
	Attr Name		Type	Value	e
	customerId		S	444	
	name		S	Emory	y Board
	pFirstItem		Р	(nil)	)
	pNextCust		Р	(nil)	)
	balance		D	44.4	40000