

Rocket Uniface Library 10.4

Struct Functions

Struct functions enable you to get information about a Struct (such as the number of members it has), get or set Struct annotations, or perform actions such as inserting and moving Struct members.

Syntactically, they are treated as Struct members and are accessed using the dereference operator (->):

Struct -> StructFunction

For example:

vBook->\$membercount

Unlike true members, Struct functions are not part of the Struct member list and they do not have an index.

Struct function names always begin with a dollar sign \$. Unlike other functions, they do not use parentheses ().

Table: Struct Functions

ProcScript	Description
<u>\$collSize</u>	Get the number of Structs in the collection.
<u>\$dbgString</u>	Get a string that represents the Struct or Struct collection.
\$dbgStringPlain	Get a string that represents the Struct or Struct collection, but without annotations.
<u>\$index</u>	Get or set the index of the Struct in a Struct collection.
<u>\$isLeaf</u>	Check whether a Struct is a Struct leaf (the logical end point in a Struct tree).
<u>\$isScalar</u>	Check whether a Struct is a scalar Struct.
<u>\$istags</u>	Check whether the Struct is a \$tags Struct for another Struct.
<u>\$memberCount</u>	Get the number of members in a Struct.
<u>\$name</u>	Get the name of a Struct.
<u>\$parent</u>	Get or set the parent of the Struct.
<u>\$scalar</u>	Get or set the scalar members of a Struct.
\$tags	Get or set annotations for a Struct.

Setting Struct Functions

Although most Struct functions only return information, the **\$index**, **\$parent**, and **\$tag** functions can be used to change data. You can use:

- \$index to insert a member into a Struct at the specified index.
- **\$parent** to move a Struct member from one Struct to another.
- \$tags to set the value of annotations, or define your own annotations fro use in conversion routines.

For more information, see **Struct Annotations**.

Related reference

ProcScript: Struct Functions		