

# White Rabbit X — 完全ユーザーマニュアル

現在の EA ソースと set マニフェストから生成した正式リファレンス — EA 1.11 — 127 inputs — 3738 sets

## 範囲と正本

EA ソースが inputs、既定値、機能を定義し、マニフェストが各 set の状態、パス、SHA-256 を定義します。旧 Quantum 資料は履歴専用です。

EA SHA-256: D85A30A0836A9BE75F6DFC55868BDC664EE1FC7F5DD0840C029DEB0EF8AC8973.

Manifest SHA-256:

E96B9E4050F8EA8B764E187BD6CC1E907AE2AE8C4A6489C9EF2D3317C6003F75.

自動生成資料。パラメータ識別子は EA と完全に一致します。

## インストールと初回実行

一致する EX5 を導入し、Tester Inputs で set を読み、正確な銘柄を選び Journal を確認します。

## シグナルとエントリー

6 エンジン reversal、signal/reference cross、baseline/reference cross を共有します。And は同じ確定足、All はいずれかを意味します。

- 12 のネイティブエンジン: MACD、EMA Cross、Momentum、Stochastic、TRIX、RSI、CCI、Williams %R、DeMarker、MFI、OsMA、Ichimoku。
- 確定足における AND/OR を明示した 7 エントリー方式。
- 独立した MTF、MA、ADX、ATR、news フィルター。
- 4 PositionSizeMode と equity/margin 保護。
- Stop、take、breakeven、trailing、reversal の決済。
- Dashboard、時間、言語、WFO を統合。
- EntryIndicator: MACD, EMA\_Cross, Momentum, Stochastic, TRIX, RSI, CCI, WPR, DeMarker, MFI, OsMA, Ichimoku.
- EntryMethod: Reversal, SignalCross, ReferenceCross, ReversalAndSignalCross, ReversalAndReferenceCross, SignalAndReferenceCross, All.
- PositionSizeMode: Percentage, Monetary, FixedLot, FixedR.
- RecoveryMode: None, Martingale, DAlembert.
- GridMode: Disabled, SeparateProfit, UnifiedProfit.

## フィルター

MTF は上位足 MACD 整合、MA、ADX、ATR volatility、news は独立です。追加すると標本が減少します。

## News filter and CSV workflow

Live mode reads the MT5 Economic Calendar in broker-server time and blocks new entries if the calendar query fails. Backtests cannot read that live calendar: run MQL5 \ Scripts \ White Rabbit News Exporter on a live/demo chart, cover the entire test interval, and write NewsCSVFile to the terminal Common \ Files folder. The semicolon-delimited header is datetime;currency;importance;event\_name, where importance 2 is moderate and 3 is high. Use the same broker/server timezone; for suffixed or

non-FX symbols set ExportMoedas and NewsMoedasManual explicitly. Manual currencies take precedence over automatic symbol parsing.

## 執行とポジション管理

spread、margin、volume step、tick size、stops/freeze 制約を確認し、Journal で結果を確認します。

## Grid cycle and ATR spacing

Every additional grid leg is measured from the newest already-confirmed position on that side and must satisfy  $ATR \times DistanciaMinima$ . The initial order cannot recursively trigger another leg in the same calculation event; it becomes the anchor on the following cycle. Individual grid take-profits are disabled: Separate mode evaluates independent BUY/SELL cycles against frozen monetary targets and ends a side when it becomes flat; Unified evaluates the aggregate BUY+SELL basket and ends when both sides are flat. Realized commissions, swap, fees and stopped legs remain in the result while the corresponding cycle is open. The target triggers a close request, so actual exit costs and slippage can leave the final result slightly below it. Live cycle state is persisted across an EA restart. Grid is hedging-only and must be reoptimized after any EA, broker-contract or cost change.

## 決済スタック

Stop、ATR take、breakeven、ATR trailing、reversal exit は独立です。ReversalExitUseEntryFilters が決済フィルターを制御します。

## リスクとリカバリー

PositionSizeMode は一つだけ選択します。Percentage/Fixed-R は stop 必須。Grid/Martingale/D'Alembert は研究用です。

## 時間、表示、WFO

ブローカーサーバー時刻を使い、日跨ぎと Saturday/Sunday に対応します。WFO は IS/OOS を定義します。

## Diagnostics and supplied utilities

The Experts/ Journal tab is authoritative for rejected inputs, OrderCheck failures, news-calendar errors and close retries. Compile and run MQL5 \ Scripts \ WhiteRabbit Filters SelfTest; its final line must report zero failures. Use White Rabbit News Exporter to build the test CSV, then verify its date range, currencies, delimiter and Common \ Files location before a news-enabled backtest.

## サイクル・ダッシュボードのテレメトリ

パネルはロット計算とバスケット決済と同じ状態スナップショットを使用します。

- tick の定期更新は毎秒 1 回までです。初期化と取引イベントは即時更新できます。
- Balance/Equity は口座全体です。Closed P&L は OnInit 以降の差分、Open P&L と positions は Symbol + Magic で絞った現在値です。
- Martingale は BUY/SELL 別に連続損失、サイクル損失回数・総額、recovered、deficit、deficit  $\times$  Multiplicador の target を表示します。
- MaxMartingaleSteps 超過で hard reset し、旧 deficit を破棄して次注文を base lot にします。各側の保有は最大 1 です。
- D'Alembert は BUY/SELL の現在レベルと正規化した次ロットを表示します。

- Grid は legs/volume、コスト込み realized、open P&L、cycle P&L、開始時に固定した target、remaining を表示します。
- Anchor は直近の確定ポジションです。BUY は  $\text{anchor} - \text{ATR} \times \text{DistanciaMinima}$  未満、SELL は  $\text{anchor} + \text{ATR} \times \text{DistanciaMinima}$  超を厳密に要求し、進捗は ATR で示します。
- Separate は flat になった側だけ終了し、Unified は BUY/SELL 両方が flat で終了します。処理中注文は reset を遅らせます。
- Target は決済要求のトリガーです。実際の exit commission、fee、slippage により最終値が少し下回る場合があります。
- InterfaceLanguage は 11 言語を維持します。Auto は Tester で English、live で端末言語を使い、未翻訳 label は English にフォールバックします。

## 互換性と制約

これは保守的な規則で、ブローカー制限が優先されます。

- Percentage と Fixed-R は AtivarStop=true が必須です。
- Grid は Monetary/Fixed Lot、Recovery\_None、hedging account のみです。
- Grid は take、正の DistanciaMinima、2 以上の上限が必要です。
- バasketが開いている間、そのサイクルの確定損失、swap、commission、fees は目標到達に必要な結果へ残り、単独レッグの利益では消えません。
- Grid\_SeparateProfit では BUY/SELL のサイクルは独立します。一方の全ポジションがなくなるとその側のサイクルは終了し、次のエントリーは終了済み損失を持ち越さない新サイクルです。
- D'Alembert は Fixed Lot、Grid\_Disabled、DAlembertStep>0 のみです。
- Martingale は MaxMartingaleSteps/MaxMartingaleLot に従います。
- OnOppositeOrder は hedging、両方向、grid 無効が必要です。
- News backtest は Common \ Files の CSV が必要です。
- 時間はブローカーサーバー基準です。
- suffix と銘柄仕様をブローカーごとに確認します。

## 検出された set ライブラリ

件数はファイルとマニフェストから取得します。set は研究仮説です。Counts and fingerprints were read at generation time.

| Folder                 | Sets | Purpose                                       |
|------------------------|------|-----------------------------------------------|
| 01_Forex               | 168  | Per-asset baselines — Forex.                  |
| 02_Metals              | 18   | Per-asset baselines — Metals.                 |
| 03_Cryptocurrencies    | 36   | Per-asset baselines — Cryptocurrencies.       |
| 04_Indices_Energies    | 42   | Per-asset baselines — Indices Energies.       |
| 05_US_Stocks_CFD       | 300  | Per-asset baselines — US Stocks CFD.          |
| 06_Research_Matrix     | 935  | Controlled one-axis research.                 |
| 07_Entry_System_Matrix | 3360 | Indicator × entry method × management matrix. |
| 08_Filter_Stack_Matrix | 320  | Signal-filter stack combinations.             |
| 09_Risk_Engine_Matrix  | 130  | Compatible sizing, risk and recovery models.  |
| 10_Exit_Stack_Matrix   | 720  | Exit-control stack combinations.              |

## リスク警告

EA、set、過去結果は将来を保証しません。OOS と demo で検証してください。

## 全 inputs リファレンス

表はソース順です。区切り文字列も .set schema の一部です。

| No. | Section                                               | Subsection         | Parameter                          | Type                                | Default                     | Source description                                        | Enum options                                                                                                                                                                                                                                                                                                                                                                                 | Operational notes                                                                                          |   |
|-----|-------------------------------------------------------|--------------------|------------------------------------|-------------------------------------|-----------------------------|-----------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------|---|
| 1   | General                                               | —                  | NomedaEs<br>trategia               | string                              | "White<br>Rabbit X"         | Strategy<br>Name                                          | —                                                                                                                                                                                                                                                                                                                                                                                            | Use within<br>its<br>declared<br>section<br>and<br>validate<br>the<br>complete<br>combinati<br>on.         |   |
| 2   | Entries,<br>Signal and<br>Position M<br>anagemen<br>t | —                  | TimeFram<br>e                      | ENUM_AL<br>LOWED_TI<br>MEFRAME<br>S | M1                          | Entry<br>timeframe                                        | M1, M5,<br>M15,<br>M30, H1,<br>H4, D1,<br>W1                                                                                                                                                                                                                                                                                                                                                 | Signal<br>evaluation<br>is gated to<br>one<br>decision<br>per closed<br>bar of this<br>timeframe<br>.      |   |
| 3   | Entries,<br>Signal and<br>Position M<br>anagemen<br>t | Entry<br>Indicator | myBlankS<br>paceEntryI<br>ndicator | string                              | ""                          | \                                                         | \                                                                                                                                                                                                                                                                                                                                                                                            | =====<br>=====<br>====<br>Entry<br>Indicator<br>=====<br>=====<br>==== \                                   | \ |
| 4   | Entries,<br>Signal and<br>Position M<br>anagemen<br>t | Entry<br>Indicator | EntryIndic<br>ator                 | ENUM_EN<br>TRY_INDIC<br>ATOR        | EntryIndic<br>ator_MAC<br>D | Selects<br>the<br>indicator<br>used by<br>Entry<br>Method | EntryIndic<br>ator_MAC<br>D, EntryIn<br>dicator_E<br>MA_Cross<br>, EntryIndi<br>cator_Mo<br>mentum,<br>EntryIndic<br>ator_Stoc<br>hastic, Ent<br>ryIndicato<br>r_TRIX, En<br>tryIndicat<br>or_RSI, En<br>tryIndicat<br>or_CCI, En<br>tryIndicat<br>or_WPR, E<br>ntryIndica<br>tor_DeMar<br>ker, EntryI<br>ndicator_<br>MFI, EntryI<br>ndicator_<br>OsMA, Ent<br>ryIndicato<br>r_Ichimok<br>u | Selects<br>the<br>engine;<br>Fast_EMA,<br>Slow_EMA<br>and MACD<br>_SMA are<br>reused by<br>that<br>engine. |   |

|   |                                                       |                    |                     |                            |                 |                                                                                                            |   |                                                                                                    |   |
|---|-------------------------------------------------------|--------------------|---------------------|----------------------------|-----------------|------------------------------------------------------------------------------------------------------------|---|----------------------------------------------------------------------------------------------------|---|
| 5 | Entries,<br>Signal and<br>Position M<br>anagemen<br>t | Entry<br>Indicator | InpApplied<br>Price | ENUM_AP<br>PLIED_PRI<br>CE | PRICE_CL<br>OSE | Applied<br>price used<br>by the<br>selected<br>indicator                                                   | — | Use within<br>its<br>declared<br>section<br>and<br>validate<br>the<br>complete<br>combinati<br>on. |   |
| 6 | Entries,<br>Signal and<br>Position M<br>anagemen<br>t | Entry<br>Indicator | Fast_EMA            | int                        | 12              | First<br>period: MA<br>CD/EMA<br>fast;<br>oscillator<br>period;<br>Stochastic<br>%K;<br>Ichimoku<br>Tenkan | — | First<br>sequential<br>period; for<br>Ichimoku<br>this is<br>Tenkan.                               |   |
| 7 | Entries,<br>Signal and<br>Position M<br>anagemen<br>t | Entry<br>Indicator | Slow_EMA            | int                        | 26              | Second<br>period: MA<br>CD/EMA<br>slow;<br>Ichimoku<br>Kijun                                               | — | Second<br>sequential<br>period; for<br>Ichimoku<br>this is<br>Kijun.                               |   |
| 8 | Entries,<br>Signal and<br>Position M<br>anagemen<br>t | Entry<br>Indicator | MACD_SM<br>A        | int                        | 9               | Third<br>period:<br>MACD<br>signal;<br>oscillator<br>signal;<br>Stochastic<br>%D;<br>Ichimoku<br>Senkou B  | — | Third<br>sequential<br>period; for<br>Ichimoku<br>this is<br>Senkou<br>Span B.                     |   |
| 9 | Entries,<br>Signal and<br>Position M<br>anagemen<br>t | Entry<br>Method    | myBlanks<br>pace1   | string                     | ""              | \                                                                                                          | \ | =====<br>=====<br>=====<br>Entry<br>Method =<br>=====<br>=====<br>= \                              | \ |

|    |                                         |              |                 |                         |                  |                                                               |                                                                                                                                                                                                                   |                                                                         |   |
|----|-----------------------------------------|--------------|-----------------|-------------------------|------------------|---------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------|---|
| 10 | Entries, Signal and Position Management | Entry Method | EntryMethod     | ENUM_ENTRY_TRIGGER_MODE | EntryTrigger_All | Reversal, signal cross, reference cross or their combinations | EntryTrigger_Reversal, EntryTrigger_SignalCross, EntryTrigger_ReferenceCross, EntryTrigger_ReversalAndSignalCross, EntryTrigger_ReversalAndReferenceCross, EntryTrigger_SignalAndReferenceCross, EntryTrigger_All | And modes require both events on the same closed bar; All is OR.        |   |
| 11 | Entries, Signal and Position Management | ATR Settings | myBlankSpace42  | string                  | ""               | \                                                             | \                                                                                                                                                                                                                 | =====<br>=====<br>=====<br>ATR Settings =<br>=====<br>=====<br>===== \  | \ |
| 12 | Entries, Signal and Position Management | ATR Settings | ATR_Time Frame  | ENUM_ALLOWED_TIMEFRAMES | M1               | Time Frame ATR                                                | M1, M5, M15, M30, H1, H4, D1, W1                                                                                                                                                                                  | Use within its declared section and validate the complete combination.  |   |
| 13 | Entries, Signal and Position Management | ATR Settings | PeriodoATR      | int                     | 14               | ATR Period                                                    | —                                                                                                                                                                                                                 | Use within its declared section and validate the complete combination.  |   |
| 14 | Entries, Signal and Position Management | Stop Loss    | myBlankSpace4s2 | string                  | ""               | \                                                             | \                                                                                                                                                                                                                 | =====<br>=====<br>=====<br>= Stop Loss ===<br>=====<br>=====<br>===== \ | \ |

|    |                                         |             |                 |        |       |                                |   |                                                                                     |   |
|----|-----------------------------------------|-------------|-----------------|--------|-------|--------------------------------|---|-------------------------------------------------------------------------------------|---|
| 15 | Entries, Signal and Position Management | Stop Loss   | AtivarStop      | bool   | true  | Enable Stop Loss               | — | Required by Percentage and Fixed-R sizing; recommended for every non-grid baseline. |   |
| 16 | Entries, Signal and Position Management | Stop Loss   | VelaStop        | int    | 0     | Stop Loss Candle               | — | Use within its declared section and validate the complete combination.              |   |
| 17 | Entries, Signal and Position Management | Stop Loss   | Stop            | double | 3     | Stop Loss ATR Multiplier       | — | Use within its declared section and validate the complete combination.              |   |
| 18 | Entries, Signal and Position Management | Take Profit | myBlankSpace101 | string | ""    | \                              | \ | =====<br>=====<br>=====<br>Take Profit ===<br>=====<br>=====<br>==== \              | \ |
| 19 | Entries, Signal and Position Management | Take Profit | TakeOrganico    | bool   | false | Enable Organic ATR Take Profit | — | Use within its declared section and validate the complete combination.              |   |
| 20 | Entries, Signal and Position Management | Take Profit | AtivarTake      | bool   | true  | Enable Take Profit             | — | Required by supported grid operation.                                               |   |



|    |                                         |                       |                  |        |       |                                        |   |                                                                        |   |
|----|-----------------------------------------|-----------------------|------------------|--------|-------|----------------------------------------|---|------------------------------------------------------------------------|---|
| 21 | Entries, Signal and Position Management | Take Profit           | VelaTake         | int    | 0     | Take Profit Candle                     | — | Use within its declared section and validate the complete combination. |   |
| 22 | Entries, Signal and Position Management | Take Profit           | Take             | double | 3     | Take Profit ATR Multiplier             | — | Use within its declared section and validate the complete combination. |   |
| 23 | Signal Filters                          | MTF Alignment         | myBlankSpaceMTF  | string | ""    | \                                      | \ | =====<br>=====<br>=====<br>MTF Alignment<br>=====<br>=====<br>===== \  | \ |
| 24 | Signal Filters                          | MTF Alignment         | AtivarFilterMTF  | bool   | false | Enable MTF Filter                      | — | Higher-timeframe alignment uses the EA's MACD trend layer.             |   |
| 25 | Signal Filters                          | MTF Alignment         | MTF_RequiresAmbo | bool   | false | Require Both Higher Timeframes Aligned | — | Use within its declared section and validate the complete combination. |   |
| 26 | Signal Filters                          | Moving Average Filter | myBlankSpaceMA   | string | ""    | \                                      | \ | =====<br>=====<br>== Moving Average Filter ==<br>=====<br>===== \      | \ |

|    |                |                       |                 |                         |                     |                              |                                                                                |                                                                        |  |
|----|----------------|-----------------------|-----------------|-------------------------|---------------------|------------------------------|--------------------------------------------------------------------------------|------------------------------------------------------------------------|--|
| 27 | Signal Filters | Moving Average Filter | AtivarFiltroMA  | bool                    | false               | Enable Moving Average Filter | —                                                                              | Use within its declared section and validate the complete combination. |  |
| 28 | Signal Filters | Moving Average Filter | MA_TimeFrame    | ENUM_ALLOWED_TIMEFRAMES | M1                  | MA Timeframe                 | M1, M5, M15, M30, H1, H4, D1, W1                                               | Use within its declared section and validate the complete combination. |  |
| 29 | Signal Filters | Moving Average Filter | MA_Period       | int                     | 200                 | MA Period                    | —                                                                              | Use within its declared section and validate the complete combination. |  |
| 30 | Signal Filters | Moving Average Filter | MA_Method       | ENUM_MA_METHOD          | MODE_EMA            | MA Method                    | —                                                                              | Use within its declared section and validate the complete combination. |  |
| 31 | Signal Filters | Moving Average Filter | MA_AppliedPrice | ENUM_APPLIED_PRICE      | PRICE_CLOSE         | Applied Price                | —                                                                              | Use within its declared section and validate the complete combination. |  |
| 32 | Signal Filters | Moving Average Filter | MetodoMA        | MetodoFiltroMA          | MA_PrecoEInclinacao | Price and Slope Rule         | MA_ApenasPreco, MA_ApenasInclinacao, MA_PrecoEInclinacao, MA_PrecoOuInclinacao | Use within its declared section and validate the complete combination. |  |

|    |                |                       |                   |                         |              |                                  |                                  |                                                                        |   |
|----|----------------|-----------------------|-------------------|-------------------------|--------------|----------------------------------|----------------------------------|------------------------------------------------------------------------|---|
| 33 | Signal Filters | Moving Average Filter | SentidoMA         | SentidoFilterMA         | MA_Tendencia | Trend or Reversal Direction      | MA_Tendencia, MA_Reversao        | Use within its declared section and validate the complete combination. |   |
| 34 | Signal Filters | Moving Average Filter | MA_Slope Lookback | int                     | 3            | Slope Lookback Bars              | —                                | Use within its declared section and validate the complete combination. |   |
| 35 | Signal Filters | ADX Filter            | myBlankSpaceMA1   | string                  | ""           | \                                | \                                | =====<br>=====<br>=====<br>ADX Filter<br>=====<br>=====<br>= \         | \ |
| 36 | Signal Filters | ADX Filter            | AtivarFilterADX   | bool                    | false        | Enable ADX Trend Strength Filter | —                                | Use within its declared section and validate the complete combination. |   |
| 37 | Signal Filters | ADX Filter            | ADX_Time Frame    | ENUM_ALLOWED_TIMEFRAMES | M1           | ADX Timeframe                    | M1, M5, M15, M30, H1, H4, D1, W1 | Use within its declared section and validate the complete combination. |   |
| 38 | Signal Filters | ADX Filter            | ADX_Period        | int                     | 14           | ADX Period                       | —                                | Use within its declared section and validate the complete combination. |   |

|    |                |                   |                        |                      |                 |                                     |                                         |                                                                           |   |
|----|----------------|-------------------|------------------------|----------------------|-----------------|-------------------------------------|-----------------------------------------|---------------------------------------------------------------------------|---|
| 39 | Signal Filters | ADX Filter        | ADX_Limit              | double               | 25              | Minimum ADX Value                   | —                                       | Use within its declared section and validate the complete combination.    |   |
| 40 | Signal Filters | ADX Filter        | MetodoADX              | MetodoFiltroADX      | ADX_ApenasForca | Strength or Strength Plus Direction | ADX_ApenasForca, ADX_ForceMaisDirecaoDI | Use within its declared section and validate the complete combination.    |   |
| 41 | Signal Filters | Volatility Filter | myBlankSpaceVolatility | string               | ""              | \                                   | \                                       | =====<br>=====<br>=====<br>Volatility Filter ===<br>=====<br>=====<br>= \ | \ |
| 42 | Signal Filters | Volatility Filter | EntradaATR             | bool                 | false           | Enable ATR Volatility Filter        | —                                       | Use within its declared section and validate the complete combination.    |   |
| 43 | Signal Filters | Volatility Filter | VolatilityFilter       | ENUM_VOLATILITY_MODE | VOL_HIGH        | Trade Volatility Condition          | VOL_LOW, VOL_HIGH                       | Use within its declared section and validate the complete combination.    |   |
| 44 | Signal Filters | News Filter       | myBlankSpaceNews       | string               | ""              | \                                   | \                                       | =====<br>=====<br>=====<br>News Filter ===<br>=====<br>=====<br>==== \    | \ |

|    |                |             |                        |        |       |                                                             |   |                                                                                                     |  |
|----|----------------|-------------|------------------------|--------|-------|-------------------------------------------------------------|---|-----------------------------------------------------------------------------------------------------|--|
| 45 | Signal Filters | News Filter | AtivarFiltroNoticias   | bool   | false | Enable News Filter                                          | — | Live calendar errors block new entries; backtests require the exported CSV under Common \ \ Files.  |  |
| 46 | Signal Filters | News Filter | NewsSomenteAltoImpacto | bool   | false | High Impact Only                                            | — | Use within its declared section and validate the complete combination.                              |  |
| 47 | Signal Filters | News Filter | NewsMinutosAntes       | int    | 15    | Minutes Blocked Before Event                                | — | Use within its declared section and validate the complete combination.                              |  |
| 48 | Signal Filters | News Filter | NewsMinutosDepois      | int    | 15    | Minutes Blocked After Event                                 | — | Use within its declared section and validate the complete combination.                              |  |
| 49 | Signal Filters | News Filter | NewsMoedasManual       | string | ""    | Manual Currencies (e.g. "USD ,EUR"); empty = auto by symbol | — | When non-empty, overrides automatic currency extraction; required for most suffixes/non-FX symbols. |  |

|    |                 |              |                     |                  |                        |                                                |                                                       |                                                                                                        |   |
|----|-----------------|--------------|---------------------|------------------|------------------------|------------------------------------------------|-------------------------------------------------------|--------------------------------------------------------------------------------------------------------|---|
| 50 | Signal Filters  | News Filter  | NewsCSVFile         | string           | "WhiteRabbit_News.csv" | Common \ \ Files CSV for Backtests             | —                                                     | Semicolon CSV in Common \ \ Files: date time;currency;importance;event_name, using broker-server time. |   |
| 51 | Exit Management | —            | AtivarBreakeven     | bool             | true                   | Enable Breakeven                               | —                                                     | Use within its declared section and validate the complete combination.                                 |   |
| 52 | Exit Management | —            | Breakeven Distancia | double           | 1.0                    | Breakeven Distance (SL or ATR Stop Multiplier) | —                                                     | Use within its declared section and validate the complete combination.                                 |   |
| 53 | Exit Management | ATR Trailing | myBlankSpace46      | string           | ""                     | \                                              | \                                                     | =====<br>=====<br>=====<br>ATR Trailing ==<br>=====<br>=====<br>===== \                                | \ |
| 54 | Exit Management | ATR Trailing | AtivarTrail ATR     | bool             | false                  | Enable ATR Trailing Stop                       | —                                                     | Use within its declared section and validate the complete combination.                                 |   |
| 55 | Exit Management | ATR Trailing | MetodoDe Calculo    | Candlestick type | CandleClose            | Trailing Price Source                          | CandleOpen, CandleClose, CandleHigh, CandleLow, Preco | Use within its declared section and validate the complete combination.                                 |   |

|    |                        |               |                             |                         |                                |                                             |                                                                                     |                                                                                 |   |
|----|------------------------|---------------|-----------------------------|-------------------------|--------------------------------|---------------------------------------------|-------------------------------------------------------------------------------------|---------------------------------------------------------------------------------|---|
| 56 | Exit Management        | ATR Trailing  | TrailVela                   | int                     | 0                              | Trailing Candle                             | —                                                                                   | Use within its declared section and validate the complete combination.          |   |
| 57 | Exit Management        | ATR Trailing  | Trail                       | double                  | 3                              | Trail                                       | —                                                                                   | Use within its declared section and validate the complete combination.          |   |
| 58 | Exit Management        | Reversal Exit | myBlankSpace10              | string                  | ""                             | \                                           | \                                                                                   | =====<br>=====<br>=====<br>Reversal Exit =====<br>=====<br>=====<br>== \        | \ |
| 59 | Exit Management        | Reversal Exit | ReversalExitMode            | ENUM_REVERSAL_EXIT_MODE | ReversalExit_OnIndicatorSignal | Declared at source line 319.                | ReversalExit_Disabled, ReversalExit_OnOppositeOrder, ReversalExit_OnIndicatorSignal | OnOppositeOrder requires a hedging account, both sides and grid disabled.       |   |
| 60 | Exit Management        | Reversal Exit | ReversalExitUseEntryFilters | bool                    | false                          | Apply entry filters to indicator exits      | —                                                                                   | False uses the raw opposite indicator signal; true also requires entry filters. |   |
| 61 | Risk and Position Size | —             | TradeCapitalPercentage      | double                  | 100                            | Percentage of Total Capital Allocated to EA | —                                                                                   | Allocation must be positive and no greater than the whole EA capital base.      |   |

|    |                        |                  |                       |                         |                       |                                                                                                     |                                                                                            |                                                                                 |   |
|----|------------------------|------------------|-----------------------|-------------------------|-----------------------|-----------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------|---|
| 62 | Risk and Position Size | —                | PositionSizeMode      | ENUM_POSITION_SIZE_MODE | PositionSize_FixedLot | Declared at source line 351.                                                                        | PositionSize_Percentage, PositionSize_Monetary, PositionSize_FixedLot, PositionSize_FixedR | Exactly one model is active; compatibility depends on stop and grid selections. |   |
| 63 | Risk and Position Size | —                | PositionSizeValue     | double                  | 0.01                  | Percentage=% risk; Monetary=currency per 1.00 lot; Fixed Lot=lots; Fixed R=% of base capital per 1R | —                                                                                          | Meaning changes with PositionSizeMode; never compare raw values across modes.   |   |
| 64 | Risk and Position Size | Fixed-R Controls | myBlankSpaceRF        | string                  | ""                    | \                                                                                                   | \                                                                                          | =====<br>=====<br>====<br>Fixed-R Controls =<br>=====<br>=====<br>==== \        | \ |
| 65 | Risk and Position Size | Fixed-R Controls | CapitalBaseR          | double                  | 0                     | Base Capital for 1R (0 = balance at OnInit)                                                         | —                                                                                          | Zero captures balance at initialization; Fixed-R only.                          |   |
| 66 | Risk and Position Size | Fixed-R Controls | MaxRiskTradeR         | double                  | 0                     | Maximum Risk per Trade in R (0 = no cap)                                                            | —                                                                                          | Zero disables this additional Fixed-R cap.                                      |   |
| 67 | Risk and Position Size | Daily Loss Limit | myBlankSpaceDL        | string                  | ""                    | \                                                                                                   | \                                                                                          | =====<br>=====<br>====<br>Daily Loss Limit ===<br>=====<br>=====<br>== \        | \ |
| 68 | Risk and Position Size | Daily Loss Limit | DailyLossLimitPercent | double                  | 0                     | Maximum Daily Loss Percentage (0 = disabled)                                                        | —                                                                                          | Zero disables the daily limit; use a value below a total account loss.          |   |



|    |                        |                          |                            |                    |               |                                                                  |                                                         |                                                                                                  |   |
|----|------------------------|--------------------------|----------------------------|--------------------|---------------|------------------------------------------------------------------|---------------------------------------------------------|--------------------------------------------------------------------------------------------------|---|
| 69 | Risk and Position Size | Equity/Margin Protection | myBlankSpaceRiskProtection | string             | ""            | \                                                                | \                                                       | =====<br>=====<br>Equity/Margin Protection<br>=====<br>=====<br>= \                              | \ |
| 70 | Risk and Position Size | Equity/Margin Protection | MaxEquity Drawdown Percent | double             | 30.0          | Maximum EA drawdown before closing positions (0 = disabled)      | —                                                       | Zero disables the EA equity stop.                                                                |   |
| 71 | Risk and Position Size | Equity/Margin Protection | MinFreeMarginPercent       | double             | 50.0          | Minimum free margin to preserve after a new entry (0 = disabled) | —                                                       | Zero disables the post-entry free-margin reserve.                                                |   |
| 72 | Grid and Recovery      | —                        | Recovery Mode              | ENUM_RECOVERY_MODE | Recovery_None | Declared at source line 368.                                     | Recovery_None, Recovery_Martingale, Recovery_D'Alembert | None, Martingale or D'Alembert are mutually exclusive.                                           |   |
| 73 | Grid and Recovery      | Recovery Target          | myBlankSpace457            | string             | ""            | \                                                                | \                                                       | =====<br>=====<br>=====<br>Recovery Target ==<br>=====<br>=====<br>== \                          | \ |
| 74 | Grid and Recovery      | Recovery Target          | Multiplicador              | double             | 1             | Martingale or Grid Target Profit Multiplier                      | —                                                       | Recovery/grid target multiplier; validate a value greater than one where escalation is intended. |   |
| 75 | Grid and Recovery      | Martingale Limits        | myBlankSpace16             | string             | ""            | \                                                                | \                                                       | =====<br>=====<br>=====<br>Martingale Limits ==<br>=====<br>=====<br>== \                        | \ |

|    |                   |                     |                    |                |               |                                                              |                                                        |                                                                                                                             |   |
|----|-------------------|---------------------|--------------------|----------------|---------------|--------------------------------------------------------------|--------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------|---|
| 76 | Grid and Recovery | Martingale Limits   | MaxMartingaleSteps | int            | 0             | Consecutive Losses Before Reset (0 = no limit)               | —                                                      | Zero means no step limit; exceeding a positive limit hard-resets the old deficit and forces the next order to the base lot. |   |
| 77 | Grid and Recovery | Martingale Limits   | MaxMartingaleLot   | double         | 0.0           | Maximum Martingale or D'Alembert Lot (0 = broker limit only) | —                                                      | Zero means broker maximum only.                                                                                             |   |
| 78 | Grid and Recovery | D'Alembert Settings | myBlankSpace_dal   | string         | ""            | \                                                            | \                                                      | =====<br>=====<br>=== D'Alembert Settings =<br>=====<br>=====<br>=== \                                                      | \ |
| 79 | Grid and Recovery | D'Alembert Settings | D'AlembertStep     | double         | 0.01          | Lot Increment per Loss for D'Alembert                        | —                                                      | Must be positive; supported with Fixed Lot and grid disabled.                                                               |   |
| 80 | Grid and Recovery | Grid Settings       | myBlankSpace17     | string         | ""            | \                                                            | \                                                      | =====<br>=====<br>=====<br>Grid Settings =<br>=====<br>=====<br>===== \                                                     | \ |
| 81 | Grid and Recovery | Grid Settings       | GridMode           | ENUM_GRID_MODE | Grid_Disabled | Declared at source line 385.                                 | Grid_Disabled, Grid_SeparateProfit, Grid_UnifiedProfit | Supported with Monetary or Fixed Lot sizing, Recovery_None and a hedging account; targets are frozen per cycle.             |   |

|    |                   |               |                     |        |       |                                             |   |                                                                                  |   |
|----|-------------------|---------------|---------------------|--------|-------|---------------------------------------------|---|----------------------------------------------------------------------------------|---|
| 82 | Grid and Recovery | Grid Settings | Use ATR Grid        | bool   | false | Use ATR Only as Grid Signal                 | — | Research switch; require an existing basket anchor before adding a grid leg.     |   |
| 83 | Grid and Recovery | Grid Settings | ATR Distance Minima | double | 2     | ATR Distance Multiplier for Next Grid Order | — | Positive ATR-distance multiplier between grid entries.                           |   |
| 84 | Trading Schedule  | Trading Hours | Trading Hours       | string | ""    | \                                           | \ | =====<br>=====<br>=====<br>Trading Hours ===<br>=====<br>=====<br>=== \          | \ |
| 85 | Trading Schedule  | Trading Hours | Trading Hours       | bool   | false | Close Positions Outside Trading Hours       | — | When enabled, positions are closed whenever server time is outside the interval. |   |
| 86 | Trading Schedule  | Trading Hours | TOD_From_Hour       | int    | 00    | Trading Start Hour                          | — | Use within its declared section and validate the complete combination.           |   |
| 87 | Trading Schedule  | Trading Hours | TOD_From_Min        | int    | 00    | Trading Start Minute                        | — | Use within its declared section and validate the complete combination.           |   |

|    |                  |               |                         |        |      |                            |   |                                                                         |   |
|----|------------------|---------------|-------------------------|--------|------|----------------------------|---|-------------------------------------------------------------------------|---|
| 88 | Trading Schedule | Trading Hours | TOD_To_Hour             | int    | 23   | Trading End Hour           | — | Use within its declared section and validate the complete combination.  |   |
| 89 | Trading Schedule | Trading Hours | TOD_To_Min              | int    | 55   | Trading End Minute         | — | Use within its declared section and validate the complete combination.  |   |
| 90 | Trading Schedule | Trading Days  | myBlankSpaceTradingDays | string | ""   | \                          | \ | =====<br>=====<br>=====<br>Trading Days ===<br>=====<br>=====<br>==== \ | \ |
| 91 | Trading Schedule | Trading Days  | TradeMonday             | bool   | true | Allow Trading on Monday    | — | Use within its declared section and validate the complete combination.  |   |
| 92 | Trading Schedule | Trading Days  | TradeTuesday            | bool   | true | Allow Trading on Tuesday   | — | Use within its declared section and validate the complete combination.  |   |
| 93 | Trading Schedule | Trading Days  | TradeWednesday          | bool   | true | Allow Trading on Wednesday | — | Use within its declared section and validate the complete combination.  |   |

|     |                  |                  |                       |        |       |                                       |   |                                                                                  |   |
|-----|------------------|------------------|-----------------------|--------|-------|---------------------------------------|---|----------------------------------------------------------------------------------|---|
| 94  | Trading Schedule | Trading Days     | TradeThursday         | bool   | true  | Allow Trading on Thursday             | — | Use within its declared section and validate the complete combination.           |   |
| 95  | Trading Schedule | Trading Days     | TradeFriday           | bool   | true  | Allow Trading on Friday               | — | Use within its declared section and validate the complete combination.           |   |
| 96  | Trading Schedule | Trading Days     | TradeSaturday         | bool   | false | Allow Trading on Saturday             | — | Explicit weekend permission; useful only when the broker symbol trades Saturday. |   |
| 97  | Trading Schedule | Trading Days     | TradeSunday           | bool   | false | Allow Trading on Sunday               | — | Explicit weekend permission; useful only when the broker symbol trades Sunday.   |   |
| 98  | General Settings | Market Execution | myBlankSpaceExecution | string | ""    | \                                     | \ | =====<br>=====<br>====<br>Market Execution<br>=====<br>=====<br>===== \          | \ |
| 99  | General Settings | Market Execution | MaxSpread             | double | 0     | Maximum Allowed Spread for New Trades | — | Zero disables the entry spread ceiling.                                          |   |
| 100 | General Settings | Market Execution | MaxSlippage           | int    | 10    | Slippage, ajustado no OnInit          | — | Use within its declared section and validate the complete combination.           |   |

|     |                  |                        |                       |        |        |                                     |   |                                                                                                            |   |
|-----|------------------|------------------------|-----------------------|--------|--------|-------------------------------------|---|------------------------------------------------------------------------------------------------------------|---|
| 101 | General Settings | Position Exposure      | myBlankSpaceExposure  | string | ""     | \                                   | \ | =====<br>=====<br>=====<br>Position Exposure<br>=====<br>=====<br>==== \                                   | \ |
| 102 | General Settings | Position Exposure      | MaxLongTrades         | int    | 1      | Maximum Simultaneous BUY Positions  | — | Zero disables BUY entries; grid sides require zero or at least two, while Martingale permits at most one.  |   |
| 103 | General Settings | Position Exposure      | MaxShort Trades       | int    | 1      | Maximum Simultaneous SELL Positions | — | Zero disables SELL entries; grid sides require zero or at least two, while Martingale permits at most one. |   |
| 104 | General Settings | Position Exposure      | Hedging               | bool   | false  | Allow Hedging                       | — | Does not change the account type; the real MT5 account must also support hedging.                          |   |
| 105 | General Settings | Identity and Interface | myBlankSpaceInterface | string | ""     | \                                   | \ | =====<br>=====<br>= Identity and Interface<br>=====<br>=====<br>== \                                       | \ |
| 106 | General Settings | Identity and Interface | MagicNumber           | int    | 384457 | Magic Number                        | — | Must be unique for each independent strategy/symbol scope.                                                 |   |

|     |                  |                        |                          |                         |                   |                                                                 |                                                                                                                                                                                                                      |                                                                                                            |   |
|-----|------------------|------------------------|--------------------------|-------------------------|-------------------|-----------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------|---|
| 107 | General Settings | Identity and Interface | ModificationSafetyPoints | int                     | 0                 | Optional extra distance beyond broker limits and current spread | —                                                                                                                                                                                                                    | Additional points beyond broker distance/spread constraints.                                               |   |
| 108 | General Settings | Identity and Interface | InterfaceLanguage        | ENUM_INTERFACE_LANGUAGE | Language_Auto     | Live chart interface language                                   | Language_Auto, Language_English, Language_Portuguese, Language_Russian, Language_Chinese, Language_Spanish, Language_Japanese, Language_German, Language_Korean, Language_French, Language_Italian, Language_Turkish | Eleven live/visual UI languages; Auto uses English in Tester and untranslated labels fall back to English. |   |
| 109 | General Settings | Chart Dashboard        | myBlankSpaceDashboard    | string                  | ""                | \                                                               | \                                                                                                                                                                                                                    | =====<br>=====<br>====<br>Chart Dashboard<br>=====<br>=====<br>==== \                                      | \ |
| 110 | General Settings | Chart Dashboard        | EnableChartDashboard     | bool                    | true              | Show visual P&L panel on live and visual tester charts          | —                                                                                                                                                                                                                    | Live/visual panel; periodic tick refresh is capped at once per second.                                     |   |
| 111 | General Settings | Chart Dashboard        | Dashboard Corner         | ENUM_BASE_CORNER        | CORNER_LEFT_UPPER | Dashboard chart corner                                          | —                                                                                                                                                                                                                    | Use within its declared section and validate the complete combination.                                     |   |

|     |                  |                 |                         |      |      |                                                             |   |                                                                        |  |
|-----|------------------|-----------------|-------------------------|------|------|-------------------------------------------------------------|---|------------------------------------------------------------------------|--|
| 112 | General Settings | Chart Dashboard | Dashboard OffsetX       | int  | 12   | Horizontal offset in pixels                                 | — | Use within its declared section and validate the complete combination. |  |
| 113 | General Settings | Chart Dashboard | Dashboard OffsetY       | int  | 24   | Vertical offset in pixels                                   | — | Use within its declared section and validate the complete combination. |  |
| 114 | General Settings | Chart Dashboard | ShowClosedDealLabels    | bool | true | Show monetary and percentage result at each closed trade    | — | Use within its declared section and validate the complete combination. |  |
| 115 | General Settings | Chart Dashboard | MaxVisibleDealLabels    | int  | 120  | Maximum closed-trade labels kept on chart                   | — | Use within its declared section and validate the complete combination. |  |
| 116 | General Settings | Chart Dashboard | ClosedDealLabelFontSize | int  | 10   | Closed-trade label font size                                | — | Use within its declared section and validate the complete combination. |  |
| 117 | General Settings | Chart Dashboard | ApplyEmbeddedChartTheme | bool | true | Apply the White Rabbit X clean chart style on every machine | — | Use within its declared section and validate the complete combination. |  |



|     |                    |             |                          |                 |              |                                         |                                                            |                                                                                            |   |
|-----|--------------------|-------------|--------------------------|-----------------|--------------|-----------------------------------------|------------------------------------------------------------|--------------------------------------------------------------------------------------------|---|
| 118 | Optimization (WFO) | —           | AtivarWFO                | bool            | false        | Enable WFO                              | —                                                          | Enables the internal WFO boundary logic; still requires an external chronological process. |   |
| 119 | Optimization (WFO) | —           | MetodoDeEntradaWFO       | WFO_TIPO        | Insample     | Optimization Mode                       | Insample, InSampleAndOutSample                             | Use within its declared section and validate the complete combination.                     |   |
| 120 | Optimization (WFO) | —           | input_end_date           | string          | "2025.02.28" | Backtest End Date (manual)              | —                                                          | Manual tester end date; keep synchronized with the selected test range.                    |   |
| 121 | Optimization (WFO) | WFO Periods | myBlankSpaceWFOPeriods   | string          | ""           | \                                       | \                                                          | =====<br>=====<br>=====<br>WFO Periods ==<br>=====<br>=====<br>===== \                     | \ |
| 122 | Optimization (WFO) | WFO Periods | wfo_windowSize           | WFO_TIME_PERIOD | Ano          | In-Sample Window Size                   | Nenhum, Ano, Semestre, Trimestre, Mes, Semana, Dia, Custom | Use within its declared section and validate the complete combination.                     |   |
| 123 | Optimization (WFO) | WFO Periods | wfo_customWindowSizeDays | int             | 0            | Custom Window Size in Days (0 = unused) | —                                                          | Use within its declared section and validate the complete combination.                     |   |

|     |                        |                               |                                   |                     |          |                                                     |                                                                                 |                                                                                                                               |   |
|-----|------------------------|-------------------------------|-----------------------------------|---------------------|----------|-----------------------------------------------------|---------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------|---|
| 124 | Optimizati<br>on (WFO) | WFO<br>Periods                | wfo_step<br>Size                  | WFO_TIM<br>E_PERIOD | Semestre | Out-of-Sa<br>mple Step<br>Size                      | Nenhum,<br>Ano,<br>Semestre,<br>Trimestre,<br>Mes,<br>Semana,<br>Dia,<br>Custom | Use within<br>its<br>declared<br>section<br>and<br>validate<br>the<br>complete<br>combinati<br>on.                            |   |
| 125 | Optimizati<br>on (WFO) | WFO<br>Periods                | wfo_cust<br>omStepSiz<br>ePercent | int                 | 0        | Custom<br>Step Size<br>in Days or<br>Percentag<br>e | —                                                                               | Custom<br>step: posit<br>ive=perce<br>ntage of<br>IS; negativ<br>e=fixed<br>number of<br>OOS days<br>(for<br>example<br>-61). |   |
| 126 | Optimizati<br>on (WFO) | Optimizati<br>on<br>Criterion | myBlankS<br>pace4447              | string              | ""       | \                                                   | \                                                                               | =====<br>=====<br>= Optimiz<br>ation<br>Criterion =<br>=====<br>=====<br>= \                                                  | \ |

|     |                    |                        |                 |                   |                                    |                             |                                                                                                                                                                                                                                                                                                                                                                                                                           |                                                                                     |  |
|-----|--------------------|------------------------|-----------------|-------------------|------------------------------------|-----------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------|--|
| 127 | Optimization (WFO) | Optimization Criterion | selectedFormula | CustomFormulaType | Formula_ProfitPerTradeAdjustedByDD | Custom Optimization Formula | Formula_None, Formula_GridSurvivalScore, Formula_Profit, Formula_ProfitWinTradeDD, Formula_EfficiencyRelativeToDeposit, Formula_AdjustedEfficiencyForGrid, Formula_ProfitRelativeToDDAndDeposit, Formula_ProfitPerTradeAdjustedByDD, Formula_SharpeAdjustedByDD, Formula_PessimisticProfit, Formula_ResilienceToDrawdown, Formula_ReturnUniformity, Formula_SystemRobustness, Formula_LevainCompositeScore, Formula_SomaR | Optimization on criterion only; inspect stability and OOS results before selection. |  |
|-----|--------------------|------------------------|-----------------|-------------------|------------------------------------|-----------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------|--|

**EA SHA-256:** D85A30A0836A9BE75F6DFC55868BDC664EE1FC7F5DD0840C029DEB0EF8AC8973 **EA**  
**version:** 1.12