Oracle® Solaris 11.3 Tunable Parameters Reference Manual



Oracle Solaris 11.3 Tunable Parameters Reference Manual

#### Part No: E54818

Copyright © 2000, 2016, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

#### **Documentation Accessibility**

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

#### Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

#### Référence: E54818

Copyright © 2000, 2016, Oracle et/ou ses affiliés. Tous droits réservés.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf stipulation expresse de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, accorder de licence, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est livré sous licence au Gouvernement des Etats-Unis, ou à quiconque qui aurait souscrit la licence de ce logiciel pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer des dommages corporels. Si vous utilisez ce logiciel ou matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour ce type d'applications.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Xeon sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Opteron, le logo AMD et le logo AMD Opteron sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée d'The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers, sauf mention contraire stipulée dans un contrat entre vous et Oracle. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation, sauf mention contraire stipulée dans un contrat entre vous et Oracle.

#### Accessibilité de la documentation

Pour plus d'informations sur l'engagement d'Oracle pour l'accessibilité à la documentation, visitez le site Web Oracle Accessibility Program, à l'adresse http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

#### Accès aux services de support Oracle

Les clients Oracle qui ont souscrit un contrat de support ont accès au support électronique via My Oracle Support. Pour plus d'informations, visitez le site http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info ou le site http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs si vous êtes malentendant.

# Contents

U	sing This Documentation	13
1	Overview of Orocle Salarie System Tuning	1.
_	Overview of Oracle Solaris System Tuning	
	Tuning an Oracle Solaris System	
	Tuning Format of Tunable Parameters Descriptions	
	Tuning the Oracle Solaris Kernel	
	/etc/system File and the /etc/system.d Directory	
	kmdb Command	
	mdb Command	
	Special Oracle Solaris tune and var Structures	
	Viewing Oracle Solaris System Configuration Information	
	sysdef Command	21
	kstat Utility	21
2	Oracle Solaris Kernel Tunable Parameters	23
	General Kernel and Memory Parameters	24
	physmem	24
	default stksize	25
	lwp_default_stksize	
	logevent_max_q_sz	
	segkpsize	
	noexec user stack	28
	fsflush and Related Parameters	
	fsflush	
	tune t fsflushr	
	autoup	
	·	
	dopageflush	
	doiflush	
	Process-Sizing Parameters	33

maxusers	33
reserved_procs	34
pidmax	35
max_nprocs	36
maxuprc	36
ngroups_max	37
Paging-Related Parameters	38
lotsfree	39
desfree	40
minfree	41
throttlefree	42
pageout_reserve	43
pages_pp_maximum	44
tune_t_minarmem	
fastscan	
slowscan	
min_percent_cpu	47
handspreadpageshandspreadpages	
pages_before_pager	
maxpgio	
Swapping-Related Parameters	
swapfs_reserve	
swapfs minfree	
Kernel Memory Allocator	
kmem flags	
kmem stackinfo	
General Driver Parameters	
moddebug	53
ddi msix alloc limit	
Network Driver Parameters	
IP Protocol Parameters in the Kernel	55
igb Parameters	57
ixgbe Parameters	
General I/O Parameters	
maxphys	63
rlim fd max	
rlim fd cur	
General File System Parameters	65

	ncsize	65
	<pre>dnlc_dir_enable</pre>	66
	dnlc_dir_min_size	66
	dnlc_dir_max_size	67
	dnlc_dircache_percent	67
	TMPFS Parameters	68
	tmpfs:tmpfs_maxkmem	68
	<pre>tmpfs:tmpfs_minfree</pre>	69
	Pseudo Terminals	69
	pt_cnt	70
	pt_pctofmem	71
	pt_max_pty	72
	STREAMS Parameters	72
	nstrpush	72
	strmsgsz	73
	strctlsz	73
	System V Message Queues	74
	System V Semaphores	74
	System V Shared Memory	74
	segspt_minfree	75
	pr_segp_disable	75
	Scheduling	77
	disp_rechoose_interval	77
	Timers	78
	hires_tick	78
	timer_max	78
	SPARC: Platform Specific Parameters	79
	tsb_alloc_hiwater_factor	79
	default_tsb_size	80
	enable_tsb_rss_sizing	81
	tsb_rss_factor	81
	Locality Group Parameters	82
	lpg_alloc_prefer	82
	lgrp_mem_pset_aware	83
3	Oracle Solaris ZFS Tunable Parameters	85
•	Tuning ZFS Considerations	
	7FS Mamory Management Parameters	86

	user_reserve_hint_pct86
	zfs_arc_min 87
	zfs_arc_max 87
	ZFS File-Level Prefetch
	zfs_prefetch_disable88
	ZFS Device I/O Queue Depth
	zfs_vdev_max_pending89
	Tuning ZFS When Using Flash Storage
	Adding Flash Devices as ZFS Log or Cache Devices
	Ensuring Proper Cache Flush Behavior for Flash and NVRAM Storage
	Devices
	Tuning ZFS for Database Products
	Tuning ZFS for an Oracle Database
	Using ZFS with MySQL Considerations
4	NFS Tunable Parameters
	Tuning the NFS Environment
	NFS Module Parameters
	nfs:nfs3_pathconf_disable_cache 102
	nfs:nfs_allow_preepoch_time 102
	nfs:nfs_cots_timeo 103
	nfs:nfs3_cots_timeo
	nfs:nfs4_cots_timeo
	nfs:nfs_do_symlink_cache 105
	nfs:nfs3_do_symlink_cache106
	nfs:nfs_dynamic 106
	nfs:nfs3_dynamic 107
	nfs:nfs_lookup_neg_cache 108
	nfs:nfs3_lookup_neg_cache108
	nfs:nfs4_lookup_neg_cache109
	nfs:nfs_max_threads 110
	nfs:nfs3_max_threads 111
	nfs:nfs4 max threads
	nfs:nfs_nra 112
	nfs:nfs3 nra 113
	nfs:nrnode114
	nfs:nfs shrinkreaddir115
	nfs:nfs3_shrinkreaddir116
	<del>-</del>

	nfs:nfs_write_error_interval	116
	nfs:nfs_write_error_to_cons_only	117
	nfs:nfs_disable_rddir_cache	117
	nfs:nfs3_bsize	118
	nfs:nfs4_bsize	119
	nfs:nfs_async_clusters	120
	nfs:nfs3_async_clusters	121
	nfs:nfs4_async_clusters	121
	nfs:nfs_async_timeout	122
	nfs:nacache	123
	nfs:nfs3_jukebox_delay	124
	nfs:nfs3_max_transfer_size	125
	nfs:nfs4_max_transfer_size	126
	nfs:nfs3_max_transfer_size_clts	126
	nfs:nfs3_max_transfer_size_cots	127
	NFS-Related SMF Configuration Parameters	128
	server_authz_cache_refresh	128
	netgroup_refresh	128
	nfssrv Module Parameters	129
	nfssrv:nfs_portmon	129
	rpcmod Module Parameters	130
	rpcmod:clnt_max_conns	130
	rpcmod:clnt_idle_timeout	130
	rpcmod:svc_idle_timeout	131
	rpcmod:maxdupreqs	131
	rpcmod:cotsmaxdupreqs	132
5	Internet Protocol Suite Tunable Parameters	135
	Overview of Tuning IP Suite Parameters	135
	IP Suite Parameter Validation	136
	Internet Request for Comments	136
	IP Tunable Parameters	136
	_icmp_err_interval and _icmp_err_burst	136
	_respond_to_echo_broadcast and _respond_to_echo_multicast (IPv4 or	
	,	137
		137
	forwarding (IPv4 or IPv6)	
	ttl	138

	hoplimit (IPv6)	138
	_addrs_per_if	138
	hostmodel (IPv4 or IPv6)	139
	IP Tunable Parameters Related to Duplicate Address Detection	140
	IP Tunable Parameters With Additional Cautions	145
ГСР	Tunable Parameters	146
	tcp_cwnd_normal	146
	_deferred_ack_interval	147
	_local_dack_interval	147
	_deferred_acks_max	148
	_local_dacks_max	148
	_wscale_always	149
	_tstamp_always	149
		150
		150
	max_buf	150
	cwnd-max	151
	_slow_start_initial	151
	_local_slow_start_initial	152
	_slow_start_after_idle	152
	sack	152
	_rev_src_routes	153
	_time_wait_interval	153
	ecn	154
	_conn_req_max_q	155
	_conn_req_max_q0	155
	_conn_req_min	156
	rst sent rate enabled	156
	rst sent rate	157
	smallest anon port	157
	largest anon port	158
	TCP Parameters With Additional Cautions	158
UDP	Tunable Parameters	162
		162
		162
		163
		163
		164

	IPQoS Tunable Parameter	164
	_policy_mask	164
	SCTP Tunable Parameters	165
	_max_init_retr	165
	_pa_max_retr	165
	_pp_max_retr	166
	_cwnd_max	166
	_ipv4_ttl	167
	_ipv6_hoplimit	167
	_heartbeat_interval	168
	_new_secret_interval	168
	_initial_mtu	168
	_deferred_ack_interval	169
	_ignore_path_mtu	169
	_initial_ssthresh	169
		170
	_xmit_lowat	170
		170
		171
	_rto_min	171
	_rto_max	172
	_rto_initial	172
	_cookie_life	172
	_max_in_streams	173
	_initial_out_streams	173
	_shutack_wait_bound	173
	_maxburst	174
	_addip_enabled	174
	_prsctp_enabled	174
		175
		175
	Per-Route Metrics	176
6	System Facility Parameters	177
	System Default Parameters	177
	autofs	177
	cron	178
	devfsadm	178

	dhcpagent $1$	78
	fs	78
	ftp	78
	inetinit	79
	init 1	79
	ipsec	79
	kbd	79
	keyserv 1	80
	login	80
	mpathd	80
	nfs	81
	nfslogd 1	81
	nss	81
	passwd	81
	su	81
	syslog	82
	tar	82
	telnetd 1	82
	utmpd	82
A S	System Check Script 1	83
	Confirming Flush Behavior on the System	83
Inde	ay 1	85

# **Using This Documentation**

- Overview Provides reference information about Oracle Solaris OS kernel and network tunable parameters. This manual does not provide tunable parameter information about desktop systems or Java environments.
- Audience System administrators who might need to change kernel tunable parameters in certain situations.
- **Required knowledge** Oracle Solaris or UNIX system administration experience and general file system administration experience.

# **Product Documentation Library**

Documentation and resources for this product and related products are available at http://www.oracle.com/pls/topic/lookup?ctx=E53394.

# **Feedback**

Provide feedback about this documentation at http://www.oracle.com/goto/docfeedback.

# · · · CHAPTER 1

# Overview of Oracle Solaris System Tuning

This section provides overview information about the format of the tuning information in this manual. This section also describes the different ways to tune an Oracle Solaris system.

- "Tuning an Oracle Solaris System" on page 15
- "Tuning Format of Tunable Parameters Descriptions" on page 16
- "Tuning the Oracle Solaris Kernel" on page 17
- "Special Oracle Solaris tune and var Structures" on page 20
- "Viewing Oracle Solaris System Configuration Information" on page 21
- "kstat Utility" on page 21

# **Tuning an Oracle Solaris System**

As an operating system, Oracle Solaris adjusts easily to system load and thus requires minimal tuning. However, in certain cases, tuning might be necessary. This book provides details about the officially supported tuning options available for Oracle Solaris.

The Oracle Solaris kernel is composed of a core portion, which is always loaded, and a number of loadable modules that are loaded as these modules are being referenced. Many kernel parameters listed in this guide are core parameters. However, a few parameters belong to loadable modules.

Note that to improve performance, tuning system parameters most often is the least effective method to use. Improving and tuning the application is a better and more effective approach. Moreover, adding more physical memory and balancing disk I/O patterns can also increase performance. Only in a few rare cases does changing system parameters provide substantial benefits to performance.

Remember that one system's /etc/system settings might not be applicable, either wholly or in part, to another system's environment. Carefully consider the values in the file with respect to the environment in which they will be applied. Make sure that you understand the behavior of a system before attempting to apply changes to the system variables listed this book.

To tune an Oracle Solaris system, create an empty file. Provide the file with a company specific name and separate the components of the file name with a colon, for example, *MyCompany*: kernel:configurations. As a first step, add only those tunables that are required by in-house or third-party applications. After baseline testing has been established, evaluate system performance to determine if additional tunable settings are required.



**Caution -** The tunable parameters described in this book can and do change from one Oracle Solaris release to the next. Publication of these tunable parameters does not preclude changes to the tunable parameters and their descriptions without notice.

# **Tuning Format of Tunable Parameters Descriptions**

This section describes the format for tuning Oracle Solaris parameters.

Parameter The exact name that is typed in the /etc/system file, or found in the

/etc/default/facility file.

Some parameters use the naming convention *module:parameter* to indicate that the parameter belongs to a loadable module. For example, tmpfs:tmpfs\_maxkmem means that tmpfs\_maxkmem is a parameter of the

tmpfs module.

Description Briefly describes what the parameter does or controls.

Data Type Indicates the signed or unsigned short integer or long integer. A long

integer is twice the width in bits as an integer. For example, an unsigned

integer = 32 bits, an unsigned long integer = 64 bits.

Units (Optional) Describes the unit type.

Default Indicates the value that the system uses by default.

Range Specifies the possible range allowed by system validation or the bounds

of the data type.

■ MAXINT – A shorthand description for the maximum value of a

signed integer (2,147,483,647)

■ MAXUINT – A shorthand description for the maximum value of an

unsigned integer (4,294,967,295)

Dynamic? Indicates whether the parameter can by configured on a running

system with the mdb or kmdb debugger (Yes), or only during boot time

initialization (No).

Validation Checks that the system applies to the value of the variable either as specified in the /etc/system file or the default value, as well as when the validation is applied. **Implicit** (Optional) Provides unstated constraints that might exist on the parameter, especially in relation to other parameters. When to Change Explains why someone might want to change this value. Includes error messages or return codes. **Zone Configuration** Identifies whether the parameter can be set in a exclusive-IP zone or must be set in the global zone. None of the parameters can be set in shared-IP zones. Commitment Level Identifies the stability of the interface. Many of the parameters in this manual are still evolving and are classified as unstable. For more

information, see the attributes(5) man page.

# **Tuning the Oracle Solaris Kernel**

The following table describes the different ways tunable parameters can be applied.

Apply Tunable Parameters in These Ways	For More Information
Set the parameter in a configuration file in the /etc/system.d directory.	"/etc/system File and the /etc/system.d Directory" on page 17
Use the kernel debugger (kmdb).	"kmdb Command" on page 19
Use the modular debugger (mdb).	"mdb Command" on page 19
Use the ipadm command to set TCP/IP parameters.	Chapter 5, "Internet Protocol Suite Tunable Parameters"
Modify the /etc/default files.	Chapter 6, "System Facility Parameters"

# /etc/system File and the /etc/system.d Directory

The /etc/system file provides a static mechanism for adjusting the values of kernel parameters. Values specified in this file are read at boot time and are applied. Any changes that are made to the file are not applied to the operating system until the system is rebooted.

The /etc/system can be used by administrators to customize settings on a specific system for a specific purpose. However, the same file is also used by other ISV and IHV software for tuning purposes that are specific to the software. Oracle Solaris utilities also add or remove entries from the /etc/system file. To manage the changes to which the file is subjected from multiple sources, the /etc/system.d directory is provided to store files that tune specific parameters

for the ystem. This method enables parameter tuning on a ystem without directly manipulating the /etc/system file. The /etc/system remains the reference file for the configuration of a specific system. However, to revise a configuration, using a file in the /etc/system.d directory is the preferred method.

One pass is made to set all the values before the configuration parameters are calculated.

**Note -** Throughout this book, parameter settings refer to the /etc/system, which is the operative file for the implementation of specific configuration on a ystem. However, when revising parameters such as kernel tunables, the book assumes that the fine-tuning is accomplished through parameter files in the /etc/system.d directory.

#### **EXAMPLE 1** Setting a ZFS Parameter for a Specific System

The following entry sets the ZFS ARC maximum (zfs\_arc\_max) to 30 GB.

#### $set zfs:zfs_arc_max = 0x780000000$

Suppose that the name of your company is Widget, Inc. You would store this entry in the widget:zfs or similarly named file in the /etc/system.d directory. When the system is booted, all parameter configurations in /etc/system.d are added to the /etc/system file. The system is then configured according to the contents of /etc/system.

### **Recovering From an Incorrect Value**

You can recover from an incorrect value by using one of the following approaches:

### Resetting the Parameter in the /etc/system.d/file

Remove the defective parameter setting from your configuration file in the /etc/system.d directory. At boot time, the /etc/system file is updated with the previous configurations which are then reapplied to the system.

### **Using a Cloned Boot Environment**

Before you introduce system parameter changes, clone the boot environment first.

#### # beadm create BE-clonename

Then, if your current BE becomes unusable after applying changes to /etc/system, reboot the system. From the x86 GRUB menu or SPARC boot menu, select the BE clone. After booting completes, you can optionally activate the BE clone to become the default BE to be used in subsequent system boots.

### **Using File Copies**

Make a copy of the /etc/system file before updating it with new parameters from configuration files in the /etc/system.d directory so that you can easily recover from incorrect value. For example:

#### # cp /etc/system /etc/system.good

If a value specified in the configuration file in /etc/system.d causes the system to become unbootable, you can recover with the following command:

```
ok boot -a
```

This command causes the system to ask for the name of various files used in the boot process. Press the Return key to accept the default values until the name of the /etc/system file is requested. When the Name of system file [/etc/system]: prompt is displayed, type the name of the good /etc/system file or /dev/null:

```
Name of system file [/etc/system]: /etc/system.good
```

If /dev/null is specified, this path causes the system to attempt to read from /dev/null for its configuration information. Because this file is empty, the system uses the default values. After the system is booted, the /etc/system file can be corrected.

For more information on system recovery, see *Troubleshooting System Administration Issues in Oracle Solaris 11.3*.

### kmdb Command

kmdb is a interactive kernel debugger with the same general syntax as mdb. An advantage of interactive kernel debugger is that you can set breakpoints. When a breakpoint is reached, you can examine data or step through the execution of kernel code.

kmdb can be loaded and unloaded on demand. You do not have to reboot the system to perform interactive kernel debugging, as was the case with kadb.

For more information, see the kmdb(1) man page.

### mdb Command

The modular debugger, mdb, is unique among Oracle Solaris debuggers because it is easily extensible. A programming API is available that allows compilation of modules to perform desired tasks within the context of the debugger.

mdb also includes a number of desirable usability features, including command-line editing, command history, built-in output pager, syntax checking, and command pipelining. mdb is the recommended post-mortem debugger for the kernel.

For more information, see the mdb(1) man page.

### **EXAMPLE 2** Using mdb to Display Information

Display a high-level view of a system's memory usage. For example:

#### # mdb -k

Physical

> \$q

Loading modules: [ unix genunix specfs dtrace mac cpu.generic cpu\_ms.AuthenticAMD.15 uppc pcplusmp scsi\_vhci zfs mpt sd ip hook neti arp usba sockfs kssl qlc fctl stmf stmf\_sbd md lofs random idm fcp crypto cpc smbsrv nfs fcip sppp ufs logindmux ptm nsmb scu mpt sas pmcs emlxs ]

> ::memstat			
Page Summary	Pages	MB	%Tot
Kernel	160876	628	16%
ZFS File Data	303401	1185	30%
Anon	25335	98	2%
Exec and libs	1459	5	0%
Page cache	5083	19	1%
Free (cachelist)	6616	25	1%
Free (freelist)	510870	1995	50%
Total	1013640	3959	

1013639

For more information on using the modular debugger, see the *Oracle Solaris Modular Debugger Guide*.

When using either kmdb or mdb debugger, the module name prefix is not required. After a module is loaded, its symbols form a common name space with the core kernel symbols and any other previously loaded module symbols.

3959

# Special Oracle Solaris tune and var Structures

Oracle Solaris tunable parameters come in a variety of forms. The tune structure defined in the/usr/include/sys/tuneable.h file is the runtime representation of tune\_t\_fsflushr, tune\_t\_minarmem, and tune\_t\_flkrec. After the kernel is initialized, all references to these variables are found in the appropriate field of the tune structure.

The proper way to set parameters for this structure at boot time is to initialize the special parameter that corresponds to the desired field name. The system initialization process then loads these values into the tune structure.

A second structure into which various tunable parameters are placed is the var structure named v. You can find the definition of a var structure in the /usr/include/sys/var.h file. The runtime representation of variables such as autoup and bufhwm is stored here.

Do not change either the tune or v structure on a running system. Changing any field in these structures on a running system might cause the system to panic.

# **Viewing Oracle Solaris System Configuration Information**

Several tools are available to examine system configuration information. Some tools require superuser privilege. Other tools can be run by a non-privileged user. Every structure and data item can be examined with the kernel debugger by using mdb on a running system or by booting under kmdb.

For more information, see the mdb(1) or kadb(1M) man page.

# sysdef Command

The sysdef command provides the values of memory and process resource limits, and portions of the tune and v structures. For example, the sysdef "Tunable Parameters" section from a SPARC T3-4 system with 500 GB of memory is as follows:

```
2206203904
                maximum memory allowed in buffer cache (bufhwm)
65546
                maximum number of processes (v.v proc)
99
                maximum global priority in sys class (MAXCLSYSPRI)
65541
                maximum processes per user id (v.v maxup)
30
                auto update time limit in seconds (NAUTOUP)
25
                page stealing low water mark (GPGSLO)
1
                fsflush run rate (FSFLUSHR)
25
                minimum resident memory for avoiding deadlock (MINARMEM)
                minimum swapable memory for avoiding deadlock (MINASMEM)
```

For more information, see the sysdef(1M) man page.

# kstat Utility

kstats are data structures maintained by various kernel subsystems and drivers. They provide a mechanism for exporting data from the kernel to user programs without requiring that the

program read kernel memory or have superuser privilege. For more information, see the kstat(1M) or kstat(3KSTAT) man page.



# **Oracle Solaris Kernel Tunable Parameters**

This chapter describes most of the Oracle Solaris kernel tunable parameters.

- "General Kernel and Memory Parameters" on page 24
- "fsflush and Related Parameters" on page 29
- "Process-Sizing Parameters" on page 33
- "Paging-Related Parameters" on page 38
- "Swapping-Related Parameters" on page 49
- "Kernel Memory Allocator" on page 51
- "General Driver Parameters" on page 53
- "Network Driver Parameters" on page 55
- "General I/O Parameters" on page 62
- "General File System Parameters" on page 65
- "TMPFS Parameters" on page 68
- "Pseudo Terminals" on page 69
- "STREAMS Parameters" on page 72
- "System V Message Queues" on page 74
- "System V Semaphores" on page 74
- "System V Shared Memory" on page 74
- "Scheduling" on page 77
- "Timers" on page 78
- "Platform Specific Parameters" on page 79
- "Locality Group Parameters" on page 82

For other types of tunable parameters, refer to the following:

- Oracle Solaris ZFS tunables parameters Chapter 3, "Oracle Solaris ZFS Tunable Parameters"
- NFS tunable parameters Chapter 4, "NFS Tunable Parameters"
- Internet Protocol Suite tunable parameters Chapter 5, "Internet Protocol Suite Tunable Parameters"
- System facility tunable parameters Chapter 6, "System Facility Parameters"

**Note -** Most parameters are tuned by using the /etc/system file, as indicated in this document. However, for better practice, consider using a parameter file in the /etc/system.d directory instead when customizing parameters. See "/etc/system File and the /etc/system.d Directory" on page 17 for more details.

# **General Kernel and Memory Parameters**

This section describes general kernel parameters that are related to physical memory and stack configuration. For ZFS-related memory parameters, see Chapter 3, "Oracle Solaris ZFS Tunable Parameters".

### physmem

Description Modifies the system's configuration of the number of physical pages of

memory after the Oracle Solaris OS and firmware are accounted for.

Data Type Unsigned long

Default Number of usable pages of physical memory available on the system, not

counting the memory where the core kernel and data are stored

Range 1 to amount of physical memory on system

Units Pages

Dynamic? No

Validation None

When to Change Whenever you want to test the effect of running the system with less

physical memory. Because this parameter does *not* take into account the memory used by the core kernel and data, as well as various other data structures allocated early in the startup process, the value of physmem should be less than the actual number of pages that represent the smaller

amount of memory.

Commitment Level Unstable

### default\_stksize

Description Specifies the default stack size of all threads. No thread can

be created with a stack size smaller than default\_stksize. If default stksize is set, it overrides lwp default stksize. See also

"lwp default stksize" on page 26.

Data Type Integer

Default ■ 3 x PAGESIZE on SPARC systems with sun4u processors

■ 4 x PAGESIZE on SPARC systems with sun4v processors

■ 5 x PAGESIZE on x64 systems

Range Minimum is the default values:

3 x PAGESIZE on SPARC systems with sun4u processors

4 x PAGESIZE on SPARC systems with sun4v processors

■ 5 x PAGESIZE on x64 systems

Maximum is 32 times the default value.

Units Bytes in multiples of the value returned by the getpagesize parameter.

For more information, see the getpagesize(3C) man page.

Dynamic? Yes. Affects threads created after the variable is changed.

Validation Must be greater than or equal to 8192 and less than or equal to 262,144

(256 x 1024). Also must be a multiple of the system page size. If these

conditions are not met, the following message is displayed:

Illegal stack size, Using N

The value of N is the default value of default stksize.

When to Change When the system panics because it has run out of stack space. The best solution for this problem is to determine why the system is running out of

space and then make a correction.

Increasing the default stack size means that almost every kernel thread will have a larger stack, resulting in increased kernel memory consumption for no good reason. Generally, that space will be unused. The increased consumption means other resources that are competing for the same pool of memory will have the amount of space available to them reduced, possibly decreasing the system's ability to perform work. Among the side effects is a reduction in the number of threads that the kernel can create. This solution should be treated as no more than an

interim workaround until the root cause is remedied.

Commitment Level Unstable

# lwp\_default\_stksize

Description Specifies the default value of the stack size to be used when a kernel

thread is created, and when the calling routine does not provide an explicit size to be used. Any stack size that you specify is increased by a

one-page redzone.

Data Type Integer

Default SPARC stack size is 3 pages (3 x 8,192 = 24,576) + 8 KB

redzone

■ Default x64 stack size is 5 pages (5 x 4,096 = 20,480) + 4 KB

redzone

Range Minimum is the default values:

■ 3 x PAGESIZE on SPARC systems

■ 5 x PAGESIZE on x64 systems

Maximum is 32 times the default value.

Units Bytes in multiples of the value returned by the getpagesize parameter.

For more information, see the getpagesize(3C) man page.

Dynamic? Yes. Affects threads created after the variable is changed.

Validation Must be greater than or equal to 8192 and less than or equal to 262,144

(256 x 1024). Also must be a multiple of the system page size. If these

conditions are not met, the following message is displayed:

Illegal stack size, Using N

The value of N is the default value of  $lwp_default_stksize$ .

When to Change When the system panics because it has run out of stack space. The best

solution for this problem is to determine why the system is running out of  $% \left\{ 1\right\} =\left\{ 1\right\}$ 

space and then make a correction.

Increasing the default stack size means that almost every kernel thread will have a larger stack, resulting in increased kernel memory consumption for no good reason. Generally, that space will be unused. The increased consumption means other resources that are competing for the same pool of memory will have the amount of space available to them reduced, possibly decreasing the system's ability to perform work. Among the side effects is a reduction in the number of threads that the

kernel can create. This solution should be treated as no more than an interim workaround until the root cause is remedied.

Commitment Level Unstable

### logevent\_max\_q\_sz

Description Maximum number of system events allowed to be queued and waiting

for delivery to the syseventd daemon. Once the size of the system event queue reaches this limit, no other system events are allowed on the

queue.

Data Type Integer

Default 5000

Range 0 to MAXINT

Units System events

Dynamic? Yes

Validation The system event framework checks this value every time a system event

is generated by ddi log sysevent and sysevent post event.

For more information, see the  $\mbox{ddi} \mbox{log} \mbox{sysevent} (9F)$  and

sysevent\_post\_event(3SYSEVENT) man pages.

When to Change When error log messages indicate that a system event failed to be logged,

generated, or posted.

Commitment Level Unstable

# segkpsize

Description

Specifies the amount of kernel pageable memory available. This memory is used primarily for kernel thread stacks. Increasing this number allows either larger stacks for the same number of threads or more threads. Default system thread stack sizes are described in "lwp\_default\_stksize" on page 26.

- SPARC: This parameter can be modified in the /etc/system file.
- x64: This parameter can be only be modified as follows:
  - Boot under the kernel debugger

• Set a breakpoint at the beginning of the system startup process

Set the desired value

Data Type Unsigned long

Default 2 GB x the smaller result of nCPUs / 128 or the amount of physical

memory / 256 GB

Range 512 MB to 64 GB (SPARC)

200 MB to 8 GB (x64)

Units Pages

Dynamic? No

Value is compared to minimum and maximum sizes. If smaller than the

minimum or larger than the maximum, it is reset to 2 GB. A message to

that effect is displayed.

On SPARC systems, the segkpsize value cannot exceed twice the size of physical memory. On x64 systems, the value cannot exceed the size of

physical memory.

When to Change Required to support large numbers of processes on a system. The default

size allows creation of 32- KB stacks for 65,535 kernel threads. The size of a kernel stack in a 64-bit kernel is the same whether the process is a

32-bit process or a 64-bit process.

Commitment Level Unstable

# noexec\_user\_stack

**Note -** Although noexec\_user\_stack is still operational, this parameter is deprecated in this Oracle Solaris release. Use the nxheap and nxstack security extensions instead. You can control and configure Oracle Solaris extensions at the system level and at the process level with the sxadm command.

For procedures and examples that show the use of nxheap and nxstack, see "Protecting the Process Heap and Executable Stacks From Compromise" in *Securing Systems and Attached Devices in Oracle Solaris* 11.3.

For more information about the sxadm command, see the sxadm(1M) man page.

For guidelines to secure and harden Oracle Solaris, see *Oracle Solaris 11 Security and Hardening Guidelines*.

Description Enables the stack to be marked as nonexecutable, which helps make

buffer-overflow attacks more difficult.

An Oracle Solaris system running a 64-bit kernel makes the stacks of all 64-bit applications nonexecutable by default. Setting this parameter is necessary to make 32-bit applications nonexecutable. This parameter, together with noexec\_user\_stack\_log, can be set in the /etc/system.d file. See "Protecting the Process Heap and Executable Stacks From Compromise" in Securing Systems and Attached Devices in Oracle

Solaris 11.3

Data Type Signed integer

Default 0 (disabled)

Range 0 (disabled) or 1 (enabled)

Units Toggle (on/off)

Dynamic? Yes. Does not affect currently running processes, only processes created

after the value is set.

Validation None

When to Change Should be enabled at all times unless applications are deliberately placing

executable code on the stack without using mprotect to make the stack executable. For more information, see the mprotect(2) man page.

Commitment Level Unstable

# fsflush and Related Parameters

This section describes fsflush and related tunables.

### fsflush

The system daemon, fsflush, runs periodically to do three main tasks:

- 1. On every invocation, fsflush flushes dirty file system pages over a certain age to disk.
- 2. On every invocation, fsflush examines a portion of memory and causes modified pages to be written to their backing store. Pages are written if they are modified and if they do not meet one of the following conditions:
  - Pages are kernel page

- Pages are free
- Pages are locked
- Pages are associated with a swap device
- Pages are currently involved in an I/O operation

The net effect is to flush pages from files that are mapped with mmap with write permission and that have actually been changed.

Pages are flushed to backing store but left attached to the process using them. This will simplify page reclamation when the system runs low on memory by avoiding delay for writing the page to backing store before claiming it, if the page has not been modified since the flush.

3. fsflush writes file system metadata to disk. This write is done every *n*th invocation, where *n* is computed from various configuration variables. See "tune t fsflushr" on page 30 and "autoup" on page 31 for details.

The following features are configurable:

- Frequency of invocation (tune t fsflushr)
- Whether memory scanning is executed (dopageflush)
- Whether file system data flushing occurs (doiflush)
- The frequency with which file system data flushing occurs (autoup)

For most systems, memory scanning and file system metadata synchronizing are the dominant activities for fsflush. Depending on system usage, memory scanning can be of little use or consume too much CPU time.

# tune\_t\_fsflushr

Description Specifies the number of seconds between fsflush invocations

Data Type Signed integer

Default 1

Range 1 to MAXINT

Units Seconds

Dynamic? No

Validation If the value is less than or equal to zero, the value is reset to 1 and a

warning message is displayed. This check is done only at boot time.

When to Change See the autoup parameter.

Commitment Level Unstable

### autoup

Description

Along with tune\_t\_flushr, autoup controls the amount of memory examined for dirty pages in each invocation and frequency of file system synchronizing operations.

The value of autoup is also used to control whether a buffer is written out from the free list. Buffers marked with the B\_DELWRI flag (which identifies file content pages that have changed) are written out whenever the buffer has been on the list for longer than *autoup* seconds. Increasing the value of autoup keeps the buffers in memory for a longer time.

Data Type Signed integer

Default 30

Range 1 to MAXINT

Units Seconds

Dynamic? No

Validation If autoup is less than

If autoup is less than or equal to zero, it is reset to 30 and a warning message is displayed. This check is done only at boot time.

Implicit autoup should be an integer multiple of tune t fsflushr.

At a minimum, autoup should be at least 6 times the value of

 ${\sf tune\_t\_fsflushr.}\ If\ not,\ excessive\ amounts\ of\ memory\ are\ scanned$ 

each time fsflush is invoked.

The total system pages multiplied by tune\_t\_fsflushr should be greater than or equal to autoup to cause memory to be checked if dopageflush is

non-zero.

When to Change

Here are several potential situations for changing autoup, tune t fsflushr, or both:

- Systems with large amounts of memory In this case, increasing autoup reduces the amount of memory scanned in each invocation of fsflush.
- Systems with minimal memory demand Increasing both autoup and tune\_t\_fsflushr reduces the number of scans made. autoup should be increased also to maintain the current ratio of autoup / tune t fsflushr.

 Systems with large numbers of transient files (for example, mail servers or software build ystems) – If large numbers of files are created and then deleted, fsflush might unnecessarily write data pages for those files to disk.

Commitment Level Unstable

### dopageflush

Description Controls whether memory is examined for modified pages during

fsflush invocations. In each invocation of fsflush, the number of physical memory pages in the system is determined. This number might have changed because of a dynamic reconfiguration operation. Each invocation scans by using this algorithm: total number of pages x

tune\_t\_fsflushr / autoup pages

Data Type Signed integer

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Units Toggle (on/off)

Dynamic? Yes

Validation None

When to Change If the system page scanner rarely runs, which is indicated by a value of 0

in the sr column of vmstat output.

Commitment Level Unstable

### doiflush

Description Controls whether file system metadata syncs will be executed during

fsflush invocations. This synchronization is done every Nth invocation of fsflush where N= (autoup / tune\_t\_fsflushr). Because this algorithm is integer division, if tune\_t\_fsflushr is greater than autoup, a synchronization is done on every invocation of fsflush because the code checks to see if its iteration counter is greater than or equal to N. Note that N is computed once on invocation of fsflush. Later changes

to  $tune\_t\_fsflushr$  or autoup have no effect on the frequency of

synchronization operations.

Data Type Signed integer

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Units Toggle (on/off)

Dynamic? Yes

Validation None

When to Change When files are frequently modified over a period of time and the load

caused by the flushing perturbs system behavior.

Files whose existence, and therefore consistency of state, does not matter if the system reboots are better kept in a TMPFS file system (for example, /tmp). Inode traffic can be reduced on systems by using the mount -noatime option. This option eliminates inode updates when the

file is accessed.

For a system engaged in realtime processing, you might want to disable this option and use explicit application file synchronizing to achieve

consistency.

Commitment Level Unstable

# **Process-Sizing Parameters**

Several parameters (or variables) are used to control the number of processes that are available on the system and the number of processes that an individual user can create. The foundation parameter is maxusers. This parameter drives the values assigned to max\_nprocs and maxuprc.

### maxusers

Description Originally, maxusers defined the number of logged in users the system

could support. When a kernel was generated, various tables were sized based on this setting. Current Oracle Solaris releases do much of its sizing based on the amount of memory on the system. Thus, much of the past use of maxusers has changed. A number of subsystems that are still

derived from maxusers:

■ The maximum number of processes on the system

■ The number of quota structures held in the system

■ The size of the directory name look-up cache (DNLC)

Data Type Signed integer

Default Lesser of the amount of memory in MB or 2048, and the greater of that

value and nCPUs x 8

Range 1 to the greater of 2048 or nCPUs x 8, based on the size of physical

memory, if not set in the /etc/system file

1 to the greater of 4096 or the nCPUs x 8, if set in the /etc/system file

Units Users

Dynamic? No. After computation of dependent parameters is done, maxusers is

never referenced again.

Validation If the value is greater than the maximum allowed, it is reset to the

maximum. A message to that effect is displayed.

When to Change When the default number of user processes derived by the system is too

low. This situation is evident when the following message displays on the

system console:

out of processes

You might also change this parameter when the default number of processes is too high, as in these situations:

Database servers that have a lot of memory and relatively few

maxusers is reduced.

 If file servers have a lot of memory and few running processes, you might reduce this value. However, you should explicitly set the size

running processes can save system memory when the default value of

of the DNLC. See "ncsize" on page 65.

Commitment Level Unstable

# reserved\_procs

Description Specifies the number of system process slots to be reserved in the process

table for processes with a UID of root (0). For example, fsflush has a

UID of root (0).

Data Type Signed integer

Default 5

Range 5 to MAXINT

Units Processes

Dynamic? No. Not used after the initial parameter computation.

Validation Any /etc/system setting is honored.

Commitment Level Unstable

When to Change Consider increasing to 10 + the normal number of UID 0 (root) processes

on system. This setting provides some cushion should it be necessary to obtain a root shell when the system is otherwise unable to create user-

level processes.

### pidmax

Description Specifies the value of the largest possible process ID.

pidmax sets the value for the maxpid variable. Once maxpid is set, pidmax

is ignored. maxpid is used elsewhere in the kernel to determine the

maximum process ID and for validation checking.

Any attempts to set maxpid by adding an entry to the /etc/system file

have no effect.

Data Type Signed integer

Default 30,000

Range 5 to 999,999

Units Processes

Dynamic? No. Used only at boot time to set the value of pidmax.

Validation Yes. Value is compared to the value of reserved procs and 999,999.

If less than reserved procs or greater than 999,999, the value is set to

999,999.

Implicit max\_nprocs range checking ensures that max\_nprocs is always less than

or equal to this value.

When to Change Required to enable support for more than 30,000 processes on a system.

See also "max\_nprocs" on page 36.

Commitment Level Unstable

### max\_nprocs

Description Specifies the maximum number of processes that can be created on

a system. Includes system processes and user processes. Any value specified in /etc/system is used in the computation of maxuprc.

This value is also used in determining the size of several other system data structures. Other data structures where this parameter plays a role are as follows:

 Determining the size of the directory name lookup cache (if ncsize is not specified)

 Verifying that the amount of memory used by configured system V semaphores does not exceed system limits

Configuring Hardware Address Translation resources for x86 platforms

Data Type Signed integer

Default 10 + (16 x maxusers) if maxusers is set in the /etc/system file

The larger of 30,000 or  $10 + (128 \times number of CPUs)$ , if maxusers is not

set in the /etc/system file

Range 26 to value of maxpid

Dynamic? No

Validation Yes. If the value exceeds maxpid, it is set to maxpid.

When to Change Changing this parameter is one of the steps necessary to enable support

for more than 30,000 processes on a system.

Commitment Level Unstable

### maxuprc

Description Specifies the maximum number of processes that can be created on a

system by any one user.

Data Type Signed integer

Default max nprocs - reserved procs

Range 1 to max nprocs - reserved procs

Units Processes

Dynamic? No

Validation Yes. This value is compared to max nprocs - reserved procs and set to

the smaller of the two values.

When to Change When you want to specify a hard limit for the number of processes a user

can create that is less than the default value of however many processes the system can create. Attempting to exceed this limit generates the following warning messages on the console or in the messages file:

out of per-user processes for uid  ${\it N}$ 

Commitment Level Unstable

### ngroups\_max

Description Specifies the maximum number of supplemental groups per process.

Data Type Signed integer

Default 16

Range 0 to 1024

Units Groups

Dynamic? No

Validation Yes. If ngroups max is set to an invalid value, it is automatically reset to

the closest legal value. For example, if it is set to less than zero, it is reset

to 0. If it is set to greater than 1024, it is reset to 1024.

When to Change Review the following considerations if you are using NFS AUTH SYS

authentication and you want to increase the default ngroups\_max value:

 If ngroups\_max is set to 16 or if the NFS client's AUTH\_SYS credential that is provided has 15 or fewer groups, the client's group information is used. 2. If ngroups\_max is set to greater than 16 and the NFS client's AUTH\_SYS credential from the name server contains exactly 16 groups, the maximum allowed, the NFS server consults the name server and matches the client's UID to a user name. Then, the name server computes a list of groups to which the user belongs.

Commitment Level Unstable

# **Paging-Related Parameters**

The Oracle Solaris OS uses a demand paged virtual memory system. As the system runs, pages are brought into memory as needed. When memory becomes occupied above a certain threshold and demand for memory continues, paging begins. Paging goes through several levels that are controlled by certain parameters.

The general paging algorithm is as follows:

- A memory deficit is noticed. The page scanner thread runs and begins to walk through memory. A two-step algorithm is employed:
  - 1. A page is marked as unused.
  - 2. If still unused after a time interval, the page is viewed as a subject for reclaim.

If the page has been modified, a request is made to the pageout thread to schedule the page for I/O. Also, the page scanner continues looking at memory. Pageout causes the page to be written to the page's backing store and placed on the free list. When the page scanner scans memory, no distinction is made as to the origin of the page. The page might have come from a data file, or it might represent a page from an executable's text, data, or stack.

As memory pressure on the system increases, the algorithm becomes more aggressive in the pages it will consider as candidates for reclamation and in how frequently the paging algorithm runs. (For more information, see "fastscan" on page 45 and "slowscan" on page 46.) As available memory falls between the range lotsfree and minfree, the system linearly increases the amount of memory scanned in each invocation of the pageout thread from the value specified by slowscan to the value specified by fastscan. The system uses the desfree parameter to control a number of decisions about resource usage and behavior.

The system initially constrains itself to use no more than 4 percent of one CPU for pageout operations. As memory pressure increases, the amount of CPU time consumed in support of pageout operations linearly increases until a maximum of 80 percent of one CPU is consumed. The algorithm looks through some amount of memory between slowscan and fastscan, then stops when one of the following occurs:

• Enough pages have been found to satisfy the memory shortfall.

- The planned number of pages have been looked at.
- Too much time has elapsed.

If a memory shortfall is still present when pageout finishes its scan, another scan is scheduled for 1/4 second in the future.

The configuration mechanism of the paging subsystem was changed. Instead of depending on a set of predefined values for fastscan, slowscan, and handspreadpages, the system determines the appropriate settings for these parameters at boot time. Setting any of these parameters in the /etc/system file can cause the system to use less than optimal values.



**Caution -** Remove all tuning of the VM system from the /etc/system file. Run with the default settings and determine if it is necessary to adjust any of these parameters. Do not set either cachefree or priority\_paging.

Dynamic reconfiguration (DR) for CPU and memory is supported. A system in a DR operation that involves the addition or deletion of memory recalculates values for the relevant parameters, unless the parameter has been explicitly set in /etc/system. In that case, the value specified in /etc/system is used, unless a constraint on the value of the variable has been violated. In this case, the value is reset.

#### lotsfree

Description Serves as the initial trigger for system paging to begin. When this

threshold is crossed, the page scanner wakes up to begin looking for

memory pages to reclaim.

Data Type Unsigned long

Default The greater of 1/64th of physical memory or 512 KB

Range The minimum value is 512 KB or 1/64th of physical memory,

whichever is greater, expressed as pages using the page size returned by getpagesize. For more information, see the getpagesize(3C) man page.

The maximum value is the number of physical memory pages. The maximum value should be no more than 30 percent of physical memory. The system does not enforce this range, other than that described in the

Validation section.

Units Pages

Dynamic? Yes, but dynamic changes are lost if a memory-based DR operation

occurs.

Validation If lotsfree is greater than the amount of physical memory, the value is

reset to the default.

Implicit The relationship of lotsfree being greater than desfree, which is

greater than minfree, should be maintained at all times.

When to Change When demand for pages is subject to sudden sharp spikes, the memory

algorithm might be unable to keep up with demand. One workaround is to start reclaiming memory at an earlier time. This solution gives the

paging system some additional margin.

A rule of thumb is to set this parameter to 2 times what the system needs to allocate in a few seconds. This parameter is workload dependent. A DBMS server can probably work fine with the default settings. However, you might need to adjust this parameter for a system doing heavy file

system I/O.

For systems with relatively static workloads and large amounts of memory, lower this value. The minimum acceptable value is 512 KB, expressed as pages using the page size returned by getpagesize.

Commitment Level Unstable

#### desfree

Description Specifies the preferred amount of memory to be free at all times on the

system.

Data Type Unsigned integer

Default lotsfree / 2

Range The minimum value is 256 KB or 1/128th of physical memory,

whichever is greater, expressed as pages using the page size returned by

getpagesize.

The maximum value is the number of physical memory pages. The maximum value should be no more than 15 percent of physical memory. The system does not enforce this range other than that described in the

Validation section.

Units Pages

Dynamic? Yes, unless dynamic reconfiguration operations that add or delete

memory occur. At that point, the value is reset to the value provided in the /etc/system file or calculated from the new physical memory value.

Validation

If desfree is greater than lotsfree, desfree is set to lotsfree / 2. No message is displayed.

**Implicit** 

The relationship of lotsfree being greater than desfree, which is greater than minfree, should be maintained at all times.

Side Effects

Several side effects can arise from increasing the value of this parameter. When the new value nears or exceeds the amount of available memory on the system, the following can occur:

- Asynchronous I/O requests are not processed, unless available memory exceeds desfree. Increasing the value of desfree can result in rejection of requests that otherwise would succeed.
- NFS asynchronous writes are executed as synchronous writes.
- The swapper is awakened earlier, and the behavior of the swapper is biased towards more aggressive actions.
- The system might not preload (prefault) as many executable pages as possible into the system. This side effect results in applications potentially running slower than they otherwise would.

When to Change

For systems with relatively static workloads and large amounts of memory, lower this value. The minimum acceptable value is 256 KB, expressed as pages using the page size returned by getpagesize.

Commitment Level

Unstable

#### minfree

Description

Specifies the minimum acceptable memory level. When memory drops below this number, the system biases allocations toward allocations necessary to successfully complete pageout operations or to swap processes completely out of memory. Either allocation denies or blocks other allocation requests.

Data Type Unsigned integer

Default desfree / 2

Range The minimum value is 128 KB or 1/256th of physical memory,

whichever is greater, expressed as pages using the page size returned by

getpagesize.

The maximum value is the number of physical memory pages. The maximum value should be no more than 7.5 percent of physical memory.

The system does not enforce this range other than that described in the

Validation section.

Units Pages

Dynamic? Yes, unless dynamic reconfiguration operations that add or delete

memory occur. At that point, the value is reset to the value provided in the /etc/system file or calculated from the new physical memory value.

Validation If minfree is greater than desfree, minfree is set to desfree / 2. No

message is displayed.

Implicit The relationship of lotsfree being greater than desfree, which is

greater than minfree, should be maintained at all times.

When to Change The default value is generally adequate. For systems with relatively

static workloads and large amounts of memory, lower this value. The minimum acceptable value is 128 KB, expressed as pages using the page

size returned by getpagesize.

Commitment Level Unstable

### throttlefree

Description Specifies the memory level at which blocking memory allocation

requests are put to sleep, even if the memory is sufficient to satisfy the

request.

Data Type Unsigned integer

Default minfree

Range The minimum value is 128 KB or 1/256th of physical memory,

whichever is greater, expressed as pages using the page size returned by

getpagesize.

The maximum value is the number of physical memory pages. The maximum value should be no more than 4 percent of physical memory. The system does not enforce this range other than that described in the

Validation section.

Units Pages

Dynamic? Yes, unless dynamic reconfiguration operations that add or delete

memory occur. At that point, the value is reset to the value provided in the /etc/system file or calculated from the new physical memory value.

Validation If throttlefree is greater than desfree, throttlefree is set to

minfree. No message is displayed.

Implicit The relationship of lotsfree is greater than desfree, which is greater

than minfree, should be maintained at all times.

When to Change The default value is generally adequate. For systems with relatively

static workloads and large amounts of memory, lower this value. The minimum acceptable value is 128 KB, expressed as pages using the page size returned by getpagesize. For more information, see the

getpagesize(3C) man page.

Commitment Level Unstable

### pageout\_reserve

Description Specifies the number of pages reserved for the exclusive use of the

pageout or scheduler threads. When available memory is less than this value, nonblocking allocations are denied for any processes other than pageout or the scheduler. Pageout needs to have a small pool of memory for its use so it can allocate the data structures necessary to do the I/O for

writing a page to its backing store.

Data Type Unsigned integer

Default throttlefree / 2

Range The minimum value is 64 KB or 1/512th of physical memory,

whichever is greater, expressed as pages using the page size returned by

getpagesize(3C).

The maximum is the number of physical memory pages. The maximum value should be no more than 2 percent of physical memory. The system does not enforce this range, other than that described in the Validation

section.

Units Pages

Dynamic? Yes, unless dynamic reconfiguration operations that add or delete

memory occur. At that point, the value is reset to the value provided in the /etc/system file or calculated from the new physical memory value.

Validation If pageout reserve is greater than throttlefree / 2, pageout reserve

is set to throttlefree / 2. No message is displayed.

Implicit The relationship of lotsfree being greater than desfree, which is

greater than minfree, should be maintained at all times.

When to Change The default value is generally adequate. For systems with relatively

static workloads and large amounts of memory, lower this value. The minimum acceptable value is 64 KB, expressed as pages using the page

size returned by getpagesize.

Commitment Level Unstable

## pages\_pp\_maximum

Description Defines the number of pages that must be unlocked. If a request to lock

pages would force available memory below this value, that request is

refused.

Data Type Unsigned long

Default The greater of (tune t minarmem + 100 and [4% of memory available at

boot time + 4 MB])

Range Minimum value enforced by the system is tune t minarmem + 100. The

system does not enforce a maximum value.

Units Pages

Dynamic? Yes, unless dynamic reconfiguration operations that add or delete

memory occur. At that point, the value is reset to the value provided in the /etc/system file or was calculated from the new physical memory

value.

Validation If the value specified in the /etc/system file or the calculated default is

less than tune t minarmem + 100, the value is reset to tune t minarmem

+ 100.

No message is displayed if the value from the /etc/system file is increased. Validation is done only at boot time and during dynamic reconfiguration operations that involve adding or deleting memory.

When to Change When memory-locking requests fail or when attaching to a shared

memory segment with the SHARE MMU flag fails, yet the amount of

memory available seems to be sufficient.

Excessively large values can cause memory locking requests (mlock, mlockall, and memortl) to fail unnecessarily. For more information, see

the mlock(3C), mlockall(3C), and memcntl(2) man pages.

Commitment Level Unstable

### tune t minarmem

Description Defines the minimum available resident (not swappable) memory to

maintain necessary to avoid deadlock. Used to reserve a portion of memory for use by the core of the OS. Pages restricted in this way are not seen when the OS determines the maximum amount of memory

available.

Data Type Signed integer

Default 25

Range 1 to physical memory

Units Pages

Dynamic? No

Validation None. Large values result in wasted physical memory.

When to Change The default value is generally adequate. Consider increasing the default

value if the system locks up and debugging information indicates that no

memory was available.

Commitment Level Unstable

### fastscan

Description Defines the maximum number of pages per second that the system looks

at when memory pressure is highest.

Data Type Signed integer

Default The fastscan default value is set in one of the following ways:

- The fastscan value set in the /etc/system file is used.
- The maxfastscan value set in the /etc/system file is used.
- If neither fastscan nor maxfastscan is set in the /etc/system file, fastscan is set to 64 MB when the system is booted. Then, after the system is booted for a few minutes, the fastscan value is set to the

number of pages that the scanner can scan in one second using 10% of a CPU.

In all three cases, if the derived value is more than half the memory in the system, the fastscan value is capped at the value of half the memory in the system.

Range 64 MB to half the system's physical memory

Units Pages

Dynamic? Yes, unless dynamic reconfiguration operations that add or delete

memory occur. At that point, the value is reset to the value provided by /etc/system or calculated from the new physical memory value.

Validation The maximum value is the lesser of 64 MB and 1/2 of physical memory.

When to Change When more aggressive scanning of memory is preferred during periods

of memory shortfall, especially when the system is subject to periods of

intense memory demand or when performing heavy file I/O.

Commitment Level Unstable

#### slowscan

Description Defines the minimum number of pages per second that the system looks

at when attempting to reclaim memory.

Data Type Signed integer

Default The smaller of 1/20th of physical memory in pages and 100.

Range 1 to fastscan / 2

Units Pages

Dynamic? Yes, unless dynamic reconfiguration operations that add or delete

memory occur. At that point, the value is reset to the value provided in the /etc/system file or calculated from the new physical memory value.

Validation If slowscan is larger than fastscan / 2, slowscan is reset to fastscan /

2. No message is displayed.

When to Change When more aggressive scanning of memory is preferred during periods

of memory shortfall, especially when the system is subject to periods of

intense memory demand.

Commitment Level Unstable

## min\_percent\_cpu

Description Defines the minimum percentage of CPU that pageout can consume.

This parameter is used as the starting point for determining the maximum

amount of time that can be consumed by the page scanner.

Data Type Signed integer

Default 4

Range 1 to 80

Units Percentage

Dynamic? Yes

Validation None

When to Change Increasing this value on systems with multiple CPUs and lots of memory,

which are subject to intense periods of memory demand, enables the

pager to spend more time attempting to find memory.

Commitment Level Unstable

## handspreadpages

Description The Oracle Solaris OS uses a two-handed clock algorithm to look for

pages that are candidates for reclaiming when memory is low. The first hand of the clock walks through memory marking pages as unused. The second hand walks through memory some distance after the first hand, checking to see if the page is still marked as unused. If so, the page is subject to being reclaimed. The distance between the first hand and the

second hand is handspreadpages.

Data Type Unsigned long

Default fastscan

Range 1 to maximum number of physical memory pages on the system.

Units Pages

Dynamic? Yes. This parameter requires that the kernel reset\_hands parameter also

be set to a non-zero value. Once the new value of handspreadpages has

been recognized, reset hands is set to zero.

Validation The value is set to the lesser of either the amount of physical memory and

the handspreadpages value.

When to Change When you want to increase the amount of time that pages are potentially

resident before being reclaimed. Increasing this value increases the separation between the hands, and therefore, the amount of time before a

page can be reclaimed.

Commitment Level Unstable

## pages\_before\_pager

Description Defines part of a system threshold that immediately frees pages after

an I/O completes instead of storing the pages for possible reuse. The threshold is lotsfree + pages\_before\_pager. The NFS environment also uses this threshold to curtail its asynchronous activities as memory

pressure mounts.

Data Type Signed integer

Default 200

Range 1 to amount of physical memory

Units Pages

Dynamic? No

Validation None

When to Change You might change this parameter when the majority of I/O is done for

pages that are truly read or written once and never referenced again. Setting this variable to a larger amount of memory keeps adding pages to

the free list.

You might also change this parameter when the system is subject to bursts of severe memory pressure. A larger value here helps maintain a

larger cushion against the pressure.

Commitment Level Unstable

### maxpgio

Description Defines the maximum number of page I/O requests that can be queued

by the paging system. This number is divided by 4 to get the actual maximum number used by the paging system. This parameter is used to throttle the number of requests as well as to control process swapping.

Data Type Signed integer

Default 400

Range 1 to a variable maximum that depends on the system architecture, but

mainly by the I/O subsystem, such as the number of controllers, disks,

and disk swap size

Units I/0s

Dynamic? No

Validation None

Implicit The maximum number of I/O requests from the pager is limited by the

size of a list of request buffers, which is currently sized at 256.

When to Change Increase this parameter to page out memory faster. A larger value might

help to recover faster from memory pressure if more than one swap device is configured or if the swap device is a striped device. Note that the existing I/O subsystem should be able to handle the additional I/O load. Also, increased swap I/O could degrade application I/O performance if the swap partition and application files are on the same

disk.

Commitment Level Unstable

# **Swapping-Related Parameters**

Swapping in the Oracle Solaris OS is accomplished by the swapfs pseudo file system. The combination of space on swap devices and physical memory is treated as the pool of space available to support the system for maintaining backing store for anonymous memory. The system attempts to allocate space from disk devices first, and then uses physical memory as backing store. When swapfs is forced to use system memory for backing store, limits are enforced to ensure that the system does not deadlock because of excessive consumption by swapfs.

## swapfs\_reserve

Description Defines the amount of system memory that is reserved for use by system

(UID = 0) processes.

Data Type Unsigned long

Default The smaller of 4 MB and 1/16th of physical memory

Range The minimum value is 4 MB or 1/16th of physical memory, whichever is

smaller, expressed as pages using the page size returned by getpagesize.

The maximum value is the number of physical memory pages. The maximum value should be no more than 10 percent of physical memory. The system does not enforce this range, other than that described in the

Validation section.

Units Pages

Dynamic? No

Validation None

When to Change Generally not necessary. Only change when recommended by a software

provider, or when system processes are terminating because of an inability to obtain swap space. A much better solution is to add physical

memory or additional swap devices to the system.

Commitment Level Unstable

## swapfs\_minfree

Description Defines the desired amount of physical memory to be kept free for the

rest of the system. Attempts to reserve memory for use as swap space by any process that causes the system's perception of available memory to fall below this value are rejected. Pages reserved in this manner can only be used for locked-down allocations by the kernel or by user-level

processes.

Data Type Unsigned long

Default The larger of 2 MB and 12.5% of physical memory

Range 1 to amount of physical memory

Units Pages

Dynamic? No

Validation None

When to Change Consider reducing this parameter value when processes are failing

because of an inability to obtain swap space, yet the system has memory available. For example, change this value to use no more than 6.25% of system memory, but do not reduce it below 5% of system memory.

On SPARC systems, the value should be at least 2 times the value of tsb\_alloc\_hiwater\_factor. For more information, see

"tsb\_alloc\_hiwater\_factor" on page 79.

Commitment Level Unstable

# **Kernel Memory Allocator**

The Oracle Solaris kernel memory allocator distributes chunks of memory for use by clients inside the kernel. The allocator creates a number of caches of varying size for use by its clients. Clients can also request the allocator to create a cache for use by that client (for example, to allocate structures of a particular size). Statistics about each cache that the allocator manages can be seen by using the kstat -c kmem cache command.

Occasionally, systems might panic because of memory corruption. The kernel memory allocator supports a debugging interface (a set of flags), that performs various integrity checks on the buffers. The kernel memory allocator also collects information on the allocators. The integrity checks provide the opportunity to detect errors closer to where they actually occurred. The collected information provides additional data for support people when they try to ascertain the reason for the panic.

Use of the flags incurs additional overhead and memory usage during system operations. The flags should only be used when a memory corruption problem is suspected.

## kmem\_flags

Description

The Oracle Solaris kernel memory allocator has various debugging and test options.

Five supported flag settings are described here.

Flag	Setting	Description
AUDIT	0×1	The allocator maintains a log that contains recent
		history of its activity. The number of items logged

Flag	Setting	Description
		depends on whether CONTENTS is also set. The log is a fixed size. When space is exhausted, earlier records are reclaimed.
TEST	0×2	The allocator writes a pattern into freed memory and checks that the pattern is unchanged when the buffer is next allocated. If some portion of the buffer is changed, then the memory was probably used by a client that had previously allocated and freed the buffer. If an overwrite is identified, the system panics.
REDZONE	0×4	The allocator provides extra memory at the end of the requested buffer and inserts a special pattern into that memory. When the buffer is freed, the pattern is checked to see if data was written past the end of the buffer. If an overwrite is identified, the kernel panics.
CONTENTS	0×8	The allocator logs up to 256 bytes of buffer contents when the buffer is freed. This flag requires that AUDIT also be set.
		The numeric value of these flags can be logically added together and set by the /etc/system file.
LITE	0×100	Does minimal integrity checking when a buffer is allocated and freed. When enabled, the allocator checks that the redzone has not been written into, that a freed buffer is not being freed again, and that the buffer being freed is the size that was allocated. Do not combine this flag with any other flags.

Data Type Signed integer

Default 0 (disabled)

Range 0 (disabled) or 1 - 15 or 256 (0x100)

Dynamic? Yes. Changes made during runtime only affect new kernel memory

caches. After system initialization, the creation of new caches is rare.

Validation None

When to Change When memory corruption is suspected

Commitment Level Unstable

# kmem\_stackinfo

at kernel thread creation time, the kernel thread stack is filled with a specific pattern instead of filled with zeros. During kernel thread

execution, this kernel thread stack pattern is progressively overwritten. A simple count from the stack top until the pattern is not found gives a high watermark value, which is the maximum kernel stack space used by a kernel thread. This mechanism allows the following features:

- Compute the percentage of kernel thread stack really used (a high watermark) for current kernel threads in the system
- When a kernel thread ends, the system logs the last kernel threads that have used the most of their kernel thread stacks before dying to a small circular memory buffer

Data Type Unsigned integer

Default 0 (disabled)

Range 0 (disabled) or 1 (enabled)

Dynamic? Yes

Validation None

When to Change When you want to monitor kernel thread stack usage. Keep in mind

that when kmem\_stackinfo is enabled, the performance of creating and deleting kthreads is decreased. For more information, see *Oracle Solaris* 

Modular Debugger Guide.

Zone Configuration This parameter must be set in the global zone.

Commitment Level Unstable

# **General Driver Parameters**

This section describes other drivers that apply to the kernel.

# moddebug

Description When this parameter is enabled, messages about various steps in the

module loading process are displayed.

Data Type Signed integer

Default 0 (messages off)

Range

Here are the most useful values:

• 0x80000000 - Prints [un] loading... message. For every module loaded, messages such as the following appear on the console and in the /var/adm/messages file:

```
Apr 20 17:18:04 neo genunix: [ID 943528 kern.notice] load 'sched/TS_DPTBL' id 15 loaded @ 0x7belb2f8/0x19c8380 size 176/2096 Apr 20 17:18:04 neo genunix: [ID 131579 kern.notice] installing TS_DPTBL, module id 15.
```

 0x40000000 – Prints detailed error messages. For every module loaded, messages such as the following appear on the console and in the /var/adm/messages file:

```
Apr 20 18:30:00 neo unix: Errno = 2
Apr 20 18:30:00 neo unix: kobj_open: vn_open of /platform/sun4v/
kernel/exec/sparcv9/intpexec fails
Apr 20 18:30:00 neo unix: Errno = 2
Apr 20 18:30:00 neo unix: kobj_open: '/kernel/exec/sparcv9/
intpexec'
Apr 20 18:30:00 neo unix: vp = 60015777600
Apr 20 18:30:00 neo unix: kobj_close: 0x60015777600
Apr 20 18:30:00 neo unix: kobj_open: vn_open of /platform/
SUNW,Sun-Fire-T200/kernel/exec/sparcv9
/intpexec fails,
Apr 20 18:30:00 neo unix: Errno = 2
Apr 20 18:30:00 neo unix: kobj_open: vn_open of /platform/sun4v/
kernel/exec/sparcv9/intpexec fails
```

 0x20000000 - Prints even more detailed messages. This value doesn't print any additional information beyond what the 0x40000000 flag does during system boot. However, this value does print additional information about releasing the module when the module is unloaded.

These values can be added together to set the final value.

Dynamic? Yes

Validation None

When to Change When a module is either not loading as expected, or the system seems to

hang while loading modules. Note that when 0x40000000 is set, system boot is slowed down considerably by the number of messages written to

the console.

Commitment Level Unstable

## ddi\_msix\_alloc\_limit

Description x86 only: This parameter controls the number of Extended Message

Signaled Interrupts (MSI-X) that a device instance can allocate. Due to an existing system limitation, the default value is 2. You can increase the number of MSI-X interrupts that a device instance can allocate by increasing the value of this parameter. This parameter can be set either by editing the /etc/system file or by setting it with mdb before the device

driver attach occurs.

Data Type Signed integer

Default SPARC based systems: 8

x86 based systems: 2 If the system supports x2APIC, the apix module

can increase the default value to 8.

Range 2-8

Dynamic? Yes

Validation None

When to Change To increase the number of MSI-X interrupts that a device instance can

allocate. However, if you increase the number of MSI-X interrupts that a device instance can allocate, adequate interrupts might not be available to satisfy all allocation requests. If this happens, some devices might stop functioning or the system might fail to boot. Reduce the value or remove

the parameter in this case.

Commitment Level Unstable

## **Network Driver Parameters**

This section describes network parameters that affect the kernel.

## **IP Protocol Parameters in the Kernel**

The following IP parameters can be set only in the /etc/system file. After the file is modified, reboot the system.

For example, the following entry sets the ipcl conn hash size parameter:

set ip:ipcl\_conn\_hash\_size=value

### ipcl\_conn\_hash\_size

Description Controls the size of the connection hash table used by IP. The default

value of 0 means that the system automatically sizes an appropriate value for this parameter at boot time, depending on the available memory.

Data Type Unsigned integer

Default 0

Range 0 to 82,500

Dynamic? No. The parameter can only be changed at boot time.

value can be increased accordingly. Increasing the hash table size means that more memory is wired down, thereby reducing available memory to

user applications.

Commitment Level Unstable

#### ip\_squeue\_worker\_wait

Description Governs the maximum delay in waking up a worker thread to process

TCP/IP packets that are enqueued on an squeue. An *squeue* is a serialization queue that is used by the TCP/IP kernel code to process

TCP/IP packets.

Default 10 milliseconds

Range 0-50 milliseconds

Dynamic? Yes

When to Change Consider tuning this parameter if latency is an issue, and network traffic

is light. For example, if the stem serves mostly interactive network

traffic.

The default value usually works best on a network file server, a web

server, or any stem that has substantial network traffic.

Zone Configuration This parameter can only be set in the global zone.

Commitment Level Unstable

### ip\_squeue\_fanout

Description Determines the mode of associating TCP/IP connections with squeues.

A value of 0 associates a new TCP/IP connection with the CPU that creates the connection. A value of 1 associates the connection with

multiple squeues that belong to different CPUs.

Default 1

Range 0 or 1

Dynamic? Yes

When to Change Consider setting this parameter to 1 to spread the load across all CPUs

in certain situations. For example, when the number of CPUs exceed the number of NICs, and one CPU is not capable of handling the network

load of a single NIC, change this parameter to 1.

Zone Configuration This parameter can only be set in the global zone.

Commitment Level Unstable

# igb Parameters

#### mr\_enable

Description This parameter enables or disables multiple receive and transmit queues

that are used by the igb network driver. This parameter can be set by editing the /etc/driver/drv/igb.conf file before the igb driver attach

occurs.

Data Type Boolean

Default 1 (disable multiple queues)

Range 0 (enable multiple queues) or 1 (disable multiple queues)

Dynamic? No

Validation None

When to Change To enable or disable multiple receive and transmit queues that are used

by the igb network driver.

Commitment Level Unstable

### intr\_force

Description This parameter is used to force an interrupt type, such as MSI, MSI-X,

or legacy, that is used by the igb network driver. This parameter can be set by editing the /etc/driver/drv/igb.conf file before the igb driver

attach occurs.

Data Type Unsigned integer

Default 0 (do not force an interrupt type)

Range 0 (do not force an interrupt type)

1 (force MSI-X interrupt type)2 (force MSI interrupt type)3 (force legacy interrupt type)

Dynamic? No

Validation None

When to Change To force an interrupt type that is used by the igb network driver.

Commitment Level Unstable

# ixgbe Parameters

#### tx\_queue\_number

Description This parameter controls the number of transmit queues that are used

by the ixgbe network driver. You can increase the number of transmit queues by increasing the value of this parameter. This parameter can be set by editing the /etc/driver/drv/ixgbe.conf file before the ixgbe

driver attach occurs.

Data Type Unsigned integer

Default 8

Range 1 to 32

Dynamic? No

Validation None

When to Change To change the number of transmit queues that are used by the ixgbe

network driver.

Commitment Level Unstable

#### rx\_queue\_number

Description This parameter controls the number of receive queues that are used by

the ixgbe network driver. You can increase the number of receive queues by increasing the value of this parameter. This parameter can be set by editing the /etc/driver/drv/ixgbe.conf file before the ixgbe driver

attach occurs.

Data Type Unsigned integer

Default 8

Range 1 to 64

Dynamic? No

Validation None

When to Change To change the number of receive queues that are used by the ixgbe

network driver.

Commitment Level Unstable

#### intr\_throttling

Description This parameter controls the interrupt throttling rate of the ixgbe network

driver. You can increase the rate of interrupt by decreasing the value of this parameter. This parameter can be set by editing the /etc/driver/

drv/ixgbe.conf file before the ixgbe driver attach occurs.

Data Type Unsigned integer

Default 200

Range 0 to 65535

Dynamic? No

Validation None

When to Change To change the interrupt throttling rate that is used by the ixgbe network

driver.

Commitment Level Unstable

### rx\_limit\_per\_intr

Description This parameter controls the maximum number of receive queue buffer

descriptors per interrupt that are used by the ixgbe network driver. You can increase the number of receive queue buffer descriptors by increasing the value of this parameter. This parameter can be set by editing the /etc/driver/drv/ixgbe.conf file before the ixgbe driver attach occurs.

Data Type Unsigned integer

Default 256

Range 16 to 4096

Dynamic? No

Validation None

When to Change To change the number of receive queue buffer descriptors that are

handled per interrupt by the ixgbe network driver.

Commitment Level Unstable

#### tx\_ring\_size

Description This parameter controls the transmit queue size that is used by the ixgbe

network driver. You can increase the transmit queue size by increasing the value of this parameter. This parameter can be set by editing the /etc/driver/drv/ixgbe.conf file before the ixgbe driver attach occurs.

Data Type Unsigned integer

Default 1024

Range 64 to 4096

Dynamic? No

Validation None

When to Change To change the transmit queue size that is used by the ixgbe network

driver.

Commitment Level Unstable

#### rx\_ring\_size

Description This parameter controls the receive queue size that is used by the ixgbe

network driver. You can increase the receive queue size by increasing the value of this parameter. This parameter can be set by editing the /etc/driver/drv/ixgbe.conf file before the ixgbe driver attach occurs.

Data Type Unsigned integer

Default 1024

Range 64 to 4096

Dynamic? No

Validation None

When to Change To change the receive queue size that is used by the ixgbe network

driver.

Commitment Level Unstable

### tx\_copy\_threshold

Description This parameter controls the transmit buffer copy threshold that is used

by the ixgbe network driver. You can increase the transmit buffer copy threshold by increasing the value of this parameter. This parameter can

be set by editing the /etc/driver/drv/ixgbe.conf file before the ixgbe

driver attach occurs.

Data Type Unsigned integer

Default 512

Range 0 to 9126

Dynamic? No

Validation None

When to Change To change the transmit buffer copy threshold that is used by the ixgbe

network driver.

Commitment Level Unstable

### rx\_copy\_threshold

Description This parameter controls the receive buffer copy threshold that is used

by the ixgbe network driver. You can increase the receive buffer copy threshold by increasing the value of this parameter. This parameter can be set by editing the /etc/driver/drv/ixgbe.conf file before the ixgbe

driver attach occurs.

Data Type Unsigned integer

Default 128

Range 0 to 9126

Dynamic? No

Validation None

When to Change To change the receive buffer copy threshold that is used by the ixgbe

network driver.

Commitment Level Unstable

### **General I/O Parameters**

This section describes parameters in function of input and output processes in the kernel.

### maxphys

Description Defines the maximum size of physical I/O requests. If a driver

encounters a request larger than this size, the driver breaks the request into maxphys sized chunks. File systems can and do impose their own

limit.

Data Type Signed integer

Default 131,072 (sun4u or sun4v) or 57,344 (x86). The sd driver uses the value

of 1,048,576 if the drive supports wide transfers. The ssd driver uses

1,048,576 by default.

Range stem-specific page size to MAXINT

Units Bytes

Dynamic? Yes, but many file systems load this value into a per-mount point data

structure when the file system is mounted. A number of drivers load the value at the time a device is attached to a driver-specific data structure.

Validation None

When to Change When doing I/O to and from raw devices in large chunks. Note that

a DBMS doing OLTP operations issues large numbers of small I/Os. Changing maxphys does not result in any performance improvement in

that case.

Commitment Level Unstable

# rlim fd max

Description Specifies the "hard" limit on file descriptors that a single process might

have open. Overriding this limit requires superuser privilege.

Data Type Signed integer

Default 65,536

Range 128 to MAXINT

Units File descriptors

Dynamic? No

Validation

None

When to Change

When the maximum number of open files for a process is not enough. Other limitations in system facilities can mean that a larger number of file descriptors is not as useful as it might be. For example:

- A 32-bit program using standard I/O is limited to 256 file descriptors.
   A 64-bit program using standard I/O can use up to 2 billion descriptors. Specifically, standard I/O refers to the stdio(3C) functions in libc(3LIB).
- select is by default limited to 1024 descriptors per fd\_set. For more information, see the select(3C) man page. A 32-bit application code can be recompiled with a larger fd\_set size (less than or equal to 65,536). A 64-bit application uses an fd\_set size of 65,536, which cannot be changed.

An alternative to changing this on a system wide basis is to use the plimit command. If a parent process has its limits changed by plimit, all children inherit the increased limit. This alternative is useful for daemons such as inetd.

Commitment Level

Unstable

## rlim fd cur

Description

Defines the "soft" limit on file descriptors that a single process can have open. A process might adjust its file descriptor limit to any value up to the "hard" limit defined by rlim\_fd\_max by using the setrlimit() call or by issuing the limit command in whatever shell it is running. You do not require superuser privilege to adjust the limit to any value less than or equal to the hard limit.

Data Type Signed integer

Default 256

Range 128 to MAXINT

Units File descriptors

Dynamic? No

Validation Compared to rlim\_fd\_max. If rlim\_fd\_cur is greater than rlim\_fd\_max,

rlim\_fd\_cur is reset to rlim\_fd\_max.

When to Change When the default number of open files for a process is not enough.

Increasing this value means only that it might not be necessary for a program to use setrlimit to increase the maximum number of file

descriptors available to it.

Commitment Level Unstable

# **General File System Parameters**

This section describes parameters that relate to file systems.

### ncsize

Description Defines the number of entries in the directory name look-up cache

(DNLC). This parameter is used by UFS, NFS, and ZFS to cache

elements of path names that have been resolved.

The DNLC also caches negative look-up information, which means it

caches a name not found in the cache.

Data Type Signed integer

Default  $(4 \times (v.v \text{ proc} + \text{maxusers}) + 320) + (4 \times (v.v \text{ proc} + \text{maxusers}) +$ 

320) / 100

Range 0 to MAXINT

Units DNLC entries

Dynamic? No

Validation None. Larger values cause the time it takes to unmount a file system

to increase as the cache must be flushed of entries for that file system

during the unmount process.

When to Change You can use the kstat -n dnlcstats command to determine when

entries have been removed from the DNLC because it was too small. The sum of the pick\_heuristic and the pick\_last parameters represents otherwise valid entries that were reclaimed because the cache was too

small.

Excessive values of ncsize have an immediate impact on the system because the system allocates a set of data structures for the DNLC based

on the value of ncsize. By default, a system allocates 64-byte structures for ncsize. The value has a further effect on UFS and NFS, unless ufs ninode and nfs:nrnode are explicitly set.

Commitment Level Unstable

## dnlc\_dir\_enable

Description Enables large directory caching

Note - This parameter has no effect on NFS or ZFS file systems.

Data Type Unsigned integer

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Dynamic? Yes, but do not change this tunable dynamically. You can enable this

parameter if it was originally disabled. Or, you can disable this parameter if it was originally enabled. However, enabling, disabling, and then

enabling this parameter might lead to stale directory caches.

Validation No

When to Change Directory caching has no known problems. However, if problems occur,

then set dnlc\_dir\_enable to 0 to disable caching.

Commitment Level Unstable

# dnlc\_dir\_min\_size

Description Specifies the minimum number of entries cached for one directory.

Note - This parameter has no effect on NFS or ZFS file systems.

Data Type Unsigned integer

Default 40

Range 0 to MAXUINT (no maximum)

Units Entries

Dynamic? Yes, this parameter can be changed at any time.

Validation None

increase dnlc dir min size. Note that individual file systems might

have their own range limits for caching directories.

Commitment Level Unstable

## dnlc\_dir\_max\_size

Description Specifies the maximum number of entries cached for one directory.

Note - This parameter has no effect on NFS or ZFS file systems.

Data Type Unsigned integer

Default MAXUINT (no maximum)

Range 0 to MAXUINT

Dynamic? Yes, this parameter can be changed at any time.

Validation None

dnlc\_dir\_max\_size.

Commitment Level Unstable

# dnlc\_dircache\_percent

Description Calculates the maximum percentage of physical memory that the DNLC

directory cache can consume.

Data Type Integer

Default 100

Range 0 to 100

Units Percentage

Dynamic? No

Validation At boot time, the value range is checked and default value is enforced.

When to Change When the system experiences a memory shortage and high kernel

memory consumption, consider lowering this value. If performance issues are seen with the default value, consider increasing the value.

**Note -** The DNLC is used by UFS and ZFS file systems and NFS clients. Setting this tunable might be considered for better performance when there are memory shortages and high kernel memory consumption or when a memory is needed by the ARC or other kernel caches.

Commitment Level Unstable

### **TMPFS Parameters**

This section describes parameters that affect temporary file storage facility.

## tmpfs:tmpfs\_maxkmem

Description Defines the maximum amount of kernel memory that TMPFS can use for

its data structures (tmpnodes and directory entries).

Data Type Unsigned long

Default One page or 4 percent of physical memory, whichever is greater.

Range Number of bytes in one page (8192 for sun4u or sun4v systems, 4096

for all other systems) to 25 percent of the available kernel memory at the

time TMPFS was first used.

Units Bytes

Dynamic? Yes

Validation None

When to Change Increase if the following message is displayed on the console or written

in the messages file:

tmp\_memalloc: tmpfs over memory limit

The current amount of memory used by TMPFS for its data structures is held in the tmp kmemspace field. This field can be examined with a

kernel debugger.

Commitment Level Unstable

## tmpfs:tmpfs\_minfree

Description Defines the minimum amount of swap space that TMPFS leaves for the

rest of the system.

Data Type Signed long

Default 256

Range 0 to maximum swap space size

Units Pages

Dynamic? Yes

Validation None

When to Change To maintain a reasonable amount of swap space on systems with large

amounts of TMPFS usage, you can increase this number. The limit has been reached when the console or messages file displays the following

message:

fs-name: File system full, swap space limit exceeded

Commitment Level Unstable

## **Pseudo Terminals**

Pseudo terminals, pty, are used for two purposes in Oracle Solaris software:

Supporting remote logins by using the telnet, rlogin, or rsh commands

 Providing the interface through which the X Window system creates command interpreter windows

The default number of pseudo-terminals is sufficient for a desktop workstation. So, tuning focuses on the number of pty available for remote logins.

The default number of pty is now based on the amount of memory on the system. This default should be changed only to restrict or increase the number of users who can log in to the system.

Three related variables are used in the configuration process:

- pt cnt Default maximum number of pty.
- pt\_pctofmem Percentage of kernel memory that can be dedicated to ptysupport structures.
   A value of zero means that no remote users can log in to the system.
- pt max pty Hard maximum for number of pty.

pt\_cnt has a default value of zero, which tells the system to limit logins based on the amount of memory specified in pct\_pctofmem, unless pt\_max\_pty is set. If pt\_cnt is non-zero, pty are allocated until this limit is reached. When that threshold is crossed, the system looks at pt\_max\_pty. If pt\_max\_pty has a non-zero value, it is compared to pt\_cnt. The pty allocation is allowed if pt\_cnt is less than pt\_max\_pty. If pt\_max\_pty is zero, pt\_cnt is compared to the number of pty supported based on pt\_pctofmem. If pt\_cnt is less than this value, the ptyallocation is allowed. Note that the limit based on pt\_pctofmem only comes into play if both pt cnt and ptms ptymax have default values of zero.

To put a hard limit on pty that is different than the maximum derived from pt\_pctofmem, set pt\_cnt and ptms\_ptymax in /etc/system to the preferred number of pty. The setting of ptms\_pctofmem is not relevant in this case.

To dedicate a different percentage of system memory to ptysupport and let the operating system manage the explicit limits, do the following:

- Do not set pt cnt or ptms ptymax in /etc/system.
- Set pt\_pctofmem in /etc/system to the preferred percentage. For example, set pt pctofmem=10 for a 10 percent setting.

Note that the memory is not actually allocated until it is used in support of a pty Once memory is allocated, it remains allocated.

### pt\_cnt

Description

The number of available /dev/pts entries is dynamic up to a limit determined by the amount of physical memory available on the system. pt\_cnt is one of three variables that determines the minimum number of logins that the system can accommodate. The default maximum number

of /dev/pts devices the system can support is determined at boot time by computing the number of pty structures that can fit in a percentage of system memory (see pt\_pctofmem). If pt\_cnt is zero, the system allocates up to that maximum. If pt\_cnt is non-zero, the system allocates to the greater of pt\_cnt and the default maximum.

Data Type Unsigned integer

Default 0

Range 0 to maxpid

Units Logins/windows

Dynamic? No

Validation None

When to Change When you want to explicitly control the number of users who can

remotely log in to the system.

Commitment Level Unstable

## pt\_pctofmem

Description Specifies the maximum percentage of physical memory that can be

consumed by data structures to support /dev/pts entries. A system

consumes 176 bytes per /dev/pts entry.

Data Type Unsigned integer

Default 5

Range 0 to 100

Units Percentage

Dynamic? No

Validation None

When to Change When you want to either restrict or increase the number of users who can

log in to the system. A value of zero means that no remote users can log

in to the system.

Commitment Level Unstable

### pt\_max\_pty

Description Defines the maximum number of ptys the system offers

Data Type Unsigned integer

Default 0 (Uses system-defined maximum)

Range 0 to MAXUINT

Units Logins/windows

Dynamic? Yes

Validation None

Implicit Should be greater than or equal to pt\_cnt. Value is not checked until the

number of ptysallocated exceeds the value of pt cnt.

When to Change When you want to place an absolute ceiling on the number of logins

supported, even if the system could handle more based on its current

configuration values.

Commitment Level Unstable

## **STREAMS Parameters**

This section describes STREAMS-related parameters.

## nstrpush

Description Specifies the number of modules that can be inserted into (pushed onto) a

STREAM.

Data Type Signed integer

Default 9

Range 9 to 16

Units Modules

Dynamic? Yes

Validation None

When to Change At the direction of your software vendor. No messages are displayed

when a STREAM exceeds its permitted push count. A value of EINVAL is

returned to the program that attempted the push.

Commitment Level Unstable

### strmsgsz

Description Specifies the maximum number of bytes that a single system call can

pass to a STREAM to be placed in the data part of a message. Any write exceeding this size is broken into multiple messages. For more

information, see the write(2) man page.

Data Type Signed integer

Default 65,536

Range 0 to 262,144

Units Bytes

Dynamic? Yes

Validation None

When to Change When putmsg calls return ERANGE. For more information, see the

putmsg(2) man page.

Commitment Level Unstable

#### strctlsz

Description Specifies the maximum number of bytes that a single system call can

pass to a STREAM to be placed in the control part of a message

Data Type Signed integer

Default 1024

Range 0 to MAXINT

Units Bytes

Dynamic? Yes

Validation None

When to Change At the direction of your software vendor. putmsg() calls return ERANGE if

they attempt to exceed this limit.

Commitment Level Unstable

# System V Message Queues

System V message queues provide a message-passing interface that enables the exchange of messages by queues created in the kernel. Interfaces are provided in the Oracle Solaris environment to enqueue and dequeue messages. Messages can have a type associated with them. Enqueueing places messages at the end of a queue. Dequeuing removes the first message of a specific type from the queue or the first message if no type is specified.

For detailed information on tuning these system resources, see Chapter 6, "About Resource Controls" in *Administering Resource Management in Oracle Solaris* 11.3.

# **System V Semaphores**

System V semaphores provide counting semaphores in the Oracle Solaris OS. A *semaphore* is a counter used to provide access to a shared data object for multiple processes. In addition to the standard set and release operations for semaphores, System V semaphores can have values that are incremented and decremented as needed (for example, to represent the number of resources available). System V semaphores also provide the ability to do operations on a group of semaphores simultaneously as well as to have the system undo the last operation by a process if the process dies.

# **System V Shared Memory**

System V shared memory allows the creation of a segment by a process. Cooperating processes can attach to the memory segment (subject to access permissions on the segment) and gain

access to the data contained in the segment. This capability is implemented as a loadable module. Entries in the /etc/system file must contain the shmsys: prefix.

A special kind of shared memory known as *intimate shared memory* (ISM) is used by DBMS vendors to maximize performance. When a shared memory segment is made into an ISM segment, the memory for the segment is locked. This feature enables a faster I/O path to be followed and improves memory usage. A number of kernel resources describing the segment are then shared between all processes that attach to the segment in ISM mode.

### segspt minfree

Description Identifies pages of system memory that cannot be allocated for ISM

shared memory.

Data Type Unsigned long

Default 5 percent of available system memory when the first ISM segment is

created

Range 0 to 50 percent of physical memory

Units Pages

Dynamic? Yes

Validation None. Values that are too small can cause the system to hang or

performance to severely degrade when memory is consumed with ISM

segments.

When to Change On database servers with large amounts of physical memory using

ISM, the value of this parameter can be decreased. If ISM segments are not used, this parameter has no effect. A maximum value of 128 MB (0x4000) is almost certainly sufficient on large memory stems.

Commitment Level Unstable

### pr\_segp\_disable

Description Disables the page lock cache flushing when trying to retire a page that

might belong to ISM.

When locked or busy (heavy I/O) pages are in the pending page retirement queue, the page retire thread flushes the segp\_cache to

encourage retirement of pending pages that might be owned by ISM. Periodic or repeated flushes of the segp\_cache can be a bottleneck for high memory stems.

Default behavior is to flush the page cache every 30 seconds and if locked pages are observed in queue, then timeout exponentially backs off until 1 hour in multiples of 2.

Enabling pr\_segp\_disable does not disable the system's ability to retire memory pages, such as those that are faulted as a result of system diagnostic measures.

Data Type Boolean

Default 1 (disabled)

Range 0 (enabled) and 1 (disabled)

Dynamic? No

Validation No.

When to Change

When locked or busy (heavy I/O) pages are in the pending page retirement queue, the page retire thread flushes the segp\_cache to encourage retirement of pending pages that **might** be owned by ISM. Periodic or repeated flushes of the segp\_cache can be a bottleneck for high memory stems.

If you have a latency sensitive database or a large shared memory application, consider disabling this parameter to completely skip segp cache flushing.

Symptoms of locked kernel pages that can't be retired are as follows:

Brief database latency or momentary database unresponsive events along with brief periodic elevated SYS CPU events upon successful page retirements, However, locked or busy pages that repeatedly fail to retire might continue to trigger page retirement threads at slower rates.

For example, locked memory pages that can't be retired might retry at small intervals and repeat forever at 1 hour intervals. After the system reboots, the scheduled pages *might retire*, or it might start trying again at 30 seconds, the default rate.

 Brief unexpected or elevated smtx lock contention might be seen when monitoring segspt\_shmfault, segspt\_softunlock, segspt\_shmpagelock, segspt\_shmfree, segspt\_shmunmap, segspt\_shmattach, and segspt\_dismfault structures.

Commitment Level Unstable

# **Scheduling**

This section describes parameters pertaining to the scheduling of kernel processes.

### disp rechoose interval

Description

Similar to the previous rechoose\_interval parameter, this parameter specifies the amount of time before a process is deemed to have lost all affinity for the last CPU it ran on. However, this parameter is set in more granular time increments. This parameter should be used instead of the deprecated rechoose\_interval parameter, but the rechoose\_interval parameter is still accepted if it is set in the /etc/system file.

After this interval expires, any CPU is considered a candidate for scheduling a thread. This parameter does not apply to threads in the real-time class, but applies to threads in all other scheduling classes.

Use mdb if you want to change the value of this parameter by using the following steps:

 Convert nanoseconds to unscaled time. For example, to convert a 5000000 nanosecond based value to unscaled time, use the following syntax:

```
# mdb -kw
.
.
.
.
> 0t50000000::time -u
0xb6a4444
```

2. Set disp\_rechoose\_interval to the unscaled time value. For example, provide the value that was returned in preceding step.

```
> disp_rechoose_interval /Z 0xb6a444
disp_rechoose_interval: 0x447d998 = 0xb6a444
```

3. Verify that disp\_rechoose\_interval has been set to the right value. For example:

```
> disp_rechoose_interval::print
0xb6a444
```

Data Type Signed integer

Default 3

Range 0 to MAXINT

Dynamic? Yes

Validation None

When to Change When caches are large, or when the system is running a critical process

or a set of processes that seem to suffer from excessive cache misses not

caused by data access patterns.

Consider using the processor set capabilities or processor binding before changing this parameter. For more information, see the psrset(1M) or

pbind(1M) man page.

Commitment Level Unstable

### **Timers**

This section describes parameters that determine timer behavior.

### hires\_tick

Description When set, this parameter causes the Oracle Solaris OS to use a system

clock rate of 1000 instead of the default value of 100.

Data Type Signed integer

Default 0

Range 0 (disabled) or 1 (enabled)

Dynamic? No. Causes new system timing variable to be set at boot time. Not

referenced after boot.

Validation None

When to Change When you want timeouts with a resolution of less than 10 milliseconds,

and greater than or equal to 1 millisecond.

Commitment Level Unstable

### timer\_max

Description Specifies the number of POSIX<sup>TM</sup> timers available.

Data Type Signed integer

Default 1000

Range 0 to MAXINT

Dynamic? No. Increasing the value can cause a system crash.

Validation None

When to Change When the default number of timers offered by the system is inadequate.

Applications receive an EAGAIN error when executing timer create

system calls.

Commitment Level Unstable

# **SPARC: Platform Specific Parameters**

The following parameters apply to sun4v and SPARC M-Series sun4u platforms.

### tsb\_alloc\_hiwater\_factor

Description Initializes tsb\_alloc\_hiwater to impose an upper limit on the amount

of physical memory that can be allocated for translation storage buffers

(TSBs) as follows:

tsb\_alloc\_hiwater = physical memory (bytes) /

tsb\_alloc\_hiwater\_factor

When the memory that is allocated to TSBs is equal to the value of tsb alloc hiwater, the TSB memory allocation algorithm attempts to

reclaim TSB memory as pages are unmapped.

Exercise caution when using this factor to increase the value of

tsb\_alloc\_hiwater. To prevent system hangs, the resulting high water value must be considerably lower than the value of swapfs minfree and

segspt minfree.

Data Type Integer

Default 32

Range 1 to MAXINIT

Note that a factor of 1 makes all physical memory available for allocation to TSBs, which could cause the system to hang. A factor that is too high will not leave memory available for allocation to TSBs, decreasing system performance.

Dynamic? Yes

Validation None

When to Change Change the value of this parameter if the system has many processes that

attach to very large shared memory segments. Under most circumstances,

tuning of this variable is not necessary.

Commitment Level Unstable

### default\_tsb\_size

Description Selects size of the initial translation storage buffers (TSBs) allocated to

all processes.

Data Type Integer

Default is 0 (8 KB), which corresponds to 512 entries

Range Possible values are:

Value	Description
0	8 KB
1	16 KB
3	32 KB
4	128 KB
5	256 KB
6	512 KB
7	1 MB

Dynamic? Yes

Validation None

When to Change Generally, you do not need to change this value. However, doing so

might provide some advantages if the majority of processes on the system have a larger than average working set, or if resident set size

(RSS) sizing is disabled.

Commitment Level Unstable

### enable\_tsb\_rss\_sizing

Description Enables a resident set size (RSS) based TSB sizing heuristic.

Data Type Boolean

Default 1 (TSBs can be resized)

Range 0 (TSBs remain at tsb default size) or 1 (TSBs can be resized)

If set to 0, then tsb\_rss\_factor is ignored.

Dynamic? Yes

Validation Yes

When to Change Can be set to 0 to prevent growth of the TSBs. Under most

circumstances, this parameter should be left at the default setting.

Commitment Level Unstable

### tsb rss factor

Description Controls the RSS to TSB span ratio of the RSS sizing heuristic. This

factor divided by 512 yields the percentage of the TSB span which must be resident in memory before the TSB is considered as a candidate for

resizing.

Data Type Integer

Default 384, resulting in a value of 75%. Thus, when the TSB is 3/4 full, its size

will be increased. Note that some virtual addresses typically map to the same slot in the TSB. Therefore, conflicts can occur before the TSB is at

100% full.

Range 0 to 512

Dynamic? Yes

Validation None

When to Change If the system is experiencing an excessive number of traps due to TSB

misses, for example, due to virtual address conflicts in the TSB, you

might consider decreasing this value toward 0.

For example, changing tsb\_rss\_factor to 256 (effectively, 50%) instead of 384 (effectively, 75%) might help eliminate virtual address conflicts in the TSB in some cases, but will use more kernel memory, particularly on

a heavily loaded system.

TSB activity can be monitored with the trapstat -T command.

Commitment Level Unstable

# **Locality Group Parameters**

This section provides generic memory tunables, which apply to any SPARC or x86 system that uses a Non-Uniform Memory Architecture (NUMA).

### lpg\_alloc\_prefer

Description Controls a heuristic for allocation of large memory pages when the

requested page size is not immediately available in the local memory

group, but could be satisfied from a remote memory group.

By default, the Oracle Solaris OS allocates a remote large page if local free memory is fragmented, but remote free memory is not. Setting this parameter to 1 indicates that additional effort should be spent attempting to allocate larger memory pages locally, potentially moving smaller pages

around to coalesce larger pages in the local memory group.

Data Type Boolean

Default 0 (Prefer remote allocation if local free memory is fragmented and

remote free memory is not)

Range 0 (Prefer remote allocation if local free memory is fragmented and

remote free memory is not)

1 (Prefer local allocation whenever possible, even if local free memory is

fragmented and remote free memory is not)

Dynamic? No

Validation None

When to Change

This parameter might be set to 1 if long-running programs on the system tend to allocate memory that is accessed by a single program, or if memory that is accessed by a group of programs is known to be running in the same locality group (Igroup). In these circumstances, the extra cost of page coalesce operations can be amortized over the long run of the programs.

This parameter might be left at the default value (0) if multiple programs tend to share memory across different locality groups, or if pages tend to be used for short periods of time. In these circumstances, quick allocation of the requested size tends to be more important than allocation in a particular location.

TLB miss activity might be observed by using the trapstat -T command.

Commitment Level Uncommitted

### lgrp mem pset aware

Description If a process is running within a user processor set, this variable

determines whether *randomly* placed memory for the process is selected from among all the lgroups in the system or only from those lgroups that

are spanned by the processors in the processor set.

For more information about creating processor sets, see the  $\ensuremath{\operatorname{\mathsf{psrset}}}(1M)$ 

man page.

Data Type Boolean

Default 0, the Oracle Solaris OS selects memory from all the lgroups in the

system

Range • 0, the Oracle Solaris OS selects memory from all the Igroups in the system (default)

1, try selecting memory only from those lgroups that are spanned by the processors in the processor set. If the first attempt fails, memory

can be allocated in any lgroup.

Dynamic? No

Validation None

When to Change Setting this value to a value of one (1) might lead to more reproducible

performance when processor sets are used to isolate applications from

one another.

Commitment Level Uncommitted



### Oracle Solaris ZFS Tunable Parameters

This chapter describes ZFS tunable parameters that might need consideration, depending on your system and application requirements. In addition, tunable recommendations for using ZFS with database products are provided.

- "Tuning ZFS Considerations" on page 85
- "ZFS Memory Management Parameters" on page 86
- "ZFS File-Level Prefetch" on page 88
- "ZFS Device I/O Queue Depth" on page 89
- "Tuning ZFS When Using Flash Storage" on page 90
- "Tuning ZFS for Database Products" on page 94

For other types of tunable parameters, refer to the following:

- Oracle Solaris kernel tunable parameters Chapter 2, "Oracle Solaris Kernel Tunable Parameters"
- NFS tunable parameters Chapter 4, "NFS Tunable Parameters"
- Internet Protocol Suite tunable parameters Chapter 5, "Internet Protocol Suite Tunable Parameters"
- System facility tunable parameters Chapter 6, "System Facility Parameters"

### **Tuning ZFS Considerations**

Review the following considerations before tuning ZFS:

- Default values are generally the best value. If a better value exists, it should be the default.
   While alternative values might help a given workload, it could quite possibly degrade some other aspects of performance. Occasionally, catastrophically so.
- The ZFS best practices should be followed before ZFS tuning is applied. These practices are a set of recommendations that have been shown to work in different environments and are expected to keep working in the foreseeable future. So, before turning to tuning, make sure you've read and understood the best practices. For more information, see Chapter 13, "Recommended Oracle Solaris ZFS Practices" in *Managing ZFS File Systems in Oracle Solaris* 11.3.

 Unless noted otherwise, the tunable parameters are global and impact ZFS behavior across the system.

# **ZFS Memory Management Parameters**

This section describes parameters related to ZFS memory management.

### user\_reserve\_hint\_pct

Description Informs the system about how much memory is reserved for application

use, and therefore limits how much memory can be used by the ZFS

ARC cache as the cache increases over time.

By means of this parameter, administrators can maintain a large reserve of available free memory for future application demands. The user\_reserve\_hint\_pct parameter is intended to be used in place of the zfs arc max parameter to restrict the growth of the ZFS ARC cache.

**Note -** Review Document 1663862.1, *Memory Management Between ZFS and Applications in Oracle Solaris 11.2*, in My Oracle Support (MOS) for guidance in tuning this parameter.

Data Type Unsigned Integer (64-bit)

Default 0

If a dedicated system is used to run a set of applications with a known memory footprint, set the parameter to the value of that footprint, such as

the sum of the SGA of Oracle database.

To assign a value to the parameter, run the script that is provided in Document 1663862.1 in My Oracle Support (MOS). To make the tuning persistent across reboots, refer to script output for instructions about

using -p option.

Range 0-99

Units Percent

Dynamic Yes

You can adjust the setting of this parameter dynamically on a running

system.

When to Change For upward adjustments, increase the value if the initial value is

determined to be insufficient over time for application requirements, or

if application demand increases on the system. Perform this adjustment only within a scheduled system maintenance window. After you have changed the value, reboot the system.

For downward adjustments, decrease the value if allowed by application requirements. Make sure to use decrease the value only by small amounts, no greater than 5% at a time.

Commitment Level Unstable

### zfs\_arc\_min

Description Determines the minimum size of the ZFS Adaptive Replacement Cache

(ARC). See also "zfs\_arc\_max" on page 87.

Data Type Unsigned Integer (64-bit)

Default 0.5% of total memory

Range 64 MB to zfs arc max

Units Bytes

Dynamic? No

Validation Yes, the range is validated.

When to Change When a system's workload demand for memory fluctuates, the ZFS ARC

caches data at a period of weak demand and then shrinks at a period of strong demand. However, ZFS does not shrink below the value of zfs arc min. Generally, you do not need to change the default value.

Commitment Level Unstable

### zfs\_arc\_max

Description Determines the maximum size of the ZFS Adaptive Replacement Cache

(ARC). See also "zfs arc min" on page 87.

Data Type Unsigned Integer (64-bit)

Default 75% of memory on systems with less than 4 GB of memory

physmem minus 1 GB on systems with greater than 4 GB of memory

Range 64 MB to physmem

Units Bytes

Dynamic? No

Validation Yes, the range is validated.

When to Change If a future memory requirement is significantly large and well defined,

you might consider reducing the value of this parameter to cap the ARC so that it does not compete with the memory requirement. For example, if you know that a future workload requires 20% of memory, it makes sense to cap the ARC such that it does not consume more than the remaining

80% of memory.

Commitment Level Unstable

### **ZFS File-Level Prefetch**

This section describes the parameter that regulates the behavior of the prefetching mechanism.

# zfs\_prefetch\_disable

Description

This parameter determines a file-level prefetching mechanism called zfetch. This mechanism looks at the patterns of reads to files and anticipates on some reads, thereby reducing application wait times. The current behavior suffers from two drawbacks:

- Sequential read patterns made of small reads very often hit in the cache. In this case, the current behavior consumes a significant amount of CPU time trying to find the next I/O to issue, whereas performance is governed more by the CPU availability.
- The zfetch code has been observed to limit scalability of some loads. CPU profiling can be done by using the lockstat -I command or er kernel as described here:

http://www.oracle.com/technetwork/java/index.html

You can disable prefetching by setting zfs\_prefetch\_disable in the /etc/system file. For instructions, see "/etc/system File and the /etc/system.d Directory" on page 17.

Device-level prefetching is disabled when zfs\_vdev\_cache\_size is disabled. This means that tuning vdev cache shift is no longer necessary if zfs\_vdev\_cache\_size is disabled.

Data Type Boolean

Default 0 (enabled)

Range 0 (enabled) or 1 (disabled)

Dynamic? Yes

Validation No

When to Change If the results of er\_kernel show significant time in zfetch\_\* functions,

or if lock profiling with lockstat shows contention around zfetch locks, then disabling file level prefetching should be considered.

Commitment Level Unstable

# **ZFS Device I/O Queue Depth**

This section describes the parameter pertaining to concurrent I/O processes for ZFS.

# zfs\_vdev\_max\_pending

Description This parameter controls the maximum number of concurrent I/Os

pending to each device.

Data Type Integer

Default 10

Range 0 to MAXINT

Dynamic? Yes

Validation No

When to Change In a storage array where LUNs are made of a large number of disk drives,

the ZFS queue can become a limiting factor on read IOPS. This behavior is one of the underlying reasoning for the best practice of presenting as

many LUNS as there are backing spindles to the ZFS storage pool. That is, if you create LUNS from a 10 disk-wide array level raid-group, then using 5 to 10 LUNs to build a storage pool allows ZFS to manage enough of an I/O queue without the need to set this specific tunable.

However, when no separate intent log is in use and the pool is made of JBOD disks, using a small <code>zfs\_vdev\_max\_pending</code> value, such as 10, can improve the synchronous write latency as those are competing for the disk resource. Using separate intent log devices can alleviate the need to tune this parameter for loads that are synchronously write intensive since those synchronous writes are not competing with a deep queue of non-synchronous writes.

Tuning this parameter is not expected to be effective for NVRAM-based storage arrays in the case where volumes are made of small number of spindles. However, when ZFS is presented with a volume made of a large (greater than 10) number of spindles, then this parameter can limit the read throughput obtained on the volume. The reason is that with a maximum of 10 or 35 queued I/Os per LUN, this can translate into less than 1 I/O per storage spindle, which is not enough for individual disks to deliver their IOPS. This issue would appear in iostat actv queue output approaching the value of zfs\_vdev\_max\_pending.

Device drivers may also limit the number of outstanding I/Os per LUN. If you are using LUNs on storage arrays that can handle large numbers of concurrent IOPS, then the device driver constraints can limit concurrency. Consult the configuration for the drivers your system uses. For example, the limit for the QLogic ISP2200, ISP2300, and SP212 family FCl HBA (qlc) driver is described as the execution-throttle parameter in /kernel/drv/qlc.conf.

Commitment Level Unstable

# **Tuning ZFS When Using Flash Storage**

The following information applies to Flash SSDs, F20 PCIe Accelerator Card, F40 PCIe Accelerator Card, F5100 Flash Storage Array, and F80 PCIe Accelerator Card.

Review the following general comments when using ZFS with Flash storage:

Consider using LUNs or low latency disks that are managed by a controller with persistent memory, if available, for the ZIL (ZFS intent log). This option can be considerably more cost effective than using flash for low latency commits. The size of the log devices must only be large enough to hold 10 seconds of maximum write throughput. Examples would include a storage array based LUN, or a disk connected to an HBA with a battery protected write cache.

- If no such device is available, segment a separate pool of flash devices for use as log devices in a ZFS storage pool.
- The F40, F20, and F80 Flash Accelerator cards contain and export 4 independent flash modules to the OS. The F5100 contains up to 80 independent flash modules. Each flash module appear to the operating system as a single device. SSDs are viewed as a single device by the OS. Flash devices may be used as ZFS log devices to reduce commit latency, particularly if used in an NFS server. For example, a single flash module of a flash device used as a ZFS log device can reduce latency of single lightly threaded operations by 10x. More flash devices can be striped together to achieve higher throughput for large amounts of synchronous operations.
- Log devices should be mirrored for reliability. For maximum protection, the mirrors should be created on separate flash devices. In the case of F20, F40, and F80 PCIe accelerator cards, maximum protection is achieved by ensuring that mirrors reside on different physical PCIe cards. Maximum protection with the F5100 storage array is obtained by placing mirrors on separate F5100 devices.
- Flash devices that are not used as log devices may be used as second level cache devices. This serves to both offload IOPS from primary disk storage and also to improve read latency for commonly used data.

# Adding Flash Devices as ZFS Log or Cache Devices

Review the following recommendations when adding flash devices as ZFS log or cache devices.

- A ZFS log or cache device can be added to an existing ZFS storage pool by using the zpool add command. Be very careful with zpool add commands. Mistakenly adding a log device as a normal pool device is a mistake that will require you to destroy and restore the pool from scratch. Individual log devices themselves can be removed from a pool.
- Familiarize yourself with the zpool add command before attempting this operation on active storage. You can use the zpool add -n option to preview the configuration without creating the configuration. For example, the following incorrect zpool add preview syntax attempts to add a device as a log device:

#### # zpool add -n tank c4t1d0

```
vdev verification failed: use -f to override the following errors: mismatched replication level: pool uses mirror and new vdev is disk Unable to build pool from specified devices: invalid vdev configuration
```

This is the correct zpool add preview syntax for adding a log device to an existing pool:

```
# zpool add -n tank log c4t1d0
would update 'tank' to the following configuration:
tank
```

mirror c4t0d0 c5t0d0 logs

c4t1d0

If multiple devices are specified, they are striped together. For more information, see the examples below or <code>zpool(1M)</code>.

A flash device, c4t1d0, can be added as a ZFS log device:

```
# zpool add pool log c4t1d0
```

If 2 flash devices are available, you can add mirrored log devices:

```
# zpool add pool log mirror c4t1d0 c4t2d0
```

Available flash devices can be added as a cache device for reads.

```
# zpool add pool cache c4t3d0
```

You can't mirror cache devices, they will be striped together.

# zpool add pool cache c4t3d0 c4t4d0

# **Ensuring Proper Cache Flush Behavior for Flash** and NVRAM Storage Devices

ZFS is designed to work with storage devices that manage a disk-level cache. ZFS commonly asks the storage device to ensure that data is safely placed on stable storage by requesting a cache flush. For JBOD storage, this works as designed and without problems. For many NVRAM-based storage arrays, a performance problem might occur if the array takes the cache flush request and actually does something with it, rather than ignoring it. Some storage arrays flush their large caches despite the fact that the NVRAM protection makes those caches as good as stable storage.

ZFS issues infrequent flushes (every 5 second or so) after the uberblock updates. The flushing infrequency is fairly inconsequential so no tuning is warranted here. ZFS also issues a flush every time an application requests a synchronous write (O\_DSYNC, fsync, NFS commit, and so on). The completion of this type of flush is waited upon by the application and impacts performance. Greatly so, in fact. From a performance standpoint, this neutralizes the benefits of having an NVRAM-based storage.

Cache flush tuning was recently shown to help flash device performance when used as log devices. When all LUNs exposed to ZFS come from NVRAM-protected storage array and procedures ensure that no unprotected LUNs will be added in the future, ZFS can be tuned to

not issue the flush requests by setting zfs\_nocacheflush. If some LUNs exposed to ZFS are not protected by NVRAM, then this tuning can lead to data loss, application level corruption, or even pool corruption. In some NVRAM-protected storage arrays, the cache flush command is a no-op, so tuning in this situation makes no performance difference.

A recent OS change is that the flush request semantic has been qualified to instruct storage devices to ignore the requests if they have the proper protection. This change requires a fix to our disk drivers and for the NVRAM device to support the updated semantics. If the NVRAM device does not recognize this improvement, use these instructions to tell the Solaris OS not to send any synchronize cache commands to the array. If you use these instructions, make sure all targeted LUNS are indeed protected by NVRAM.

Occasionally, flash and NVRAM devices do not properly advertise to the OS that they are non-volatile devices, and that caches do not need to be flushed. Cache flushing is an expensive operation. Unnecessary flushes can drastically impede performance in some cases.

Review the following zfs\_nocacheflush syntax restrictions before applying the tuning entries below:

- The tuning syntax below can be included in sd.conf but there must be only a single sd-config-list entry per vendor/product.
- If multiple devices entries are desired, multiple pairs of vendor IDs and sd tuning strings can be specified on the same line by using the following syntax:

Make sure the vendor ID (VID) string is padded to 8 characters and the Product ID (PID) string is padded to 16 characters as described in the preceding example.



**Caution -** All cache sync commands are ignored by the device. Use at your own risk.

1. Use the format utility to run the inquiry subcommand on a LUN from the storage array. For example:

- 2. Select one of the following based on your architecture:
  - For all devices, copy the file /kernel/drv/sd.conf to the /etc/driver/drv/sd.conf file.
  - For F40 flash devices, add the following entry to /kernel/drv/sd.conf. In the entry below, ensure that ATA is padded to 8 characters, and 3E128-TS2-550B01 contains 16 characters. Total string length is 24.
    - sd-config-list="ATA 3E128-TS2-550B01","disksort:false, cache-nonvolatile:true,
      physical-block-size:4096";
  - For F80 flash devices, add the following entry to /kernel/drv/sd.conf. Ensure that ATA is padded to 8 characters, and 3E128-TS2-550B01 contains 16 characters. Total string length is 24.
    - sd-config-list="ATA????2E256-TU2-510B00","disksort:false, cache-nonvolatile:true,
      physical-block-size:4096";
  - For F20 and F5100 flash devices, choose one of the following based on your architecture. In the entries below, ATA is padded to 8 characters, and MARVELL SD88SA02 contains 16 characters. The total string length is 24.
  - Add the following entry to /etc/driver/drv/sd.conf

```
sd-config-list="ATA MARVELL SD88SA02","throttle-max:32, disksort:false, cache-
nonvolatile:true";
```

- 3. Carefully add whitespace to make the vendor ID (VID) 8 characters long (here ATA) and Product ID (PID) 16 characters long (here MARVELL) in the sd-config-list entry as illustrated.
- 4. Reboot the system.
  - You can tune zfs\_nocacheflush back to it's default value (0) with no adverse effect on performance.
- 5. Confirm that the flush behavior is correct.
  - Use the script provided in Appendix A, "System Check Script" for verification.

# **Tuning ZFS for Database Products**

Review the following considerations when using ZFS with a database product.

- If the database uses a fixed disk block or record size for I/O, set the ZFS recordsize property to match it. You can do this on a per-file system basis, even though multiple file systems might share a single pool.
- With ZFS's copy-on-write design, tuning down the recordsize is a way to improve OLTP performance at the expense of batch reporting queries.
- ZFS checksums every block stored on disk. This alleviates the need for the database layer to checksum data an additional time. If checksums are computed by ZFS instead of at the

- database layer, any discrepancy can be caught and fixed before the data is returned to the application.
- UFS direct I/O is used to overcome some of the design deficiencies of UFS and to eliminate double buffering of data. In ZFS, the UFS design deficiencies do not exist and ZFS uses the primarycache and secondarycache properties to manage buffering data in the ARC. Note that using the secondarycache (L2ARC) property to improve random reads also requires the primarycache property to be enabled.
- Keep pool space under 90% utilization to maintain pool performance.

# **Tuning ZFS for an Oracle Database**

ZFS is recommended for any Oracle database version in single instance mode. ZFS can be used with an Oracle RAC database when it is available as a NFS-shared file system.

Review the following recommendations below for tuning ZFS for an Oracle database:

Verify that you are running the latest Oracle Solaris release.

Start with the latest Oracle Solaris 10 or Oracle Solaris 11 release, with the Solaris 10 9/10 release as a minimum starting point.

Create LUNs for your ZFS storage pools, if needed.

Use your storage array tools to create LUNs that will be presented to the ZFS storage pool. Or, consider using whole disks for your mirrored ZFS storage pools. For more information, see Chapter 5, "Managing Oracle Solaris ZFS Storage Pools" in *Managing ZFS File Systems in Oracle Solaris 11.3*.

Create a storage pool for data files for tables, index, undo and temp data.

Consider creating a mirrored storage pool to provide a higher level of data redundancy. For example:

#### # zpool status dbpool

pool: dbpool
state: ONLINE

scan: none requested

config:

NAME	STATE	READ	WRITE	CKSUM
dbpool	ONLINE	0	0	0
mirror-0	ONLINE	0	0	0
c0t5000C500335F95E3d0	ONLINE	0	0	0
c0t5000C500335F907Fd0	ONLINE	0	0	0
mirror-1	ONLINE	0	0	0
c0t5000C500335BD117d0	ONLINE	0	0	0
c0t5000C500335DC60Fd0	ONLINE	0	0	0

```
errors: No known data errors
```

For databases with high redo log activity, such as a typical OLTP database with many commits, use a separate LUN for a separate log device.

#### Create a storage pool for the archivelog.

If available, a system's internal disk can handle this type of load. The archivelog file system can also be a file system in the dbpool.

#### # zpool create archivepool c0t5000C500335E106Bd0

Create the ZFS file systems and set the specific file system properties by using the following guidelines.

Create separate file systems for redo, archive, undo, and temp database components and specify 1M for recordsize.

Note - If you are using Oracle Solaris 11 or previous releases, specify 128K for recordsize.

The general rule is to set the file system <code>recordsize = db\_block\_size</code> for the file systems that contains Oracle data files. For table data and index components, create a file system with an 8 KB record size. Also consider providing metadata caching hints for your database file systems by using the <code>primarycache</code> property. For more information about ZFS file system properties, see Chapter 7, "Managing Oracle Solaris ZFS File Systems" in <code>Managing ZFS File Systems</code> in <code>Oracle Solaris 11.3</code>.

Create file systems for the table data files and index data files with an 8 KB recordsize. Use the default value for primarycache.

```
# zfs create -o recordsize=8k -o mountpoint=/my_db_path/index dbpool/index
# zfs set logbias=throughput dbpool/index
```

# zfs get primarycache,recordsize,logbias dbpool/index

NAME	PROPERTY	VALUE	SOURCE
dbpool/index	primarycache	all	default
dbpool/index	recordsize	8K	local
dbpool/index	logbias	throughput	local

• Create file systems for temporary and undo table spaces.

For Oracle Solaris 11 and earlier releases, use the default recordsize and primarycache values.

```
# zfs create -o mountpoint=/my_db_path/temp dbpool/temp
# zfs set logbias=throughput dbpool/temp
# zfs create -o mountpoint=/my_db_path/undo dbpool/undo
# zfs set logbias=throughput dbpool/undo
```

For Oracle Solaris 11.1 and later releases, use the following recordsize and default primarycache values.

```
# zfs create -o recordsize=1m -o mountpoint=/my_db_path/temp dbpool/temp
# zfs set logbias=throughput dbpool/temp
# zfs create -o recordsize=1m -o mountpoint=/my_db_path/undo dbpool/undo
# zfs set logbias=throughput dbpool/undo
```

Create a storage pool for redo logs with a separate log device. For databases with high
redo log activity, such as a typical OLTP database with many commits, use a separate
log device LUN.

Partition the disk into two slices, a small slice, s0, in the 64 to 150 MB range, for the separate log device. The s1 slice contains the remaining disk space for the redo log.

# # zpool create redopool c0t50015179594B6F11d0s1 log c0t50015179594B6F11d0s0 # zpool status redopool

pool: redopool
state: ONLINE

scan: none requested

config:

NAME	STATE	READ	WRITE	CKSUM
redopool	ONLINE	0	0	0
c0t50015179594B6F11d0s1	ONLINE	0	0	0
logs				
c0t50015179594B6F11d0s0	ONLINE	0	0	0

errors: No known data errors

Create a file system for redo logs in the redo pool.

For Oracle Solaris 11 and earlier releases, use the default file system values for recordsize and primarycache.

```
# zfs create -o mountpoint=/my_db_path/redo redopool/redo
# zfs set logbias=latency redopool/redo
```

For Solaris 11.1 and later releases, use the following recordsize and default primarycache values.

```
# zfs create -o recordsize=lm -o mountpoint=/my_db_path/redo redopool/redo
# zfs set logbias=latency redopool/redo
```

• Create a file system for archivelog files in the archive pool.

For Oracle Solaris 11 and earlier releases, enable compression using the default value for recordsize and set primarycache to metadata.

archivepool/archive	primarycache	metadata	local
archivepool/archive	recordsize	128K	default
archivepool/archive	compressratio	1.32x	-
archivepool/archive	compression	on	local
archivepool/archive	available	40.0G	-
archivepool/archive	used	10.0G	-
archivepool/archive	quota	50G	local

For Solaris 11.1 and later releases - Enable compression, set primarycache to metadata and use the following recordsize value:

NAME	PROPERTY	VALUE	SOURCE
archivepool/archive	primarycache	all	local
archivepool/archive	recordsize	1M	local
archivepool/archive	compressratio	1.32x	-
archivepool/archive	compression	on	local
archivepool/archive	available	40.0G	-
archivepool/archive	used	10.0G	-
archivepool/archive	quota	50G	local

Consider setting quotas so that your database file systems have sufficient disk space to operate and taking snapshots of your database file systems. In addition, set a reservation on a dummy file system to reserve 10-20% of pool space to maintain pool performance.

#### # zfs set reservation=20gb dbpool/freespace

- For additional information about tuning storage arrays and memory resources, see the white paper at http://www.oracle.com/technetwork/server-storage/solaris/configsolaris-zfs-wp-167894.pdf.
- Additional Oracle database configuration recommendations
  - Configuring Your Oracle Database on ZFS File Systems in the white paper at http://www.oracle.com/technetwork/server-storage/solaris/config-solaris-zfs-wp-167894.pdf.
  - Dynamic SGA Tuning of Oracle Database on Oracle Solaris with DISM white paper at http://www.oracle.com/technetwork/articles/systems-hardware-architecture/ using-dynamic-intimate-memory-sparc-168402.pdf.
  - Oracle 11g Installation Guides
    - Oracle Database Quick Installation Guide 11g Release 2 (11.2) for Oracle Solaris on SPARC (64-Bit).
    - Oracle Database Quick Installation Guide 11g Release 2 (11.2) for Oracle Solaris on x86-64 (64-Bit)

# **Using ZFS with MySQL Considerations**

Review the following considerations when using ZFS with MySQL.

#### ZFS recordsize

Match the ZFS recordsize property to the storage engine block size for better OLTP performance.

#### InnoDB

With a known application memory footprint, such as for a database application, you might cap the ARC size so that the application will not need to reclaim its necessary memory from the ZFS cache.

- Create a separate pool for the logs.
- Set a different path for data and log in the my.cnf file.
- Set the ZFS recordsize property to 16K for the InnoDB data files, and use the default recordsize value for InnoDB logs, prior to creating data files.

# · · · CHAPTER 4

### **NFS Tunable Parameters**

This section describes the NFS tunable parameters.

- "Tuning the NFS Environment" on page 101
- "NFS Module Parameters" on page 101
- "NFS-Related SMF Configuration Parameters" on page 128
- "rpcmod Module Parameters" on page 130

For other types of tunable parameters, refer to the following:

- Oracle Solaris kernel tunable parameters Chapter 2, "Oracle Solaris Kernel Tunable Parameters"
- Oracle Solaris ZFS tunable parameters Chapter 3, "Oracle Solaris ZFS Tunable Parameters"
- Internet Protocol Suite tunable parameters Chapter 5, "Internet Protocol Suite Tunable Parameters"
- System facility tunable parameters Chapter 6, "System Facility Parameters"

# **Tuning the NFS Environment**

You can define NFS parameters in the /etc/system file, which is read during the boot process. Each parameter includes the name of its associated kernel module. For more information, see "Tuning the Oracle Solaris Kernel" on page 17.



**Caution -** The names of the parameters, the modules that they reside in, and the default values can change between releases. Check the documentation for the version of the active SunOS release before making changes or applying values from previous releases.

### **NFS Module Parameters**

This section describes parameters related to the NFS kernel module.

### nfs:nfs3 pathconf disable cache

Description Controls the caching of pathconf information for NFS Version 3

mounted file systems.

Data Type Integer (32-bit)

Default 0 (caching enabled)

Range 0 (caching enabled) or 1 (caching disabled)

Units Boolean values

Dynamic? Yes

Validation None

When to Change The pathconf information is cached on a per file basis. However, if the

NFS server can change the information for a specific file dynamically, use this parameter to disable caching. There is no mechanism for the NFS

client to validate its cache entry.

Commitment Level Unstable

# nfs:nfs\_allow\_preepoch\_time

Description

Controls whether files with incorrect or *negative* time stamps should be made visible on the NFS client.

Historically, neither the NFS client nor the NFS server would do any range checking on the file times being returned. The over-the-wire timestamp values are unsigned and 32-bits long. So, all values have been legal.

The timestamp values on the 64-bit Oracle Solaris kernel are signed and 64-bits long. It is impossible to determine whether a time field represents a full 32-bit time or a negative time, that is, a time prior to January 1, 1970.

It is impossible to determine whether to sign extend a time value when converting from 32 bits to 64 bits. The time value should be sign extended if the time value is truly a negative number. However, the time value should not be sign extended if it does truly represent a full 32-bit time value. This problem is resolved by simply disallowing full 32-bit time values.

Data Type Integer (32-bit)

Default 0 (32-bit time stamps disabled)

Range 0 (32-bit time stamps disabled) or 1 (32-bit time stamps enabled)

Units Boolean values

Dynamic? Yes

Validation None

When to Change Even during normal operation, it is possible for the timestamp values

on some files to be set very far in the future or very far in the past. If access to these files is preferred using NFS mounted file systems, set this parameter to 1 to allow the timestamp values to be passed through

unchecked.

Commitment Level Unstable

### nfs:nfs\_cots\_timeo

Description Controls the default RPC timeout for NFS version 2 mounted file

systems using connection-oriented transports such as TCP for the

transport protocol.

Data Type Signed integer (32-bit)

Default 600 (60 seconds)

Range  $0 \text{ to } 2^{31} - 1$ 

Units 10th of seconds

Dynamic? Yes, but the RPC timeout for a file system is set when the file system is

mounted. To affect a particular file system, unmount and mount the file

system after changing this parameter.

Validation None

When to Change TCP does a good job ensuring requests and responses are delivered

appropriately. However, if the round-trip times are very large in a particularly slow network, the NFS version 2 client might time out

prematurely.

Increase this parameter to prevent the client from timing out incorrectly. The range of values is very large, so increasing this value too much might result in situations where a retransmission is not detected for long periods of time.

Commitment Level Unstable

### nfs:nfs3 cots timeo

Description Controls the default RPC timeout for NFS version 3 mounted file

systems using connection-oriented transports such as TCP for the

transport protocol.

Data Type Signed integer (32-bit)

Default 600 (60 seconds)

Range  $0 \text{ to } 2^{31} - 1$ 

Units 10th of seconds

Dynamic? Yes, but the RPC timeout for a file system is set when the file system is

mounted. To affect a particular file system, unmount and mount the file

system after changing this parameter.

Validation None

When to Change TCP does a good job ensuring requests and responses are delivered

appropriately. However, if the round-trip times are very large in a particularly slow network, the NFS version 3 client might time out

prematurely.

Increase this parameter to prevent the client from timing out incorrectly. The range of values is very large, so increasing this value too much might result in situations where a retransmission is not detected for long periods

of time.

Commitment Level Unstable

### nfs:nfs4\_cots\_timeo

Description Controls the default RPC timeout for NFS version 4 mounted file

systems using connection-oriented transports such as TCP for the

transport protocol.

The NFS Version 4 protocol specification disallows retransmission over the same TCP connection. Thus, this parameter primarily controls how quickly the NFS client responds to certain events, such as detecting a forced unmount operation or detecting how quickly the NFS server fails over to a new server.

Data Type Signed integer (32-bit)

Default 600 (60 seconds)

Range  $0 \text{ to } 2^{31} - 1$ 

Units 10th of seconds

Dynamic? Yes, but this parameter is set when the file system is mounted. To affect a

particular file system, unmount and mount the file system after changing

this parameter.

Validation None

When to Change TCP does a good job ensuring requests and responses are delivered

appropriately. However, if the round-trip times are very large in a particularly slow network, the NFS version 4 client might time out

prematurely.

Increase this parameter to prevent the client from timing out incorrectly. The range of values is very large, so increasing this value too much might result in situations where a retransmission is not detected for long periods

of time.

Commitment Level Unstable

### nfs:nfs\_do\_symlink\_cache

Description Controls whether the contents of symbolic link files are cached for NFS

version 2 mounted file systems.

Data Type Integer (32–bit)

Default 1 (caching enabled)

Range 0 (caching disabled) or 1 (caching enabled)

Units Boolean values

Dynamic? Yes

Validation None

When to Change If a NFS server changes the contents of a symbolic link file without

updating the modification timestamp on the file or if the granularity of the timestamp is too large, then changes to the contents of the symbolic link file might not be visible on the NFS client for extended periods. In this case, use this parameter to disable the caching of symbolic link contents. Doing so makes the changes immediately visible to applications

running on the client.

Commitment Level Unstable

### nfs:nfs3\_do\_symlink\_cache

Description Controls whether the contents of symbolic link files are cached for NFS

version 3 mounted file systems.

Data Type Integer (32-bit)

Default 1 (caching enabled)

Range 0 (caching disabled) or 1 (caching enabled)

Units Boolean values

Dynamic? Yes

Validation None

When to Change If a NFS server changes the contents of a symbolic link file without

updating the modification timestamp on the file or if the granularity of the timestamp is too large, then changes to the contents of the symbolic link file might not be visible on the NFS client for extended periods. In this case, use this parameter to disable the caching of symbolic link contents. Doing so makes the changes immediately visible to applications

running on the client.

Commitment Level Unstable

### nfs:nfs\_dynamic

Description Controls whether a feature known as *dynamic retransmission* is enabled

for NFS version 2 mounted file systems using connectionless transports

such as UDP. This feature attempts to reduce retransmissions by monitoring NFS server response times and then adjusting RPC timeouts

and read- and write- transfer sizes.

Data Type Integer (32-bit)

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Dynamic? Yes, but this parameter is set per file system at mount time. To affect a

particular file system, unmount and mount the file system after changing

this parameter.

Validation None

When to Change Do not change this parameter.

Commitment Level Unstable

### nfs:nfs3\_dynamic

Description Controls whether a feature known as *dynamic retransmission* is enabled

for NFS version 3 mounted file systems using connectionless transports

such as UDP. This feature attempts to reduce retransmissions by monitoring NFS server response times and then adjusting RPC timeouts

and read- and write- transfer sizes.

Data Type Integer (32-bit)

Default 0 (disabled)

Range 0 (disabled) or 1 (enabled)

Units Boolean values

Dynamic? Yes, but this parameter is set per file system at mount time. To affect a

particular file system, unmount and mount the file system after changing

this parameter.

Validation None

When to Change Do not change this parameter.

Commitment Level Unstable

### nfs:nfs\_lookup\_neg\_cache

Description Controls whether a negative name cache is used for NFS version 2

mounted file systems. This negative name cache records file names that were looked up, but not found. The cache is used to avoid over-the-network look-up requests made for file names that are already known to

not exist.

Data Type Integer (32-bit)

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Units Boolean values

Dynamic? Yes

Validation None

When to Change For the cache to perform correctly, negative entries must be strictly

verified before they are used. This consistency mechanism is relaxed slightly for read-only mounted file systems. It is assumed that the file system on the NFS server is not changing or is changing very slowly, and that it is okay for such changes to propagate slowly to the NFS client. The consistency mechanism becomes the normal attribute cache

mechanism in this case.

If file systems are mounted read-only on the NFS client, but are expected to change on the NFS server and these changes need to be seen immediately by the client, use this parameter to disable the negative

cache.

If you disable the nfs:nfs\_disable\_rddir\_cache parameter, you should probably also disable this parameter. For more information, see "nfs:

nfs\_disable\_rddir\_cache" on page 117.

Commitment Level Unstable

### nfs:nfs3 lookup neg cache

Description Controls whether a negative name cache is used for NFS version 3 read-

only mounted file systems. This negative name cache records file names that were looked up, but were not found. The cache is used to avoid overthe-network look-up requests made for file names that are already known

to not exist.

Data Type Integer (32-bit)

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Units Boolean values

Dynamic? Yes

Validation None

When to Change For the cache to perform correctly, negative entries must be strictly

verified before they are used. This consistency mechanism is relaxed slightly for read-only mounted file systems. It is assumed that the file system on the NFS server is not changing or is changing very slowly, and that it is okay for such changes to propagate slowly to the NFS client. The consistency mechanism becomes the normal attribute cache

mechanism in this case.

If file systems are mounted read-only on the client, but are expected to change on the NFS server and these changes need to be seen immediately by the NFS client, use this parameter to disable the negative cache.

If you disable the  $nfs:nfs\_disable\_rddir\_cache$  parameter, you should probably also disable this parameter. For more information, see "nfs:

nfs\_disable\_rddir\_cache" on page 117.

Commitment Level Unstable

# nfs:nfs4\_lookup\_neg\_cache

Description Controls whether a negative name cache is used for NFS version 4

mounted file systems. This negative name cache records file names that were looked up, but were not found. The cache is used to avoid over-the-network look-up requests made for file names that are already known to

not exist.

Data Type Integer (32-bit)

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Units Boolean values

Dynamic? Yes

Validation None

When to Change For the cache to perform correctly, negative entries must be strictly

verified before they are used. This consistency mechanism is relaxed slightly for read-only mounted file systems. It is assumed that the file system on the NFS server is not changing or is changing very slowly, and that it is okay for such changes to propagate slowly to the NFS client. The consistency mechanism becomes the normal attribute cache mechanism in this case.

If file systems are mounted read-only on the NFS client, but are expected to change on the NFS server and these changes need to be seen immediately by the client, use this parameter to disable the negative cache.

If you disable the nfs:nfs\_disable\_rddir\_cache parameter, you should probably also disable this parameter. For more information, see "nfs: nfs disable rddir cache" on page 117.

Commitment Level Unstable

## nfs:nfs\_max\_threads

Description Controls the number of kernel threads that perform asynchronous I/O

for each file system for the NFS version 2 client. Because NFS is based on RPC and RPC is inherently synchronous, separate execution contexts are required to perform NFS operations that are asynchronous from the

calling thread.

The operations that can be executed asynchronously are read for read-ahead, readdir for readdir read-ahead, write for putpage and pageio operations, commit, and inactive for cleanup operations that the NFS

client performs when it stops using a file.

Data Type Unsigned short

Default 8

Range 0 to 2<sup>15</sup> - 1

Units Threads

Dynamic? Yes, but this parameter is set per file system at mount time. To affect a

particular file system, unmount and mount the file system after changing

this parameter.

Validation None

When to Change

To increase or reduce the number of simultaneous I/O operations that are outstanding at any given time. For example, for a very low bandwidth network, you might want to decrease this value so that the NFS client does not overload the network. Alternately, if the network is very high bandwidth, and the NFS client and NFS server have sufficient resources, you might want to increase this value. Doing so can more effectively utilize the available network bandwidth, and the client and server resources.

Commitment Level Unstable

#### nfs:nfs3\_max\_threads

Description Controls the number of kernel threads that perform asynchronous I/O

for each file system for the NFS version 3 client. Because NFS is based on RPC and RPC is inherently synchronous, separate execution contexts are required to perform NFS operations that are asynchronous from the

calling thread.

The operations that can be executed asynchronously are read for readahead, readdir for readdir read-ahead, write for putpage and pageio

requests, and commit.

Data Type Unsigned short

Default 8

Range 0 to 2<sup>15</sup> - 1

Units Threads

Dynamic? Yes, but this parameter is set per file system at mount time. To affect a

particular file system, unmount and mount the file system after changing

this parameter.

Validation None

When to Change To increase or reduce the number of simultaneous I/O operations that are

outstanding at any given time. For example, for a very low bandwidth network, you might want to decrease this value so that the NFS client does not overload the network. Alternately, if the network is very high bandwidth, and the NFS client and NFS server have sufficient resources, you might want to increase this value. Doing so can more effectively utilize the available network bandwidth, and the client and server

resources.

Commitment Level Unstable

#### nfs:nfs4 max threads

Description Controls the number of kernel threads that perform asynchronous I/O

for each file system for the NFS version 4 client. Because NFS is based on RPC and RPC is inherently synchronous, separate execution contexts are required to perform NFS operations that are asynchronous from the

calling thread.

The operations that can be executed asynchronously are read for readahead, write-behind, directory read-ahead, and cleanup operations that

the client performs when it stops using a file.

Data Type Unsigned short

Default 8

Range 0 to 2<sup>15</sup> - 1

Units Threads

Dynamic? Yes, but this parameter is set per file system at mount time. To affect a

particular file system, unmount and mount the file system after changing

this parameter.

Validation None

When to Change To increase or reduce the number of simultaneous I/O operations that are

outstanding at any given time. For example, for a very low bandwidth network, you might want to decrease this value so that the NFS client does not overload the network. Alternately, if the network is very high bandwidth, and the NFS client and NFS server have sufficient resources, you might want to increase this value. Doing so can more effectively utilize the available network bandwidth, and the client and server

resources.

Commitment Level Unstable

# nfs:nfs\_nra

Description Controls the number of read-ahead operations that are queued by the

NFS version 2 client when sequential access to a file is discovered. These read-ahead operations increase concurrency and read throughput. Each read-ahead request is generally for one logical block of file data.

Data Type Integer (32-bit)

Default 4

Range  $0 \text{ to } 2^{31} - 1$ 

Units Logical blocks.

Dynamic? Yes

Validation None

When to Change To increase or reduce the number of read-ahead requests that are

outstanding for a specific file at any given time. For example, for a very low bandwidth network or on a low memory client, you might want to decrease this value so that the NFS client does not overload the network or the system memory. Alternately, if the network is very high bandwidth, and the NFS client and NFS server have sufficient resources, you might want to increase this value. Doing so can more effectively utilize the available network bandwidth, and the client and

server resources.

Commitment Level Unstable

## nfs:nfs3 nra

Description Controls the number of read-ahead operations that are queued by the

NFS version 3 client when sequential access to a file is discovered. These read-ahead operations increase concurrency and read throughput. Each read-ahead request is generally for one logical block of file data.

Data Type Integer (32-bit)

Default 4

Range  $0 \text{ to } 2^{31} - 1$ 

Units Logical blocks. (See "nfs:nfs3\_bsize" on page 118.)

Dynamic? Yes

Validation None

When to Change To increase or reduce the number of read-ahead requests that are

outstanding for a specific file at any given time. For example, for a very

low bandwidth network or on a low memory client, you might want to decrease this value so that the NFS client does not overload the network or the system memory. Alternately, if the network is very high bandwidth and the NFS client and NFS server have sufficient resources, you might want to increase this value. Doing so can more effectively utilize the available network bandwidth, and the client and server resources.

Commitment Level Unstable

#### nfs:nrnode

Description Controls the size of the rnode cache on the NFS client.

> The rnode, used by NFS version 2, 3, and 4 clients, is the central data structure that describes a file on the NFS client. The rnode contains the file handle that identifies the file on the NFS server. The rnode also contains pointers to various caches used by the NFS client to avoid network calls to the server. Each rnode has a one-to-one association with

a vnode. The vnode caches file data.

The NFS client attempts to maintain a minimum number of rnodes to attempt to avoid destroying cached data and metadata. When an rnode is reused or freed, the cached data and metadata must be destroyed.

Data Type Integer (32-bit)

Default The default setting of this parameter is 0, which means that the value of

> nrnode should be set to the value of the ncsize parameter. Actually, any non positive value of nrnode results in nrnode being set to the value of

ncsize.

1 to 2<sup>31</sup> - 1 Range

Units rnodes

Dynamic? No. This value can only be changed by adding or changing the parameter

in the /etc/system file, and then rebooting the system.

Validation The system enforces a maximum value such that the rnode cache can

only consume 25 percent of available memory.

When to Change Because rnodes are created and destroyed dynamically, the system tends

> to settle upon a *nrnode*-size cache, automatically adjusting the size of the cache as memory pressure on the system increases or as more files are simultaneously accessed. However, in certain situations, you could set

the value of nrnode if the mix of files being accessed can be predicted in advance. For example, if the NFS client is accessing a few very large files, you could set the value of nrnode to a small number so that system memory can cache file data instead of rnodes. Alternately, if the client is accessing many small files, you could increase the value of nrnode to optimize for storing file metadata to reduce the number of network calls for metadata.

Although it is not recommended, the rnode cache can be effectively disabled by setting the value of nrnode to 1. This value instructs the client to only cache 1 rnode, which means that it is reused frequently.

Commitment Level Unstable

## nfs:nfs\_shrinkreaddir

Description Some older NFS servers might incorrectly handle NFS version 2 READDIR

requests for more than 1024 bytes of directory information. This problem is due to a bug in the server implementation. However, this parameter  $\frac{1}{2}$ 

contains a workaround in the NFS version 2 client.

When this parameter is enabled, the client does not generate a READDIR request for larger than 1024 bytes of directory information. If this parameter is disabled, then the over-the-wire size is set to the lesser of either the size passed in by using the getdents system call or by using NFS\_MAXDATA, which is 8192 bytes. For more information, see

getdents(2).

Data Type Integer (32-bit)

Default 0 (disabled)

Range 0 (disabled) or 1 (enabled)

Units Boolean values

Dynamic? Yes

Validation None

When to Change Examine the value of this parameter if an older NFS version 2 only

server is used and interoperability problems occur when the server tries to read directories. Enabling this parameter might cause a slight decrease

in performance for applications that read directories.

#### nfs:nfs3 shrinkreaddir

Description Some older NFS servers might incorrectly handle NFS version 3 READDIR

requests for more than 1024 bytes of directory information. This problem is due to a bug in the server implementation. However, this parameter

contains a workaround in the NFS version 3 client.

When this parameter is enabled, the client does not generate a READDIR request for larger than 1024 bytes of directory information. If this parameter is disabled, then the over-the-wire size is set to the minimum of either the size passed in by using the getdents system call or by using MAXBSIZE, which is 8192 bytes. For more information, see the

getdents(2) man page.

Data Type Integer (32-bit)

Default 0 (disabled)

Range 0 (disabled) or 1 (enabled)

Units Boolean values

Dynamic? Yes

Validation None

When to Change Examine the value of this parameter if an older NFS version 3 only

server is used and interoperability problems occur when the server tries to read directories. Enabling this parameter might cause a slight decrease

in performance for applications that read directories.

Commitment Level Unstable

## nfs:nfs\_write\_error\_interval

Description Controls the time duration in between logging ENOSPC and EDQUOT write

errors received by the NFS client. This parameter affects NFS version 2,

3, and 4 clients.

Data Type Long integer (64-bit)

Default 5 seconds

Range 0 to 2<sup>63</sup> - 1

Units Seconds

Dynamic? Yes

Validation None

When to Change Increase or decrease the value of this parameter in response to the volume

of messages being logged by the NFS client. Typically, you might want to increase the value of this parameter to decrease the number of out of space messages being printed when a full file system on a NFS server is

being actively used.

Commitment Level Unstable

# nfs:nfs\_write\_error\_to\_cons\_only

Description Controls whether NFS write errors are logged to the system console and

syslog or to the system console only. This parameter affects messages

for NFS version 2, 3, and 4 clients.

Data Type Integer (32-bit)

Default 0 (system console and syslog)

Range 0 (system console and syslog) or 1 (system console)

Units Boolean values

Dynamic? Yes

Validation None

When to Change Examine the value of this parameter to avoid filling up the file system

containing the messages logged by the syslogd daemon. When this parameter is enabled, messages are printed on the system console only

and are not copied to the syslog messages file.

Commitment Level Unstable

# nfs:nfs\_disable\_rddir\_cache

Description Controls the use of a cache to hold responses from READDIR and

READDIRPLUS requests. This cache avoids over-the-wire calls to the NFS

server to retrieve directory information.

Data Type Integer (32-bit)

Default 0 (caching enabled)

Range 0 (caching enabled) or 1 (caching disabled)

Units Boolean values

Dynamic? Yes

Validation None

When to Change Examine the value of this parameter if interoperability problems develop

due to a NFS server that does not update the modification time on a directory when a file or directory is created in it or removed from it. The symptoms are that new names do not appear in directory listings after they have been added to the directory or that old names do not disappear

after they have been removed from the directory.

This parameter controls the caching for NFS version 2, 3, and 4 mounted file systems. This parameter applies to all NFS mounted file systems, so caching cannot be disabled or enabled on a per file system basis.

If you disable this parameter, you should also disable the following parameters to prevent bad entries in the DNLC negative cache:

"nfs:nfs\_lookup\_neg\_cache" on page 108

"nfs:nfs3\_lookup\_neg\_cache" on page 108

"nfs:nfs4\_lookup\_neg\_cache" on page 109

Commitment Level Unstable

## nfs:nfs3 bsize

Description Controls the logical block size used by the NFS version 3 client. This

block size represents the amount of data that the client attempts to read

from or write to the NFS server when it needs to do an I/O.

Data Type Unsigned integer (32-bit)

Default 32,768 (32 KB)

Range  $0 \text{ to } 2^{31} - 1$ 

Units Bytes

Dynamic? Yes, but the block size for a file system is set when the file system is

mounted. To affect a particular file system, unmount and mount the file

system after changing this parameter.

Validation None. Setting this parameter too low or too high might cause the system

to malfunction. Do not set this parameter to anything less than PAGESIZE for the specific platform. Do not set this parameter too high because it might cause the system to hang while waiting for memory allocations to

be granted.

When to Change Examine the value of this parameter when attempting to change the

maximum data transfer size. Change this parameter in conjunction with the nfs:nfs3\_max\_transfer\_size parameter. If larger transfers are preferred, increase both parameters. If smaller transfers are preferred,

then just reducing this parameter should suffice.

Commitment Level Unstable

## nfs:nfs4\_bsize

Description Controls the logical block size used by the NFS version 4 client. This

block size represents the amount of data that the client attempts to read

from or write to the NFS server when it needs to do an I/O.

Data Type Unsigned integer (32-bit)

Default 32,768 (32 KB)

Range  $0 \text{ to } 2^{31} - 1$ 

Units Bytes

Dynamic? Yes, but the block size for a file system is set when the file system is

mounted. To affect a particular file system, unmount and mount the file

system after changing this parameter.

Validation None. Setting this parameter too low or too high might cause the system

to malfunction. Do not set this parameter to anything less than PAGESIZE for the specific platform. Do not set this parameter too high because it might cause the system to hang while waiting for memory allocations to

be granted.

When to Change Examine the value of this parameter when attempting to change the

maximum data transfer size. Change this parameter in conjunction with the nfs:nfs4 max transfer size parameter. If larger transfers are preferred, increase both parameters. If smaller transfers are preferred, then just reducing this parameter should suffice.

Commitment Level Unstable

## nfs:nfs\_async\_clusters

Description Controls the mix of asynchronous requests that are generated by the NFS

version 2 client. The four types of asynchronous requests are read-ahead, putpage, pageio, and readdir-ahead. The client attempts to round-robin between these different request types to attempt to be fair and not starve

one request type in favor of another.

However, the functionality in some NFS version 2 servers such as write gathering depends upon certain behaviors of existing NFS Version 2 clients. In particular, this functionality depends upon the client sending out multiple WRITE requests at about the same time. If one request is taken out of the queue at a time, the client would be defeating this server

functionality designed to enhance performance for the client.

Thus, use this parameter to control the number of requests of each

request type that are sent out before changing types.

Data Type Unsigned integer (32-bit)

Default 1

Range  $0 \text{ to } 2^{31} - 1$ 

Units Asynchronous requests

Dynamic? Yes, but the cluster setting for a file system is set when the file system is

mounted. To affect a particular file system, unmount and mount the file

system after changing this parameter.

Validation None. However, setting the value of this parameter to 0 causes all of

the queued requests of a particular request type to be processed before moving on to the next type. This effectively disables the fairness portion

of the algorithm.

When to Change To increase the number of each type of asynchronous request that is

generated before switching to the next type. Doing so might help with NFS server functionality that depends upon clusters of requests coming

from the NFS client.

#### nfs:nfs3\_async\_clusters

Description Controls the mix of asynchronous requests that are generated by the

NFS version 3 client. The five types of asynchronous requests are readahead, putpage, pageio, readdir-ahead, and commit. The client attempts to round-robin between these different request types to attempt to be fair

and not starve one request type in favor of another.

However, the functionality in some NFS version 3 servers such as write gathering depends upon certain behaviors of existing NFS version 3 clients. In particular, this functionality depends upon the client sending out multiple WRITE requests at about the same time. If one request is taken out of the queue at a time, the client would be defeating this server functionality designed to enhance performance for the client.

Thus, use this parameter to control the number of requests of each

request type that are sent out before changing types.

Data Type Unsigned integer (32-bit)

Default 1

Range  $0 \text{ to } 2^{31} - 1$ 

Units Asynchronous requests

Dynamic? Yes, but the cluster setting for a file system is set when the file system is

mounted. To affect a particular file system, unmount and mount the file

system after changing this parameter.

Validation None. However, setting the value of this parameter to 0 causes all of

the queued requests of a particular request type to be processed before moving on to the next type. This value effectively disables the fairness

portion of the algorithm.

When to Change To increase the number of each type of asynchronous operation that is

generated before switching to the next type. Doing so might help with NFS server functionality that depends upon clusters of operations coming

from the NFS client.

Commitment Level Unstable

## nfs:nfs4\_async\_clusters

Description Controls the mix of asynchronous requests that are generated by the NFS

version 4 client. The six types of asynchronous requests are read-ahead,

putpage, pageio, readdir-ahead, commit, and inactive. The client attempts to round-robin between these different request types to attempt to be fair and not starve one request type in favor of another.

However, the functionality in some NFS version 4 servers such as write gathering depends upon certain behaviors of existing NFS version 4 clients. In particular, this functionality depends upon the client sending out multiple WRITE requests at about the same time. If one request is taken out of the queue at a time, the client would be defeating this server functionality designed to enhance performance for the client.

Thus, use this parameter to control the number of requests of each request type that are sent out before changing types.

Data Type Unsigned integer (32-bit)

Default 1

Range  $0 \text{ to } 2^{31} - 1$ 

Units Asynchronous requests

Dynamic? Yes, but the cluster setting for a file system is set when the file system is

mounted. To affect a particular file system, unmount and mount the file

system after changing this parameter.

Validation None. However, setting the value of this parameter to 0 causes all of

the queued requests of a particular request type to be processed before moving on to the next type. This effectively disables the fairness portion

of the algorithm.

When to Change To increase the number of each type of asynchronous request that is

generated before switching to the next type. Doing so might help with NFS server functionality that depends upon clusters of requests coming

from the NFS client.

Commitment Level Unstable

## nfs:nfs\_async\_timeout

Description Controls the duration of time that threads, which execute asynchronous

I/O requests, sleep with nothing to do before exiting. When there are no more requests to execute, each thread goes to sleep. If no new requests come in before this timer expires, the thread wakes up and exits. If a request does arrive, a thread is woken up to execute requests until there

are none again. Then, the thread goes back to sleep waiting for another request to arrive, or for the timer to expire.

Data Type Integer (32-bit)

Default 6000 (1 minute expressed as 60 sec \* 100Hz)

Range  $0 \text{ to } 2^{31} - 1$ 

Units Hz. (Typically, the clock runs at 100Hz.)

Dynamic? Yes

Validation None. However, setting this parameter to a non positive value causes

these threads exit as soon as there are no requests in the queue for them

to process.

rate of asynchronous I/O requests can be predicted, it might be possible to tune this parameter to optimize performance slightly in either of the

following ways:

By making the threads expire more quickly, thus freeing up kernel

resources more quickly

By making the threads expire more slowly, thus avoiding thread

create and destroy overhead

Commitment Level Unstable

#### nfs:nacache

Description Tunes the number of hash queues that access the file access cache on

the NFS client. The file access cache stores file access rights that users have with respect to files that they are trying to access. The cache itself is dynamically allocated. However, the hash queues used to index into the cache are statically allocated. The algorithm assumes that there is one access cache entry per active file and four of these access cache entries per hash bucket. Thus, by default, the value of this parameter is set to the

value of the nrnode parameter.

Data Type Integer (32-bit)

Default The default setting of this parameter is 0. This value means that the value

of nacache should be set to the value of the nrnode parameter.

Range 1 to 2<sup>31</sup> - 1

Units Access cache entries

Dynamic? No. This value can only be changed by adding or changing the parameter

in the /etc/system file, and then rebooting system.

Validation None. However, setting this parameter to a negative value will probably

cause the system to try to allocate a very large set of hash queues. While

trying to do so, the system is likely to hang.

When to Change Examine the value of this parameter if the basic assumption of one access

cache entry per file would be violated. This violation could occur for systems in a timesharing mode where multiple users are accessing the same file at about the same time. In this case, it might be helpful to increase the expected size of the access cache so that the hashed access to

the cache stays efficient.

Commitment Level Unstable

## nfs:nfs3 jukebox delay

Description Controls the duration of time that the NFS version 3 client waits to

transmit a new request after receiving the NFS3ERR\_JUKEBOX error from a previous request. The NFS3ERR\_JUKEBOX error is generally returned from the NFS server when the file is temporarily unavailable for some reason. This error is generally associated with hierarchical storage, and CD or

tape jukeboxes.

Data Type Long integer (64-bit)

Default 1000 (10 seconds expressed as 10 sec \* 100Hz)

Range  $0 \text{ to } 2^{63} - 1 \text{ on } 64\text{-bit platforms}$ 

Units Hz. (Typically, the clock runs at 100Hz.)

Dynamic? Yes

Validation None

When to Change Examine the value of this parameter and perhaps adjust it to match the

behaviors exhibited by the NFS server. Increase this value if the delays in making the file available are long in order to reduce network overhead due to repeated retransmissions. Decrease this value to reduce the delay

in discovering that the file has become available.

Commitment Level Unstable

## nfs:nfs3\_max\_transfer\_size

Description Controls the maximum size of the data portion of an NFS version 3 READ,

WRITE, READDIR, or READDIRPLUS request. This parameter controls both the maximum size of the request that the NFS server returns as well as

the maximum size of the request that the NFS client generates.

Data Type Integer (32-bit)

Default 194,304 (MB)

Range  $0 \text{ to } 2^{31} - 1$ 

Units Bytes

Dynamic? Yes, but this parameter is set per file system at mount time. To affect a

particular file system, unmount and mount the file system after changing

this parameter.

Validation None. However, setting the maximum transfer size on the NFS server

to 0 is likely to cause NFS clients to malfunction or just decide not to

attempt to talk to the server.

There is also a limit on the maximum transfer size when using NFS over the UDP transport. UDP has a hard limit of 64 KB per datagram. This 64 KB must include the RPC header as well as other NFS information, in addition to the data portion of the request. Setting the limit too high might result in errors from UDP and communication problems between

the NFS client and the NFS server.

When to Change To tune the size of data transmitted over the network. In general, the nfs:

nfs3 bsize parameter should also be updated to reflect changes in this

parameter.

For example, when you attempt to increase the transfer size beyond 32 KB, update nfs:nfs3\_bsize to reflect the increased value. Otherwise, no change in the over-the-wire request size is observed. For more

information, see "nfs:nfs3 bsize" on page 118.

If you want to use a smaller transfer size than the default transfer size, use the mount command's -wsize or -rsize option on a per-file system

basis.

#### nfs:nfs4\_max\_transfer\_size

Description Controls the maximum size of the data portion of an NFS version 4 READ,

WRITE, READDIR, or READDIRPLUS request. This parameter controls both the maximum size of the request that the NFS server returns as well as the maximum size of the request that the NFS client generates.

Data Type Integer (32-bit)

Default 32, 768 (32 KB)

Range  $0 \text{ to } 2^{31} - 1$ 

Units Bytes

Dynamic? Yes, but this parameter is set per file system at mount time. To affect a

particular file system, unmount and mount the file system after changing

this parameter.

Validation None. However, setting the maximum transfer size on the NFS server to

0 is likely to causeFS clients to malfunction or just decide not to attempt

to talk to the server.

There is also a limit on the maximum transfer size when using NFS over the UDP transport. For more information on the maximum for UDP, see

"nfs:nfs3 max transfer size" on page 125.

When to Change To tune the size of data transmitted over the network. In general, the nfs:

nfs4 bsize parameter should also be updated to reflect changes in this

parameter.

For example, when you attempt to increase the transfer size beyond 32 KB, update nfs:nfs4\_bsize to reflect the increased value. Otherwise, no change in the over-the-wire request size is observed. For more

information, see "nfs:nfs4 bsize" on page 119.

If you want to use a smaller transfer size than the default transfer size, use the mount command's -wsize or -rsize option on a per-file system

basis.

Commitment Level Unstable

# nfs:nfs3\_max\_transfer\_size\_clts

Description Controls the maximum size of the data portion of an NFS version 3 READ,

WRITE, READDIR, or READDIRPLUS request over UDP. This parameter

controls both the maximum size of the request that the NFS server returns as well as the maximum size of the request that the NFS client  $\frac{1}{2}$ 

generates.

Data Type Integer (32-bit)

Default 32, 768 (32 KB)

Range  $0 \text{ to } 2^{31} - 1$ 

Units Bytes

Dynamic? Yes, but this parameter is set per file system at mount time. To affect a

particular file system, unmount and mount the file system after changing

this parameter.

Validation None. However, setting the maximum transfer size on the NFS server

to 0 is likely to cause NFS clients to malfunction or just decide not to

attempt to talk to the server.

When to Change Do not change this parameter.

Commitment Level Unstable

# nfs:nfs3\_max\_transfer\_size\_cots

Description Controls the maximum size of the data portion of an NFS version 3

READ, WRITE, READDIR, or READDIRPLUS request over TCP. This parameter controls both the maximum size of the request that the NFS server returns as well as the maximum size of the request that the NFS client

generates.

Data Type Integer (32-bit)

Default 1,048,576 bytes

Range  $0 \text{ to } 2^{31} - 1$ 

Units Bytes

Dynamic? Yes, but this parameter is set per file system at mount time. To affect a

particular file system, unmount and mount the file system after changing

this parameter.

Validation None. However, setting the maximum transfer size on the NFS server

to 0 is likely to cause NFS clients to malfunction or just decide not to

attempt to talk to the server.

When to Change Do not change this parameter unless transfer sizes larger than 1 MB are

preferred.

Commitment Level Unstable

# **NFS-Related SMF Configuration Parameters**

In Oracle Solaris 11.2, the network/nfs/server service includes the nfs-props property group, which provides configurable parameters to control the refresh of the NFS authentication cache and to control the mountd netgroup cache.

- "server authz cache refresh" on page 128
- "netgroup\_refresh" on page 128

You can use sharectl command to get and set these properties.

```
# sharectl get -p server_authz_cache_refresh nfs
server_authz_cache_refresh=600
$ sharectl set -p server_authz_cache_refresh=1 nfs
```

You can also get and set these properties by using SMF commands but you will need to refresh the network/nfs/server service.

```
# svccfg -s nfs/server:default setprop nfs-props/server_authz_cache_refresh=1
# svcprop -p nfs-props/server_authz_cache_refresh svc:/network/nfs/server:default
1
# svcadm restart nfs/server:default
```

# server\_authz\_cache\_refresh

This parameter controls the refresh of the NFS authentication cache. The default value of the integer property is 600, the minimum is 0, and the max is INT32\_MAX. A value of zero ('0') means no expiration.

# netgroup\_refresh

This parameter controls the mountd netgroup cache. The default value of the integer property is 600, the minimum is 0, and the max is INT32\_MAX. A value of zero ('0') means no expiration.

#### nfssrv Module Parameters

This section describes NFS parameter for the nfssrv module.

#### nfssrv:nfs\_portmon

**Note** - This parameter is deprecated in Oracle Solaris 11.3. To set this tunable, use the sharectl command to set the clientresvport property instead.

# sharectl set -p clientresvport=true nfs

For more information, see the sharectl(1M) man page.

Description Controls some security checking that the NFS server attempts to do to

enforce integrity on the part of its clients. The NFS server can check whether the source port from which a request was sent was a *reserved port*. A reserved port has a number less than 1024. For BSD-based systems, these ports are reserved for processes being run by root. This security checking can prevent users from writing their own RPC-based applications that defeat the access checking that the NFS client uses.

Data Type Integer (32-bit)

Default 0 (security checking disabled)

Range 0 (security checking disabled) or 1 (security checking enabled)

Units Boolean values

Dynamic? Yes

Validation None

When to Change Use this parameter to prevent malicious users from gaining access to files

by using the NFS server that they would not ordinarily have access to. However, the *reserved port* notion is not universally supported. Thus, the security aspects of the check are very weak. Also, not all NFS client implementations bind their transport endpoints to a port number in the reserved range. Thus, interoperability problems might result if the

security checking is enabled.

## rpcmod Module Parameters

This section describes NFS parameters for the rpcmod module.

## rpcmod:clnt\_max\_conns

Description Controls the number of TCP connections that the NFS client uses when

communicating with each NFS server. The kernel RPC is constructed so that it can multiplex RPCs over a single connection. However, multiple

connections can be used, if preferred.

Data Type Integer (32-bit)

Default 8

Range  $1 \text{ to } 2^{31} - 1$ 

Units Connections

Dynamic? Yes

Validation None

When to Change In general, one connection is sufficient to achieve full network

bandwidth. However, if TCP cannot utilize the bandwidth offered by the network in a single stream, then multiple connections might increase the

throughput between the NFS client and the NFS server.

Increasing the number of connections doesn't come without consequences. Increasing the number of connections also increases kernel resource usage needed to keep track of each connection.

Commitment Level Unstable

# rpcmod:clnt\_idle\_timeout

Description Controls the duration of time on the NFS client that a connection

between the NFS client and NFS server is allowed to remain idle before

being closed.

Data Type Long integer (64-bit)

Default 300,000 milliseconds (5 minutes)

Range  $0 \text{ to } 2^{63} - 1$ 

Units Milliseconds

Dynamic? Yes

Validation None

When to Change Use this parameter to change the time that idle connections are allowed

to exist on the NFS client before being closed. You might want to close connections at a faster rate to avoid consuming system resources.

Commitment Level Unstable

## rpcmod:svc\_idle\_timeout

Description Controls the duration of time on the NFS server that a connection

between the NFS client and NFS server is allowed to remain idle before

being closed.

Data Type Long integer (64-bit)

Default 360,000 milliseconds (6 minutes)

Range 0 to 2<sup>63</sup> - 1

Units Milliseconds

Dynamic? Yes

Validation None

When to Change Use this parameter to change the time that idle connections are allowed

to exist on the NFS server before being closed. You might want to close

connections at a faster rate to avoid consuming system resources.

Commitment Level Unstable

# rpcmod:maxdupreqs

Description Controls the size of the duplicate request cache that detects RPC-

level retransmissions on connectionless transports. This cache is

indexed by the client network address and the RPC procedure number, program number, version number, and transaction ID. This cache avoids processing retransmitted requests that might not be idempotent.

Data Type Integer (32-bit)

Default 8192

Range  $1 \text{ to } 2^{31} - 1$ 

Units Requests

Dynamic? The cache is dynamically sized, but the hash queues that provide fast

access to the cache are statically sized. Making the cache very large might result in long search times to find entries in the cache.

Do not set the value of this parameter to 0. This value prevents the NFS

server from handling non idempotent requests.

Validation None

When to Change Examine the value of this parameter if false failures are encountered by

NFS clients. For example, if an attempt to create a directory fails, but the directory is actually created, perhaps that retransmitted MKDIR request

was not detected by the server.

The size of the cache should match the load on the server. The cache records non idempotent requests and so only needs to track a portion of the total requests. The cache does need to hold the information long enough to be able to detect a retransmission by the client. Typically, the client timeout for connectionless transports is relatively short, starting

around 1 second and increasing to about 20 seconds.

Commitment Level Unstable

## rpcmod:cotsmaxdupreqs

Description Controls the size of the duplicate request cache that detects RPC-

level retransmissions on connection-oriented transports. This cache is indexed by the client network address and the RPC procedure number, program number, version number, and transaction ID. This cache avoids

processing retransmitted requests that might not be idempotent.

Data Type Integer (32–bit)

Default 8192

Range  $1 \text{ to } 2^{31} - 1$ 

Units Requests

Dynamic? Yes

Validation The cache is dynamically sized, but the hash queues that provide fast

access to the cache are statically sized. Making the cache very large

might result in long search times to find entries in the cache.

Do not set the value of this parameter to 0. It prevents the NFS server

from handling non-idempotent requests.

When to Change Examine the value of this parameter if false failures are encountered by

NFS clients. For example, if an attempt to create a directory fails, but the directory is actually created, it is possible that a retransmitted MKDIR

request was not detected by the server.

The size of the cache should match the load on the server. The cache records non-idempotent requests and so only needs to track a portion of the total requests. It does need to hold the information long enough to be able to detect a retransmission on the part of the client. Typically, the client timeout for connection oriented transports is very long, about 1 minute. Thus, entries need to stay in the cache for fairly long times.



## Internet Protocol Suite Tunable Parameters

This chapter describes various Internet Protocol (IP) suite properties.

- "IP Tunable Parameters" on page 136
- "TCP Tunable Parameters" on page 146
- "UDP Tunable Parameters" on page 162
- "IPQoS Tunable Parameter" on page 164
- "SCTP Tunable Parameters" on page 165
- "Per-Route Metrics" on page 176

For other types of tunable parameters, refer to the following information:

- Oracle Solaris kernel tunable parameters Chapter 2, "Oracle Solaris Kernel Tunable Parameters"
- Oracle Solaris ZFS tunable parameters Chapter 3, "Oracle Solaris ZFS Tunable Parameters"
- NFS tunable parameters Chapter 4, "NFS Tunable Parameters"
- System facility tunable parameters Chapter 6, "System Facility Parameters"

# **Overview of Tuning IP Suite Parameters**

You can set all of the tuning parameters that are described in this chapter by using the following ipadm command syntax:

```
# ipadm set-prop -p parameter ip|ipv4|ipv6|tcp|udp|sctp
```

For example, you would set the extra\_priv\_ports tunable parameter as follows:

```
# ipadm set-prop -p extra_priv_ports=1047 tcp
PROTO PROPERTY PERM CURRENT PERSISTENT DEFAULT POSSIBLE
tcp extra_priv_ports rw 1047 1047 2049,4045 1-65535
```

For more information, see the ipadm(1M) man page.

## **IP Suite Parameter Validation**

All of the parameters that are described are checked to verify that they fall in the parameter range. The parameter's range is provided with the description for each parameter.

# **Internet Request for Comments**

Internet protocol and standard specifications are described in Internet Request for Comments (RFC) documents. You can review RFCs at the following site:

http://www.ietf.org/rfc.html

You can browse RFC topics by entering an RFC number or an Internet-draft file name in the Internet Engineering Task Force (IETF) Repository Retrieval search field.

#### **IP Tunable Parameters**

This section describes parameters pertaining to the IP protocol.

# 

Description Controls the rate of IP in generating ICMP error messages. IP

generates only up to \_icmp\_err\_burst IP error messages in any

\_icmp\_err\_interval.

The \_icmp\_err\_interval parameter protects IP from denial of service attacks. Setting this parameter to 0 disables rate limiting. It does not

disable the generation of error messages.

Default 100 milliseconds for icmp err interval

10 error messages for icmp err burst

Range 0-99,999 milliseconds for icmp err interval

1 - 99,999 error messages for icmp err burst

Dynamic? Yes

purposes.

# \_respond\_to\_echo\_broadcast and \_respond\_to\_echo\_multicast (IPv4 or IPv6)

Description Controls whether IP responds to a broadcast ICMPv4 echo request or a

IPv6 multicast ICMPv6 echo request.

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Dynamic? Yes

When to Change If you do not want this behavior for security reasons, disable it.

Commitment Level Unstable

Description Controls whether IPv4 or IPv6 sends out ICMPv4 or ICMPv6 redirect

messages.

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Dynamic? Yes

When to Change If you do not want this behavior for security reasons, disable it.

Commitment Level Stable

# forwarding (IPv4 or IPv6)

Description Controls whether IPv4 or IPv6 forwards packets with source IPv4 routing

options or IPv6 routing headers.

Default Off

Range Off or On

Dynamic? Yes

When to Change Keep this parameter disabled to prevent denial of service attacks.

Commitment Level Stable

#### ttl

Description Controls the time to live (TTL) value in the IPv4 header for the outbound

IPv4 packets on an IP association.

Default 255

Range 1 to 255

Dynamic? Yes

When to Change Generally, you do not need to change this value.

Commitment Level Stable

# hoplimit (IPv6)

Description Sets the value of the hop limit in the IPv6 header for the outbound IPv6

packets on an IP association.

Default 255

Range 1 to 255

Dynamic? Yes

When to Change Generally, you do not need to change this value.

Commitment Level Stable

# \_addrs\_per\_if

Description Defines the maximum number of logical IP interfaces associated with a

real interface.

Default 256

Range 1 to 8,192

Dynamic? Yes

When to Change Do not change the value. If more logical interfaces are required, you

might consider increasing the value. However, recognize that this change

might have a negative impact on IP's performance.

Commitment Level Unstable

# hostmodel (IPv4 or IPv6)

Description Controls send and receive behavior for IPv4 or IPv6 packets on a multi-

homed system. This property can have the following values: weak,

strong, and src-priority. The default value is weak.

Default weak

Range weak, strong, or src-priority

■ weak

- Outgoing packets The source address of the packet going out need not match the address configured on the outgoing interface.
- Incoming packets The destination address of the incoming packet need not match the address configured on the incoming interface.
- strong
  - Outgoing packets The source address of the packet going out must match the address configured on the outgoing interface.
  - Incoming packets The destination address of the incoming packet must match the address configured on the incoming interface.
- src-priority
  - Outgoing packets If multiple routes for the IP destination in the packet are available, the system prefers routes where the IP source address in the packet is configured on the outgoing interface.

If no such route is available, the system falls back to selecting the *best* route, as with the weak ES case.

 Incoming packets - The destination address of the incoming packet must be configured on any one of the host's interface.

Dynamic? Yes

When to Change If a ystem has interfaces that cross strict networking domains (for example, a firewall or a VPN node), set this parameter to strong.

Commitment Level Stable

# IP Tunable Parameters Related to Duplicate Address Detection

The following parameters can be configured to perform duplicate address detection (DAD) in the network.

#### \_arp\_defend\_interval/\_ndp\_defend\_interval

Description Interval in which the system broadcasts address announcements for IPv4

ARP and IPv6 NDP, respectively, to detect duplicate addresses in the

network,

Default 300,000 milliseconds

Range 0-360,000

Dynamic? Yes

When to Change Never

Commitment Level Unstable

## \_arp\_defend\_period/\_ndp\_defend\_period

Description Time period within which unrequested address-defense ARP or NDP

messages are generated on any one physical network interface. These parameters work together with "\_arp\_defend\_rate/\_ndp\_defend\_rate".

These parameters does not apply to normal ARP or NDP resolution or to address defense due to detected conflicts. Rather, the parameters are

implemented only on unbidden conflict detection traffic.

Default 3,600 seconds

Range 0-3,600

Dynamic? Yes

When to Change Never

#### \_arp\_defend\_rate/\_ndp\_defend\_rate

Description Number of unrequested address-defense ARP or NDP messages

that can be generated in an hour period on any one physical network interface. The time period can be revised by configuring

"\_arp\_defend\_period/\_ndp\_defend\_period".

These parameters does not apply to normal ARP or NDP resolution nor to address defense due to detected conflicts. Rather, the parameters are

implemented only on unbidden conflict detection traffic.

Default 100 messages/hour

Range 0-20,000

Dynamic? Yes

When to Change Never

Commitment Level Unstable

#### \_arp\_fastprobe\_count

Description In a transmit-pause sequence, the number of probes that are transmitted

to detect duplicate addresses before pausing. The length of time is defined in "\_arp\_fastprobe\_interval". The parameter is used for faster

probing for duplicate addresses.

Default 3 packets

Range 0-20

Dynamic? Yes

When to Change Never

Commitment Level Unstable

#### \_arp\_fastprobe\_interval

Description Similar function to "arp probe interval", which is the time between

the sending of a set number of probes to detect duplicate addresses. To accelerate the process in bringing up an IP interface, and if the underlying driver can properly report link up or link down events, the

system uses this parameter as the interval between sending out probes.

This parameter works together with " arp fastprobe count".

Default 150 milliseconds

Range 10-20,000

Dynamic? Yes

When to Change Never

Commitment Level Unstable

#### \_arp\_probe\_count

Description In a transmit-pause sequence, the number of probes that are transmitted

to detect duplicate addresses before pausing. The length of the pause is determined by "arp probe interval". After the pause time expires,

probing resumes.

Default 3 packets

Range 0-20

Dynamic? Yes

When to Change Never

Commitment Level Unstable

#### \_arp\_probe\_interval

Description Time between the sending of a set number of probes to detect duplicate

addresses. The number of probes that is sent after each interval is defined

in "\_arp\_probe\_count".

Default 1,500 milliseconds

Range 10-20,000

Dynamic? Yes

When to Change Never

Description Number of packets transmitted for IPv4 ARP and IPv6 NDP,

respectively, in every unsolicited address announcement in order to update the address cache of network peers. The

announcements are sent after a local IP address has been successfully

brought up and are transmitted at intervals controlled by the "arp publish interval/ndp unsolicit interval" parameters.

Default 3 packets

Range 1-20

Dynamic? Yes

When to Change Never

Commitment Level Stable

#### arp\_publish\_interval/ndp\_unsolicit\_interval

Description Time a system sends out unsolicited address announcements for IPv4

ARP and IPv6 NDP, respectively, after a local IP address is successfully brought up. The announcements are sent to update the address cache of network peers. The number of packets in every announcement is

controlled by the "" parameters.

Default 2,000 milliseconds

Range 1,000-20,000

Dynamic? Yes

When to Change Never

Commitment Level Stable

#### \_defend\_interval

Description Length of time a system defends its local address when it is detected to

be in conflict with another system's IP address. The number of attempts to defend the address within this period is defined in " max defend".

Default 30 seconds

Range 0-999,999

Dynamic? Yes

When to Change Never

Commitment Level Unstable

#### \_dup\_recovery

Description Time between the transmission of probes after the system marks a non-

temporary address down because it conflicts with the same address in a remote system. The local system sends out probes periodically to test whether the conflict persists. If the probe receives no reply, the conflict is

considered cleared and the address is marked up again.

Default 300,000 milliseconds

Range 0-360,000

Dynamic? Yes

When to Change Never

Commitment Level Unstable

#### \_max\_defend

Description The number of times an IP address is defended if the address conflicts

with another system's IP address. Defense of the address occurs within

the time specified in "\_defend\_interval".

Default 3 counts

Range 0-1,000

Dynamic? Yes

When to Change Never

Commitment Level Unstable

#### \_max\_temp\_defend

Description Number of times a system defends a temporary local address or a DHCP

controlled address when that address is in conflict with another system's

IP address. When the value of  ${\tt \_max\_temp\_defend}$  is passed, the system

gives up the address.

Default 1 count

Range 0-1,000

Dynamic? Yes

When to Change Never

Commitment Level Unstable

### **IP Tunable Parameters With Additional Cautions**

Changing the following parameters is not recommended.

#### \_pathmtu\_interval

Description Specifies the interval in milliseconds at which IP flushes the path

maximum transfer unit (PMTU) discovery information, and tries to

rediscover PMTU.

Refer to RFC 1191 on PMTU discovery.

Default 1,200 milliseconds (20 minutes)

Range 2-999,999,999

Dynamic? Yes

When to Change Do not change this value.

Commitment Level Unstable

## \_icmp\_return\_data\_bytes (IPv4 or IPv6)

Description When IPv4 or IPv6 sends an ICMPv4 or ICMPv6 error message, it

includes the IP header of the packet that caused the error message. This parameter controls how many extra bytes of the packet beyond the IPv4 or IPv6 header are included in the ICMPv4 or ICMPv6 error message.

Default 64 for IPv4

1,280 for IPv6

Range 8-65,536 for IPv4

8-1,280 for IPv6

Dynamic? Yes

When to Change Do not change the value. Including more information in an ICMP error

message might help in diagnosing network problems. If this feature is

needed, increase the value.

Commitment Level Unstable

#### **TCP Tunable Parameters**

This section describes parameters specific to the TCP transport protocol.

### tcp cwnd normal

Description

One of three variables for the congestion window burst throttle, along side tcp\_cwnd\_infinite and tcp\_cwnd\_ss that together manage packet transfers in cases of congestion.

To prevent performance degradation from transfer congestion, change the parameter's value in the /etc/system file as follows:

# echo "set ip:tcp\_cwnd\_normal=0xFF" >> /etc/system.d/site:filename
# reboot

where *site:filename* refers to the file that contains the new parameter setting (0xFF). The new setting will be read into the /etc/system file during the reboot. The naming convention *site:filename* enables you to identify the file and the change that you implemented on the parameter. For more information about using files in /etc/system.d, see "/etc/system File and the /etc/system.d Directory" on page 17.

For more information about the congestion window, refer to RFC 2581 and RFC 3390.

Default 16

Range 1-65535

Dynamic? Yes

When to Change See Description

Commitment Level able

### \_deferred\_ack\_interval

Description Specifies the time-out value for the TCP-delayed acknowledgment

(ACK) timer for stems that are not directly connected.

Refer to RFC 1122, 4.2.3.2.

Default 100 milliseconds

Range 1 millisecond to 60,000 milliseconds

Dynamic? Yes

When to Change Do not increase this value to more than 500 milliseconds.

Increase the value under the following circumstances:

■ Slow network links (less than 57.6 Kbps) with greater than 512 bytes

maximum segment size (MSS)

■ The interval for receiving more than one TCP segment is short

Commitment Level Unstable

## \_local\_dack\_interval

Description Specifies the time-out value for TCP-delayed acknowledgment (ACK)

timer for stems that are directly connected.

Refer to RFC 1122, 4.2.3.2.

Default 50 milliseconds

Range 10 milliseconds to 500 milliseconds

Dynamic? Yes

When to Change Do not increase this value to more than 500 milliseconds.

Increase the value under the following circumstances:

 Slow network links (less than 57.6 Kbps) with greater than 512 bytes maximum segment size (MSS) ■ The interval for receiving more than one TCP segment is short

Commitment Level Unstable

### \_deferred\_acks\_max

Description Specifies the maximum number of TCP segments received from remote

destinations (not the same subnet) before an acknowledgment (ACK) is generated. TCP segments are measured in units of maximum segment size (MSS) for individual connections. If set to 0 or 1, no ACKs are delayed, assuming all segments are 1 MSS long. The actual number is dynamically calculated for each connection. The value is the default

maximum.

Default 2

Range 0 to 16

Dynamic? Yes

When to Change This parameter should not be changed in normal circumstances.

Commitment Level Unstable

## \_local\_dacks\_max

Description Specifies the maximum number of TCP segments received from peers

on the same subnet before an acknowledgment (ACK) is generated. TCP segments are measured in units of maximum segment size (MSS) for individual connections. If set to 0 or 1, it means no ACKs are delayed, assuming all segments are 1 MSS long. The actual number is dynamically calculated for each connection. The value is the default

maximum.

Default 8

Range 0 to 16

Dynamic? Yes

When to Change Do not change the value. In some circumstances, when the network

traffic becomes very bursty because of the delayed ACK effect, decrease

the value. Do not decrease this value below 2.

Commitment Level Unstable

#### \_wscale\_always

Description When this parameter is enabled, which is the default setting, TCP always

sends a SYN segment with the window scale option, even if the window scale option value is 0. Note that if TCP receives a SYN segment with the window scale option, even if the parameter is disabled, TCP responds with a SYN segment with the window scale option. In addition, the

option value is set according to the receive window size.

Refer to RFC 1323 for the window scale option.

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Dynamic? Yes

When to Change If there is an interoperability problem with an old TCP stack that does not

support the window scale option, disable this parameter.

Commitment Level Unstable

## \_tstamp\_always

Description If set to 1, TCP always sends a SYN segment with the timestamp option.

If set to 2, timestamps are completely disabled, regardless of whether the TCP connection was opened actively or passively. Note that if TCP receives a SYN segment with the timestamp option, TCP responds with a SYN segment with the timestamp option even if the parameter is set to 0.

Default 0 (disabled)

Range 0 (disabled), 1 (enabled), or 2 (disabled regardless of how TCP

connection was opened)

Dynamic? Yes

When to Change If getting an accurate measurement of round-trip time (RTT) and TCP

sequence number wraparound is a problem, enable this parameter.

Refer to RFC 1323 for more reasons to enable this option.

Commitment Level Unstable

Description Defines the default send window size in bytes. Refer to "Per-Route

Metrics" on page 176 for a discussion of setting a different value on a

per-route basis. See also "max buf" on page 150.

Default 49,152

Range 4,096 to the current value of "max buf" on page 150

Dynamic? Yes

When to Change An application can use setsockopt SO SNDBUF command to change the

individual connection's send buffer. See the setsockopt(3XNET) man

page for information.

Commitment Level Stable

Description Defines the default receive window size in bytes. Refer to "Per-

Route Metrics" on page 176 for a discussion of setting a different value on a per-route basis. See also "max buf" on page 150 and

" recv hiwat minmss" on page 162.

Default 128,000

Range 2,048 to the current value of "max\_buf" on page 150

Dynamic? Yes

When to Change An application can use setsockopt SO RCVBUF command to change the

individual connection's receive buffer. See the setsockopt(3XNET) man

page for information.

Commitment Level Stable

max\_buf

Description Defines the maximum send and receive buffer size in bytes. This

parameter controls how large the send and receive buffers are set to by an

application that uses setsockopt().

Default 1,048,576

Range 128,000 to 1,073,741,824

Dynamic? Yes

environment, increase the value to match the network link speed. The \_cwnd\_max parameter should probably be increased at the same time.

Commitment Level Stable

#### cwnd-max

Description Defines the maximum value of the TCP congestion window (cwnd) in

bytes.

For more information on the TCP congestion window, refer to RFC 1122

and RFC 2581.

Default 1,048,576

Range 128 to 1,073,741,824

Dynamic? Yes

When to Change Even if an application uses setsockopt() to change the window size to

a value higher than \_cwnd\_max, the actual window used can never grow beyond \_cwnd\_max. Thus, \_max\_buf should be greater than \_cwnd\_max.

Commitment Level Unstable

## \_slow\_start\_initial

Description Defines the maximum initial congestion window (cwnd) size in the

maximum segment size (MSS) of a TCP connection.

Refer to RFC 2414 on how the initial congestion window size is

calculated.

Default 10

Range 1 to 10

Dynamic? Yes

When to Change Do not change the value.

If the initial cwnd size causes network congestion under special

circumstances, decrease the value.

Commitment Level Unstable

### \_local\_slow\_start\_initial

Description Defines the initial congestion window (cwnd) size in the maximum

segment size (MSS) of a TCP connection betweenstems on the same

subnet.

Default 10

Range 1 to 16,384

Dynamic? Yes

When to Change Consider increasing this parameter value if applications would benefit

from a larger initial window.

Commitment Level Unstable

## \_slow\_start\_after\_idle

Description The congestion window size in the maximum segment size (MSS) of a

TCP connection after it has been idled (no segment received) for a period

of one retransmission timeout (RTO).

Refer to RFC 2414 on how the initial congestion window size is

calculated.

Default 4

Range 1 to 16,384

Dynamic? Yes

When to Change For more information, see "\_slow\_start\_initial" on page 151.

Commitment Level Unstable

#### sack

Description If set to active, TCP always sends a SYN segment with the selective

acknowledgment (SACK) permitted option. If TCP receives a SYN

segment with a SACK-permitted option and this parameter is set to passive TCP responds with a SACK-permitted option. If the parameter is set to never TCP does not send a SACK-permitted option, regardless of whether the incoming segment contains the SACK permitted option.

Refer to RFC 2018 for information on the SACK option.

Default ative

Range never, pssive, or ative

Dynamic? Yes

When to Change SACK processing can improve TCP retransmission performance so it

should be actively enabled. Sometimes, the other side can be confused with the SACK option actively enabled. If this confusion occurs, set the value to passive so that SACK processing is enabled only when

incoming connections allow SACK processing.

Commitment Level Stable

#### rev src routes

Description If set to 0, TCP does not reverse the IP source routing option for

incoming connections for security reasons. If set to 1, TCP does the

normal reverse source routing.

Default 0 (disabled)

Range 0 (disabled) or 1 (enabled)

Dynamic? Yes

Commitment Level Unstable

## time wait interval

Description Specifies the time in milliseconds that a TCP connection stays in TIME-

WAIT state.

For more information, refer to RFC 1122, 4.2.2.13.

Default 60,000 (60 seconds)

Range 1 second to 600,000 milliseconds

Dynamic? Yes

When to Change This parameter does not need to be changed in normal circumstances. If

the normal usage of a system results in thousands and thousands of TCP connections waiting in TIME-WAIT state, the parameter value may be

decreased. The value should not be lower than 10 seconds.

Commitment Level Unstable

#### ecn

Description Controls Explicit Congestion Notification (ECN) support.

If this parameter is set to never TCP does not negotiate with a peer that

supports the ECN mechanism.

If this parameter is set to passive when initiating a connection, TCP does

not tell a peer that it supports ECN mechanism.

However, TCP tells a peer that it supports ECN mechanism when accepting a new incoming connection request if the peer indicates that it

supports ECN mechanism in the SYN segment.

If this parameter is set to active, in addition to negotiating with a peer on the ECN mechanism when accepting connections, TCP indicates in the outgoing SYN segment that it supports the ECN mechanism when

TCP makes active outgoing connections.

Refer to RFC 3168 for information on ECN.

Default Passive

Range never, passive, or active

Dynamic? Yes

When to Change ECN can help TCP better handle congestion control. However, there

y be existing TCP implementations, firewalls, NATs, and other non-conforming network devices that are confused by this mechanism. These devices do not comply to the IETF standard. It is suggested that these devices be replaced. In situations where replacing non-conforming devices is not feasible, this parameter value can be set to passive or

never.

Commitment Level Stable

#### \_conn\_req\_max\_q

Description Specifies the default maximum number of pending TCP connections

for a TCP listener waiting to be accepted by accept(). See also

"\_conn\_req\_max\_q0" on page 155.

Default 128

Range 1 to 4,294,967,295

Dynamic? Yes

When to Change For applications such as web servers that might receive several

connection requests, the default value might be increased to match the

incoming rate.

Do not increase the parameter to a very large value. The pending TCP connections can consume excessive memory. Also, if an application cannot handle that many connection requests fast enough because the number of pending TCP connections is too large, new incoming requests

might be denied.

Note that increasing <code>\_conn\_req\_max\_q</code> does not mean that applications can have that many pending TCP connections. Applications can use <code>listen()</code> to change the maximum number of pending TCP connections for each socket. This parameter is the maximum an application can use <code>listen()</code> to set the number to. Thus, even if this parameter is set to a very large value, the actual maximum number for a socket might be much less than <code>\_conn\_req\_max\_q</code>, depending on the value used in

listen().

Commitment Level Unstable

## \_conn\_req\_max\_q0

Description Specifies the default maximum number of incomplete (three-way

handshake not yet finished) pending TCP connections for a TCP listener.

For more information on TCP three-way handshake, refer to RFC 793.

See also "\_conn\_req\_max\_q" on page 155.

Default 1,024

Range 0 to 4,294,967,295

Dynamic? Yes

When to Change For applications such as web servers that might receive excessive

connection requests, you can increase the default value to match the

incoming rate.

The following explains the relationship between  ${\tt \_conn\_req\_max\_q0}$  and

the maximum number of pending connections for each socket.

When a connection request is received, TCP first checks if the number of pending TCP connections (three-way handshake is done) waiting to be accepted exceeds the maximum (*N*) for the listener. If the connections are excessive, the request is denied. If the number of connections is allowable, then TCP checks if the number of incomplete pending TCP connections exceeds the sum of *N* and \_conn\_req\_max\_q0. If it does not, the request is accepted. Otherwise, the oldest incomplete pending TCP

request is dropped.

Commitment Level Unstable

### \_conn\_req\_min

Description Specifies the default minimum value for the maximum number of

pending TCP connection requests for a listener waiting to be accepted. This is the lowest maximum value of listen() that an application can

use.

Default 1

Range 1 to 1,024

Dynamic? Yes

When to Change This parameter can be a solution for applications that use listen() to set

the maximum number of pending TCP connections to a value too low. Increase the value to match the incoming connection request rate.

Commitment Level Unstable

## \_rst\_sent\_rate\_enabled

Description If this parameter is set to 1, the maximum rate of sending a RST segment

is controlled by the ipadm parameter, <code>rst\_sent\_rate</code>. If this parameter is set to 0, no rate control when sending a RST segment is available.

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Dynamic? Yes

When to Change This tunable helps defend against denial of service attacks on TCP by

limiting the rate by which a RST segment is sent out. The only time this rate control should be disabled is when strict conformance to RFC 793 is

required.

Commitment Level Unstable

### \_rst\_sent\_rate

Description Sets the maximum number of RST segments that TCP can send out per

second.

Default 40

Range 0 to 4,294,967,295

Dynamic? Yes

When to Change In a TCP environment, there might be a legitimate reason to generate

more RSTs than the default value allows. In this case, increase the default

value of this parameter.

Commitment Level Unstable

## smallest\_anon\_port

Description This parameter controls the smallest port number TCP can select as an

ephemeral port. An application can use an ephemeral port when it creates a connection with a specified protocol and it does not specify a port number. Ephemeral ports are not associated with a specific application. When the connection is closed, the port number can be reused by a

different application.

Unit Port number

Default 32,768

Range 1,024 to 65,535

Dynamic? Yes

When to Change When a larger ephemeral port range is required.

Commitment Level Stable

### largest anon port

Description This parameter controls the largest port number TCP can select as an

ephemeral port. An application can use an ephemeral port when it creates a connection with a specified protocol and it does not specify a port number. Ephemeral ports are not associated with a specific application. When the connection is closed, the port number can be reused by a

different application.

Unit Port number

Default 65,535

Range 32,768 to 65,535

Dynamic? Yes

When to Change When a larger ephemeral port range is required.

Commitment Level Stable

## **TCP Parameters With Additional Cautions**

Changing the following parameters is not recommended.

#### \_keepalive\_interval

Description This ipadm parameter sets a probe interval that is first sent out after a

TCP connection is idle on a system-wide basis.

Oracle Solaris supports the TCP keep-alive mechanism as described in RFC 1122. This mechanism is enabled by setting the SO\_KEEPALIVE

socket option on a TCP socket.

If SO\_KEEPALIVE is enabled for a socket, the first keep-alive probe is sent out after a TCP connection is idle for two hours, the default value of the tcp\_keepalive\_interval parameter. If the peer does not respond to the probe after eight minutes, the TCP connection is aborted. For more information, refer to "rexmit interval initial" on page 159.

You can also use the TCP\_KEEPALIVE\_THRESHOLD socket option on individual applications to override the default interval so that each application can have its own interval on each socket. The option value is an unsigned integer in milliseconds. Also see the tcp(7P) man page.

Default 2 hours

Range 10 seconds to 10 days

Units Unsigned integer (milliseconds)

Dynamic? Yes

When to Change Do not change the value. Lowering it may cause unnecessary network

traffic and might also increase the chance of premature termination of the

connection because of a transient network problem.

Commitment Level Unstable

#### \_ip\_abort\_interval

Description Specifies the default total retransmission timeout value for a TCP

connection. For a given TCP connection, if TCP has been retransmitting for \_ip\_abort\_interval period of time and it has not received any acknowledgment from the other endpoint during this period, TCP closes

this connection.

For TCP retransmission timeout (RTO) calculation, refer to RFC 1122,

4.2.3. See also "\_rexmit\_interval\_max" on page 160.

Default 5 minutes

Range 500 milliseconds to 1193 hours

Dynamic? Yes

When to Change Do not change this value. See "rexmit interval max" on page 160

for exceptions.

Commitment Level Unstable

#### \_rexmit\_interval\_initial

Description Specifies the default initial retransmission timeout (RTO) value for a

TCP connection. Refer to "Per-Route Metrics" on page 176 for a discussion of setting a different value on a per-route basis.

Default 1,000 milliseconds

Range 1 millisecond to 20,000 milliseconds

Dynamic? Yes

When to Change Do not change this value. Lowering the value can result in unnecessary

retransmissions. The TCP\_RTO\_INITIAL socket option can be used to

change the initial retransmission timeout on a per-socket basis.

Commitment Level Unstable

#### rexmit interval max

Description Defines the default maximum retransmission timeout value (RTO). The

calculated RTO for all TCP connections cannot exceed this value. See

also "\_ip\_abort\_interval" on page 159.

Default 60,000 milliseconds

Range 1 millisecond to 7,200,000 milliseconds

Dynamic? Yes

When to Change Do not change the value in a normal network environment.

If, in some special circumstances, the round-trip time (RTT) for a connection is about 10 seconds, you can increase this value. If you change this value, you should also change the <code>\_ip\_abort\_interval</code> parameter. Change the value of <code>\_ip\_abort\_interval</code> to at least four times the value of <code>\_rexmit\_interval\_max</code>. The TCP\_RTO\_MAX socket option can be used to change the initial retransmission timeout on a per-

socket basis.

Commitment Level Unstable

#### \_rexmit\_interval\_min

Description Specifies the default minimum retransmission time out (RTO) value. The

calculated RTO for all TCP connections cannot be lower than this value.

See also "rexmit interval max" on page 160.

Default 200 milliseconds

Range 1 millisecond to 7,200,000 milliseconds

Dynamic? Yes

When to Change Do not change the value in a normal network environment.

TCP's RTO calculation should cope with most RTT fluctuations. If, in some very special circumstances, the round-trip time (RTT) for a connection is about 10 seconds, increase this value. If you change this value, you should change the <code>rexmit\_interval\_max</code> parameter. Change the value of <code>rexmit\_interval\_max</code> to at least eight times the value of <code>rexmit\_interval\_min</code>. The TCP\_RTO\_MIN socket option can be used to change the initial retransmission timeout on a per-socket basis.

Commitment Level Unstable

#### \_rexmit\_interval\_extra

Description Specifies a constant added to the calculated retransmission time out value

(RTO).

Default 0 milliseconds

Range 0 to 7,200,000 milliseconds

Dynamic? Yes

When to Change Do not change the value.

When the RTO calculation fails to obtain a good value for a connection,

you can change this value to avoid unnecessary retransmissions.

Commitment Level Unstable

#### \_tstamp\_if\_wscale

Description If this parameter is set to 1, and the window scale option is enabled for a

connection, TCP also enables the timestamp option for that connection.

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Dynamic? Yes

When to Change Do not change this value. In general, when TCP is used in high-speed

network, protection against sequence number wraparound is essential.

Thus, you need the timestamp option.

Commitment Level Unstable

### \_recv\_hiwat\_minmss

Description Controls the default minimum receive window size. The minimum is

\_recv\_hiwat\_minmss times the size of maximum segment size (MSS) of

a connection.

Default 8

Range 1 to 65,536

Dynamic? Yes

When to Change Do not change the value. If changing it is necessary, do not change the

value lower than 4.

Commitment Level Unstable

### **UDP Tunable Parameters**

This section describes parameters specific to the UDP protocol.

Description Defines the default send buffer size for a UDP socket. For more

information, see "" on page 163.

Default 57,344 bytes

Range 1,024 to the current value of "" on page 163

Dynamic? Yes

When to Change Note that an application can use setsockopt() SO SNDBUF to change the

size for an individual socket. In general, you do not need to change the

default value.

Commitment Level Stable

Description Defines the default receive buffer size for a UDP socket. For more

information, see "" on page 163.

Default 57,344 bytes

Range 128 to the current value of "" on page 163

Dynamic? Yes

When to Change Note that an application can use setsockopt(3XNET) SO RCVBUF to

change the size for an individual socket. In general, you do not need to

change the default value.

Commitment Level able

Description Defines the maximum send and receive buffer size for a UDP socket.

It controls how large the send and receive buffers are set to by an

application that uses getsockopt().

Default 2,097,152

Range 65,536 to 1,073,741,824

Dynamic? Yes

When to Change Increase the value of this parameter to match the network link speed if

associations are being made in a high-speed network environment.

Commitment Level able

Description This parameter controls the smallest port number UDP can select as an

ephemeral port. An application can use an ephemeral port when it creates a connection with a specified protocol and it does not specify a port number. Ephemeral ports are not associated with a specific application. When the connection is closed, the port number can be reused by a

different application.

Unit Port number

Default 32,768

Range 1,024 to 65,535

Dynamic? Yes

When to Change When a larger ephemeral port range is required.

Commitment Level able

Description This parameter controls the largest port number UDP can select as an

ephemeral port. An application can use an ephemeral port when it creates a connection with a specified protocol and it does not specify a port number. Ephemeral ports are not associated with a specific application. When the connection is closed, the port number can be reused by a

different application.

Unit Port number

Default 65,535

Range 32,768 to 65,535

Dynamic? Yes

When to Change When a larger ephemeral port range is required.

Commitment Level Stable

## **IPQoS Tunable Parameter**

This section describes parameters pertaining to IP Quality of Service.

## \_policy\_mask

Description

Enables or disables IPQoS processing in any of the following callout positions: forward outbound, forward inbound, local outbound, and local inbound. This parameter is a bitmask as follows:

Not	Not	Not	Not	Forward	Forward	Local	Local
Used	Used	Used	Used	Outbound	Inbound	Outbound	Inbound
X	X	X	X	0	0	0	

A 1 in any of the position masks or disables IPQoS processing in that particular callout position. For example, a value of 0x01 disables IPQoS processing for all the local inbound packets.

Default The default value is 0, meaning that IPQoS processing is enabled in all

the callout positions.

Range 0 (0x00) to 15 (0x0F). A value of 15 indicates that IPQoS processing is

disabled in all the callout positions.

Dynamic? Yes

positions.

Commitment Level Unstable

### **SCTP Tunable Parameters**

This section describes parameters related to the stream control transmission protocol.

### max init retr

Description Controls the maximum number of attempts an SCTP endpoint should

make at resending an INIT chunk. The SCTP endpoint can use the SCTP

initiation structure to override this value.

Default 8

Range 0 to 128

Dynamic? Yes

When to Change The number of INIT retransmissions depend on

" pa max retr" on page 165. Ideally, max init retr should be less

than or equal to \_pa\_max\_retr.

Commitment Level Unstable

### pa max retr

Description Controls the maximum number of retransmissions (over all paths) for an

SCTP association. The SCTP association is aborted when this number is

exceeded.

Default 10

Range 1 to 128

Dynamic? Yes

When to Change The maximum number of retransmissions over all paths depend on

the number of paths and the maximum number of retransmission over each path. Ideally, sctp\_pa\_max\_retr should be set to the sum of "\_pp\_max\_retr" on page 166 over all available paths. For example, if there are 3 paths to the destination and the maximum number of retransmissions over each of the 3 paths is 5, then \_pa\_max\_retr should be set to less than or equal to 15. (See the Note in Section 8.2, RFC

2960.)

Commitment Level Unstable

#### pp max retr

Description Controls the maximum number of retransmissions over a specific path.

When this number is exceeded for a path, the path (destination) is

considered unreachable.

Default 5

Range 1 to 128

Dynamic? Yes

When to Change Do not change this value to less than 5.

Commitment Level Unstable

## \_cwnd\_max

Description Controls the maximum value of the congestion window for an SCTP

association.

Default 1,048,576

Range 128 to 1,073,741,824

Dynamic? Yes

When to Change Even if an application uses setsockopt() to change the window size

to a value higher than \_cwnd\_max, the actual window used can never grow beyond \_cwnd\_max. Thus, "" on page 171 should be greater than

\_cwnd\_max.

This parameter does not need to be changed in normal circumstances. If the system needs to communicate with peers far away (round trip time in the order of hundreds of milliseconds) using very fast network (in the order of Gbps), increase the default value to match the bandwidth-delay product to those peers. Note that max-buf parameter should also be

increased at the same time.

Commitment Level Unstable

## \_ipv4\_ttl

Description Controls the time to live (TTL) value in the IP version 4 header for the

outbound IPv4 packets on an SCTP association.

Default 64

Range 1 to 255

Dynamic? Yes

When to Change Generally, you do not need to change this value.

Commitment Level Unstable

## \_ipv6\_hoplimit

Description Sets the value of the hop limit in the IPv6 header for the outbound IPv6

packets on an SCTP association.

Default 60

Range 0 to 255

Dynamic? Yes

When to Change Generally, you do not need to change this value.

Commitment Level Unstable

## \_heartbeat\_interval

Description Computes the interval between HEARTBEAT chunks to an idle

destination, that is allowed to heartbeat.

An SCTP endpoint periodically sends an HEARTBEAT chunk to monitor the reachability of the idle destinations transport addresses of its peer.

Default 30 seconds

Range 0 to 86,400 seconds

Dynamic? Yes

When to Change Refer to RFC 2960, section 8.3.

Commitment Level Unstable

## \_new\_secret\_interval

Description Determines when a new secret needs to be generated. The generated

secret is used to compute the MAC for a cookie.

Default 2 minutes

Range 0 to 1,440 minutes

Dynamic? Yes

When to Change Refer to RFC 2960, section 5.1.3.

Commitment Level Unstable

## \_initial\_mtu

Description Determines the initial maximum send size for an SCTP packet including

the length of the IP header.

Default 1500 bytes

Range 68 to 65,535

Dynamic? Yes

When to Change Increase this parameter if the underlying link supports frame sizes that

are greater than 1500 bytes.

Commitment Level Unstable

## \_deferred\_ack\_interval

Description Sets the time-out value for SCTP delayed acknowledgment (ACK) timer

in milliseconds.

Default 100 milliseconds

Range 1 to 60,000 milliseconds

Dynamic? Yes

When to Change Refer to RFC 2960, section 6.2.

Commitment Level Unstable

## \_ignore\_path\_mtu

Description Enables or disables path MTU discovery.

Default 0 (disabled)

Range 0 (disabled) or 1 (enabled)

Dynamic? Yes

When to Change Enable this parameter if you want to ignore MTU changes along the path.

However, doing so might result in IP fragmentation if the path MTU

decreases.

Commitment Level Unstable

## \_initial\_ssthresh

Description Sets the initial slow start threshold for a destination address of the peer.

Default 1,048,576

Range 1,024 to 4,294,967,295

Dynamic? Yes

When to Change Refer to RFC 2960, section 7.2.1.

Commitment Level Unstable

Description Defines the default send buffer size in bytes. See also "" on page 171.

Default 102,400

Range 8,192 to the current value of "" on page 171

Dynamic? Yes

When to Change An application can use setsockopt() SO\_SNDBUF to change the

individual connection's send buffer.

Commitment Level Stable

## xmit lowat

Description Controls the lower limit on the send window size.

Default 8,192

Range 8,192 to 1,073,741,824

Dynamic? Yes

When to Change Generally, you do not need to change this value. This parameter sets the

minimum size required in the send buffer for the socket to be marked writable. If required, consider changing this parameter in accordance

with "" on page 170.

Commitment Level Unstable

Description Defines the default receive buffer size in bytes. See also

"" on page 171.

Default 102,400

Range 8,192 to the current value of "" on page 171

Dynamic? Yes

When to Change An application can use setsockopt(3XNET) SO\_RCVBUF to change the

individual connection's receive buffer.

Commitment Level able

Description Controls the maximum send and receive buffer size in bytes. It controls

how large the send and receive buffers are set to by an application that

uses getsockopt().

Default 1,048,576

Range 102,400 to 1,073,741,824

Dynamic? Yes

When to Change Increase the value of this parameter to match the network link speed if

associations are being made in a high-speed network environment.

Commitment Level able

## \_rto\_min

Description Sets the lower bound for the retransmission timeout (RTO) in

milliseconds for all the destination addresses of the peer.

Default 1,000

Range 500 to 60,000

Dynamic? Yes

When to Change Refer to RFC 2960, section 6.3.1.

Commitment Level Unstable

#### \_rto\_max

Description Controls the upper bound for the retransmission timeout (RTO) in

milliseconds for all the destination addresses of the peer.

Default 60,000

Range 1,000 to 60,000,000

Dynamic? Yes

When to Change Refer to RFC 2960, section 6.3.1.

Commitment Level Unstable

## \_rto\_initial

Description Controls the initial retransmission timeout (RTO) in milliseconds for all

the destination addresses of the peer.

Default 3,000

Range 1,000 to 60,000,000

Dynamic? Yes

When to Change Refer to RFC 2960, section 6.3.1.

Commitment Level Unstable

## \_cookie\_life

Description Sets the lifespan of a cookie in milliseconds.

Default 60,000

Range 10 to 60,000,000

Dynamic? Yes

When to Change Generally, you do not need to change this value. This parameter might be

changed in accordance with "rto max" on page 172.

Commitment Level Unstable

### \_max\_in\_streams

Description Controls the maximum number of inbound streams permitted for an

SCTP association.

Default 32

Range 1 to 65,535

Dynamic? Yes

When to Change Refer to RFC 2960, section 5.1.1.

Commitment Level Unstable

### \_initial\_out\_streams

Description Controls the maximum number of outbound streams permitted for an

SCTP association.

Default 32

Range 1 to 65,535

Dynamic? Yes

When to Change Refer to RFC 2960, section 5.1.1.

Commitment Level Unstable

## \_shutack\_wait\_bound

Description Controls the maximum time, in milliseconds, to wait for a SHUTDOWN

ACK after having sent a SHUTDOWN chunk.

Default 60,000

Range 0 to 300,000

Dynamic? Yes

When to Change Generally, you do not need to change this value. This parameter might be

changed in accordance with "\_rto\_max" on page 172.

Commitment Level Unstable

### \_maxburst

Description Sets the limit on the number of segments to be sent in a burst.

Default 4

Range 2 to 8

Dynamic? Yes

When to Change You do not need to change this parameter. You might change it for testing

purposes.

Commitment Level Unstable

## addip enabled

Description Enables or disables SCTP dynamic address reconfiguration.

Default 0 (disabled)

Range 0 (disabled) or 1 (enabled)

Dynamic? Yes

When to Change The parameter can be enabled if dynamic address reconfiguration is

needed. Due to security implications, enable this parameter only for

testing purposes.

Commitment Level Unstable

## \_prsctp\_enabled

Description Enables or disables the partial reliability extension (RFC 3758) to SCTP.

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Dynamic? Yes

When to Change Disable this parameter if partial reliability is not supported in your SCTP

environment.

Commitment Level Unstable

Description This parameter controls the smallest port number SCTP can select as an

ephemeral port. An application can use an ephemeral port when it creates a connection with a specified protocol and it does not specify a port number. Ephemeral ports are not associated with a specific application. When the connection is closed, the port number can be reused by a

different application.

Unit Port number

Default 32,768

Range 1,024 to 65,535

Dynamic? Yes

When to Change When a larger ephemeral port range is required.

Commitment Level table

Description This parameter controls the largest port number SCTP can select as an

ephemeral port. An application can use an ephemeral port when it creates a connection with a specified protocol and it does not specify a port number. Ephemeral ports are not associated with a specific application. When the connection is closed, the port number can be reused by a

different application.

Unit Port number

Default 65,535

Range 32,768 to 65,535

Dynamic? Yes

When to Change When a larger ephemeral port range is required.

Commitment Level Stable

### **Per-Route Metrics**

You can use per-route metrics to associate some properties with IPv4 and IPv6 routing table entries.

For example, a system has two different network interfaces, a fast Ethernet interface and a gigabit Ethernet interface. The system default recv\_maxbuf is 128,000 bytes. This default is sufficient for the fast Ethernet interface, but may not be sufficient for the gigabit Ethernet interface.

Instead of increasing the system's default for <code>recv\_maxbuf</code>, you can associate a different default TCP receive window size to the gigabit Ethernet interface routing entry. By making this association, all TCP connections going through the route will have the increased receive window size.

For example, the following is in the routing table (netstat -rn), assuming IPv4:

Routina	Table:	TPv4
VOU L'ILIA	iabte.	TL A4

Moderning rabbeer in vi					
Destination	Gateway	Flags	Ref	Use	Interface
192.123.123.0	192.123.123.4	U	1	4	net0
192.123.124.0	192.123.124.4	U	1	4	net1
default	192.123.123.1	UG	1	8	

In this example, do the following:

```
# route change -net 192.123.124.0 -recvpipe x
```

Then, all connections going to the 192.123.124.0 network, which is on the net1 link, use the receive buffer size x, instead of the default 128,000 receive window size.

If the destination is in the a.b.c.d network, and no specific routing entry exists for that network, you can add a prefix route to that network and change the metric. For example:

```
# route add -net a.b.c.d 192.123.123.1 -netmask w.x.y.z # route change -net a.b.c.d -recvpipe y
```

Note that the prefix route's gateway is the default router. Then, all connections going to that network use the receive buffer size y. If you have more than one interface, use the -ifp argument to specify which interface to use. This way, you can control which interface to use for specific destinations. To verify the metric, use the route get command.



## System Facility Parameters

This chapter describes most of the parameters default values for various system facilities.

For other types of tunable parameters, refer to the following:

- Oracle Solaris kernel tunable parameters Chapter 2, "Oracle Solaris Kernel Tunable Parameters"
- Oracle Solaris ZFS tunable parameters Chapter 3, "Oracle Solaris ZFS Tunable Parameters"
- NFS tunable parameters Chapter 4, "NFS Tunable Parameters"
- Internet Protocol Suite tunable parameters Chapter 5, "Internet Protocol Suite Tunable Parameters"

## **System Default Parameters**

The functioning of various system facilities is governed by a set of values that are read by each facility on startup. The values for each facility might be stored in a file for the facility located in the /etc/default directory, or in properties of a service instance in the Service Management Facility (SMF) configuration repository. For more information on SMF services and properties, see *Managing System Services in Oracle Solaris 11.3*.

For information about setting power management properties, see *Managing System Information*, *Processes*, *and Performance in Oracle Solaris 11.2*.

#### autofs

You can display or configure SMF autofs properties by using the sharectl command. For example:

# sharectl get autofs
timeout=600
automount\_verbose=false
automountd\_verbose=false

```
nobrowse=false
trace=0
environment=
# sharectl set -p timeout=200 autofs
For details, see sharectl(1M).
```

#### cron

This facility enables you to disable or enable cron logging.

#### devfsadm

This file is not currently used.

### dhcpagent

Client usage of DHCP is provided by the dhcpagent daemon. When ipadm is used to create a DHCP address object, or when ipadm identifies an interface that has been configured to receive its network configuration from DHCP, dhcpagent is started to manage an address on that interface.

For more information, see the /etc/default/dhcpagent information in the FILES section of dhcpagent(1M).

#### fs

File system administrative commands have a generic and file system-specific portion. If the file system type is not explicitly specified with the -F option, a default is applied. The value is specified in this file. For more information, see the Description section of default fs(4).

## ftp

This facility enables you to set the ls command behavior to the RFC 959 NLST command. The default ls behavior is the same as in the previous Solaris release.

```
For details, see ftp(4).
```

#### inetinit

This facility enables you to configure TCP sequence numbers and to enable or disable support for 6to4 relay routers.

#### init

System initialization properties are now part of the following SMF service:

```
svc:/system/environment:init
```

You can display and configure system initialization properties, such as TZ and LANG, by using similar syntax:

```
# svccfg -s svc:/system/environment:init
svc:/system/environment:init> setprop
Usage: setprop pg/name = [type:] value
setprop pg/name = [type:] ([value...])
Set the pg/name property of the currently selected entity. Values may be
enclosed in double-quotes. Value lists may span multiple lines.
svc:/system/environment:init> listprop
umask
                                 application
                                astring 022
umask/umask
umask/value_authorization astring
                                            solaris.smf.value.environment
environment
                                application
environment/LANG
                                astring
environment/LC ALL
                                astring
```

For more information, see the FILES section of init(1M).

## ipsec

This facility enables you to configure parameters, such as IKE daemon debugging information and the ikeadm privilege level.

#### kbd

Keyboard configuration properties are now part of the following SMF service:

```
svc:/system/keymap:default
```

You display and configure keyboard properties by using similar syntax:

```
# svccfg -s svc:/system/keymap:default
svc:/system/keymap:default> setprop
Usage: setprop pg/name = [type:] value
setprop pg/name = [type:] ([value...])
Set the pg/name property of the currently selected entity. Values may be
enclosed in double-quotes. Value lists may span multiple lines.
svc:/system/keymap:default> listprop
general
                                      framework
general/complete
                                      astring
general/enabled
                                      boolean
                                                    false
keymap
                                     system
keymap/console_beeper_freq integer
keymap/kbd_beeper_freq integer
keymap/keyboard_abort astring
keymap/keyclick boolean
                                                    900
                                                    2000
                                                    enable
keymap/keyclick
                                                    false
                                      boolean
```

For more information, see kbd(1).

### keyserv

For details, see the /etc/default/keyserv information in the FILES section of keyserv(1M).

## login

For details, see the /etc/default/login information in the FILES section of login(1).

#### mpathd

This facility enables you to set in.mpathd configuration parameters.

For details, see in.mpathd(1M).

#### nfs

You can display or configure SMF NFS properties by using the sharectl command. For example:

```
# sharectl get nfs
servers=1024
lockd_listen_backlog=32
lockd_servers=1024
lockd_retransmit_timeout=5
grace_period=90
server_versmin=2
server_versmin=2
client_versmin=2
client_versmax=4
server_delegation=on
nfsmapid_domain=
# sharectl set -p grace_period=60 nfs
For details, see nfs(4).
```

## nfslogd

For details, see the Description section of nfslogd(1M).

#### nss

This facility enables you to configure initgroups (3C) lookup parameters.

For details, see nss(4).

#### passwd

For details, see the /etc/default/passwd information in the FILES section of passwd(1).

#### su

For details, see the /etc/default/su information in the FILES section of su(1M).

#### syslog

For details, see the /etc/default/syslogd information in the FILES section of syslogd(1M).

#### tar

For a description of the -f function modifier, see tar(1).

If the TAPE environment variable is not present and the value of one of the arguments is a number and -f is not specified, the number matching the archiveN string is looked up in the /etc/default/tar file. The value of the archiveN string is used as the output device with the blocking and size specifications from the file.

For example:

```
% tar -c 2 /tmp/*
```

This command writes the output to the device specified as archive2 in the /etc/default/tar file.

#### telnetd

This file identifies the default BANNER that is displayed upon a telnet connection.

#### utmpd

The utmpd daemon monitors /var/adm/utmpx (and /var/adm/utmp in earlier Solaris versions) to ensure that utmp entries inserted by non-root processes by pututxline(3C) are cleaned up on process termination.

Two entries in /etc/default/utmpd are supported:

- SCAN\_PERIOD The number of seconds that utmpd sleeps between checks of /proc to see if monitored processes are still alive. The default is 300.
- MAX\_FDS The maximum number of processes that utmpd attempts to monitor. The default value is 4096 and should never need to be changed.

# System Check Script

# **Confirming Flush Behavior on the System**

This script facilitates confirmation that flush behavior is correct on your system after tuning ZFS and flash storage. For more details, refer to "Ensuring Proper Cache Flush Behavior for Flash and NVRAM Storage Devices" on page 92. After you have completed the steps indicated, run the following script.

# Index

A _addip_enabled, 174 _addrs_per_if, 138 _arp_defend_interval, 140 _arp_defend_period, 140 arp_defend_rate, 141	dhcpagent, 178 disp_rechoose_interval, 77 dnlc_dir_enable, 66 dnlc_dir_max_size, 67 dnlc_dir_min_size, 66 dnlc_dircache percent, 67
_arp_fastprobe_count, 141	doiflush, 32
_arp_fastprobe_interval, 142	dopageflush, 32
_arp_probe_count, 142	_dup_recovery, 144
_arp_probe_interval, 142 arp_publish_count, 143	
arp publish interval, 143	E
autofs, 177	ecn, 154
autoup, 31	enable_tsb_rss_sizing, 81
С	F
_conn_req_max_q, 155	fastscan, 45
conn req max q0, 155	forwarding, 137
conn_req_min, 156	fs, 178
_cookie_life, 172	fsflush, 29
cron, 178	ftp, 178
_cwnd_max (SCTP), 166	
_cwnd_max (TCP), 151	
	Н
D	handspreadpages, 47 _heartbeat_interval, 168
ddi_msix_alloc_limit parameter, 55	hires_tick, 78
default_stksize, 25	hoplimit (IPv6), 138
default_tsb_size, $80$	hostmodel, 139
_defend_interval, 143	
_deferred_ack_interval, 147, 169	
_deferred_acks_max, 148	1
desfree, 40	_icmp_err_burst, 136

_icmp_err_interval, 136 _icmp_return_data_bytes, 145 _ignore_path_mtu, 169 inetinit, 179 init, 179 _initial_mtu, 168 _initial_out_streams, 173 _initial_ssthresh, 169 intr_force, 58 intr_throttling, 59 _ip_abort_interval, 159 ip_squeue_fanout, 57 ip_squeue_worker_wait, 56 ipcl_conn_hash_size, 56 ipsec, 179 _ipv4_ttl, 167 _ipv6_hoplimit, 167	max_buf (UDP), 163 _max_defend, 144 _max_in_streams, 173 _max_init_retr, 165 max_nprocs, 36 _max_temp_defend, 145 _maxburst, 174 maxpgio, 49 maxphys, 63 maxpid, 35 maxuprc, 36 maxusers, 33 min_percent_cpu, 47 minfree, 41 moddebug, 53 mpathd, 180 mr_enable, 57
K kbd, 179 _keepalive_interval, 158 keyserv, 180 kmem_flags, 51 kmem_stackinfo, 53	<b>N</b> ncsize, 65 _ndp_defend_interval, 140 _ndp_defend_period, 140 _ndp_defend_rate, 141 ndp_unsolicit_count, 143
L largest_anon_port, 158, 164, 175 lgrp_mem_pset_aware, 83 _local_dack_interval, 147 _local_dacks_max, 148 _local_slow_start_initial, 152 logevent_max_q_sz, 27 login, 180 lotsfree, 39 lpg_alloc_prefer, 82 lwp_default_stksize, 26	ndp_unsolicit_interval, 143 _new_secret_interval, 168 nfs:nacache, 123 nfs:nfs3_async_clusters, 121 nfs:nfs3_bsize, 118 nfs:nfs3_cots_timeo, 104 nfs:nfs3_do_symlink_cache, 106 nfs:nfs3_dynamic, 107 nfs:nfs3_jukebox_delay, 124 nfs:nfs3_lookup_neg_cache, 108 nfs:nfs3_max_transfer_size, 125 nfs:nfs3_max_transfer_size_clts, 126 nfs:nfs3_max_transfer_size_cots, 127
M max_buf (SCTP), 171 max_buf (TCP), 150	nfs:nfs3_nra, 113 nfs:nfs3_pathconf_disable_cache, 102 nfs:nfs3_shrinkreaddir, 116 nfs:nfs4_async_clusters, 122

nfs:nfs4_bsize, 119	primarycache
nfs:nfs4_cots_timeo, 104	ZFS file system property, 95
nfs:nfs4_lookup_neg_cache, 109	_prsctp_enabled, 174
nfs:nfs4_max_threads, 112	pt_cnt, 70
nfs:nfs4_max_transfer_size, 126	pt_max_pty, 72
nfs:nfs_allow_preepoch_time, 102	pt_pctofmem, 71
nfs:nfs_async_clusters, 120	
nfs:nfs_async_timeout, 122	
nfs:nfs cots timeo, 103	R
nfs:nfs_disable_rddir_cache, 117	recordsize
nfs:nfs_do_symlink_cache, 105	ZFS file system property, 94
nfs:nfs dynamic, 106	recv_buf (SCTP), 170
nfs:nfs lookup neg cache, 108	recv_buf (TCP), 150
nfs:nfs nra, 112	recv_buf (UDP), 162
nfs:nfs shrinkreaddir, 115	_recv_hiwat_minmss, 162
nfs:nfs write error interval, 116	reserved_procs, 34
nfs:nfs write error to cons only, 117	respond to echo broadcast, 137
nfs:nrnode, 114	_respond_to_echo_multicast, 137
nfs max threads, 110	_rev_src_routes, 153
nfslogd, 181	rexmit interval extra, 161
nfssrv:nfs_portmon, 129	_rexmit_interval_initial, 159
ngroups max, 37	_rexmit_interval_max, 160
noexec user stack, 29	rexmit interval min, 160
nss, 181	rlim fd cur, 64
nstrpush, 72	rlim fd max, 63
	rpcmod:clnt idle timeout, 130
	rpcmod:clnt max conns, 130
0	rpcmod:cotsmaxdupreqs, 132
Oracle database tuning	rpcmod:maxdupreqs, 131
ZFS file systems, 95	rpcmod:svc idle timeout, 131
22 o me systems, so	_rst_sent_rate, 157
	rst sent rate enabled, 156
P	_rto_max, 172
pa max retr, 165	rto max, 172
pageout reserve, 43	rto min, 171
pages_before_pager, 48	rx copy threshold, 62
pages_pp_maximum, 44	rx_limit_per_intr, 60
passwd, 181	rx_queue_number, 59
_pathmtu_interval, 145	rx ring size, 61
physmem, 24	1X_11119_512c, 01
pidmax, 35	
policy mask, 164	S
pp max retr, 166	sack, 152
pr segp disable, 75	secondarycache
hi_seAh_arsance, 19	secondar yeache

ZFS file system property, 95 Χ segspt minfree, 75 xmit lowat, 170 send\_buf (SCTP), 170 send\_buf (TCP), 150 send buf (UDP), 162 Ζ send\_redirects, 137 ZFS file system property shutack wait bound, 173 primarycache, 95 slow start after idle, 152 recordsize, 94 slow start initial, 151 secondarycache, 95 slowscan, 46 ZFS file systems  $smallest_anon_port, 157, 163, 175$ tuning for an Oracle database, 95 strmsgsz, 73,73 zfs\_arc\_max, 87 su, 181 zfs\_arc\_min, 87  $swapfs_minfree, 50$ zfs\_prefetch\_disable, 88 swapfs\_reserve, 50 syslog, 182 Т tar, 182 tcp cwnd normal, 146 throttlefree, 42 time wait interval, 153 timer\_max, 78 tmpfs maxkmem, 68 tmpfs minfree, 69 tsb\_alloc\_hiwater, 79 tsb rss factor, 81 \_tstamp\_always, 149 \_tstamp\_if\_wscale, 161 ttl (IPv4), 138 tune\_t\_fsflushr, 30 tune\_t\_minarmem, 45 tx copy threshold, 62 tx\_queue\_number, 58  $tx\_ring\_size, 60$ U utmpd, 182

wscale always, 149