Creating and Using Oracle[®] Solaris 10 Zones



Creating and Using Oracle Solaris 10 Zones

Part No: E54750

Copyright © 2011, 2016, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

Référence: E54750

Copyright © 2011, 2016, Oracle et/ou ses affiliés. Tous droits réservés.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf stipulation expresse de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, accorder de licence, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est livré sous licence au Gouvernement des Etats-Unis, ou à quiconque qui aurait souscrit la licence de ce logiciel pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer des dommages corporels. Si vous utilisez ce logiciel ou matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour ce type d'applications.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Xeon sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Opteron, le logo AMD et le logo AMD Opteron sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée d'The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers, sauf mention contraire stipulée dans un contrat entre vous et Oracle. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation, sauf mention contraire stipulée dans un contrat entre vous et Oracle.

Accessibilité de la documentation

Pour plus d'informations sur l'engagement d'Oracle pour l'accessibilité à la documentation, visitez le site Web Oracle Accessibility Program, à l'adresse http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Accès aux services de support Oracle

Les clients Oracle qui ont souscrit un contrat de support ont accès au support électronique via My Oracle Support. Pour plus d'informations, visitez le site http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info ou le site http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs si vous êtes malentendant.

Contents

U	Using This Documentation					
	Interduction to Const. Only 5 40 Tanas	•				
1	Introduction to Oracle Solaris 10 Zones					
	About the solaris10 Brand					
	solaris10 Zone Support					
	SVR4 Packaging and Patching in Oracle Solaris 10 Zones					
	About Using Packaging and Patching in solaris10 Branded Zones 1					
	About Performing Package and Patch Operations Remotely 1					
	Non-Global Zones as NFS Clients					
	General Zones Concepts					
	About Oracle Solaris 10 Zones in This Release					
	Operating Limitations					
	Networking in Oracle Solaris 10 Zones					
	If native Non-Global Zones Are Installed	5				
2	Assessing an Oracle Solaris 10 System and Creating an Archive 1	7				
	Source and Target System Prerequisites					
	Enabling Oracle Solaris 10 Package and Patch Tools	7				
	Installing the Required Oracle Solaris Package on the Target System	7				
	Assess the System To Be Migrated By Using the zonep2vchk Utility	8				
	Oracle Solaris 10 Systems Only: Obtaining the zonep2vchk Utility 1					
	Creating the Image for Directly Migrating Oracle Solaris 10 Systems Into Zones 1					
	▼ How to Use flarcreate to Create the Image					
	▼ How to Use flarcreate to Exclude Certain Data					
	Other Archive Creation Methods					
	Host ID Emulation					
_	Winnerform on Oncolo Calorin 40 and Man Clabal Town Late Co. 1					
	Migrating an Oracle Solaris 10 native Non-Global Zone Into an Oracle plaris 10 Zone	כי				
3	Archive Considerations 2					

	Overview of the solaris10 Zone Migration Process	23
	About Detaching and Attaching the solaris10 Zone	24
	Migrating a solaris10 Branded Zone	24
	Migrating an Existing Zone on an Oracle Solaris 10 System	25
	▼ How to Migrate an Existing native Non-Global Zone	25
4	Configuring the solaris10 Branded Zone	29
	Preconfiguration Tasks	
	Resources Included in the Configuration by Default	
	Configured Devices in solaris10 Branded Zones	
	Privileges Defined in solaris10 Branded Zones	
	solaris10 Branded Zone Configuration Process	
	Configuring the Target Zone	
	▼ How to Configure an Exclusive-IP solaris10 Branded Zone	
	▼ How to Configure a Shared-IP solaris10 Branded Zone	
5	Installing the solaris10 Branded Zone	27
J	Zone Installation Images	
	Types of System Images	
	Image sysidcfg Status	
	Install the solaris10 Branded Zone	
	Installer Options	
	■ How to Install the solaris10 Branded Zone	
6	Posting a Zona Lagging Into a Zona and Zona Migration	11
О	Booting a Zone, Logging Into a Zone, and Zone Migration	
	About Booting the solaris10 Branded Zone	
	Image sysidcfg Profile	
	▼ solaris10 Branded Zone Internal Configuration	
	▼ How to Boot the solaris10 Branded Zone	
	About Multiple Boot Environments On solaris10 Zones	44
	▼ How to Create and Activate Multiple Boot Environments on a solaris10	11
	Branded Zone	
	Migrating a solaris10 Branded Zone to Another Host	46
In	idex	47

Using This Documentation

- **Overview** Describes how to administer Oracle Solaris 10 Zones in the Oracle Solaris 11.3 release.
- **Audience** Technicians, system administrators, and authorized service providers
- **Required knowledge** Experience administering Oracle Solaris environments. Experience with virtualized environments is a plus.

Product Documentation Library

Documentation and resources for this product and related products are available at http://www.oracle.com/pls/topic/lookup?ctx=E53394.

Feedback

Provide feedback about this documentation at http://www.oracle.com/goto/docfeedback.

· · · CHAPTER 1

Introduction to Oracle Solaris 10 Zones

BrandZ provides the framework to create branded zones, which are used to run applications that cannot be run in an OracleTM Solaris 11 environment. The brand described here is the solaris10 brand, Oracle Solaris 10 Zones. Workloads running within these solaris10 branded zones can take advantage of the enhancements made to the Oracle Solaris kernel and utilize some of the innovative technologies available only on the Oracle Solaris 11 release, such as virtual NICs (VNICs) and ZFS deduplication.

Note - If you want to create a solaris10 branded zone now, go to Chapter 2, "Assessing an Oracle Solaris 10 System and Creating an Archive".

About the solaris10 Brand

The solaris10 branded zone, described in the solaris10(5) man page, is a complete runtime environment for Oracle Solaris 10 applications on SPARC and x86 machines running the Oracle Solaris 10 9/10 operating system or later released update. If you are running an Oracle Solaris 10 release earlier than Oracle Solaris 10 9/10, it is possible to use the earlier update release if you first install the kernel patch 142909-17 (SPARC) or 142910-17 (x86/x64), or later version, on the original system. You must install the patch before you create the archive that will be used to install the zone. It is the kernel patch of the release that is the prerequisite for migration to Oracle Solaris 10 Zones, not the full Oracle Solaris 10 9/10 or later release. The software download site for patches is My Oracle Support (https://support.oracle.com). Click on the "Patches & Updates" tab. On that site, you can view the download instructions and download the images. Contact your support provider for additional information regarding patches.


Non-global zones running within a single global zone instance are supported on all architectures that the Oracle Solaris 11.3 release has defined as supported platforms.

The brand includes the tools required to install an Oracle Solaris 10 system image into a non-global zone. You cannot install a solaris10 brand zone directly from Oracle Solaris 10 media. A physical-to-virtual (P2V) capability is used to directly migrate an existing system into a non-global zone on a target system. The zonep2vchk tool is used to generate information needed for the P2V process and to output a template zonecfg command file for use on the target system. The utility creates a zone that matches the source system's configuration. To use the utility on

Oracle Solaris 10, download the unbundled package from the Oracle Technology Network (OTN). The unbundled package installs into /opt/SUNWzonep2vchk.

The brand also supports the tools used to migrate an Oracle Solaris 10 native zone into a solaris10 brand non-global zone. The virtual-to-virtual (V2V) process for migrating an Oracle Solaris 10 native non-global zone into a solaris10 branded zone supports the same archive formats as P2V. See Chapter 3, "Migrating an Oracle Solaris 10 native Non-Global Zone Into an Oracle Solaris 10 Zone" for more information.

FIGURE 1 Oracle Solaris 10 Containers Transition to Oracle Solaris 10 Zones



solaris10 Zone Support

The solaris10 brand zone supports the whole root non-global zone model. All of the required Oracle Solaris 10 software and any additional packages are installed into the private file systems of the zone.

The non-global zone must reside on its own ZFS dataset; only ZFS is supported. The ZFS dataset will be created automatically when the zone is installed or attached. If a ZFS dataset cannot be created, the zone will not install or attach. Note that the parent directory of the zone path must also be a ZFS dataset, or the file system creation will fail.

Any application or program that executes in a native Oracle Solaris 10 non-global zone should also work in a solaris10 branded zone.

Note that zones do not support statically linked binaries.

Note - You can create and install solaris10 branded zones on an Oracle Solaris Trusted Extensions system that has labels enabled, but you can only boot branded zones on this system configuration *if* the brand being booted is the labeled brand. Customers using Oracle Solaris Trusted Extensions on Oracle Solaris 10 systems must transition to a certified Oracle Solaris system configuration.

SVR4 Packaging and Patching in Oracle Solaris 10 Zones

About Using Packaging and Patching in solaris10 Branded Zones

The SVR4 package metadata is available inside the zone, and the package and patch commands work correctly. For proper operation, note that you *must* install patches 119254-75 (SPARC) or 119255-75 (x86/x64), or later versions, on your Oracle Solaris 10 system *before* the archive is created. The software download site for patches is My Oracle Support (https://support.oracle.com). Click on the "Patches & Updates" tab to view the download instructions and download the images. Contact your support provider for additional information regarding patches.

Because the solaris10 brand zones are whole root zones, all packaging and patch operations work as described in the man pages and other documentation. Note that the kernel components of the package or patch are not used for the installation. SVR4 packages are only installed into the current zone. For information about SVR4 packaging used in solaris10 and native zones, see "Chapter 25, About Packages on an Solaris System With Zones Installed (Overview)" and "Chapter 26, Adding and Removing Packages and Patches on a Solaris System With Zones Installed (Tasks)" in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*. This is the Oracle Solaris 10 version of the guide.

For information on system release level, see Chapter 1, "Introduction to Oracle Solaris 10 Zones".

About Performing Package and Patch Operations Remotely

For patch operations initiated from within Oracle Solaris 10 Zones, if the remote system is another solaris10 zone, the patching operation works correctly. However, if the remote system is a miniroot or an Oracle Solaris 10 system that is not a solaris10 zone, the operation will produce undefined results. Similarly, the patch tools will produce undefined results if used to

patch Oracle Solaris 10 Zones from miniroots or physical systems instead of Oracle Solaris 10 Zones.

Note that in general, the patchadd and patchrm tools allow administrators to specify alternate roots when running patch operations. This capability allows administrators to patch remote systems, such as Oracle Solaris 10 miniroots and Oracle Solaris 10 physical systems, which have root directories visible over NFS. For example, if the root directory of an Oracle Solaris 10 system is NFS-mounted onto a local system's /net/a-system directory, then the remote Oracle Solaris 10 system could be patched from the local system.

To install patch 142900-04 (or later version) on the remote system:

patchadd -R /net/a-system 142900-04

For more information, see the following man pages in the *man pages section 1M: System Administration Commands*:

- patchadd(1M), the -R and -C options
- \blacksquare patchrm(1M)

Non-Global Zones as NFS Clients

Zones can be NFS clients. Version 2, version 3, and version 4 protocols are supported. For information on these NFS versions, see "Features of the NFS Service" in *Managing Network File Systems in Oracle Solaris* 11.3.

The default version is NFS version 4. You can enable other NFS versions on a client by using one of the following methods:

- You can edit /etc/default/nfs to set NFS_CLIENT_VERSMAX=number so that the zone uses the specified version by default. See "Setting Up the NFS Service" in Managing Network File Systems in Oracle Solaris 11.3. Use the procedure "How to Select Different Versions of NFS on a Client by Modifying the /etc/default/nfs File" from the task map.
- You can manually create a version mount. This method overrides the contents of /etc/default/nfs. See "Setting Up the NFS Service" in *Managing Network File Systems in Oracle Solaris 11.3*. Use the procedure How to Use the Command Line to Select Different Versions of NFS on a Client from the task map.

General Zones Concepts

You should be familiar with the following resource management and zones concepts, which are discussed in *Administering Resource Management in Oracle Solaris 11.3* and in *Creating and Using Oracle Solaris Zones*.

- zonep2vchk tool
- Supported and unsupported features
- Resource controls that enable the administrator to control how applications use available system resources
- Commands used to configure, install, and administer zones, primarily zonecfg, zoneadm, and zlogin
- zonecfg resources and property types
- The global zone and the non-global zone
- The whole-root non-global zone model
- Authorizations granted through the zonecfg utility
- The global administrator and the zone administrator
- The zone state model
- The zone isolation characteristics
- Privileges
- Networking
- Using the anet resource to configure IPoIB
- Zone shared-IP and exclusive-IP types
- The use of resource management features, such as resource pools, with zones
- The fair share scheduler (FSS), a scheduling class that enables you to allocate CPU time based on shares
- The resource capping daemon (rcapd), which can be used from the global zone to control resident set size (RSS) usage of branded zones

About Oracle Solaris 10 Zones in This Release

Operating Limitations

A /dev/sound device cannot be configured into the solaris10 branded zone.

The file-mac-profile property used to create read-only zones is not available.

The quota command documented in quota(1M) cannot be used to retrieve quota information for UFS file systems being used inside the solaris10 branded zone.

A solaris10 branded zone cannot be an NFS server.

An automounter in a solaris10 branded zone does not support the NIS+ naming service.

Networking in Oracle Solaris 10 Zones

The following sections identify Oracle Solaris 10 networking components that are either not available in Oracle Solaris 10 Zones or that are different in Oracle Solaris 10 Zones.

Networking Components That Are Not Supported

- Automatic tunnels using the atun STREAMS module are not supported.
- The following ndd tunable parameters are not supported in a solaris10 branded zone:
 - ip squeue fanout
 - ip soft rings cnt
 - ip ire pathmtu_interval
 - tcp mdt max pbufs

Networking Features That Are Different

In a solaris10 branded zone with an exclusive-IP configuration, the following features are different from a physical Oracle Solaris 10 system:

- Mobile IP is not available because it is not available in the Oracle Solaris 11 release.
- In a solaris10 branded zone, an autopush configuration will be ignored when the tcp, udp, or icmp sockets are open. These sockets are mapped to modules instead of STREAMS devices by default. To use autopush, explicitly map these sockets to STREAMS-based devices by using the soconfig and sock2path.d utilities described in the soconfig(1M) and sock2path.d(4) man pages.
- In a solaris10 branded zone archived from a physical system running Oracle Solaris 10 9/10 or an earlier update, /dev/net links, such as VNICs, are not supported by the Data Link Provider Interface library (libdlpi). These links are supported on Oracle Solaris 10 8/11. The library is described in thelibdlpi(3LIB) man page.
 - Applications that do not use either the libdlpi library in Oracle Solaris 10 8/11 or libpcap versions 1.0.0 or higher libraries will not be able to access /dev/net links, such as VNICs.
- Because IP Network Multipathing (IPMP) in Oracle Solaris 10 Zones is based on the Oracle Solaris 11 release, there are differences in the output of the ifconfig command when compared to the command output in the Oracle Solaris 10 operating system. However, the documented features of the ifconfig command and IPMP have not changed. Therefore, Oracle Solaris 10 applications that use the documented interfaces will continue to work in Oracle Solaris 10 Zones without modification. All of the standard Oracle Solaris 10 networking facilities, such as ifconfig and /etc/hostname.name, should be used to configure and use IPMP and perform all other network configuration.

The following example shows ifconfig command output in a solaris10 branded zone for an IPMP group ipmp0 with data address 192.168.1.3 and the underlying interfaces e1000g1 and e1000g2, with test addresses 192.168.1.1 and 192.168.1.2, respectively.

- Unlike the display produced on an Oracle Solaris 10 system, the ifconfig command in an Oracle Solaris 10 Container does not show the binding of the underlying interfaces to IP addresses. This information can be obtained by using the arp command with the -an options.
- If an interface is plumbed for IPv6 and address configuration succeeds, then the interface is given its own global address. In an Oracle Solaris 10 system, each physical interface in an IPMP group will have its own global address, and the IPMP group will have as many global addresses as there are interfaces. In a Oracle Solaris 10 Zones, only the IPMP interface will have its own global address. The underlying interfaces will not have their own global addresses.
- Unlike the Oracle Solaris 10 operating system, if there is only one interface in an IPMP group, then its test address and its data address cannot be the same.
- For information on configuring an IPMP group in a solaris10 zone in an Oracle Solaris Zones cluster, refer to the Oracle Solaris Cluster 4.1 Release Notes.

See the arp(1M) and ifconfig(1M) man pages, and "IP Network Multipathing in Exclusive-IP Zones" in *Creating and Using Oracle Solaris Zones*.

If native Non-Global Zones Are Installed

An additional step in the P2V process occurs when there are native zones on the Oracle Solaris 10 9/10 (or later released update) source physical system. Because zones do not nest, the P2V process on these systems makes the existing zones unusable inside the branded zone. The

existing zones are detected when the zone is installed, and a warning is issued indicating that any nested zones will not be usable and that the disk space could be recovered. Those zones can be migrated first using the V2V process described in Chapter 3, "Migrating an Oracle Solaris 10 native Non-Global Zone Into an Oracle Solaris 10 Zone".

If you apply the kernel patch on a system running an earlier release, apply the patch before you migrate the existing zones.



Assessing an Oracle Solaris 10 System and Creating an Archive

This chapter discusses obtaining information about the Oracle Solaris 10 10/09 (or later released update) system and creating the archive of the system. A physical-to-virtual (P2V) capability is used to directly migrate an existing Oracle Solaris system into a non-global zone on a target system. Information on required packages on the target system is also provided.

Source and Target System Prerequisites

Enabling Oracle Solaris 10 Package and Patch Tools

To use the Oracle Solaris 10 package and patch tools in Oracle Solaris 10 Zones, install the following patches for your architecture on your source system *before* the image is created.

- 119254-75, 119534-24, and 140914-02 (SPARC)
- 119255-75, 119535-24 and 140915-02 (x86/x64)

The P2V process will work without the patches, but the package and patch tools will not work properly within the solaris10 branded zone.

Installing the Required Oracle Solaris Package on the Target System

To use Oracle Solaris 10 Zones on your system, pkg:/system/zones/brand/brand-solaris10 must be installed on the system running Oracle Solaris 11.

For more information on the repository, see *Adding and Updating Software in Oracle Solaris* 11.3.

For package installation instructions, see Chapter 3, "Installing and Updating Software Packages" in *Adding and Updating Software in Oracle Solaris* 11.3.

Assess the System To Be Migrated By Using the zonep2vchk Utility

An existing Oracle Solaris 10 9/10 system (or later released Solaris 10 update) can be directly migrated into a solaris10 branded zone on an Oracle Solaris 11 system.

To begin, examine the source system and collect needed information by using the zonep2vchk tool documented in zonep2vchk(1M) and Chapter 7, "Migrating and Converting Oracle Solaris Zones" in *Creating and Using Oracle Solaris Zones*. This tool is used to assess the system to be migrated and to produce a zonecfq template that includes a networking configuration.

Depending on the services performed by the original system, the global administrator or a user granted the appropriate authorizations might need to manually customize the zone after it has been installed. For example, the privileges assigned to the zone might need to be modified. This is not done automatically. Also, because not all system services work inside zones, not every Oracle Solaris 10 system is a good candidate for migration into a zone.

Note - If there are any native non-global zones on the system to be migrated, these zones must either be deleted, or be archived and moved into zones on the new target system first. For a sparse root zone, the archive must be made with the zone in the ready state. For additional information on migration, see Chapter 3, "Migrating an Oracle Solaris 10 native Non-Global Zone Into an Oracle Solaris 10 Zone". For additional information on sparse root zones, see "Zones Overview" in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones* in the Oracle Solaris 10 documentation.

Oracle Solaris 10 Systems Only: Obtaining the zonep2vchk Utility

To use the utility on the Oracle Solaris 10 system, you can download the unbundled package from the Oracle Technology Network (OTN). The unbundled package installs into /opt/SUNWzonep2vchk.

Creating the Image for Directly Migrating Oracle Solaris 10 Systems Into Zones

You can use the Oracle Solaris Flash archiving tools to create an image of an installed system that can be migrated into a zone.

Note - Oracle Solaris Flash archiving tools are supported only with solaris10 branded zones. As of Oracle Solaris 11.2, Unified Archives are the only supported archiving file type for solaris and solaris-kz branded zones. See Chapter 7, "Migrating and Converting Oracle Solaris Zones" in *Creating and Using Oracle Solaris Zones* and *Using Unified Archives for System Recovery and Cloning in Oracle Solaris 11.3* for information on working with Unified Archives.

The system can be fully configured with all of the software that will be run in the zone before the image is created. This image is then used by the installer when the zone is installed.

▼ How to Use flarcreate to Create the Image

On a system with a ZFS root, you can use the flarcreate command described in the flarcreate(1M) Oracle Solaris 10 man page to create the system image. By default, the flar created is a ZFS send stream as described in "Saving, Sending, and Receiving ZFS Data" in Managing ZFS File Systems in Oracle Solaris 11.3.

This example procedure uses NFS to place the flash archive on the target Oracle Solaris 11 system, but you could use any method to move the files.

You must be the global administrator or a user with the required rights profile in the global zone to perform this procedure.

1. Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

- 2. Log into the source Oracle Solaris 10 system to be archived.
- Change directories to the root directory.

cd /

4. Use flarcreate to create a flash archive image file named s10-system on the source system, and place the archive onto the target Oracle Solaris 11 system:

source-system # flarcreate -n s10-system /net/target/export/archives/s10-system.flar

▼ How to Use flarcreate to Exclude Certain Data

To exclude data that is not on a ZFS dataset boundary from the archive, you must use cpio or pax with flarcreate. You can use the -L archiver option to specify cpio or pax as the method to archive the files.

This example procedure uses NFS to place the flash archive on the target Oracle Solaris 11 system, but you could use any method to move the files.

You must be the global administrator or a user with the required rights profile in the global zone to perform this procedure.

1. Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

- 2. Log in to the source Oracle Solaris 10 system to be archived.
- 3. Change directories to the root directory.

cd /

4. Use flarcreate to create a flash archive image file named s10-system on the source system, and place the archive onto the target Oracle Solaris 11 system:

```
source-system # flarcreate -S -n s10-system -x /path/to/exclude -L cpio /net/target/
export/archives/s10-system.flar
Determining which filesystems will be included in the archive...
Creating the archive...
cpio: File size of "etc/mnttab" has
increased by 435
2068650 blocks
1 error(s)
Archive creation complete.
```

Tip - In some cases, flarcreate can display errors from the cpio command. Most commonly, these are messages such as File size of etc/mnttab has increased by 33. When these messages pertain to log files or files that reflect system state, they can be ignored. Be sure to review all error messages thoroughly.

Other Archive Creation Methods

You can use alternate methods for creating the archive. The installer can accept the following archive formats:

- cpio archives
- gzip compressed cpio archives
- bzip2 compressed cpio archives
- pax archives created with the -x xustar (XUSTAR) format
- ufsdump level zero (full) backups

Additionally, the installer can only accept a directory of files created by using an archiving utility that saves and restores file permissions, ownership, and links.

For more information, see the cpio(1), pax(1), bzip2(1), gzip(1), and ufsdump(1M) man pages.

Note - If you use a method other than flash archive for creating an archive for P2V, you must unmount the processor-dependent libc.so.1 lofs-mounted hardware capabilities (hwcap) library on the source system before you create the archive. Otherwise, the zone installed with the archive might not boot on the target system.

The mountpoints to unmount vary by architecture and release of Oracle Solaris 10. You must grep the mountpoints for libc and umount any that exist. After you have created the archive, you can remount the proper hardware capabilities by restarting the filesystem/root service.

1. Determine optimized libc mountpoints.

```
source-system# mount | egrep '(libc_psr.so.1|libc.so.1)'
```

2. umount any exisiting libc mountpoints.

SPARC command examples:

```
source-system# umount /platform/sun4v/lib/libc_psr.so.1
source-system# umount /platform/sun4v/lib/sparcv9/libc_psr.so.1
x86 command example:
```

```
source-system# umount /lib/libc.so.1
```

- 3. Create archive of Oracle Solaris10 system.
- 4. Restart the filesystem/root service.

source-system# svcadm restart svc:/system/filesystem/root:default

Host ID Emulation

When applications are migrated from a standalone Oracle Solaris system into a zone on a new system, the hostid changes to be the hostid of the new system.

In some cases, applications depend on the original hostid, and it is not possible to update the application configuration. In these cases, the zone can be configured to use the hostid of the original system. This is done by setting a zonecfg property to specify the hostid, as described in "How to Configure the Zone" in *Creating and Using Oracle Solaris Zones* . The value used should be the output of the hostid command as run on the original system. To view the hostid in an installed zone, also use the hostid command.

For more information about host IDs, see hostid(1).



Migrating an Oracle Solaris 10 native Non-Global Zone Into an Oracle Solaris 10 Zone

This chapter describes migrating native non-global zones on an Oracle Solaris 10 9/10 (or later released update) system into Oracle Solaris 10 Zones on a system running the Oracle Solaris 11 release.

Only read this chapter if there are any native non-global zones on the system that you want to migrate. These zones must be archived and moved into branded zones on the new target system first.

Archive Considerations

A sparse root zone on an Oracle Solaris 10 system is converted by the system to a whole root model for the solaris10 branded zone migration. A sparse root zone must be in the ready state on the source system before the V2V process occurs. This will mount any inherited-pkg-dir resources before the archive is created. See "Zones Overview" in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones* in the Oracle Solaris 10 version of this guide for more information on these concepts.

The zone's brand will be changed as part of the process.

Overview of the solaris10 Zone Migration Process

The virtual-to-virtual (V2V) process for migrating an Oracle Solaris 10 native zone to a solaris10 branded zone supports the same archive formats as P2V. This process uses the zoneadm install subcommand. The solaris10 brand install subcommand uses the following options, which correspond to the same options in the attach subcommand.

Note - Use of the install subcommand is recommended.

Option	Description	
-a path	Specifies a path to an archive to unpack into the zone. Full flash archive and pax, cpio, gzip compressed cpio, bzip compressed cpio, and level 0 ufsdump are supported.	
-d <i>path</i>	Specifies a path to a tree of files as the source for the installation.	
-d —	Use the -d option with the dash parameter to direct that the existing directory layout be used in the zonepath. Thus, if the administrator manually sets up the zonepath directory before the installation, the -d – option can be used to indicate that the directory already exists.	

About Detaching and Attaching the solaris10 Zone

A solaris10 zone can be migrated to an Oracle Solaris host by configuring the zone on the target system, then using the zoneadm command with the detach and attach subcommands and either the -a option to attach an archive or the -d option to specify a zonepath. This process is described in Chapter 7, "Migrating and Converting Oracle Solaris Zones" in *Creating and Using Oracle Solaris Zones*.

Note - Use of the install subcommand is recommended.

Migrating a solaris10 Branded Zone

The zonecfg and zoneadm commands can be used to migrate an existing non-global zone from one system to another. The zone is halted and detached from its current host. The zonepath is moved to the target host, where it is attached.

The zoneadm detach process creates the information necessary to attach the zone on a different system. The zoneadm attach process verifies that the target system has the correct configuration to host the zone.

Because there are several ways to make the zonepath available on the new host, the actual movement of the zonepath from one system to another is a manual process that is performed by the global administrator.

When attached to the new system, the zone is in the installed state.

EXAMPLE 1 Sample attach Command

host2# zoneadm -z zonename attach -a /net/machine_name/s10-system.flar

Migrating an Existing Zone on an Oracle Solaris 10 System

Before a physical system can be migrated, any existing non-global zones on the system must be archived and moved into zones on the new target system first.

▼ How to Migrate an Existing native Non-Global Zone

Use the V2V process to migrate an existing zone on your Solaris 10 system to a solaris 10 brand zone on a system running the Oracle Solaris 11 release.

Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris 11.3*.

2. Print the existing zone's configuration. You will need this information to recreate the zone on the destination system:

```
source# zonecfg -z my-zone info
zonename: my-zone
zonepath: /zones/my-zone
brand: native
autoboot: false
bootargs:
pool:
limitoriv:
scheduling-class:
ip-type: shared
hostid: 1337833f
inherit-pkg-dir:
         dir: /lib
inherit-pkg-dir:
         dir: /platform
inherit-pkg-dir:
         dir: /sbin
inherit-pkg-dir:
         dir: /usr
net:
         address: 192.168.0.90
         physical: bge0
```

3. Halt the zone:

```
source# zoneadm -z my-zone halt
```

You should not archive a running zone because the application or system data within the zone might be captured in an inconsistent state.

4. (Optional) If the zone is a sparse root zone that has inherit-pkg-dir settings, then first ready the zone so that the inherited directories will be archived:

```
source# zoneadm -z my-zone ready
```

- 5. Archive the zone with the zonepath /zones/my-zone.
 - Create a gzip compressed cpio archive named my-zone.cpio.gz for the zone, which will still be named my-zone on the target system:

```
source# cd /zones
source# find my-zone -print | cpio -oP@ | gzip >/zones/my-zone.cpio.gz
```

■ Create the archive from within the zonepath if you intend to rename the zone on the target system:

```
source# cd /zones/my-zone
source# find root -print | cpio -oP@ | gzip >/zones/my-zone.cpio.gz
```

- 6. Transfer the archive to the target Oracle Solaris 11.3 system, using any file transfer mechanism to copy the file, such as:
 - The sftp command described in the sftp(1) man page
 - NFS mounts
 - Any other file transfer mechanism to copy the file.
- 7. On the target system, recreate the zone.

```
target# zonecfg -z my-zone
my-zone: No such zone configured
Use 'create' to begin configuring a new zone.
zonecfg:my-zone> create -t SYSsolaris10
zonecfg:my-zone> set zonepath=/zones/my-zone
...
```

Note - The zone's brand must be solaris10 and the zone cannot use any inherit-pkg-dir settings, even if the original zone was configured as a sparse root zone. See Part II, "Zones," in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones* for information on inherit-pkg-dir resources.

If the destination system has different hardware, different network interfaces, or other devices or file systems that must be configured on the zone, you must update the zone's configuration. See Chapter 1, "Non-Global Zone Configuration" in *Oracle Solaris Zones Configuration Resources*, Chapter 7, "Migrating and Converting Oracle Solaris Zones" in *Creating and Using Oracle Solaris Zones*, and Chapter 1, "How to Plan and Configure Non-Global Zones" in *Creating and Using Oracle Solaris Zones*.

8. Display the zone's configuration:

9. Install the zone from the archive that was created on the source system, with the archive transferred into the /zones directory on the destination system:

```
target# zoneadm -z my-zone install -a /zones/my-zone.cpio.gz
```

Once the zone installation has completed successfully, the zone is ready to boot.

You can save the zone's archive for possible later use, or remove it from the system.

To remove the archive from the destination system:

```
target# rm /zones/myzone.cpio.gz
```



Configuring the solaris10 Branded Zone

This chapter discusses configuring the solaris10 branded zone.

Preconfiguration Tasks

You will need the following:

- A supported SPARC or x86 system running the Oracle Solaris 11.3 release.
- The default is the exclusive-IP type with an anet resource. For a shared-IP zone that requires network connectivity, you will need to provide one or more unique IPv4 addresses for each zone you want to create. You must also specify the physical interface.
- A machine running the Oracle Solaris 10 10/09 (or later released update) operating system that you want to migrate into a solaris10 container. An earlier update can be migrated with the appropriate kernel patch. You can generate your own images from existing systems. The process is described in "Creating the Image for Directly Migrating Oracle Solaris 10 Systems Into Zones" on page 19.

Resources Included in the Configuration by Default

Devices, file systems, and privileges in a branded zone are included in the configuration by default.

Configured Devices in solaris10 Branded Zones

The devices supported by each zone are documented in the man pages and other documentation for that brand. The solaris10 zone does not allow the addition of any unsupported or unrecognized devices. The framework detects any attempt to add an unsupported device. An error message is issued that indicates the zone configuration cannot be verified.

To learn more about device considerations in non-global zones, see "Device Use in Non-Global Zones" in *Creating and Using Oracle Solaris Zones*.

Privileges Defined in solaris10 Branded Zones

Processes are restricted to a subset of privileges. Privilege restriction prevents a zone from performing operations that might affect other zones. The set of privileges limits the capabilities of privileged users within the zone.

Default, required default, optional, and prohibited privileges are defined by each brand. You can also add or remove certain privileges by using the limitpriv property as shown in Step 8 of "How to Configure the Zone" in *Creating and Using Oracle Solaris Zones*. See "Privileges in a Non-Global Zone" in *Creating and Using Oracle Solaris Zones* for a list of Solaris privileges and the status of each with respect to zones.

For more information about privileges, see the ppriv(1) man page and *Securing Users and Processes in Oracle Solaris* 11.3.

solaris10 Branded Zone Configuration Process

The zonecfg command is used to do the following:

- Set the brand for the zone.
- Create the configuration for the solaris10 zone.
- Verify the configuration to determine whether the specified resources and properties are allowed and internally consistent on a hypothetical system.
- Perform a brand-specific verification.

You can create the zone configuration by using the zonep2vchk utility.

The check performed by the zonecfg verify command for a given configuration verifies the following:

- Ensures that a zone path is specified
- Ensures that all of the required properties for each resource are specified
- Ensures that brand requirements are met

For more information about the zonecfg command, see the zonecfg(1M) man page.

Configuring the Target Zone

The following must be installed on your Oracle Solaris 11 system: pkg:/system/zones/brand/brand-solaris10.

Create the new zone configuration on the target system by using the zonecfg command.

The zonecfg prompt is of the following form:

zonecfg:zonename>

When you are configuring a specific resource type, such as a file system, that resource type is also included in the prompt:

zonecfg:zonename:fs>

Tip - If you know you will be using CDs or DVDs to install applications in a solaris10 branded zone, use add fs to add read-only access to CD or DVD media in the global zone when you initially configure the branded zone. A CD or DVD can then be used to install a product in the branded zone. See "How to Add Access to CD or DVD Media in a Non-Global Zone" in *Creating and Using Oracle Solaris Zones* for more information.

▼ How to Configure an Exclusive-IP solaris10 Branded Zone

You must be the global administrator or a user with the appropriate authorizations in the global zone to perform this procedure.

Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

2. Create an exclusive-IP solaris10 zone with the zone name s10-zone.

global# zonecfg -z s10-zone

If this is the first time you have configured this zone, you will see the following system message:

Use 'create' to begin configuring a new zone.

3. Create the new solaris10 zone configuration by using the SYSsolaris10 template.

zonecfg:s10-zone> create -t SYSsolaris10

The SYSsolaris10 profile creates an exclusive-IP zone that includes an automatic anet resource by default.

4. Set the zone path, /zones/s10-zone in this procedure.

zonecfg:s10-zone> set zonepath=/zones/s10-zone

5. Set the autoboot value.

```
zonecfg:s10-zone> set autoboot=true
```

If set to true, the zone is automatically booted when the global zone is booted. The default value is false. Note that for the zones to autoboot, the zones service svc:/system/zones: default must also be enabled. You can enable the zones service with the svcadm command.

6. Add a ZFS file system shared with the global zone.

zonecfg:s10-zone> add fs

a. Set the type to zfs.

zonecfg:s10-zone:fs> set type=zfs

b. Set the directory to mount from the global zone.

zonecfg:s10-zone:fs> set special=share/zone/s10-zone

c. Specify the mount point.

zonecfg:s10-zone:fs> set dir=/opt/shared

d. End the specification.

```
zonecfg:s10-zone:fs> end
```

This step can be performed more than once to add more than one file system.

7. Delegate a ZFS dataset named sales in the storage pool tank.

 ${\tt zonecfg:s10-zone>~\textbf{add}~\textbf{dataset}}$

a. Specify the path to the ZFS dataset sales.

zonecfg:s10-zone> set name=tank/sales

b. End the dataset specification.

zonecfg:s10-zone> end

8. Set the hostid to be the hostid of the source system.

zonecfg:s10-zone> set hostid=80f0c086

9. Verify the zone configuration for the zone.

zonecfg:s10-zone> verify

10. Commit the zone configuration for the zone.

zonecfg:s10-zone> commit

11. Exit the zonecfg command.

zonecfg:s10-zone> exit

Note that even if you did not explicitly type commit at the prompt, a commit is automatically attempted when you type exit or an EOF occurs.

12. Use the info subcommand to verify that the brand is set to solaris10.

global# zonecfg -z s10-zone info

13. (Optional) Use the info subcommand to check the hostid:

global# zonecfg -z s10-zone info hostid

Next Steps

Tip - After you have configured the zone, it is a good idea to make a copy of the zone's configuration. You can use this backup to recreate the zone in the future. As root or an administrator with the correct profile, print the configuration for the zone *s10-zone* to a file. This example uses a file named *s10-zone*.config.

global# zonecfg -z s10-zone export > s10-zone.config

See Also

For additional components that can be configured using zonecfg, see Chapter 1, "Non-Global Zone Configuration" in *Oracle Solaris Zones Configuration Resources*. This guide also provides information on using the zonecfg command in either command-line or command-file mode. Note that for shared-IP zones, a static address must be assigned in a zonecfg net resource. For more information about adding ZFS file systems, see "Adding ZFS File Systems to a Non-Global Zone" in *Managing ZFS File Systems in Oracle Solaris 11.3*.

▼ How to Configure a Shared-IP solaris10 Branded Zone

You must be the global administrator or a user with the appropriate authorizations in the global zone to perform this procedure.

1. Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

2. Create a shared-IP solaris10 zone with the zone name s10-zone.

```
global# zonecfg -z s10-zone
```

If this is the first time you have configured this zone, you will see the following system message:

Use 'create' to begin configuring a new zone.

3. Create the new solaris10 zone configuration.

```
zonecfg:s10-zone> create -b
zonecfg:s10-zone> set brand=solaris10
```

Note - Do not use create -t SYSsolaris10-shared-ip to set the IP type.

4. Set the zone path, /zones/s10-zone in this procedure.

zonecfg:s10-zone> set zonepath=/zones/s10-zone

5. Set the autoboot value.

If set to true, the zone is automatically booted when the global zone is booted. Note that for the zones to autoboot, the zones service svc:/system/zones:default must also be enabled. The default value is false.

zonecfg:s10-zone> set autoboot=true

6. Create a shared-IP zone with a network virtual interface.

```
zonecfg:s10-zone> set ip-type=shared
zonecfg:s10-zone> add net
```

a. Set the physical device type for the network interface, the net device in this procedure.

 ${\tt zonecfg:s10-zone:net>~\textbf{Set~physical=net0}}$

b. Set the IP address, 10.6.10.233/24 in this procedure.

 ${\tt zonecfg:s10-zone:net>}~\textbf{set}~\textbf{address=10.6.10.233/24}$

c. End the specification.

zonecfg:s10-zone:net> end

This step can be performed more than once to add more than one network interface.

7. Add a ZFS file system shared with the global zone.

```
zonecfg:s10-zone> add fs
```

a. Set the type to zfs.

```
zonecfg:s10-zone:fs> set type=zfs
```

b. Set the directory to be mounted from the global zone.

```
zonecfg:s10-zone:fs> set special=share/zone/s10-zone
```

c. Specify the mount point.

```
zonecfg:s10-zone:fs> set dir=/opt/shared
```

d. End the specification.

```
zonecfg:s10-zone:fs> end
```

This step can be performed more than once to add more than one file system.

8. Delegate a ZFS dataset named sales in the storage pool tank.

```
zonecfg:s10-zone> add dataset
```

a. Specify the path to the ZFS dataset sales.

```
zonecfg:s10-zone> set name=tank/sales
```

b. End the dataset specification.

```
zonecfg:s10-zone> end
```

9. Set the hostid to be the hostid of the source system.

```
zonecfg:s10-zone> set hostid=80f0c086
```

10. Verify the zone configuration for the zone.

```
zonecfg:s10-zone> verify
```

11. Commit the zone configuration for the zone.

```
zonecfg:s10-zone> commit
```

12. Exit the zonecfg command.

zonecfg:s10-zone> exit

Note that even if you did not explicitly type commit at the prompt, a commit is automatically attempted when you type exit or an EOF occurs.

13. Use the info subcommand to verify that the brand is set to solaris10.

global# zonecfg -z s10-zone info

14. (Optional) Use the info subcommand to check the hostid:

global# zonecfg -z s10-zone info hostid

Next Steps

Tip - After you have configured the zone, it is a good idea to make a copy of the zone's configuration. You can use this backup to recreate the zone in the future. As root or an administrator with the correct profile, print the configuration for the zone *s10-zone* to a file. This example uses a file named *s10-zone*.config.

global# zonecfg -z s10-zone export > s10-zone.config

See Also

For additional components that can be configured using zonecfg, see Chapter 1, "Non-Global Zone Configuration" in *Oracle Solaris Zones Configuration Resources*. This guide also provides information on using the zonecfg command in either command-line or command-file mode. Note that for shared-IP zones, a static address must be assigned in a zonecfg net resource. For more information about adding ZFS file systems, see "Adding ZFS File Systems to a Non-Global Zone" in *Managing ZFS File Systems in Oracle Solaris 11.3*.



Installing the solaris10 Branded Zone

This chapter covers installing a solaris10 branded zone.

Zone Installation Images

Types of System Images

- You can use an image of an Oracle Solaris system that has been fully configured with all of the software that will be run in the zone. See "Creating the Image for Directly Migrating Oracle Solaris 10 Systems Into Zones" on page 19. The zoneadm install -a command takes an archive of a physical system.
- You can use an image of an existing Oracle Solaris 10 native zone instead of an image from a physical system. See Chapter 3, "Migrating an Oracle Solaris 10 native Non-Global Zone Into an Oracle Solaris 10 Zone". The zoneadm install -a commands take an archive of a zone or an archive of a physical system. and the zoneadm attach -a command takes an archive of a zone.

Image sysidcfg Status

The -c can be used to pass a sysidcfg file to use in configuring the zone after the installation completes.

If you created an Oracle Solaris 10 system archive from an existing system and use the -p (preserve sysidcfg) option when you install the zone, then the zone will have the same identity as the system used to create the image.

If you use the -u (sys-unconfig) and -coptions when you install the target zone, the zone produced will not have a hostname or name service configured.

Install the solaris10 Branded Zone

The zoneadm command described in "Installing and Booting Zones" in *Creating and Using Oracle Solaris Zones* and in the zoneadm(1M) man page is the primary tool used to install and administer non-global zones. Operations using the zoneadm command must be run from the global zone on the target system.

In addition to unpacking files from the archive, the install process performs checks, required postprocessing, and other functions to ensure that the zone is optimized to run on the host.

If you created an Oracle Solaris system archive from an existing system and use the -p (preserve sysidcfg) option when you install the zone, then the zone will have the same identity as the system used to create the image.

If you use the -u (sys-unconfig) option when you install the target zone, the zone produced will not have a hostname or name service configured.



Caution - You *must* use either the -p option or the -u option. If you do not specify one of these two options, an error results.

Installer Options

Option	Description
-a	Location of archive from which to copy system image. Full flash archive and pax, cpio, gzip compressed cpio, bzip compressed cpio, and level 0 ufsdump are supported.
-c path	Pass a sysidcfg file to use in configuring the zone after the install completes.
-d path	Location of directory from which to copy system image.
-d -	Use the -d option with the dash parameter to direct that the existing directory layout be used in the zonepath. Thus, if the administrator manually sets up the zonepath directory before the installation, the -d – option can be used to indicate that the directory already exists.
-p	Preserve system identity.
	Either the -p or the -u must be used.
-s	Install silently.
-u	sys-unconfig the zone.
	Either the -p or the -u must be used.
	The -c can be used in addition to the -u option, to pass in a sysidcfg file to use in configuring the zone after the installation completes.
-v	Verbose output.

The -a and -d options are mutually exclusive.

▼ How to Install the solaris10 Branded Zone

A configured solaris10 branded zone is installed by using the zoneadm command with the install subcommand.

For information about creating images of Oracle Solaris 10 systems, see "Creating the Image for Directly Migrating Oracle Solaris 10 Systems Into Zones" on page 19. To retain the sysidcfg identity from a system image that you created, without altering the image, use the -p option after the install subcommand. To remove the system identity from a system image that you created, without altering the image, use the -u option. The sys-unconfig occurs to the target zone. The -c option can be used to include a sysidcfg file that contains the information used to configure the zone after the install completes.

The example procedure shows how to use the -a option with the created archive image of a physical installed Oracle Solaris 10 system.

You must be the global administrator or a user with the appropriate authorizations in the global zone to perform this procedure.

Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

2. Install the configured zone s10-zone by using the zoneadm install command with the -p and -a options and the path to the archive:

```
global# zoneadm -z s10-zone install -a /net/data13/tmp/s10u10_sparc_sepvar.flar -p
```

You will see various messages as the installation completes. This can take some time.

3. (Optional) If an error message is displayed and the zone fails to install, use the zoneadm List command and the -c and -v options to get the zone state:

global# zoneadm list -civ

```
ID NAME STATUS PATH BRAND IP

0 global running / solaris shared
- s10-zone configured /zones/s10-zone solaris10 shared
```

- If the state is listed as configured, make the corrections specified in the message and try the zoneadm install command again.
- If the state is listed as incomplete, first execute this command:

```
global# zoneadm -z s10-zone uninstall
```

Then, make the corrections specified in the message and try the zoneadm install command again.

4. When the installation completes, use the list subcommand with the -i and -v options to list the installed zones and verify the status.

```
global# zoneadm list -iv
```

You will see a display that is similar to the following:

```
ID NAME STATUS PATH BRAND IP
0 global running / solaris shared
- s10-zone installed /zones/s10-zone solaris10 shared
```

Example 2 solaris10 Zone Installation

This example demonstrates installing the solaris10 zone s10sepvar from the archive s10u10_sparc_sepvar.flar.

```
# zoneadm -z s10sepvar install -p -a /net/datal3/tmp/s10u10_sparc_sepvar.flar -u
The following ZFS file system(s) have been created:
    rpool/zones/s10sepvar
Progress being logged to /var/log/zones/zoneadm.20120519T151123Z.s10sepvar.install
    Installing: This may take several minutes...
```

Troubleshooting

If an installation fails, review the log file. On success, the log file is in /var/log inside the zone. On failure, the log file is in /var/log/zones in the global zone.

If a zone installation is interrupted or fails, the zone is left in the incomplete state. Use the uninstall command with the -F option to reset the zone to the configured state.



Booting a Zone, Logging Into a Zone, and Zone Migration

This chapter describes how to boot the installed zone and use zlogin to complete the internal zone configuration. The chapter also discusses how to migrate the zone to another machine.

About Booting the solaris10 Branded Zone

Booting a zone places the zone in the running state. A zone can be booted from the ready state or from the installed state. A zone in the installed state that is booted transparently transitions through the ready state to the running state. Zone login is allowed for zones in the running state.

Note that you perform the internal zone configuration when you log in to the unconfigured zone for the first time after the initial boot.

Image sysidcfg Profile

If you created an Oracle Solaris 10 system archive from an existing system and use the -p (preserve sysidcfg) option when you install the zone, then the zone will have the same identity as the system used to create the image.

The -c option can be used to include a sysidcfg file to use in configuring the zone after the installation completes. To install a solaris10 zone, use a sysidcfg file in the command line. Note that a full path to the file must be supplied.

```
# zoneadm -z s10-zone install -a /net/machine_name/s10-system.flar -u -c /path_to/
sysidcfg
```

The following sample sysidcfg file uses the net0 network name and timezone to configure an exclusive-IP zone with a static-IP configuration:

```
system_locale=C
terminal=xterm
network_interface=net0 {
   hostname=test7
```

```
ip_address=192.168.0.101
netmask=255.255.255.0
default_route=NONE
protocol_ipv6=no
}
name_service=NONE
security_policy=NONE
timezone=US/Pacific
timeserver=localhost
nfs4_domain=dynamic
root_password=FSPXl81aZ7Vyo
auto_reg=disable
```

The following sample sysidcfg file is used to configure a shared-IP zone:

```
system_locale=C
terminal=dtterm
network_interface=primary {
hostname=my-zone
}
security_policy=NONE
name_service=NIS {
domain_name=special.example.com
name_server=bird(192.168.112.3)
}
nfs4_domain=domain.com
timezone=US/Central
root_password=m4qtoWN
```

The following sample sysidcfg file is used to configure an exclusive-IP zone with a static IP configuration:

```
system_locale=C
terminal=dtterm
network_interface=primary {
hostname=my-zone
default_route=10.10.10.1
ip_address=10.10.10.13
netmask=255.255.255.0
}
nfs4_domain=domain.com
timezone=US/Central
root_password=m4qtoWN
```

The following sample sysidcfg file is used to configure an exclusive-IP zone with the DHCP and IPv6 option:

```
system_locale=C
terminal=dtterm
network_interface=primary {
dhcp protocol_ipv6=yes
}
```

```
security_policy=NONE
name_service=DNS {
domain_name=example.net
name_server=192.168.224.11,192.168.224.33
}
nfs4_domain=domain.com
timezone=US/Central
root password=m4qtoWN
```

▼ solaris10 Branded Zone Internal Configuration

When no profile is given, then the configuration tool will start on the first use of zlogin -C.

The name of the zone in this procedure is s10-zone.

Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

2. In one terminal window, connect to the zone console, s10-zonein this procedure, before booting the zone by using the command:

```
# zlogin -C s10-zone
```

In a second window, boot the zone as described in "How to Boot the solaris10 Branded Zone" on page 43.

▼ How to Boot the solaris10 Branded Zone

You must be the global administrator or a user with the appropriate authorizations in the global zone to perform this procedure.

1. Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

2. Use the zoneadm command with the -z option, the name of the zone, which is s10-zone, and the boot subcommand to boot the zone.

```
global# zoneadm -z s10-zone boot
```

When the boot completes, use the List subcommand with the -v option to verify the status.

global# zoneadm list -v

You will see a display that is similar to the following:

ID	NAME	STATUS	PATH	BRAND	IP
0	global	running	/	solaris	shared
1	s10-zone	running	/zone/s10-zone	solaris10	shared

About Multiple Boot Environments On solaris10 Zones

Multiple boot environments enable administrators to switch between one or more boot environments on an as-needed basis. You can manage multiple boot environments on a solaris10 zone. For example, from a solaris10 zone, you can create and upgrade packages on an alternate boot environment. You can then activate and boot to the upgraded boot environment to perform administration tasks.

You activate an alternate boot environment by using ZFS commands. Set the zfs property com. oracle.zones.solaris10:activebe on the zone's ROOT dataset. Reboot the zone to have the new zfs property take effect.

▼ How to Create and Activate Multiple Boot Environments on a solaris10 Branded Zone

1. Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

2. Configure the solaris10 zone.

In this procedure, the zone s10_zone with the configuration file /zones/S10_ZONE.cfg is used on the global zone, global.

```
global# zonecfg -z S10_zone -f /zones/S10_ZONE.cfg
```

3. Install the solaris10 zone.

The flash archive image file /zones/s10-system.flar is used in this procedure.

```
global# zoneadm -z S10_zone install -u -v -a /zones/s10-system.flar
```

4. Boot the solaris10 zone.

global# zoneadm -z S10_zone boot

On the solaris10 zone, create a new boot environment using ZFS commands.

a. Create a ZFS snapshot.

The snapshot rpool/ROOT/zbe-0@snap is used in this procedure.

S10 zone# zfs snapshot rpool/ROOT/zbe-0@snap

b. Clone and mount the new ZFS snapshot.

In this case, the ZFS snapshot rpool/ROOT/zbe-0@snap is mounted to / and cloned to a new ZFS snapshot,rpool/ROOT/zbe-1:

S10_zone# zfs clone -o mountpoint=/ -o canmount=noauto rpool/ROOT/zbe-0@snap rpool/ ROOT/zbe-1

c. Promote the new ZFS snapshot.

S10_zone# zfs promote rpool/ROOT/zbe-1

6. Patch the new boot environment.

a. Mount the new ZFS snapshot.

 $$10_zone\# zfs mount -o mountpoint=/mnt rpool/ROOT/zbe-1$

b. Run the patchadd command on the snapshot mount point.

S10_zone# # patchadd -R /mnt -d /var/tmp
S10 zone# zfs unmount rpool/ROOT/zbe-1

c. Unmount the new ZFS snapshot.

 $S10_zone\#$ **zfs unmount rpool/ROOT/zbe-1**

7. Activate the new boot environment.

8. Boot the zone to have the changes take effect.

global# zoneadm -z S10_zone boot

See Also For further information about the zfs command and ZFS administration, refer to *Managing ZFS File Systems in Oracle Solaris* 11.3.

Migrating a solaris10 Branded Zone to Another Host

A solaris10 zone can be migrated to another host by using the zoneadm command with the detach and attach subcommands. This process is described in Chapter 7, "Migrating and Converting Oracle Solaris Zones" in *Creating and Using Oracle Solaris Zones*.

Note that the zoneadm attach -a command takes an archive of a zone, *not* an archive of a physical system.

Index

A attaching solaris10 branded zone, 24, 46	solaris10 brand, 37
B boot environments, 44 booting a solaris10 zone, 41 brand, 9	L limitations Oracle Solaris 10 Zones, 13
branded zone, 9 device support, 29 file system support, 29 privileges, 29 BrandZ, 9	M migrating a zone, 24 migration solaris10 native zone, 37 migration target zone zonecfg, 30
F flarcreate cpio, 20 default image, 19 exclude data, 20 pax, 20	N networking Oracle Solaris 10 Zones, 14
H host ID in a zone, 21 hostid property in a zone, 21	O obtaining zonep2vchk on Oracle Solaris 10, 18 Oracle Solaris 10 Zones, 9 limitations, 13 networking, 14
I image creation P2V, 19 installations	PP2V flarcreate, 19, 20 image creation, 19 system evaluation, 18 zonep2vchk, 18

S solaris10 brand, 9 SVR4 packaging, 11 solaris10 brand installations, 37 solaris10 branded zone, 9 attaching, 24, 46 boot procedure, 41 configuration overview, 30 configuring, 31, 33 defined privileges, 30 supported devices, 29 V2V, 23 solaris10 native zone migration, 37 SVR4 packaging in solaris10 brand, 11 system evaluation for P2V, 18 Ζ zone branded, 9 migrate, 24 upgrade on attach, 24 zone administration, 44 zonecfg solaris10 branded zone process, 30 zonep2vchk utility

obtaining on Oracle Solaris 10, 18