Working With Oracle® Solaris 11.3 Directory and Naming Services: LDAP



Working With Oracle Solaris 11.3 Directory and Naming Services: LDAP

#### Part No: E54912

Copyright © 2002, 2016, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

#### **Documentation Accessibility**

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

#### Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

#### Référence: E54912

Copyright © 2002, 2016, Oracle et/ou ses affiliés. Tous droits réservés.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf stipulation expresse de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, accorder de licence, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est livré sous licence au Gouvernement des Etats-Unis, ou à quiconque qui aurait souscrit la licence de ce logiciel pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer des dommages corporels. Si vous utilisez ce logiciel ou matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour ce type d'applications.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Xeon sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Opteron, le logo AMD et le logo AMD Opteron sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée d'The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers, sauf mention contraire stipulée dans un contrat entre vous et Oracle. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation, sauf mention contraire stipulée dans un contrat entre vous et Oracle.

#### Accessibilité de la documentation

Pour plus d'informations sur l'engagement d'Oracle pour l'accessibilité à la documentation, visitez le site Web Oracle Accessibility Program, à l'adresse http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

### Accès aux services de support Oracle

Les clients Oracle qui ont souscrit un contrat de support ont accès au support électronique via My Oracle Support. Pour plus d'informations, visitez le site http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info ou le site http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs si vous êtes malentendant.

# Contents

U	sing This Documentation	9
1	Introduction to the LDAP Naming Service	11
	Overview of the LDAP Naming Service	
	How LDAP Stores Information	
	LDAP Commands	
	General LDAP Commands	13
	LDAP Configuration Commands	14
2	LDAP and Authentication Service	. 15
	LDAP Naming Service Security Model	15
	Transport Layer Security	16
	Client Credential Levels	17
	Enabling Shadow Data Updates	18
	Storing Credential for LDAP Clients	19
	Authentication Methods for the LDAP Naming Service	20
	Specifying Authentication Methods for Specific Services in LDAP	21
	Pluggable Authentication Methods	22
	LDAP Service Module	22
	pam_unix_* Service Modules	23
	Kerberos Service Module	. 25
	Changing Passwords That Use PAM	25
	LDAP Account Management	26
	LDAP Account Management With the pam_unix_* Modules	27
3	Planning Requirements for LDAP Naming Services	. 29
	LDAP Planning Overview	29
	Planning the Configuration of the LDAP Client Profile	31
	LDAP Network Model	31
	Directory Information Tree	32

Security Considerations	33
Planning the Deployment of LDAP Master and Replica Servers	34
Single-Master Replication	34
Multi-Master Replication	34
Planning the LDAP Data Population	35
Service Search Descriptors and Schema Mapping	35
About Service Search Descriptors	35
Default Filters Used by the LDAP Naming Service	37
Default Client Profile Attributes for LDAP Implementation	40
Checklists for Configuring LDAP	41
4 Setting Up the Oracle Directory Server Enterprise Edition With LDAP	
Clients	43
Directory Server Requirements	43
Server Information for Configuring the Directory Server	44
LDAP Client Profile Information	44
Creating Browsing Indexes for the Directory Tree	45
Creating the Directory Tree Definitions	45
▼ How to Configure Oracle Directory Server Enterprise Edition for the LDAP	
Naming Service	
Example of Server Configuration for LDAP	
Populating the LDAP Server With Data	
Additional Directory Server Configuration Tasks	
Specifying Group Memberships by Using the Member Attribute	
Populating the Directory Server With Additional Profiles	
Configuring the Directory Server to Enable Account Management	58
5 Setting Up LDAP Clients	63
Requirements for LDAP Client Setup	63
LDAP and the Service Management Facility	64
Defining LDAP Local Client Attributes	65
Initializing an LDAP Client	66
Modifying an LDAP Client Configuration	68
Uninitializing an LDAP Client	68
Using LDAP for Client Authentication	68
Configuring PAM for LDAP	69
Setting Up TLS Security	71
▼ How to Set Up TLS Security	72

6	Troubleshooting LDAP Configurations	73
	Displaying the LDAP Naming Service Information	73
	Displaying All LDAP Containers	73
	Displaying All User Entry Attributes	74
	Monitoring LDAP Client Status	75
	Verifying the ldap_cachemgr Daemon Status	75
	Checking the Client Profile Information	76
	Verifying Basic Client-Server Communication	77
	Checking LDAP Server Data From a Non-Client Machine	77
	LDAP Configuration Problems and Solutions	77
	Unresolved Host Name	78
	Unable to Reach Systems in the LDAP Domain Remotely	78
	Login Does Not Work	78
	Lookup Too Slow	79
	ldapclient Command Cannot Bind to a Server	79
	Using the ldap_cachemgr Daemon for Debugging	80
	ldapclient Command Hangs During Setup	80
	Resolving Per-User Credentials Issues	80
	syslog File Indicates 82 Local Error	80
	Kerberos Not Initializing Automatically	80
	syslog File Indicates Invalid Credentials	81
	The Idapclient init Command Fails in the Switch Check	81
7	LDAP Schemas	83
•	IETF Schemas for LDAP	
	RFC 2307bis Network Information Service Schema	
	Mail Alias Schema	
	Directory User Agent Profile (DUAProfile) Schema	
	Oracle Solaris Schemas	
	Projects Schema	
	Role-Based Access Control and Execution Profile Schema	
	Internet Print Protocol Information for LDAP	o =
	Internet Print Protocol Attributes	95
	Internet Print Protocol ObjectClasses	101
	Printer Attributes	
		103
8	Transitioning From NIS to LDAP	105

About the NIS-to-LDAP Service	105
When Not to Use the NIS-to-LDAP Service	107
Effect of Installing the NIS-to-LDAP Service	107
NIS-to-LDAP Commands, Files, and Maps	108
Supported Standard Mappings	108
Transitioning From NIS to LDAP Task Map	109
Prerequisites for the NIS-to-LDAP Transition	110
Setting Up the NIS-to-LDAP Service	111
▼ How to Set Up the N2L Service With Standard Mappings	112
▼ How to Set Up the N2L Service With Custom or Nonstandard	
Mappings	
Examples of Custom Maps	115
NIS-to-LDAP Best Practices With Oracle Directory Server Enterprise Edition	117
Creating Virtual List View Indexes With Oracle Directory Server Enterpris	
Edition	
Avoiding Server Timeouts With Oracle Directory Server Enterprise Edition	ı 119
Avoiding Buffer Overruns With Oracle Directory Server Enterprise Edition	ı 119
NIS-to-LDAP Restrictions	120
NIS-to-LDAP Troubleshooting	120
Common LDAP Error Messages	120
NIS-to-LDAP Issues	122
Reverting to NIS	125
▼ How to Revert to Maps Based on NIS Source Files	126
▼ How to Revert to Maps Based on DIT Contents	126
Glossary	129
Index	135

# **Using This Documentation**

- Overview Describes the LDAP naming service, methods for planning its use, and steps to implement LDAP.
- **Audience** Technicians, system administrators, and authorized service providers.
- **Required knowledge** Familiarity with concepts and terminologies related to LDAP.

## **Product Documentation Library**

Documentation and resources for this product and related products are available at http://www.oracle.com/pls/topic/lookup?ctx=E53394.

### **Feedback**

Provide feedback about this documentation at http://www.oracle.com/goto/docfeedback.

# · · · CHAPTER 1

## Introduction to the LDAP Naming Service

The Lightweight Directory Access Protocol (LDAP) is the secure network protocol used to access directory servers for distributed naming and other directory services. This standard-based protocol supports a hierarchical database structure. You can use this protocol to provide naming services in both UNIX and multiplatform environments. This chapter covers the following topics:

- "Overview of the LDAP Naming Service" on page 11
- "LDAP Commands" on page 13

## **Overview of the LDAP Naming Service**

Oracle Solaris supports LDAP in conjunction with the Oracle Directory Server Enterprise Edition. However, any generic directory server can function as an LDAP server. In this book, the terms *directory server* and *LDAP server* are synonymous and used interchangeably.

For more information about directory servers, refer to the following sources:

- Oracle Directory Server Enterprise Edition Deployment Guide
- Oracle Directory Server Enterprise Edition Administration Guide
- Installation guide for the version of Oracle Directory Server Enterprise Edition that you are using

LDAP has become a term that refers more to the naming service rather than the protocol itself. Throughout this book, the term LDAP is used to refer to the service rather than the protocol.

The LDAP naming service is one of various naming services that is supported in Oracle Solaris. For information about other naming services, see *Working With Oracle Solaris 11.3 Directory and Naming Services: DNS and NIS*. For a comparison of the different naming services in Oracle Solaris, see "Comparing the Naming Services" in *Working With Oracle Solaris 11.3 Directory and Naming Services: DNS and NIS*.

LDAP performs the following services:

 Naming service – LDAP provides naming data in accordance with a client request. For example, when resolving host names, LDAP functions like DNS by providing the fully qualified domain names. Suppose that the name of a domain is west.example.net. If an application requests the host name by using gethostbyname() or getnameinfo(), LDAP returns the value <code>server.west.example.net</code>.

 Authentication service – LDAP manages and provides information that relates to client identity, authentication, and accounts. Therefore, LDAP implements security measures to provide information only to authorized requesters.

The LDAP naming service provides the following advantages:

- With the replacement of application-specific databases, information is consolidated and the number of distinct databases to manage is reduced.
- Different naming services can share data.
- Uses a central repository for data.
- Performs frequent data synchronization between masters and replicas.
- Multiplatform and multi-vendor compatible.

The following restrictions apply to the LDAP naming service:

- An LDAP server cannot be its own client.
- A client cannot be a client of NIS and LDAP at the same time.

Setting up and managing an LDAP naming service is complex and requires careful planning. For information about planning for LDAP services, see Chapter 3, "Planning Requirements for LDAP Naming Services"

### **How LDAP Stores Information**

The LDAP naming service stores information in a directory information tree (DIT). The information is stored in LDAP data interchange format (LDIF). The DIT consists of hierarchically structured containers of information that follow a defined LDAP schema.

The default schema that is followed by most DITs suffices for most networks that use LDAP. However, the DIT is flexible. You can specify search descriptors in the client profile to override the default structure of a DIT. For more information about search descriptors, see "Service Search Descriptors and Schema Mapping" on page 35.

The following table shows the containers of a DIT and the type of information each container stores.

**TABLE 1** Types of Information in Default DIT Containers

Default Container	Information Type
ou=Ethers	bootparams, ethers

Default Container	Information Type		
ou=Group	group		
ou=Hosts	hosts, ipnodes, publickey for hosts		
ou=Aliases	aliases		
ou=Netgroup	netgroup		
ou=Networks	networks, netmasks		
ou=People	passwd, shadow, user_attr, audit_user, publickey for users		
ou=Protocols	protocols		
ou=Rpc	грс		
ou=Services	services		
ou=SolarisAuthAttr	auth_attr		
ou=SolarisProfAttr	prof_attr, exec_attr		
ou=projects	project		
automountMap=auto_*	auto_* (automount maps)		

### **LDAP Commands**

Oracle Solaris provides general LDAP commands and LDAP configuration commands. The general LDAP commands do not require the system to be configured with LDAP naming service. LDAP configuration commands can be run on clients that are configured with the LDAP naming service.

### **General LDAP Commands**

General LDAP commands can be run on any system and do not require the system to be configured with the LDAP naming service. LDAP commands support a common set of options, including authentication and bind parameters. These commands support a common text-based format for representing directory information called the LDIF. You can use the following commands to manipulate directory entries:

- Idapsearch Searches the LDAP schema for specified entries. For more information, see the Idapsearch(1) man page.
- Idapmodify Modifies LDAP entries in the schema. For more information, see the Idapmodify(1) man page.
- Idapadd Adds LDAP entries in the schema. For more information, see the Idapadd(1) man page.
- ldapdelete Removes LDAP entries from the schema. For more information, see the ldapdelete(1) man page.

## **LDAP Configuration Commands**

You can use the following commands to configure the LDAP client or modify the client configuration:

- Idapaddent Creates LDAP entries in the schema from corresponding /etc files. For more information, see the Idapaddent(1M) man page.
- ldaplist Displays information retrieved from the LDAP server. For more information, see the ldaplist(1) man page.
- idsconfig Populates the DIT with data to serve LDAP clients. For more information, see the idsconfig(1M) man page.
- ldapclient Initializes an LDAP client system. For more information, see the ldapclient(1M) man page.



### LDAP and Authentication Service

The LDAP naming service can use the LDAP repository to provide authentication service. This chapter discusses LDAP's authentication services and covers the following topics:

- "LDAP Naming Service Security Model" on page 15
- "Client Credential Levels" on page 17
- "Authentication Methods for the LDAP Naming Service" on page 20
- "Pluggable Authentication Methods" on page 22
- "LDAP Account Management" on page 26

### **LDAP Naming Service Security Model**

LDAP supports security features such as authentication and controlled access to ensure integrity and privacy of the information that LDAP clients obtain. This section describes how a LDAP client authenticates to the LDAP server and how a user authenticates to a client.

To access the information in the LDAP repository, a LDAP client establishes its identity with the directory server. The identity can be either anonymous or as a host or user that is recognized by the LDAP server. LDAP supports the proxy authentication and the per-user authentication of identities.

The pluggable authentication module (PAM) service determines whether a user login is successful. Based on the client's identity and the server's access control information (ACI), the LDAP server enables the LDAP client to read directory information. For more information about ACIs, refer to the administration guide for the version of Oracle Directory Server Enterprise Edition that you are using.

The types of LDAP Authentication are as follows:

- Proxy authentication The identity is based on the systemwhere the request originates.
   After the stem is authenticated, all users on that system can access the directory server.
- Per-user authentication The identity is based on each user. Every user must be authenticated to access the directory server and issue various LDAP requests.

The basis for user authentication differs depending on the PAM module. LDAP can use the following PAM modules:

- pam\_krb5 module Uses the Kerberos server for authentication. For more information, see
  the pam\_krb5(5) man page. For a more extensive description about Kerberos, see *Managing Kerberos and Other Authentication Services in Oracle Solaris 11.3.*
- pam\_ldap module Uses the LDAP server and local host server for authentication. For more information, see the pam\_ldap(5) man page. For information about using the pam\_ldap module, see "LDAP Account Management" on page 26.
- Equivalent pam\_unix\_\* modules Information is provided by the system and the authentication is determined locally.

**Note -** The pam\_unix module is no longer supported in Oracle Solaris. This module has been replaced by a different set of service modules that provides equivalent or greater functionality. In this book, pam\_unix refers to the modules that provide equivalent functionality, not to the pam unix module.

If the pam\_ldap module is used, the naming service and the authentication service access the directory in the following ways:

- The naming service reads various entries and their attributes from the directory based on predefined identity.
- The authentication service authenticates a user's name and password with the LDAP server to determine whether the correct password has been specified.

You can use Kerberos and LDAP at the same time to provide both authentication and naming services to the network. With Kerberos, you can support a single sign-on (SSO) environment in the enterprise. You can use the Kerberos identity system for querying LDAP naming data on a per-user or per-host basis.

If you use Kerberos to perform authentication, enable LDAP naming services as a requirement of the per-user mode. Kerberos can provide dual functions: It authenticates to the LDAP server and the Kerberos identity for the user or host is used to authenticate to the directory. In this way, the same user identity that is used to authenticate to the system is also used to authenticate to the directory for lookups and updates. If required, you can use ACI in the directory to limit the results out of the naming service.

### **Transport Layer Security**

You can use Transport Layer Security (TLS) to secure communication between an LDAP client and the directory server and hence ensure both privacy and data integrity. The TLS protocol is a superset of the Secure Sockets Layer (SSL) protocol. The LDAP naming service supports TLS connections. However, using SSL adds load to the directory server and the client.

The requirements to use TLS are as follows:

- Configure the directory server and LDAP clients for SSL.
  - To configure Oracle Directory Server Enterprise Edition for SSL, see the administration guide for the version of Oracle Directory Server Enterprise Edition that you are using.
- Install the following necessary security databases, specifically the certificate and key database files.
  - If you use an older database format from Netscape Communicator, install cert7.db and key3.db.
  - If you use a new database format from Mozilla, install cert8.db, key3.db, and secmod.db

The cert\* files contain trusted certificates. The key3.db file contains the client's keys. You must install the key3.db file even if the LDAP naming service client does not use client keys. The secmod.db file contains security modules such as the PKCS#11 module.

For information about setting up TLS security, see "Setting Up TLS Security" on page 71.

### **Client Credential Levels**

The LDAP server authenticates LDAP clients according to the client credential level. You can assign any one of the following credential levels for LDAP clients:

anonymous — With an anonymous credential level, you can access only the data that is available to everyone. No LDAP BIND operation occurs. An anonymous credential level is a high security risk. Any client can change information in the DIT to which the client has write access, including another user's password or their own identity. Further, the anonymous level enables all clients to have read access to all LDAP naming entries and attributes.

**Note -** Oracle Directory Server Enterprise Edition enables you to implement security measures by restricting access based on IP addresses, DNS name, authentication method, and time-of-day. For more information, see "Managing Access Control" in the *Administration Guide* for the version of Oracle Directory Server Enterprise Edition that you are using.

proxy – With a proxy credential level, the client binds to a single shared set of LDAP bind credentials. The shared set is also called a *proxy account*. The proxy account can be any entry that is allowed to bind to the directory. The account requires sufficient access to perform the naming service functions on the LDAP server.

The proxy account is a shared-per-system resource, which means that users, including the root user, who are logged into a system using proxy access see the same information. You must configure the proxyDN and proxyPassword attributes on every client system that uses the proxy credential level. Further, the proxyDN must have the same proxyPassword on all of the LDAP servers.

The encrypted proxyPassword is stored locally on the client. If the password changes for a proxy user, you must update the password on every client system that uses that proxy user. Also, if you use password aging on LDAP accounts, make sure to exempt proxy users.

You can set up different proxies for different groups of clients. For example, you can configure a proxy that limits all the sales clients to access only the company-wide accessible directories and sales directories. Access to Human Resource directories with payroll information are forbidden. Or, in the most extreme cases, you can either assign different proxies to each client or assign just one proxy to all clients.

If you plan to set up multiple proxies for different clients, consider the choices carefully. Too few proxy agents can limit your ability to control user access to resources. However, too many proxies complicate the setup and maintenance of the system. You need to grant the appropriate rights to the proxy user depending on your environment. For more information about how to determine which authentication method to use, see "Storing Credential for LDAP Clients" on page 19.

The proxy credential level applies to all users and processes on any specific system. Users that need to use different naming policies must log in to different systems, or use the peruser authentication model.

- proxy anonymous The proxy anonymous credential level is a multi-valued entry where more than one credential level is defined. With this level, a client first attempts to be authenticated by using its proxy identity. If the authentication fails because of user lockout or expired password, then the client uses anonymous access. Depending on how the directory is configured, different credential levels might be associated with different levels of service.
- self The self credential level is also known as the per-user mode. This mode uses the Kerberos identity, called the principal, to perform a lookup for each system or user for authentication. With per-user authentication, the system administrator can use access control instructions (ACIs), access control lists (ACLs), roles, groups or other directory access control mechanisms to grant or deny access to specific naming-service data for specific users or systems.

To use the per-user authentication model, the following configurations are required:

- Deployment of the Kerberos single sign-on service
- Support for the SASL and the SASL/GSSAPI authentication mechanism in one or more directory servers
- Configuration of DNS, which Kerberos uses together with files to perform host name lookups
- Enabling of the nscd daemon

### **Enabling Shadow Data Updates**

If the enableShadowUpdate switch is set to true on the client, administrator credentials are used to update the shadow data. Shadow data is stored in the shadowAccount object

class on the directory server. Administrator credentials are defined by the values of the adminDN and adminPassword attributes, as described in "Defining LDAP Local Client Attributes" on page 65.

Administrator credentials have properties similar to proxy credentials. However, for administrator credentials, the user must have all privileges for the zone or have an effective UID of root to read or update the shadow data.

You can assign administrator credentials to any entry that is allowed to bind to the directory. However, do not use the same directory manager identity (cn=Directory Manager) of the LDAP server.

An entry with administrator credentials must have sufficient access to read and write the shadow data to the directory. The entry is a shared-per-system resource. Therefore, you must configure the adminDN and adminPassword attributes on every client.

The encrypted adminPassword is stored locally on the client. The admin password uses the same authentication methods that are configured for the client. All users and processes on a specific system uses the administrator credentials to read and update the shadow data.

### **Storing Credential for LDAP Clients**

In the LDAP implementation, proxy credentials that are set during initialization are stored in the SMF repository instead of a client's profile. This implementation improves security surrounding a proxy's distinguished name (DN) and password information.

The SMF repository is svc:/network/ldap/client. It stores proxy information of clients that use a proxy identity. Likewise, shadow data updates of clients whose credential level is not self are also saved to this repository.

For clients that use per-user authentication, the Kerberos identity and Kerberos ticket information for each principal is used during authentication. The directory server maps the Kerberos principal to a DN and the Kerberos credentials are used to authenticate to that DN. The directory server can use its ACI mechanisms to allow or deny access to naming service data as necessary.

In this environment, Kerberos ticket information is used to authenticate to the directory server. The system does not store authentication DNs or passwords. Therefore, setting the adminDN and adminPassword attributes is unnecessary when you initialize the client with the ldapclient command.

### **Authentication Methods for the LDAP Naming Service**

When you assign the proxy or proxy-anonymous credential level to a client, you must also select a method by which the proxy is authenticated. By default, the authentication method is none, which implies anonymous access. The authentication method might also have an associated transport security option.

The authentication method, like the credential level, can be multi-valued. For example, in the client profile, you can specify that the client tries to bind by using the simple method that is secured by TLS. If unsuccessful, the client would try to bind with the sasl/digest-MD5 method. In this case, you would configure the authenticationMethod attribute as tls:simple; sasl/digest-MD5.

LDAP naming service supports some Simple Authentication and Security Layer (SASL) mechanisms. These mechanisms enable a secure password exchange without requiring TLS. However, these mechanisms do not provide data integrity or privacy. For information about SASL, see RFC 4422 (http://datatracker.ietf.org/doc/rfc4422/) for information on SASL.

The LDAP supports the following authentication mechanisms:

- none The client does not authenticate to the directory. This method is equivalent to the anonymous credential level.
- simple The client system sends the user's password in the clear to bind to the LDAP server. The password is subject to snooping unless the session is protected by IPsec. This method is easy to set up and all directory servers support it.
- sasl/cram-MD5 The LDAP session is not encrypted but the client's password is protected during authentication. Do not use this obsolete authentication method.
- sasl/digest-MD5 The client's password is protected during authentication but the session is not encrypted. The primary advantage of digest-MD5 is that the password is not sent in clear text during authentication and is more secure than the simple authentication method. Refer to RFC 2831 (http://datatracker.ietf.org/doc/rfc2831/) for information on digest-MD5. digest-MD5 is an improvement over cram-MD5.
  - With sasl/digest-MD5, the authentication is secure but the session is not protected.
- sasl/GSSAPI This authentication method is used in conjunction with the per-user mode to enable per-user lookups. A per-user nscd session with the client's credentials binds to the directory server by using the sasl/GSSAPI method and the client's Kerberos credentials. Access can be controlled in the directory server on a per-user basis.
- tls:simple The client binds using the simple method and the session is encrypted. The
  password is protected.
- tls:sasl/cram-MD5 The LDAP session is encrypted and the client authenticates to the directory server using sasl/cram-MD5.

 tls:sasl/digest-MD5 – The LDAP session is encrypted and the client authenticates to the directory server using sasl/digest-MD5.



**Caution -** If you use digest-MD5, Oracle Directory Server Enterprise Edition requires passwords to be stored unencrypted. Passwords for the proxy user that uses sasl/digest-MD5 or tls:sasl/digest-MD5 authentication method must be stored unencrypted. In this case, configure the userPassword attribute with the proper ACIs to prevent it from being readable.

The following table summarizes the various authentication methods and their characteristics.

**TABLE 2** Authentication Methods

Method	Bind	Password over the wire	Password on Oracle Directory Server Enterprise Edition	Session
none	No	N/A	N/A	No encryption
simple	Yes	Clear	Any	No encryption
sasl/digest-MD5	Yes	Encryption	Clear	No encryption
sasl/cram-MD5	Yes	Encryption	N/A	No encryption
sasl/GSSAPI	Yes	Kerberos	Kerberos	Encryption
tls:simple	Yes	Encryption	Any	Encryption
tls:sasl/cram-MD5	Yes	Encryption	N/A	Encryption
tls:sasl/digest-MD5	Yes	Encryption	Clear	Encryption

# **Specifying Authentication Methods for Specific Services in LDAP**

The serviceAuthenticationMethod attribute determines the authentication method for a specific service. If this attribute is not set for the service, then the value of the authenticationMethod attribute is used.

Similarly, when the enableShadowUpdate switch is set to true, the ldap\_cachemgr daemon uses the value for the authenticationMethod attribute if the serviceAuthenticationMethod attribute is not configured. The daemon does not use the none authentication method.

You can select authentication methods for the following services:

passwd-cmd – Enables the passwd command to change the login password and password attributes. For more information, see the passwd(1) man page.

- keyserv Enables the chkey and newkey utilities to create and change a user's Diffie-Hellman key pair. For more information, see the chkey(1) and newkey(1M) man pages.
- pam\_ldap Enables authentication of users that use the pam\_ldap service. The pam\_ldap service supports account management.

**Note** - In per-user mode, the Kerberos service module is used as the authentication service and ServiceAuthenticationMethod is not needed.

The following example shows a section of a client profile in which the users use sasl/digest-MD5 to authenticate to the directory server but use an SSL session to change the password.

```
serviceAuthenticationMethod=pam_ldap:sasl/digest-MD5
serviceAuthenticationMethod=passwd-cmd:tls:simple
```

### **Pluggable Authentication Methods**

With the PAM framework, you can choose among several authentication services, including the pam\_unix\_\*, pam\_krb5, and pam\_ldap\_\* modules.

To use per-user authentication, you must enable pam\_krb5. However, you can still use pam\_krb5 authentication even if you do not assign the per-user credential level. If proxy or anonymous credential levels are used to access directory server data, then you cannot restrict access to directory data on a per-user basis.

If you choose anonymous or proxy authentication, use the pam\_ldap module instead of the equivalent pam\_unix\_\* modules. The pam\_ldap module is more flexible, supports stronger authentication methods, and can perform account management.

### **LDAP Service Module**

The serviceAuthenticationMethod attribute, if defined, determines the manner the user binds to the LDAP server. Otherwise, the authenticationMethod attribute is used. After the pam\_ldap module successfully binds to the server with the user's identity and password, the module authenticates the user. You can perform account management and retrieve the account status of users while the user is logging in without authenticating to the directory server.

The control on the directory server is 1.3.6.1.4.1.42.2.27.9.5.8. This control is enabled by default. To modify the default control configuration, add ACIs on directory server. For example:

```
dn: oid=1.3.6.1.4.1.42.2.27.9.5.8,cn=features,cn=config
objectClass: top
```

```
objectClass: directoryServerFeature
oid:1.3.6.1.4.1.42.2.27.9.5.8
cn:Password Policy Account Usable Request Control
aci: (targetattr != "aci")(version 3.0; acl "Account Usable";
allow (read, search, compare, proxy)
(groupdn = "ldap:///cn=Administrators,cn=config");)
creatorsName: cn=server,cn=plugins,cn=config
modifiersName: cn=server,cn=plugins,cn=config
```

The pam\_ldap module does not read the userPassword attribute. If no client uses UNIX authentication, granting read access to the userPassword attribute is unnecessary. Similarly, the pam\_ldap module does not support none as an authentication method.

**Note -** If the simple authentication method is used, the userPassword attribute can be read unencrypted by third parties.

The following table summarizes the differences between authentication mechanisms.

**TABLE 3** Authentication Behavior in LDAP

Event	pam_unix_*	pam_ldap	pam_krb5
Password Sent	Uses passwd service authentication method	Uses passwd service authentication method	Uses Kerberos single signon technology.
New Password Sent	Encrypted	No encryption (unless TLS is used)	Uses Kerberos. Passwords are not sent over the wire.
New Password Stored	crypt format	Password storage scheme defined on Oracle Directory Server Enterprise Edition	Uses Kerberos to manage passwords.
Requires password read?	Yes	No	No
sasl/digest-MD5 compatibility after changing password	No. Password is not stored unencrypted. User cannot authenticate.	Yes. User can authenticate if the default storage scheme is set to clear.	No. Uses sast/GSSAPI. There are no passwords over the wire and there are no passwords to be stored in the directory server except when using a Kerberos kdc that manages its password database in the LDAP directory server.
Password policy supported?	Yes. enableShadowUpdate must be set to true.	Yes, if configured.	See the pam_krb5(5) man page and Kerberos V5 Account Management Module.

## pam\_unix\_\* Service Modules

If the /etc/pam.conf file is unconfigured, UNIX authentication is enabled by default.

**Note -** The pam\_unix module has been removed and is no longer supported in Oracle Solaris. The module has been replaced by a different set of service modules that provides equivalent or greater functionality. In this guide, pam\_unix refers to the modules that provide equivalent functionality, not to the pam\_unix module itself.

The following modules provide the equivalent functionality as the original pam\_unix module. The modules are listed by using their corresponding man pages.

- pam\_authtok\_check(5)
- pam authtok get(5)
- pam authtok store(5)
- pam dhkeys(5)
- pam passwd auth(5)
- pam unix account(5)
- pam unix auth(5)
- pam unix cred(5)
- pam\_unix\_session(5)

The pam unix \* modules use the following UNIX authentication model:

- 1. The client retrieves the user's encrypted password from the name service.
- 2. The user is prompted for the password.
- 3. The user's password is encrypted.
- The client compares the two encrypted passwords to determine whether the user should be authenticated.

The pam unix \* modules have the following restrictions:

- The password must be stored in UNIX crypt format.
- The userPassword attribute must be readable by the name service.

For example, if you set the credential level to anonymous, then anyone must be able to read the userPassword attribute. Similarly, if you set the credential level to proxy, then the proxy user must be able to read the userPassword attribute.

**Note -** UNIX authentication is incompatible with the sasl/digest-MD5 authentication method. In Oracle Directory Server Enterprise Edition, passwords must be stored unencrypted to use digest-MD5.

The pam\_unix\_account module supports account management when the enableShadowUpdate switch is set to true. The controls for a remote LDAP user account are applied in the same manner that controls are applied to a local user account that is defined in the passwd and shadow files. For the LDAP account in enableShadowUpdate mode, the system updates and uses the

shadow data on the LDAP server for password aging and account locking. The shadow data of the local account only applies to the local client system, while the shadow data of an LDAP user account applies to the user on all client systems.

You can check the password history only for the local client and not for an LDAP user account.

### **Kerberos Service Module**

For information about Kerberos, see *Managing Kerberos and Other Authentication Services in Oracle Solaris 11.3* and the pam\_krb5(5) man page.

### **Changing Passwords That Use PAM**

Use the passwd command to change a password. If the enableShadowUpdate switch is not enabled, the userPassword attribute must be writable by the user as well as by the administrator credentials. The serviceAuthenticationMethod for passwd-cmd overrides the authenticationMethod for this operation. Depending on the authentication method, the current password might be unencrypted.

In UNIX authentication, the new userPassword attribute is encrypted with the UNIX crypt format. The attribute is tagged before being written to LDAP. Thus, the new password is encrypted regardless of the authentication method used to bind to the server. For more information, see the pam authtok store(5) man page.

If the enableShadowUpdate switch is enabled, the pam\_unix\_\* modules update the related shadow information when the user password is changed. Similarly, the pam\_unix\_\* modules update the shadow fields in the local shadow files that the modules update when the local user password is changed.

To support password update, the pam\_ldap module can use the pam\_authtok\_store module with the server\_policy option. When you use pam\_authtok\_store, the new password is sent to the LDAP server unencrypted. Use TLS to ensure privacy. Otherwise, the new userPassword becomes subject to snooping.

If you set an untagged password with Oracle Directory Server Enterprise Edition, the software uses the passwordStorageScheme attribute to encrypt the password. For more information about the passwordStorageScheme, see the section on user account management in the Administration Guide for the Oracle Directory Server Enterprise Edition (http://docs.oracle.com/cd/E29127 01/doc.111170/e28972/ds-password-policy.htm#fhkrj).

If NIS or any other client that uses UNIX authentication uses LDAP as a repository, then you must configure the passwordStorageScheme attribute with crypt. Also, if you use sasl/

digest-MD5 LDAP authentication with the Oracle Directory Server Enterprise Edition, you must configure the passwordStorageScheme attribute to clear text.

### **LDAP Account Management**

With pam\_krb5 performing account and password management, the Kerberos environment manages all of the account, password, account lockout, and other account management details.

If you do not use pam\_krb5, then configure the LDAP naming service to take advantage of the password and account lockout policy support in Oracle Directory Server Enterprise Edition. You can configure pam\_ldap to support user account management. With the proper PAM configuration, the passwd command enforces password syntax rules set by the Oracle Directory Server Enterprise Edition password policy. However, do not enable account management for proxy accounts.

The following account management features are supported by pam\_ldap. These features depend on Oracle Directory Server Enterprise Edition's password and account lockout policy configuration. You can enable the following account management features:

- Password aging and expiration notification Users must change their passwords according to a schedule. Otherwise, the password expires and user authentication fails.
  - Users are warned whenever they log in within the expiration warning period. The warning includes the remaining time before password expiration.
- Password syntax checking New passwords must meet the minimum password length requirements. A password must not match the value of the uid, cn, sn, or mail attributes in the user's directory entry.
- Password history checking Users cannot reuse passwords. LDAP administrators can configure the number of passwords kept in the server's history list.
- User account lockout A user account can be locked out after a specified number of repeated authentication failures. Users can also be locked out if their accounts are inactivated by an administrator. Authentication failure continues until the account lockout time is passed or the administrator reactivates the account.

These account management features work only with the Oracle Directory Server Enterprise Edition. For information about configuring the password and account lockout policy on the LDAP server, see the information in the Oracle Directory Server Enterprise Edition Administration Guide (http://docs.oracle.com/cd/E29127\_01/doc.111170/e28972/ds-configuration.htm#gcsuf). For an example of the LDAP account management with the pam\_ldap module, see Example 6, "Sample pam.conf File Using the pam\_ldap Module for Account Management," on page 69.

Before configuring the password and account lockout policy on Oracle Directory Server Enterprise Edition, make sure all hosts use the most recent version of the LDAP client with

pam\_ldap account management. Additionally, make sure the clients have a properly configured pam.conf file. Otherwise, the LDAP naming service fails when proxy or user passwords expire.

# LDAP Account Management With the pam\_unix\_\* Modules

The LDAP naming service supports the full functionality of the passwd command and the pam\_unix\_\* modules in the files naming service. If the enableShadowUpdate switch is enabled, account management functionality becomes available to both local accounts and LDAP accounts. The functionality includes password aging, account expiry and notification, and failed login account locking. Also, LDAP supports the -dluNfnwx options of the passwd command. The enableShadowUpdate switch enables the implementation of consistent account management for users who are defined in both the files and the LDAP scope.

The pam\_ldap and the pam\_unix\_\* modules are incompatible. The pam\_ldap module requires that passwords be modifiable by users, but the pam\_unix\_\* modules do not allow the users to modify passwords. Therefore, you cannot use the two modules together in the same LDAP naming domain. Either all clients use the pam\_ldap module or all clients use the pam\_unix\_\* modules. As a consequence of this limitation, you might need to use a dedicated LDAP server in cases where a web or email application, for example, might require users to change their own passwords on the LDAP server.

Implementing enableShadowUpdate also requires that the administrator credential (adminDN and adminPassword) is stored locally on every client in the svc:/network/ldap/client service.

Do not change the /etc/pam.conf file to use the pam\_unix\_\* modules for account management. The default /etc/pam.conf file is sufficient.



# Planning Requirements for LDAP Naming Services

This chapter discusses the high-level planning that you must do before beginning the server and client setup and installation processes.

This chapter covers the following topics:

- "LDAP Planning Overview" on page 29
- "Planning the Configuration of the LDAP Client Profile" on page 31
- "Planning the Deployment of LDAP Master and Replica Servers" on page 34
- "Planning the LDAP Data Population" on page 35
- "Service Search Descriptors and Schema Mapping" on page 35
- "Default Client Profile Attributes for LDAP Implementation" on page 40

## **LDAP Planning Overview**

A LDAP client uses the collection of configuration information in the LDAP client profile to access naming service information from the LDAP server. You must specify the configuration information when you build the profile on the LDAP server. During the server setup, you are prompted for the configuration information. Some of the information that is prompted is required, while other information is optional. In most cases, you accept the default values that are already provided. The individual types of information that are prompted for the profile are called client attributes.

As you gather the configuration information for the profile, you can refer to the template checklists used for configuring LDAP in "Checklists for Configuring LDAP" on page 41.

The LDAP client profile attributes are as follows:

- cn Specifies the profile name. The attribute has no default value. You must specify a value for the attribute.
- preferredServerList Specifies the host addresses of the preferred servers as a space-separated list of server addresses. Do not use host names of the servers in this list. The servers in this list are tried in order before those in defaultServerList until a successful

connection is made. This attribute has no default value. You must specify at least one server in either preferredServerList or defaultServerList.

**Note** - If you are using host names to define both defaultServerList and preferredServerList, then you must not use LDAP for host server lookup searches. Do not configure the config/host property of the svc:/network/name-service/switch service with the value ldap. For more information about LDAP and service management facility (SMF), see "LDAP and the Service Management Facility" on page 64.

- defaultServerList Specifies the host addresses of the default servers as a space-separated list of server addresses. Do not use host names of the servers in this list. After the servers in preferredServerlist are tried, the default servers on the client's subnet are tried, followed by the remaining default servers, until a connection is made. You must specify at least one server in either preferredServerList or defaultServerList. The servers in this list are tried only after the servers in the preferred server list. This attribute has no default value.
- defaultSearchBase Specifies the DN relative to which to locate the well-known containers. This attribute has no default value. However, this value can be overridden for a given service by the serviceSearchDescriptor attribute.
- defaultSearchScope Defines the scope of a database search by a LDAP client. It can be overridden by the serviceSearchDescriptor attribute. The possible values are one or sub. The default value is a single-level search.
- authenticationMethod Identifies the method of authentication used by the LDAP client.
   The default value is none. For more information, see "Authentication Methods for the LDAP Naming Service" on page 20.
- credentialLevel Identifies the type of credentials a LDAP client must use to authenticate. The possible values are anonymous, proxy, or self. self is also known as "per-user". The default value is anonymous
- serviceSearchDescriptor Defines how and where a LDAP client should search for a naming database, for example, whether the LDAP client should look in one or more points in the DIT. By default, no SSDs are defined.
- serviceAuthenticationMethod Defines the authentication method used by a LDAP client for the specified service. By default, no service authentication methods are defined. If a service does not have serviceAuthenticationMethod defined, it defaults to the value of authenticationMethod.
- attributeMap Defines the attribute mappings that the LDAP client uses. By default, no attributeMap is defined.
- objectclassMap Defines object class mappings that the LDAP client uses. By default, no objectclassMap is defined.
- searchTimeLimit Specifies the maximum time, in seconds, that a LDAP client must allow for a search to complete before timing out. This value does not affect the time the LDAP server will allow for a search to complete. The default value is 30 seconds.

- bindTimeLimit Specifies maximum time in seconds a LDAP client must allow to bind with a server before timing out. The default value is 30 seconds.
- followReferrals Specifies whether a LDAP client should follow an LDAP referral.
   Possible values are TRUE or FALSE. The default value is TRUE.
- profileTTL Specifies time between refreshes of the LDAP client profile from the LDAP server by the ldap\_cachemgr daemon. The default value is 43200 seconds or 12 hours. If given a value of 0, the profile will never be refreshed. For more information, see the ldap\_cachemgr(1M) man page.

The LDAP client profile attributes are automatically set up when you run the idsconfig command on the server.

You can use the ldapclient command to set up local client attributes. For more information, see "Defining LDAP Local Client Attributes" on page 65.

### Planning the Configuration of the LDAP Client Profile

To set up the LDAP naming service, you must first plan the configuration of the LDAP client profile. The default values of the profile attributes suffice for most networks. However, based on the network topology, you might specify non-default values for some profile attributes. This section describes the different attributes that you might want to configure.

### **LDAP Network Model**

When planning the LDAP network model, you must determine the physical servers to be deployed for the LDAP naming service. To ensure availability and performance, each subnet of the network must have one LDAP server to service the LDAP clients in that subnet. When planning for this model, you should consider the following factors:

- Number of systems to be deployed as LDAP servers Which servers are designated master servers, and which servers are replicas that serve as backups?
- The manner of access to the servers

Should all the LDAP servers have equal priority for access by LDAP client requests? Or, should the servers have different priorities and those with higher priorities be accessed first? If access to the servers is not equal, list the order in which these servers are accessed.

The information that you specify is managed by the defaultServerList and preferredServerList attributes. Note the following guidelines for the server list:

- Use LDAP servers, not a concentrator, balancer, or pool.
- Use multiple LDAP servers.

- If you are using SSL/TLS, the hostnames must match the certificate names.
- Hostnames must resolve to IP addresses.
- Timeout factors

Determine the timeout values as follows:

- bindTimeLimit attribute determines how long a TCP connect request continues before the request is dropped.
- searchTimeLimit attribute determines how long an LDAP search operation continues before the search is cancelled.
- profileTTL attribute determines how often a LDAP client downloads profiles from the servers.

For example, in a slow network, you might increase the length of time for searching and for allowing TCP connect requests. In a development environment, you might limit the frequency of downloading a profile by a LDAP client.

### **Directory Information Tree**

The LDAP naming service uses a default directory information tree (DIT) to store information. The DIT is based on an LDAP schema.

The DIT consists of containers of information that are hierarchically structured. The structure follows the standard LDAP schema described in RFC 2307 http://tools.ietf.org/html/rfc2307 and RFC 4876 http://tools.ietf.org/html/rfc4876.

The default structure of the DIT suffices for most network setups to implement LDAP. With the default structure, you only need to determine the following:

- The base node distinguished name (DN) of the tree that naming service will search for information about a specific domain. The defaultSearchBase attribute manages the base node information.
- The scope of search that a naming service lookup functionality should perform. The scope can cover either only one level below the DN, or the entire subtree below the DN. This information is managed by the attribute defaultSearchScope.

A DIT can also have a more complicated structure for storing data. For example, you can store the data about user accounts in different parts of the DIT. You should determine how to customize the behavior of the search operation such as the base DN, the scope, and the filters to use that overrides the default search sequence. The customized search sequence information is managed by the attributes serviceSearchDescriptor, attributeMap, and objectclassMap. For a detailed explanation about customizing the search sequence operation, see "Service Search Descriptors and Schema Mapping" on page 35.

Multiple servers can serve a single DIT. In this setup, the subtrees of a DIT might be distributed across multiple servers. Therefore, you must further configure LDAP servers to redirect LDAP

client requests to the appropriate LDAP servers which can provide the requested information. The followReferrals attribute manages the information about how to redirect LDAP client requests to the correct server.

Having a single LDAP server providing all the naming data for a specific domain is the typical and recommended setup. Even in this scenario, however, you can still configure the followReferrals attribute to direct LDAP clients to read-only replica servers for most of the information requests. Access to a master server to perform read and write operations is not typically provided. With a referral configuration, you prevent the master server from overload.

### **Security Considerations**

For the security of LDAP operations that process requests for directory information, consider the following :

- The manner by which LDAP clients identify themselves to access information, which is determined by the credential level that you specify for the LDAP clients. The credential level is managed by the credentialLevel attribute, to which you can assign one of the following values:
  - anonymous
  - proxy
  - proxy anonymous
  - self

For detailed descriptions of each of these values, see "Client Credential Levels" on page 17.

- The method of authenticating the LDAP client, which is managed by the authenticationMethod attribute. You can specify the authentication method by assigning one of the following options:
  - none
  - simple
  - sasl/digest-MD5
  - sasl/cram-MD5
  - sasl/GSSAPI
  - tls:simple
  - tls:sasl/cram-MD5
  - tls:sasl/digest-MD5

For detailed descriptions of each of these values, see "Authentication Methods for the LDAP Naming Service" on page 20.

In addition to the credential level to assign to LDAP clients as well as the authentication method to use, you should also consider the following:

- Whether to use Kerberos and per-user authentication
- Value to specify for the servers' passwordStorageScheme attribute
- Setup of access control information
  - For more information about ACIs, consult the administration guide for the version of Oracle Directory Server Enterprise Edition that you are using.
- Whether to use the pam\_unix\_\* or pam\_ldap module to perform LDAP account management

This consideration is related to whether the LDAP naming service is compatible with NIS.

# Planning the Deployment of LDAP Master and Replica Servers

You can deploy the master and replica servers in the following ways:

- Single-master replication
- Multi-master replication

### **Single-Master Replication**

In the single-master replication strategy, one master server exists for a specific network or subnetwork. The master server stores writable copies of the directories. Replica servers store read-only copies. Only the master server can perform write operations.

If the master server becomes unavailable, no other server can perform write operations. This strategy therefore has a single point of failure.

## **Multi-Master Replication**

In the multi-master replication strategy, multiple master servers store read-write copies of the same directories. Updating the same directories in different master servers can cause conflicts. You must establish a conflict resolution policy, such as "last writer wins" when using the multimaster replication strategy.

For information about how to set up replica servers, refer to the administration guide for the version of Oracle Directory Server Enterprise Edition that you are using. For large-scale enterprise deployments, you must use multi-master replication.

### **Planning the LDAP Data Population**

After the LDAP server has been configured with the proper DIT and schema, you need to populate the DIT with data. The source of the data are the /etc files in multiple systems. Consider the following methods for populating the DIT:

- Merge the /etc files of a specific data type into a single file for that data type. For example, merge all /etc/passwd files from different systems into a single /etc/passwd file. You can populate the server from the single host that stores all the merged /etc files.
- Populate the server by using the appropriate command from each LDAP client system that accesses the directory server.

For information about the steps to populate the directory server, see "Populating the LDAP Server With Data" on page 55.

## **Service Search Descriptors and Schema Mapping**

The LDAP naming service can use the DIT only if it is structured in a certain way. If required you can use SSDs to enable the LDAP naming service to search in locations other than the default location. Additionally, you can define attributes and object classes in place of the ones specified by the default schema. Use the ldaplist -v command to list the default filters.

**Note -** The default filters are listed in "Default Filters Used by the LDAP Naming Service" on page 37.

If you use schema mapping, you must make sure that the syntax of the mapped attribute is consistent with the attribute it is mapped to. For example, the single-valued attributes must map to single-valued attributes and the attributes must have the same syntax. Also, ensure that the mapped object classes have the correct mandatory attributes.

### **About Service Search Descriptors**

The serviceSearchDescriptor attribute defines how and where an LDAP naming service client should search for information for a particular service. The serviceSearchDescriptor contains a service name followed by one or more semicolon-separated base-scope-filter triples. These base-scope-filter triples are used to define searches only for the specific service and are searched in order. If multiple base-scope-filters are specified for a given service, when that service looks for a particular entry, it will search in each base with the specified scope and filter.

**Note -** The default location is not searched for a service (database) with an SSD unless it is included in the SSD. Unpredictable behavior will result if multiple SSDs are specified for a service.

In the following example, the LDAP naming service client performs a single-level search in ou=west,dc=example,dc=com followed by a single-level search in ou=east,dc=example,dc=com for the passwd service. To look up the passwd data for a user's username, the default LDAP filter (&(objectClass=posixAccount)(uid=username)) is used for each BaseDN.

```
serviceSearchDescriptor: passwd:ou=west,dc=example,dc=com;ou=east,
dc=example,dc=com
```

In the following example, the LDAP naming service client would perform a subtree search in ou=west,dc=example,dc=com for the passwd service. To look up the passwd data for user username, the subtree ou=west,dc=example,dc=com would be searched with the LDAP filter (& (fulltimeEmployee=TRUE) (uid=username)).

```
serviceSearchDescriptor: passwd:ou=west,dc=example,
dc=com?sub?fulltimeEmployee=TRUE
```

You can also associate multiple containers with a particular service type. In the following example, the service search descriptor specifies searching for the password entries in three containers.

```
ou=myuser,dc=example,dc=com
ou=newuser,dc=example,dc=com
ou=extuser,dc=example,dc=com
```

Note that a trailing ',' in the example implies that the defaultSearchBase is appended to the relative base in the SSD.

```
defaultSearchBase: dc=example,dc=com
serviceSearchDescriptor: \
passwd:ou=myuser,;ou=newuser,;ou=extuser,dc=example,dc=com
```

### attributeMap Attributes

The LDAP naming service enables one or more attribute names to be remapped for any of its services. If you map an attribute, you must be sure that the attribute has the same meaning and syntax as the original attribute. Note that mapping the userPassword attribute might cause problems.

Consider using schema mappings in situations where you want to map attributes in an existing directory server. If you have user names that differ only in case, you must map the uid attribute, which ignores case, to an attribute that does not ignore case.

The format for this attribute is service:attribute-name=mapped-attribute-name.

If you want to map more than one attribute for a given service, you can define multiple attributeMap attributes.

In the following example, the employeeName and home attributes would be used whenever the uid and homeDirectory attributes would be used for the passwd service.

```
attributeMap: passwd:uid=employeeName
attributeMap: passwd:homeDirectory=home
```

You can map the passwd service's gecos attribute to several attributes, as shown in the following example.

```
attributeMap: gecos=cn sn title
```

This example maps the gecos values to a space separated list of the cn, sn, and title attribute values.

### objectclassMap Attribute

The LDAP naming service enables object classes to be remapped for any of its services. If you want to map more than one object class for a given service, you can define multiple objectclassMap attributes. In the following example, the myUnixAccount object class is used whenever the posixAccount object class is used.

```
objectclassMap: passwd:posixAccount=myUnixAccount
```

## **Default Filters Used by the LDAP Naming Service**

If you do not specify a parameter for a given service using an SSD, the default filter is used. To list the default filters for a given service, use the ldaplist command with the -v option.

In the following example, filter=(&(objectclass=iphost)(cn=abcde)defines the default filters.

```
database=hosts
filter=(&(objectclass=iphost)(cn=abcde)
user data=(&(%s) (cn=abcde))
```

The ldaplist command generates the following list of default filters, where %s signifies a string and %d, a number.

```
hosts
(&(objectclass=iphost)(cn=%s))
------
passwd
(&(objectclass=posixaccount)(uid=%s))
------
services
(&(objectclass=ipservice)(cn=%s))
```

```
(&(objectclass=posixgroup)(cn=%s))
netgroup
(&(objectclass=nisnetgroup)(cn=%s))
networks
(\& (object class = ipnetwork) \, (ipnetwork number = \%s))\\
netmasks
(&(objectclass=ipnetwork)(ipnetworknumber=%s))
(&(objectclass=oncrpc)(cn=%s))
protocols
(&(objectclass=ipprotocol)(cn=%s))
bootparams
(&(objectclass=bootableDevice)(cn=%s))
ethers
(&(objectclass=ieee802Device)(cn=%s))
publickey
(&(objectclass=niskeyobject)(cn=%s))
(&(objectclass=niskeyobject)(uidnumber=%d))
aliases
(&(objectclass=mailGroup)(cn=%s))
```

The following table lists the LDAP filters used in the getXbyY call.

TABLE 4 LDAP Filters Used in getXbyY Calls

Filter	Definition
bootparamByName	(&(objectClass=bootableDevice)(cn=%s))
etherByHost	(&(objectClass=ieee802Device)(cn=%s))
etherByEther	(&(objectClass=ieee802Device)(macAddress=%s))
groupByName	(&(objectClass=posixGroup)(cn=%s))
groupByGID	(&(objectClass=posixGroup)(gidNumber=%ld))
groupByMember	(&(objectClass=posixGroup)(memberUid=%s))
hostsByName	(&(objectClass=ipHost)(cn=%s))
hostsByAddr	(&(objectClass=ipHost)(ipHostNumber=%s))
keyByUID	(&(objectClass=nisKeyObject)(uidNumber=%s))

Filter	Definition
keyByHost	(&(objectClass=nisKeyObject)(cn=%s))
netByName	(&(objectClass=ipNetwork)(cn=%s))
netByAddr	(&(objectClass=ipNetwork)(ipNetworkNumber=%s))
nisgroupMember	(membernisnetgroup=%s)
maskByNet	(&(objectClass=ipNetwork)(ipNetworkNumber=%s))
printerByName	(&(objectClass=sunPrinter)( (printer-name=%s) (printer-aliases=%s)))
projectByName	(&(objectClass=SolarisProject)(SolarisProjectName=%s))
projectByID	(&(objectClass=SolarisProject)(SolarisProjectID=%ld))
protoByName	(&(objectClass=ipProtocol)(cn=%s))
protoByNumber	(&(objectClass=ipProtocol)(ipProtocolNumber=%d))
passwordByName	(&(objectClass=posixAccount)(uid=%s))
passwordByNumber	(&(objectClass=posixAccount)(uidNumber=%ld))
rpcByName	(&(objectClass=oncRpc)(cn=%s))
rpcByNumber	(&(objectClass=oncRpc)(oncRpcNumber=%d))
serverByName	(&(objectClass=ipService)(cn=%s))
serverByPort	(&(objectClass=ipService)(ipServicePort=%ld))
serverByNameAndProto	(&(objectClass=ipService)(cn=%s)(ipServiceProtocol=%s))
specialByNameserver	(ipServiceProtocol=%s))
ByPortAndProto	(&(objectClass=shadowAccount)(uid=%s))
netgroupByTriple	(&(objectClass=nisNetGroup)(cn=%s))
netgroupByMember	(&(objectClass=nisNetGroup)(cn=%s))
authName	(&(objectClass=SolarisAuthAttr)(cn=%s))
auditUserByName	(&(objectClass=SolarisAuditUser)(uid=%s))
execByName	<pre>(&amp;(objectClass=SolarisExecAttr)(cn=%s) (SolarisKernelSecurityPolicy=% s)(SolarisProfileType=%s))</pre>
execByPolicy	<pre>(&amp;(objectClass=SolarisExecAttr)(SolarisProfileId=%s) (SolarisKernelSecurityPolicy=%s)(SolarisProfileType=%s))</pre>
profileByName	(&(objectClass=SolarisProfAttr)(cn=%s))
userByName	(&(objectClass=SolarisUserAttr)(uid=%s))

The following table lists the getent attribute filters.

**TABLE 5** getent Attribute Filters

Filter	Definition
aliases	(objectClass=rfc822MailGroup)
auth_attr	(objectClass=SolarisAuthAttr)
audit_user	(objectClass=SolarisAuditUser)

Filter	Definition
exec_attr	(objectClass=SolarisExecAttr)
group	(objectClass=posixGroup)
hosts	(objectClass=ipHost)
networks	(objectClass=ipNetwork)
prof_attr	(objectClass=SolarisProfAttr)
protocols	(objectClass=ipProtocol)
passwd	(objectClass=posixAccount)
printers	(objectClass=sunPrinter)
rpc	(objectClass=oncRpc)
services	(objectClass=ipService)
shadow	(objectclass=shadowAccount)
project	(objectClass=SolarisProject)
usr_attr	(objectClass=SolarisUserAttr)

## **Default Client Profile Attributes for LDAP Implementation**

There are several significant attributes that you might configure to implement the LDAP naming service. Note that not all of these attributes require configuration. Of the following attributes, only cn, defaultServerList, and defaultSearchBase require you to provide values. For the rest, you can accept the default values or leave the other attributes without any configuration.

- cn
- defaultServerList
- preferredServerList
- bindTimeLimit
- searchTimeLimit
- profileTTL
- defaultSearchBase
- defaultSearchScope
- serviceSearchDescriptor
- attributeMap
- objectclassMap
- followReferrals
- credentialLevel
- authenticationMethod
- serviceCredentialLevel

### serviceAuthenticationMethod

# **Checklists for Configuring LDAP**

**TABLE 6** Checklist for Server Variable Definitions

Variable	Definition for Network
Port number at which the directory server nstance s installed (389)	
Name of the LDAP server	
Replica servers (IP number:port number)	
Directory manager [dn: cn=directory manager]	
Domain name to be served	
Maximum time (in seconds) to process client requests before timing out	
Maximum number of entries returned for each search request	

### **TABLE 7** Checklist for Client Profile Variable Definitions

Variable	Definition for Network
Profile name	
Server list (defaults to the local subnet)	
Preferred server list (listed in order of which server to try first, second, and so on)	
Search scope (number of levels down through the directory tree). Possible values are 'One' or 'Sub'.	
Credential used to gain access to server. The default is anonymous.	
Follow Referrals? (Referrals are a pointer to another server if the main server is unavailable.) The default is no.	
Search time limit (in seconds) for waiting for the server to return information. The default is 30 seconds.	
Bind time limit (in seconds) for contacting the server. The default is 30 seconds.	
Authentication method. Default is none.	

# · · · CHAPTER 4

## Setting Up the Oracle Directory Server Enterprise Edition With LDAP Clients

This chapter describes how to configure Oracle Directory Server Enterprise Edition to support LDAP clients. This information is specific to the Oracle Directory Server Enterprise Edition.

**Note -** Oracle Directory Server Enterprise Edition must already be installed and configured before you can configure it to work with LDAP clients. This chapter does not describe all the features of Oracle Directory Server Enterprise Edition. Refer to the documentation of the specific directory server that you are using for more detailed information.

This chapter covers the following topics:

- "Directory Server Requirements" on page 43
- "Creating the Directory Tree Definitions" on page 45
- "Populating the LDAP Server With Data" on page 55
- "Additional Directory Server Configuration Tasks" on page 56

## **Directory Server Requirements**

To configure the directory server for the LDAP naming service, you need to provide server information and client profile information.

To support LDAP clients, all servers must support the LDAP v3 protocol and compound naming and auxiliary object classes. In addition, servers must support at least one of the following controls :

- Simple paged-mode (RFC 2696)
- Virtual List View controls

The server must support at least one of the following authentication methods:

- anonymous
- simple
- sasl/cram-MD5

- sasl/digest-MD5
- sasl/GSSAPI

If an LDAP client is using the pam\_unix\_\* modules, the server must support storing passwords in UNIX crypt format.

If an LDAP client is using TLS, the server must support SSL or TLS.

If an LDAP client is using sas1/GSSAPI, the server must support SASL, GSSAPI, Kerberos 5 authentication. Support for GSS encryption over the wire is optional.

# Server Information for Configuring the Directory Server

When you configure the directory server, you are prompted for the following information about the server:

- Port number for the directory server instance. By default, the port number is 389.
- Server name.
- IP addresses and port numbers of replica servers.
- Directory manager represented by the cn variable. By default, cn is set to directory manager.
- Domain name of the domain server.
- Maximum length of time in seconds to process client requests before the request times out.
- Maximum number of record information that is provided for each search request.

Some of the information about the server are attributes are similar to the LDAP client profile. For more information, see "Planning the Configuration of the LDAP Client Profile" on page 31.

To prepare the server information, see "Checklists for Configuring LDAP" on page 41.

## **LDAP Client Profile Information**

You need to know the LDAP client profile attributes to regulate client access to the server when requesting information. For information about LDAP client profile attributes, see "Planning the Configuration of the LDAP Client Profile" on page 31.

**Note -** Client profiles are defined per domain. You must define at least one profile for a given domain.

## **Creating Browsing Indexes for the Directory Tree**

The browsing index functionality of Oracle Directory Server Enterprise Edition is called virtual list view (VLV). With VLV, a client can view a select subset of entries from lengthy list, which reduces the search time for every client.

The creation of the directory information tree includes the creation of VLVs for the tree. Use the online instructions to create the VLVs on the directory server as described in "How to Configure Oracle Directory Server Enterprise Edition for the LDAP Naming Service" on page 46.

## **Creating the Directory Tree Definitions**

After preparing the server and client profile information, you can set up Oracle Directory Server Enterprise Edition for LDAP. Use the idsconfig to build the directory information tree with the definitions in your checklists.

When you create the DIT using the idsconfig command, you effectively build the client profile and its attributes. For more information about the client profile attributes, see "LDAP Planning Overview" on page 29. When developing and using client profiles, note the following:

- Store client profiles in a well-known location on the LDAP server. All profiles are located in the ou=profile container.
- A single profile on the server defines the configuration of all the clients that use that server. Any subsequent change to the profile attributes is propagated automatically to the clients.
- The root DN for the given domain must have an object class of nisDomainObject and a nisDomain attribute containing the client's domain.
- The client profiles must be readable anonymously.

You can create the directory definitions from any Oracle Solaris system on the network. However, the output of the idsconfig command includes the directory manager's password in clear text. To avoid publishing the password, use the idsconfig command on the directory server.

For more information about the idsconfig command, see the idsconfig(1M) man page.

**Note** - You can create SSDs at the same time as you create the directory tree. Both operations are started by the idsconfig command. However, if preferred, you can create SSDs as a separate operation. For more information about SSDs, see "Service Search Descriptors and Schema Mapping" on page 35.

## ▼ How to Configure Oracle Directory Server Enterprise Edition for the LDAP Naming Service

- Make sure the target Oracle Directory Server Enterprise Edition is running.
- 2. Build the directory information tree.

# /usr/lib/ldap/idsconfig

Provide information as prompted.

#### 3. Follow the online instructions to build the VLV indexes.

The VLV indexes are built as a separate operation at the end of the creation of the DIT. The appropriate command syntax is provided. Make sure that you perform these instructions on the server.

Note: idsconfig has created entries for VLV indexes.

For DS5.x, use the directoryserver(1m) script on myserver to stop the server. Then, using directoryserver, follow the directoryserver examples below to create the actual VLV indexes.

For DSEE6.x, use dsadm command delivered with DS on myserver to stop the server. Then, using dsadm, follow the dsadm examples below to create the actual VLV indexes.

For the complete output of the idsconfig command, see the screen example in "Building the Directory Information Tree" on page 46.

## **Example of Server Configuration for LDAP**

This section provides examples of different aspects in the configuration of Oracle Directory Server Enterprise Edition to use the LDAP naming service. The examples feature a company Example, Inc. that has branches nationwide. Specifically, these examples focus on the LDAP configuration of the company's West Coast division, whose domain name is west.example.com.

## **Building the Directory Information Tree**

The following table lists the server information for west.example.com.

**TABLE 8** Server Variables Defined for the west.example.com Domain

Variable	Definition for Example Network
Port number at which the directory server nstanceis installed	389 (default)

Variable	Definition for Example Network
Name of the LDAP server	myserver (from the FQDN myserver.west.example. com or the hostname for 192.168.0.1)
Replica servers (IPnumber:port number)	192.168.0.2 [for myreplica.west.example.com]
Directory manager	cn=directory manager (default)
Domain name to be served	west.example.com
Maximum time in seconds to process client requests before timing out	1
Maximum number of entries returned for each search request	1

The following table lists the client profile information.

TABLE 9 Client Profile Variables Defined for the west.example.com Domain

Variable	Definition for Example Network
Profile name	WestUserProfile
Server list	192.168.0.1
Preferred server list	none
Search scope	one
Credential used to gain access to server	proxy
Follow referrals to another server	Υ
Search time limit for waiting for server to return information	default
Bind time limit for contacting the server	default
Authentication method	simple

**EXAMPLE 1** Using the Server and Client Profile Information to Create the Directory Tree

#### # usr/lib/ldap/idsconfig

It is strongly recommended that you BACKUP the directory server before running idsconfig.

Hit Ctrl-C at any time before the final confirmation to exit.

```
Do you wish to continue with server setup (y/n/h)? [n] y
Enter the JES Directory Server's hostname to setup: myserver
Enter the port number for DSEE (h=help): [389]
Enter the directory manager DN: [cn=Directory Manager]
Enter passwd for cn=Directory Manager :
Enter the domainname to be served (h=help): [west.example.com]
Enter LDAP Base DN (h=help): [dc=west,dc=example,dc=com]
Checking LDAP Base DN ...
Validating LDAP Base DN and Suffix ...
No valid suffixes were found for Base DN dc=west,dc=example,dc=com
```

```
Enter suffix to be created (b=back/h=help): [dc=west,dc=example,dc=com]
Enter ldbm database name (b=back/h=help): [west]
sasl/GSSAPI is not supported by this LDAP server
Enter the profile name (h=help): [default] WestUserProfile
Default server list (h=help): [192.168.0.1]
Preferred server list (h=help):
Choose desired search scope (one, sub, h=help): [one]
The following are the supported credential levels:
1 anonymous
2 proxy
3 proxy anonymous
4 self
Choose Credential level [h=help]: [1] 2
The following are the supported Authentication Methods:
1 none
2 simple
3 sasl/DIGEST-MD5
4 tls:simple
5 tls:sasl/DIGEST-MD5
6 sasl/GSSAPI
Choose Authentication Method (h=help): [1] 2
Current authenticationMethod: simple
Do you want to add another Authentication Method? n
Do you want the clients to follow referrals (y/n/h)? [n]
Do you want to modify the server timelimit value (y/n/h)? [n] y
Enter the time limit for DSEE (current=3600): [-1]
Do you want to modify the server sizelimit value (y/n/h)? [n] y
Enter the size limit for DSEE (current=2000): [-1]
Do you want to store passwords in "crypt" format (y/n/h)? [n] y
Do you want to setup a Service Authentication Methods (y/n/h)? [n]
Client search time limit in seconds (h=help): [30]
Profile Time To Live in seconds (h=help): [43200]
Bind time limit in seconds (h=help): [10]
Do you want to enable shadow update (y/n/h)? [n]
Do you wish to setup Service Search Descriptors (y/n/h)? [n]
             Summary of Configuration
 1 Domain to serve
                               : west.example.com
                               : dc=west,dc=example,dc=com
 2 Base DN to setup
                               : dc=west,dc=example,dc=com
       Suffix to create
       Database to create
                              : west
                               : WestUserProfile
 3 Profile name to create
 4 Default Server List
                               : 192.168.0.1
 5 Preferred Server List
 6 Default Search Scope
                               : one
7 Credential Level
                               : proxy
8 Authentication Method
                              : simple
9 Enable Follow Referrals
                              : FALSE
10 DSEE Time Limit
                               : -1
11 DSEE Size Limit
                               : -1
```

```
12 Enable crypt password storage : TRUE
13 Service Auth Method pam_ldap :
14 Service Auth Method keyserv
15 Service Auth Method passwd-cmd:
16 Search Time Limit
                         : 30
17 Profile Time to Live
                           : 43200
18 Bind Limit
                           : 10
                           : FALSE
19 Enable shadow update
20 Service Search Descriptors Menu
Enter config value to change: (1-20 0=commit changes) [0]
Enter DN for proxy agent: [cn=proxyagent,ou=profile,dc=west,dc=example,dc=com]
Enter passwd for proxyagent:
Re-enter passwd:
WARNING: About to start committing changes. (y=continue, n=EXIT) {f y}
1. Changed timelimit to -1 in cn=config.
2. Changed sizelimit to -1 in cn=config.
3. Changed passwordstoragescheme to "crypt" in cn=config.
4. Schema attributes have been updated.
5. Schema objectclass definitions have been added.
6. Database west successfully created.
7. Suffix dc=west,dc=example,dc=com successfully created.
8. NisDomainObject added to dc=west,dc=example,dc=com.
9. Top level "ou" containers complete.
10. automount maps: auto home auto direct auto master auto shared processed.
11. ACI for dc=west,dc=example,dc=com modified to disable self modify.
12. Add of VLV Access Control Information (ACI).
13. Proxy Agent cn=proxyagent,ou=profile,dc=west,dc=example,dc=com added.
14. Give cn=proxyagent,ou=profile,dc=west,dc=example,dc=com read permission
for password.
15. Generated client profile and loaded on server.
16. Processing eq,pres indexes:
uidNumber (eq,pres) Finished indexing.
ipNetworkNumber (eq,pres) Finished indexing.
gidnumber (eq,pres) Finished indexing.
oncrpcnumber (eq,pres) Finished indexing.
automountKey (eq,pres) Finished indexing.
17. Processing eq,pres,sub indexes:
ipHostNumber (eq,pres,sub) Finished indexing.
membernisnetgroup (eq,pres,sub) Finished indexing.
nisnetgrouptriple (eq,pres,sub) Finished indexing.
18. Processing VLV indexes:
```

```
west.example.com.getauduent vlv_index
                              Entry created
west.example.com.getauthent vlv_index
                              Entry created
west.example.com.getexecent vlv index
                              Entry created
west.example.com.getprofent vlv index
                              Entry created
west.example.com.getmailent vlv index
                             Entry created
west.example.com.getbootent vlv index
                             Entry created
west.example.com.getethent vlv_index
                             Entry created
west.example.com.getngrpent vlv_index
                             Entry created
west.example.com.getipnent vlv_index
                             Entry created
west.example.com.getip6ent vlv index
                             Entry created
```

idsconfig: Setup of DSEE server myserver is complete.

Note: idsconfig has created entries for VLV indexes.

For DS5.x, use the directoryserver(1m) script on myserver to stop the server. Then, using directoryserver, follow the directoryserver examples below to create the actual VLV indexes.

For DSEE6.x, use dsadm command delivered with DS on myserver to stop the server. Then, using dsadm, follow the dsadm examples below to create the actual VLV indexes.

#### **EXAMPLE 2** Completing the idsconfig Setup

```
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getgrent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.gethostent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getnetent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getpwent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getrpcent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getspent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getauhoent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getsoluent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getauduent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getauthent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getexecent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getprofent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getmailent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getbootent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getethent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getngrpent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getipnent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getmaskent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getprent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getip4ent
directoryserver -s <server-instance> vlvindex -n west -T west.example.com.getip6ent
```

```
install-path/bin/dsadm reindex -l -t west.example.com.getgrent \
directory-instance-path dc=west,dc=example,dc=com
install-path/bin/dsadm reindex -l -t west.example.com.gethostent \
directory-instance-path dc=west,dc=example,dc=com
.
.
.
install-path/bin/dsadm reindex -l -t west.example.com.getip6ent \
directory-instance-path dc=west,dc=example,dc=com
```

### **EXAMPLE 3** Enabling Shadow Updates by Using idsconfig

# usr/lib/ldap/idsconfig

2 simple

You can use the idsconfig utility to enable shadow update when you build the DIT for a new profile. To enable shadow update you must type y when prompted with Do you want to enable shadow update (y/n/h)? [n]. You must type the password for the administrator when prompted with Enter passwd for the administrator:. For more information, see "Enabling Shadow Data Updates" on page 18.

```
It is strongly recommended that you BACKUP the directory server
before running idsconfig.
Hit Ctrl-C at any time before the final confirmation to exit.
Do you wish to continue with server setup (y/n/h)? [n] y
Enter the JES Directory Server's hostname to setup: myserver
Enter the port number for DSEE (h=help): [389]
Enter the directory manager DN: [cn=Directory Manager]
Enter passwd for cn=Directory Manager :
Enter the domainname to be served (h=help): [west.example.com]
Enter LDAP Base DN (h=help): [dc=west,dc=example,dc=com]
Checking LDAP Base DN ...
Validating LDAP Base DN and Suffix ...
No valid suffixes were found for Base DN dc=west,dc=example,dc=com
Enter suffix to be created (b=back/h=help): [dc=west,dc=example,dc=com]
Enter ldbm database name (b=back/h=help): [west]
sasl/GSSAPI is not supported by this LDAP server
Enter the profile name (h=help): [default] WestUserProfile
Default server list (h=help): [192.168.0.1]
Preferred server list (h=help):
Choose desired search scope (one, sub, h=help): [one]
The following are the supported credential levels:
1 anonymous
2 proxy
3 proxy anonymous
4 self
Choose Credential level [h=help]: [1] 2
The following are the supported Authentication Methods:
1 none
```

```
3 sasl/DIGEST-MD5
4 tls:simple
5 tls:sasl/DIGEST-MD5
6 sasl/GSSAPI
Choose Authentication Method (h=help): [1] 2
Current authenticationMethod: simple
Do you want to add another Authentication Method? n
Do you want the clients to follow referrals (y/n/h)? [n]
Do you want to modify the server timelimit value (y/n/h)? [n] y
Enter the time limit for DSEE (current=3600): [-1]
Do you want to modify the server sizelimit value (y/n/h)? [n] y
Enter the size limit for DSEE (current=2000): [-1]
Do you want to store passwords in "crypt" format (y/n/h)? [n] y
Do you want to setup a Service Authentication Methods (y/n/h)? [n]
Client search time limit in seconds (h=help): [30]
Profile Time To Live in seconds (h=help): [43200]
Bind time limit in seconds (h=help): [10]
Do you want to enable shadow update (y/n/h)? [n] y
Do you wish to setup Service Search Descriptors (y/n/h)? [n]
            Summary of Configuration
1 Domain to serve
                              : west.example.com
2 Base DN to setup
                              : dc=west,dc=example,dc=com
       Suffix to create
                              : dc=west,dc=example,dc=com
       Database to create
                              : west
3 Profile name to create
                              : WestUserProfile
4 Default Server List
                              : 192.168.0.1
5 Preferred Server List
                              : one
6 Default Search Scope
7 Credential Level
                               : proxy
8 Authentication Method
                              : simple
9 Enable Follow Referrals
                               : FALSE
10 DSEE Time Limit
                               : -1
11 DSEE Size Limit
12 Enable crypt password storage : TRUE
13 Service Auth Method pam_ldap :
14 Service Auth Method keyserv
15 Service Auth Method passwd-cmd:
16 Search Time Limit : 30
17 Profile Time to Live
                              : 43200
18 Bind Limit
                              : 10
19 Enable shadow update
                             : TRUE
20 Service Search Descriptors Menu
Enter config value to change: (1-20 0=commit changes) [0]
Enter DN for proxy agent: [cn=proxyagent,ou=profile,dc=west,dc=example,dc=com]
Enter passwd for proxyagent:proxy-password
Re-enter passwd:proxy-password
Enter DN for the administrator: [cn=admin,ou=profile,dc=west,dc=example,dc=com]
```

Enter passwd for the administrator:admin-password

```
WARNING: About to start committing changes. (y=continue, n=EXIT) y
1. Changed timelimit to -1 in cn=config.
2. Changed sizelimit to -1 in cn=config.
3. Changed passwordstoragescheme to "crypt" in cn=config.
4. Schema attributes have been updated.
5. Schema objectclass definitions have been added.
6. Database west successfully created.
7. Suffix dc=west,dc=example,dc=com successfully created.
8. NisDomainObject added to dc=west,dc=example,dc=com.
9. Top level "ou" containers complete.
10. automount maps: auto home auto direct auto master auto shared processed.
11. ACI for dc=west,dc=example,dc=com modified to disable self modify.
12. Add of VLV Access Control Information (ACI).
13. Proxy Agent cn=proxyagent,ou=profile,dc=west,dc=example,dc=com added.
14. Administrator identity cn=admin,ou=profile,dc=west,dc=example,dc=com added.
15. Give cn=admin,ou=profile,dc=west,dc=example,dc=com read/write access to\
   shadow data.
16. Non-Admin access to shadow data denied.
17. Generated client profile and loaded on server.
18. Processing eq,pres indexes:
uidNumber (eq,pres) Finished indexing.
ipNetworkNumber (eq,pres) Finished indexing.
gidnumber (eq,pres) Finished indexing.
oncrpcnumber (eq,pres) Finished indexing.
automountKey (eq,pres) Finished indexing.
19. Processing eq,pres,sub indexes:
ipHostNumber (eq,pres,sub) Finished indexing.
membernisnetgroup (eq,pres,sub) Finished indexing.
nisnetgrouptriple (eq,pres,sub) Finished indexing.
20. Processing VLV indexes:
west.example.com.getgrent vlv index
                              Entry created
west.example.com.getspent vlv index
                              Entry created
west.example.com.getexecent vlv index
                                Entry created
west.example.com.getprofent vlv_index
                                Entry created
west.example.com.getmailent vlv index
                                Entry created
west.example.com.getbootent vlv index
                                Entry created
west.example.com.getethent vlv index
                               Entry created
west.example.com.getngrpent vlv index
                               Entry created
west.example.com.getipnent vlv_index
                               Entry created
west.example.com.getmaskent vlv_index
                                Entry created
```

Re-enter passwd:admin-password

For information about how to initialize an LDAP client to enable shadow update, see "Initializing an LDAP Client" on page 66. When you initialize an LDAP client, you must use the same DN and password for the administrator that you provided while building the DIT.

### **Defining Service Search Descriptors**

At Example, Inc., the previous LDAP configuration stored user information in the ou=Users container of the directory tree. In this Oracle Solaris release, user entries are assumed to be stored in the ou=People container. Therefore, if the passwd service is searched and the client searches the ou=People container, the information cannot be obtained.

To avoid the complications of re-creating the company's existing directory information tree and its impact on other operations, you can create SSDs instead. These SSDs would direct the LDAP client to look for user information in the ou=Users container instead of the default container.

For information about search descriptors, see "Service Search Descriptors and Schema Mapping" on page 35.

You use the idsconfig command to create SSDs. The prompt that refers to SSDs appears as follows:

```
Do you wish to setup Service Search Descriptors (y/n/h? y

A Add a Service Search Descriptor

D Delete a SSD

M Modify a SSD

P Display all SSD's

H Help

X Clear all SSD's

Q Exit menu

Enter menu choice: [Quit] a

Enter the service id: passwd

Enter the base: service ou=user,dc=west,dc=example,dc=com
```

```
Enter the scope: one[default]
A Add a Service Search Descriptor
D Delete a SSD
M Modify a SSD
P Display all SSD's
H Help
X Clear all SSD's
Q Exit menu
Enter menu choice: [Quit] p
Current Service Search Descriptors:
Passwd:ou=Users,ou=west,ou=example,ou=com?
Hit return to continue.
A Add a Service Search Descriptor
D Delete a SSD
M Modify a SSD
P Display all SSD's
H Help
X Clear all SSD's
Q Exit menu
Enter menu choice: [Quit] q
```

## Populating the LDAP Server With Data

After the DIT is created, you populate the information tree with data. The data is derived from all systems that contain /etc files. Therefore, you must perform this task on the systems rather than on the server. The manner of populating the information tree depends on the planning that was described in "Planning the LDAP Data Population" on page 35.

The information tree can be filled with the data from the following files:

- aliases
- auto \*
- bootparams
- ethers
- group
- hosts

Similarly, information from rights-related files in the /etc directory are also added to the information tree, such as user\_attr, ~/security/auth\_attr, ~/security/prof\_attr, and ~/security/exec attr.

To populate the information tree, you use the ldapaddent command and specify the /etc file or database whose data you are loading on the tree. You must load the files in the following sequence to obtain better performance:

- 1. passwd
- 2. shadow
- 3. networks
- 4. netmasks
- 5. bootparams
- 6. ethers

Ensure that when you are loading automounter information, the file or database name uses the naming format auto\_\*, such as auto\_home.

Before populating the directory server with data, you must configure the server to store passwords in UNIX Crypt format if you are using the pam\_unix\_\* modules. If you are using pam\_ldap, you can store passwords in any format. For more information about setting the password in UNIX crypt format, see the Oracle Directory Server Enterprise Edition documents.

For more information, see the ldapaddent(1M) man page. You must issue the command on every system that has the source /etc files with which you must populate the server.

Make sure that /etc files from different client systems are not merged into single files.

Populate the server with data from each file or database in /etc:

# ldapaddent -D "cn=directory manager" -f /etc/filename container

where *container* has the same name as *filename*, such as passwd.

## **Additional Directory Server Configuration Tasks**

After the DIT is created on the server and SSDs are defined as required, you can perform the additional tasks described in this section.

- "Specifying Group Memberships by Using the Member Attribute" on page 57
- "Populating the Directory Server With Additional Profiles" on page 58
- "Configuring the Directory Server to Enable Account Management" on page 58

# **Specifying Group Memberships by Using the Member Attribute**

The RFC draft rfc2307bis specifies that you can use the groupOfMembers object class as the convenient structural class for the LDAP entries of the group service. Group entries can then have member attribute values specifying group membership in distinguished names (DNs). Oracle Solaris LDAP clients support such group entries and use the member attribute values for group membership resolution.

Although the LDAP clients also support group entries that use the groupOfUniqueNames object class and the uniqueMember attribute, do not use this object class and attribute.

You can use the posixGroup object class and the memberUid attribute to define the LDAP clients support group entries. The ldapaddent command creates this type of group entries when populating the LDAP servers for the group services. It does not add the member attribute to the group entries.

To add group entries with the groupOfMembers object class and member attribute values, use the ldapadd tool and an input file similar to the following example:

dn: cn=group1,ou=group,dc=mkg,dc=example,dc=com
objectClass: posixGroup
objectClass: groupOfNames
objectClass: top
cn: group1
gidNumber: 1234
member: uid=user1,ou=people,dc=mkg,dc=example,dc=com
member: uid=user2,ou=people,dc=mkg,dc=example,dc=com
member: cn=group2,ou=group,dc=mkg,dc=example,dc=com

LDAP clients manage group entries with a mix of none, any, or all of the memberUid, member, and uniqueMember attributes. The membership evaluation results in a group that is the union of all three member attributes with duplicates removed. That is, if a group entry G has a memberUid value referring to user U1 and U2, a member value referring to user U2, and a uniqueMember value referring to user U3, then group G has three members, U1, U2, and U3. A member attribute can have values pointing to other groups, resulting in nested groups.

To efficiently evaluate group membership to determine the groups that a user is a member of, including the nested ones, you must configure and enable the memberOf plug-in on the LDAP servers. Otherwise, only the containing groups, not the nested ones, will be resolved. By default, the memberOf plug-in is enabled by the Oracle Directory Server Enterprise Edition server. If the memberOf plug-in is not enabled, use Oracle Directory Server Enterprise Edition dsconf tool to enable it.

# Populating the Directory Server With Additional Profiles

Use the ldapclient command with the genprofile option to create an LDAP Data Interchange Format (LDIF) representation of a configuration profile, based on the attributes specified. You can load the configuration profile into an LDAP server to use it as the client profile. A client can use the ldapclient init to download the client profile.

For more information, see the ldapclient(1M) man page.

### **▼** How to Populate the Directory Server With Additional Profiles

1. Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

Use the ldapclient command to populate the directory server with additional profiles.

```
# ldapclient gen-profile \
-a profileName=profile-name \
-a defaultSearchBase=dc=west,dc=example,dc=com \
-a "defaultServerList=xxx.xxx.xx yyy.yyy.y.y:portnum" \> myprofile.ldif
```

3. Upload the new profile to the server.

```
# ldapadd -h xxx.xxx.x.x -D "cn=directory-manager" -f profile-name.ldif
```

# **Configuring the Directory Server to Enable Account Management**

You can implement account management for clients that use pam\_ldap and pam\_unix\_\* modules.



**Caution -** Do not use both the pam\_ldap and pam\_unix\_\* modules in the same LDAP naming domain. Either all clients use pam\_ldap or all clients use the pam\_unix\_\* modules. This limitation might indicate that you need a dedicated LDAP server for using each module.

# **Enabling Account Management for Clients That Use the**pam ldap Module

In order for pam\_ldap to work properly, you must properly configure the password and account lockout policy on the server. You can use the Directory Server Console or the ldapmodify command to configure the account management policy for the LDAP directory. For procedures and more information, see the Oracle Directory Server Enterprise Edition administration guide (http://docs.oracle.com/cd/E29127 01/doc.111170/e28972/toc.htm).

**Note -** The control on the directory server is 1.3.6.1.4.1.42.2.27.9.5.8. This control is enabled by default. To modify the default control configuration, add ACIs on directory server. For example:

```
dn: oid=1.3.6.1.4.1.42.2.27.9.5.8,cn=features,cn=config
objectClass: top
objectClass: directoryServerFeature
oid:1.3.6.1.4.1.42.2.27.9.5.8
cn:Password Policy Account Usable Request Control
aci: (targetattr != "aci")(version 3.0; acl "Account Usable";
allow (read, search, compare, proxy)
(groupdn = "ldap:///cn=Administrators,cn=config");)
creatorsName: cn=server,cn=plugins,cn=config
modifiersName: cn=server,cn=plugins,cn=config
```

You must ensure that the passwords for proxy users do not expire. If proxy passwords expire, clients using the proxy credential level cannot retrieve naming service information from the server. To ensure that proxy users have passwords that do not expire, modify the proxy accounts with the following script.

```
# ldapmodify -h ldapserver -D administrator-DN \
-w administrator-password <<EOF
dn: proxy-user-DN
DNchangetype: modify
replace: passwordexpirationtime
passwordexpirationtime: 20380119031407Z
EOF
```

The pam\_ldap account management relies on Oracle Directory Server Enterprise Edition to maintain and provide password aging and account expiration information for users. The directory server does not interpret the corresponding data from shadow entries to validate user accounts. The pam\_unix\_\* modules, however, examine the shadow data to determine whether accounts are locked or passwords are aged. Because the shadow data is not kept up to date by the LDAP naming service or the directory server, the modules should not grant access based on the shadow data. The shadow data is retrieved using the proxy identity. Therefore, do not allow proxy users to have read access to the userPassword attribute. Denying proxy users read access to userPassword prevents the PAM service from making an invalid account validation.

# **Enabling Account Management for Clients That Use the**pam unix \* Modules

To enable LDAP clients to use the pam\_unix\_\* modules for account management, you must set up the server to enable the updating of shadow data. Unlike pam\_ldap account management, the pam\_unix\_\* modules do not require extra configuration steps. You can use the idsconfig command to configure the pam\_unix\_\* modules.

#### **EXAMPLE 4** Using an Existing Client Profile

The following example shows the output of the idsconfig command that uses an existing client profile.

```
# /usr/lib/ldap/idsconfig
It is strongly recommended that you BACKUP the directory server
before running idsconfig.
Hit Ctrl-C at any time before the final confirmation to exit.
Do you wish to continue with server setup (y/n/h)? [n] y
Enter the JES Directory Server's hostname to setup: myserver
Enter the port number for DSEE (h=help): [389]
Enter the directory manager DN: [cn=Directory Manager]
Enter passwd for cn=Directory Manager :
Enter the domainname to be served (h=help): [west.example.com]
Enter LDAP Base DN (h=help): [dc=west,dc=example,dc=com]
Checking LDAP Base DN ...
Validating LDAP Base DN and Suffix ...
sasl/GSSAPI is not supported by this LDAP server
Enter the profile name (h=help): [default] WestUserProfile
Profile 'WestUserProfile' already exists, it is possible to enable
shadow update now. idsconfig will exit after shadow update
is enabled. You can also continue to overwrite the profile
or create a new one and be given the chance to enable
shadow update later.
Just enable shadow update (y/n/h)? [n] y
Add the administrator identity (y/n/h)? [y]
Enter DN for the administrator: [cn=admin,ou=profile,dc=west,dc=example,dc=com]
Enter passwd for the administrator:
Re-enter passwd:
ADDED: Administrator identity cn=admin,ou=profile,dc=west,dc=example,dc=com.
Proxy ACI LDAP Naming Services proxy password read does not
exist for dc=west,dc=example,dc=com.
ACI SET: Give cn=admin,ou=profile,dc=west,dc=example,dc=com read/write access
```

```
to shadow data.
ACI SET: Non-Admin access to shadow data denied.
Shadow update has been enabled.
EXAMPLE 5
                Creating a New Profile
The following example shows the output of the idsconfig command that creates a new profile
for later use. Only relevant output is displayed.
# /usr/lib/ldap/idsconfig
It is strongly recommended that you BACKUP the directory server
before running idsconfig.
Hit Ctrl-C at any time before the final confirmation to exit.
Do you wish to continue with server setup (y/n/h)? [n] y
Enter the JES Directory Server's hostname to setup: myserver
Enter the port number for DSEE (h=help): [389]
Enter the directory manager DN: [cn=Directory Manager]
Enter passwd for cn=Directory Manager :
Enter the domainname to be served (h=help): [west.example.com]
Enter LDAP Base DN (h=help): [dc=west,dc=example,dc=com]
Checking LDAP Base DN ...
Validating LDAP Base DN and Suffix ...
sasl/GSSAPI is not supported by this LDAP server
Enter the profile name (h=help): [default] WestUserProfile-new
Default server list (h=help): [192.168.0.1]
Do you want to enable shadow update (y/n/h)? [n] y
              Summary of Configuration
1 Domain to serve
                                : west.example.com
2 Base DN to setup
                                : dc=west,dc=example,dc=com
                      : dc=west,dc=example,dc=com
Suffix to create
3 Profile name to create
                               : WestUserProfile-new
```

: TRUE

Enter DN for the administrator: [cn=admin,ou=profile,dc=west,dc=example,dc=com]

19 Enable shadow update

Re-enter passwd:

Enter passwd for the administrator:



## Setting Up LDAP Clients

This chapter describes how to set up an LDAP naming service client. It covers the following topics:

- "Requirements for LDAP Client Setup" on page 63
- "Defining LDAP Local Client Attributes" on page 65
- "Populating the LDAP Server With Data" on page 55
- "Initializing an LDAP Client" on page 66
- "Modifying an LDAP Client Configuration" on page 68
- "Uninitializing an LDAP Client" on page 68
- "Using LDAP for Client Authentication" on page 68

## **Requirements for LDAP Client Setup**

Oracle Solaris clients using LDAP as a naming service must meet the following requirements:

- The client's domain name must be provided by the LDAP server.
- The name service switch must point to LDAP for the required services.
- The client must be configured with all the parameters that define its behavior.
- ldap\_cachemgr must be running on the client.
- At least one server for which a client is configured must be running.

The ldapclient utility performs all of the listed configuration steps except for starting the server. This chapter provides examples of how to use the ldapclient utility to set up an LDAP client and how to use the various other LDAP utilities to get information about an LDAP client.

**Note -** Because LDAP and NIS use the same domain name component that is defined in the network/nis/domain service, Oracle Solaris does not support a configuration in which an NIS client and a native LDAP client coexist on the same client system.

## **LDAP** and the Service Management Facility

The Oracle Solaris SMF manages the LDAP client service. For more information about SMF, refer to *Managing System Services in Oracle Solaris 11.3*. For more information about the commands used to modify the SMF service, see the svcadm(1M) and svcs(1) man pages.

The features of SMF that relate to administering the LDAP client service are as follows:

■ The svcadm command is used to enable, disable, or restart the LDAP client service.

**Tip -** You can use the -t option to temporarily disable a service to provide protection for the service configuration. If the service is disabled with the -t option, the original settings are restored for the service after a reboot. If the service is disabled without -t, the service remains disabled after reboot.

- The Fault Management Resource Identifier (FMRI) for the LDAP client service is svc:/ network/ldap/client.
- The LDAP client configuration process enables the network/nis/domain service to supply the domain name to be used by the network/ldap/client service.
- Use the svcs command to query the status of the LDAP client and the ldap\_cachemgr daemon.
  - The following example shows the svcs command and its output.

# # svcs \\*ldap\\* STATE STIME FMRI

online 15:43:46 svc:/network/ldap/client:default

Use the -l option if you want to provide the instance name in the FMRI.

#### # svcs -l network/ldap/client:default

```
fmri
            svc:/network/ldap/client:default
name
            LDAP Name Service Client
enabled
            true
state
             online
next_state none
restarter
            svc:/system/svc/restarter:default
manifest
            /lib/svc/manifest/network/ldap/client.xml
manifest
            /lib/svc/manifest/network/network-location.xml
manifest
            /lib/svc/manifest/system/name-service/upgrade.xml
manifest
            /lib/svc/manifest/milestone/config.xml
dependency
            require_all/none svc:/system/filesystem/minimal (online)
dependency
            require_all/none svc:/network/initial (online)
dependency
            optional all/none svc:/network/location:default (online)
dependency
            require all/restart svc:/network/nis/domain (online)
```

```
dependency require all/none svc:/milestone/config (online)
```

You can check for a daemon's presence on either the client or a server:

Use the ptree command on a server.

```
# ptree `pgrep slapd`
6410 zsched
11565 /export/dsee/dsee6/ds6/lib/64/ns-slapd -D /export/dsee/test1 -i /export
```

Use the ldapsearch command on a client.

```
# ldapsearch -h server-name -b "" -s base "objectclass=*" |grep -i context
namingContexts: dc=example,dc=com
```

Configuration information specified in the LDAP client profiles is automatically imported into the SMF repository when the svc:/network/ldap/client service is started.

## **Defining LDAP Local Client Attributes**

You can define the attributes of the LDAP client profile to configure the LDAP server. For more information about the LDAP client profile attributes, see Chapter 3, "Planning Requirements for LDAP Naming Services". You use the idsconfig command to set up the client profile attributes on the server.

Use the ldapclient command to set up the following local client attributes:

- adminDN Specifies the administrator entry's distinguished name for the admin credential. If the value of the enableShadowUpdate switch is true on the client system and credentialLevel has a value other than self, then you must specify the adminDN attribute.
- adminPassword Specifies the administrator entry's password for the admin credential. If the value of the enableShadowUpdate switch is true on the client system and credentialLevel has a value other than self, then you must define the adminPassword attribute.
- domainName Specifies the client's domain name, which becomes the default domain for the client system. You must specify the value of the attribute as it has no default value.
- proxyDN Specifies the proxy's distinguished name. If the client system is configured with credentialLevel set to proxy, you must specify the proxyDN.
- proxyPassword Specifies the proxy's password. If the client system is configured with credentialLevel set to proxy, you must define the proxyPassword.
- certificatePath Specifies the directory on the local file system containing the certificate databases. You must use this attribute if a client system is configured with

authenticationMethod or serviceAuthenticationMethod using TLS. The default value is /var/ldap.

**Note -** If the BaseDN in an SSD contains a trailing comma, it is used as a relative value of the defaultSearchBase. The values of the defaultSearchBase are appended to the BaseDN before a search is performed.

## **Initializing an LDAP Client**

You can initialize the LDAP client with the ldapclient in one of two ways:

- Using a profile When you use the ldapclient command, you must specify the server
  address of the profile and the domain. If you do not specify a profile, the default profile is
  assumed. The server provides the rest of the required information from the profile except
  the proxy and certificate database information.
  - If a client's credential level is proxy or proxy anonymous, you must supply the proxy bind DN and password. For more information, see "Client Credential Levels" on page 17.
  - To enable shadow data update, you must provide the administrator's credentials (adminDN and the adminPassword).
  - Using a profile reduces the complexity of LDAP configuration, particularly in enterprise environments.
- Defining all the parameters in a single command line If profile does not exist, you can
  create the profile on the client itself. With this method, the profile information is stored in
  cache files and is never refreshed by the server.

You can use various options with the ldapclient command to initialize the client depending on the type of client and the client profile:

- Initializing a client by using a profile that is configured with default values. For example:
  - # ldapclient init -a profilename=new -a domainname=west.example.com 192.168.0.1
    System successfully configured
- Initialize a client whose profile is configured with per-user credentials and uses the sasl/ GSSAPI authentication method.

**Note** - Several requirements must be fulfilled when you initialize a client that is configured with per-user credentials, such as Kerberos configuration and DNS server configuration to work with LDAP. For information about Kerberos, see *Managing Kerberos and Other Authentication Services in Oracle Solaris 11.3*. For information about DNS configuration, see Chapter 3, "Managing DNS Server and Client Services" in *Working With Oracle Solaris 11.3 Directory and Naming Services: DNS and NIS*.

The example assumes that when you built the DIT with the idsconfig command, you specified the appropriate authentication method and credential level, such as self for the credential level and sasl/GSSAPI for the authentication method. The following output shows the how the idsconfig command is used to create per-user credentials.

#### # /usr/lib/ldap/idsconfig

```
Do you wish to continue with server setup (y/n/h)? [n] y
Enter the Directory Server's hostname to setup: kdc.example.com
Enter the port number for DSEE (h=help): [389] <Enter your port>
Enter the directory manager DN: [cn=Directory Manager] <Enter your DN>
Enter passwd for cn=Directory Manager: <Enter your password>
Enter the domainname to be served (h=help): [example.com] <Enter your domain>
Enter LDAP Base DN (h=help): [dc=example,dc=com] <Enter your DN>
GSSAPI is supported. Do you want to set up gssapi:(y/n) [n] y
Enter Kerberos Realm: [EXAMPLE.COM] EXAMPLE.COM
```

In this example the name of the profile is gssapi\_EXAMPLE.COM. After creating the profile, you can issue the ldapclient command to initialize the client with the per-user profile.

```
# ldapclient init -a profilename=gssapi_EXAMPLE.COM -a \
domainname=example.com 9.9.9.50
```

• Initializing a client that uses proxy credentials. For example:

```
# ldapclient init \
-a proxyDN=cn=proxyagent,ou=profile,dc=west,dc=example,dc=com \
-a domainname=west.example.com \
-a profilename=pit1 \
-a proxypassword=test1234 192.168.0.1
```

The -a proxyDN and -a proxyPassword options are required if the profile to be used is set up for proxy. Because the credentials are not stored in the profile saved on the server, you must supply the information when you initialize the client. This method is more secure than the older method of storing the proxy credentials on the server.

The proxy information is stored in the svc:/network/ldap/client service in the config and cred property groups.

• Initializing a client to enable the shadow data to be updated. For example:

```
# ldapclient init \
-a adminDN=cn=admin,ou=profile,dc=west,dc=example,dc=com \
-a adminPassword=admin-password \
-a domainName=west.example.com \
-a profileName=WestUserProfile \
-a proxyDN=cn=proxyagent,ou=profile,dc=west,dc=example,dc=com \
-a proxyPassword=proxy-password \
-a enableShadowUpdate=TRUE \
```

**192.168.0.1**System successfully configured

## **Modifying an LDAP Client Configuration**

You can use the ldapclient command without a profile to modify a client configuration. Because the modification affects only a limited number of client attributes, you can use the following commands to modify all the selected attributes.

- Modify an LDAP client to use simple authentication method. For example:
  - # ldapclient mod -a authenticationMethod=simple
- Modify a configured LDAP client to enable updating of shadow data. For example:
  - # ldapclient mod -a enableShadowUpdate=TRUE \
    -a adminDN=cn=admin,ou=profile,dc=west,dc=example,dc=com \
    -a adminPassword=admin-password
    System successfully configured

## **Uninitializing an LDAP Client**

Uninitializing an LDAP client means restoring the client name service to its status prior to the last time the ldapclient command was issued with the init, modify, or manual options. In other words, the -uninit option of the command cancels the last changes caused by the other options of the ldapclient command. For example, if the client was configured to use profile1 and was then changed to use profile2, using ldapclient uninit would cause the client to revert to using profile1.

You use the ldapclient command to uninitialize an LDAP client.

```
# ldapclient uninit
System successfully recovered.
```

## **Using LDAP for Client Authentication**

This section describes various configuration tasks that use LDAP authentication services.

## **Configuring PAM for LDAP**

The pam\_ldap module is a PAM module option for LDAP to authenticate clients and to perform account management. If you configured the client profile's authentication mode as simple and the credential level as self, you must also enable the pam krb module.

For more information, see:

- pam ldap(5) man page
- pam\_krb5(5) man page
- Managing Kerberos and Other Authentication Services in Oracle Solaris 11.3

The following example shows a sample pam.conf file using the pam\_ldap module for account management.

**EXAMPLE 6** Sample pam. conf File Using the pam ldap Module for Account Management

This example displays a sample pam. conf file.

```
# Authentication management
 # login service (explicit because of pam_dial auth)
  login auth requisite
                                                                                                              pam authtok get.so.1
  login auth required
                                                                                                             pam_dhkeys.so.1
 login auth required
login auth required
login auth binding
                                                                                                        pam_unix_cred.so.1
pam_dial_auth.so.1
pam_unix_auth.so.1 server_policy
  login auth required
                                                                                                                    pam_ldap.so.1
 # rlogin service (explicit because of pam_rhost_auth)
rlogin auth required
rlogin auth binding
rlogin auth required
rlogin auth required
rtogin auth sinding
rtogin auth required

the results of the required to th
                                                                                                                     pam_rhosts_auth.so.1
                                                                                                                     pam_authtok_get.so.1
                                                                                                                     pam_dhkeys.so.1
                                                                                                                     pam unix cred.so.1
                                                                                                                     pam_unix_auth.so.1 server_policy
                                                                                                                     pam ldap.so.1
 # rsh service (explicit because of pam rhost auth,
 # and pam_unix_auth for meaningful pam_setcred)
                              auth sufficient pam_rhosts_auth.so.1
auth required pam_unix_cred.so.1
auth binding pam_unix_auth.so.1 server_policy
  rsh
  rsh
  rsh
                                auth required
  rsh
                                                                                                               pam ldap.so.1
 # PPP service (explicit because of pam dial auth)
```

```
#
        auth requisite
                              pam_authtok_get.so.1
ppp
ppp
       auth required
                              pam dhkeys.so.1
       auth required
aga
                              pam dial auth.so.1
       auth binding
                              pam_unix_auth.so.1 server_policy
qqq
                              pam_ldap.so.1
       auth required
ppp
# Default definitions for Authentication management
# Used when service name is not explicitly mentioned for authentication
other
       auth requisite
                              pam_authtok_get.so.1
other
       auth required
                              pam dhkeys.so.1
other
       auth required
                              pam unix cred.so.1
       auth binding
                              pam unix auth.so.1 server policy
other
other
       auth required
                              pam ldap.so.1
# passwd command (explicit because of a different authentication module)
passwd auth binding
                              pam_passwd_auth.so.1 server_policy
passwd auth required
                              pam ldap.so.1
# cron service (explicit because of non-usage of pam_roles.so.1)
#
       account required
                              pam_unix_account.so.1
cron
# Default definition for Account management
# Used when service name is not explicitly mentioned for account management
other account requisite
                              pam_roles.so.1
other account binding
                              pam_unix_account.so.1 server_policy
other account required
                              pam_ldap.so.1
# Default definition for Session management
# Used when service name is not explicitly mentioned for session management
other session required
                              pam_unix_session.so.1
# Default definition for Password management
# Used when service name is not explicitly mentioned for password management
#
other
       password required
                              pam_dhkeys.so.1
       password requisite
                             pam_authtok_get.so.1
other
                              pam authtok check.so.1
other
       password requisite
other
       password required
                              pam_authtok_store.so.1 server_policy
# Support for Kerberos V5 authentication and example configurations can
# be found in the pam_krb5(5) man page under the "EXAMPLES" section.
```

### Configuring PAM to Use UNIX policy

The /etc/pam.conf file serves as the default configuration file for PAM to use UNIX policy. Typically, you do not need to introduce changes to this file. However, if you want to change the password aging and password policy that is controlled by the shadow data, you must configure the client to use the enableShadowUpdate switch. For an example of initializing an LDAP client to enable updating of shadow data, see "Initializing an LDAP Client" on page 66.

For more information about the PAM configuration file, see the pam.conf(4) man page.

### Configuring PAM to Use LDAP server\_policy

To configure the sample pam.conf file in Example 6, "Sample pam.conf File Using the pam\_ldap Module for Account Management," on page 69 to use LDAP server\_policy, perform the following additional steps:

- 1. Add the lines that contain pam ldap.so.1 to the client's /etc/pam.conf file.
- 2. If any PAM module in the sample file specifies the binding flag and the server\_policy option, use the same flag and option for the corresponding module in the client's /etc/pam.conf file.

Using the binding control flag allows a local password to override a remote (LDAP) password. For example, if a user account is found on both the local files and the LDAP namespace, the password associated with the local account takes precedence over the remote password. Thus, if the local password expires, authentication fails even if the remote LDAP password is still valid.

The server\_policy option instructs pam\_unix\_auth, pam\_unix\_account, and pam\_passwd\_auth to ignore a user found in the LDAP namespace and to allow pam\_ldap to perform authentication or account validation. In the case of pam\_authtok\_store, a new password is passed to the LDAP server without encryption. The password is then stored in the directory according to the password encryption scheme configured on the server. For more information, see the pam.conf(4) and pam\_ldap(5) man pages.

3. Add the server\_policy option to the line that contains the service module pam authtok store.so.1.

## **Setting Up TLS Security**

If you are using transport layer security (TLS), you must install the necessary PEM certificate files before using the ldapclient command. In particular, install the self-signed server certificate and CA certificate files that are used to validate the LDAP server and possibly client access to the server are required. For example, if you have the PEM CA certificate certdb.pem, you must ensure that this file is added and readable in the certificate path.

**Note -** The PEM certificate files must be readable by everyone. Do not encrypt or limit read permissions on these files. Otherwise, commands such as ldaplist fail to function.

For information about how to create and manage PEM format certificates, see <a href="http://docs.oracle.com/cd/E29127\_01/doc.111170/e28972/ds-security.htm#bcavb">http://docs.oracle.com/cd/E29127\_01/doc.111170/e28972/ds-security.htm#bcavb</a>. After configuration, PEM certificate files must be stored in the location expected by the LDAP naming service client. The certificatePath attribute determines this location, by default, which is in /var/ldap.

## ▼ How to Set Up TLS Security

- 1. Create the necessary PEM certificate file. For example, certdb.pem.
- 2. Copy that file to the default location.

For example:

# cp certdb.pem /var/ldap

3. Ensure that everyone can read the PEM certificate file.

# chmod 444 /var/ldap/certdb.pem

**Note -** More than one certificate file might reside in the certificate path. Additionally, any given PEM certificate file might contain multiple PEM format certificates that are concatenated together. Refer to your server documentation for further details. The certificate files must be stored on a local file system if you are using them for an LDAP naming service client.



# Troubleshooting LDAP Configurations

This chapter describes common LDAP configuration problems and suggests solutions for resolving them. It covers the following topics:

- "Displaying the LDAP Naming Service Information" on page 73
- "Monitoring LDAP Client Status" on page 75
- "LDAP Configuration Problems and Solutions" on page 77
- "Resolving Per-User Credentials Issues" on page 80

### **Displaying the LDAP Naming Service Information**

You can use the ldaplist utility to display information about LDAP naming service. This LDAP utility lists the naming information from the LDAP servers in LDIF format, which can be useful for troubleshooting. For more information, see the ldaplist(1) man page.

### **Displaying All LDAP Containers**

The ldaplist command displays its output with a blank line separating records, which is helpful for big multiline records.

The output of ldaplist depends upon the client configuration. For example, if the value of ns\_ldap\_search is sub rather than one, ldaplist lists all the entries under the current search baseDN.

The following example shows sample ldaplist output.

#### # ldaplist

dn: ou=people,dc=west,dc=example,dc=com
dn: ou=group,dc=west,dc=example,dc=com

dn: ou=rpc,dc=west,dc=example,dc=com

```
dn: ou=protocols,dc=west,dc=example,dc=com
dn: ou=networks,dc=west,dc=example,dc=com
dn: ou=netgroup,dc=west,dc=example,dc=com
dn: ou=aliases,dc=west,dc=example,dc=com
dn: ou=hosts,dc=west,dc=example,dc=com
dn: ou=services,dc=west,dc=example,dc=com
dn: ou=ethers,dc=west,dc=example,dc=com
dn: ou=profile,dc=west,dc=example,dc=com
dn: automountmap=auto_home,dc=west,dc=example,dc=com
dn: automountmap=auto_direct,dc=west,dc=example,dc=com
dn: automountmap=auto_shared,dc=west,dc=example,dc=com
dn: automountmap=auto_shared,dc=west,dc=example,dc=com
dn: automountmap=auto_shared,dc=west,dc=example,dc=com
```

## **Displaying All User Entry Attributes**

To list specific information such as a user's passwd entry, use the getent command. For example:

```
# getent passwd user1
user1::30641:10:Joe Q. User:/home/user1:/bin/csh
```

You also use the getent command to perform lookups on databases that are listed in the automount table, for example, getent automount/map [key]. In the following example, auto\_home is the name of the automount map and user1 is the search key. If you do not specify any search key, then the entire content of the specified automount map is listed.

```
# getent automount/auto_home user1
user1 server-name:/home/user1
```

To list all attributes, use ldaplist with the -l option.

```
# ldaplist -l passwd user1
dn: uid=user1,ou=People,dc=west,dc=example,dc=com
uid: user1
cn: user1
uidNumber: 30641
gidNumber: 10
gecos: Joe Q. User
```

homeDirectory: /home/user1
loginShell: /bin/csh
objectClass: top

objectClass: shadowAccount objectClass: account objectClass: posixAccount shadowLastChange: 6445

## **Monitoring LDAP Client Status**

This section describes commands that are used to determine the state of the LDAP client environment. For additional information about the command options, see the related man pages.

For information about Service Management Facility (SMF), refer to *Managing System Services in Oracle Solaris 11.3*. Also refer to the svcadm(1M) and svcs(1) man pages for more details.

### Verifying the Ldap\_cachemgr Daemon Status

The ldap\_cachemgr daemon must be online and functioning correctly at all times for the system to work. When you set up and start the LDAP client service, svc:/network/ldap/client, the client SMF method automatically starts the ldap\_cachemgr daemon.

To view the state of the service, use the svcs command.

To view all information about the service, use the -l option.

### # svcs -l network/ldap/client:default

```
fmri svc:/network/ldap/client:default
name LDAP Name Service Client
enabled false
state disabled
next_state none
state_time Thu Oct 20 23:04:11 2011
logfile /var/svc/log/network-ldap-client:default.log
restarter svc:/system/svc/restarter:default
contract_id
manifest /lib/svc/manifest/network/ldap/client.xml
manifest /lib/svc/manifest/milestone/config.xml
manifest /lib/svc/manifest/network/network-location.xml
manifest /lib/svc/manifest/system/name-service/upgrade.xml
```

```
dependency optional_all/none svc:/milestone/config (online)
dependency optional_all/none svc:/network/location:default (online)
dependency require_all/none svc:/system/filesystem/minimal (online)
dependency require_all/none svc:/network/initial (online)
dependency require_all/restart svc:/network/nis/domain (online)
dependency optional_all/none svc:/system/manifest-import (online)
dependency require_all/none svc:/milestone/unconfig (online)
dependency optional all/none svc:/system/name-service/upgrade (online)
```

■ To view more extensive status information, which is useful for diagnosing a problem, pass the -g option to ldap cachemgr.

```
# /usr/lib/ldap/ldap_cachemgr -g
cachemgr configuration:
server debug level
server log file "/var/ldap/cachemgr.log"
number of calls to ldapcachemgr
                                       19
cachemgr cache data statistics:
Configuration refresh information:
Previous refresh time: 2010/11/16 18:33:28
Next refresh time: 2010/11/16 18:43:28
Server information:
Previous refresh time: 2010/11/16 18:33:28
Next refresh time: 2010/11/16 18:36:08
server: 192.168.0.0. status: UP
server: 192.168.0.1, status: ERROR
error message: Can't connect to the LDAP server
Cache data information:
Maximum cache entries:
                               256
Number of cache entries:
```

If the ldap\_cachemgr daemon is disabled, use the svcadm enable network/ldap/client command to enable the daemon.

For more information about the ldap\_cachemgr daemon, see the ldap\_cachemgr(1M) man page.

# **Checking the Client Profile Information**

Become a superuser or assume an equivalent role, and use the ldapclient command with the list option to view the current profile information. In addition to the ldapclient list command, you can also use the svccfg or svcprop commands to obtain current profile information.

```
# ldapclient list
```

```
NS_LDAP_FILE_VERSION= 2.0

NS_LDAP_BINDDN= cn=proxyagent,ou=profile,dc=west,dc=example,dc=com

NS_LDAP_BINDPASSWD= {NS1}4a3788e8c053424f

NS_LDAP_SERVERS= 192.168.0.1, 192.168.0.10

NS_LDAP_SEARCH_BASEDN= dc=west,dc=example,dc=com

NS_LDAP_AUTH= simple

NS_LDAP_SEARCH_REF= TRUE

NS_LDAP_SEARCH_SCOPE= one

NS_LDAP_SEARCH_TIME= 30

NS_LDAP_SEARCH_TIME= 30

NS_LDAP_SERVER_PREF= 192.168.0.1

NS_LDAP_ROFILE= pit1

NS_LDAP_CREDENTIAL_LEVEL= proxy

NS_LDAP_SERVICE_SEARCH_DESC= passwd:ou=people,?sub

NS_LDAP_SERVICE_SEARCH_DESC= group:ou=group,dc=west,dc=example,dc=com?one

NS_LDAP_BIND_TIME= 5
```

### **Verifying Basic Client-Server Communication**

Use the ldaplist command to verify whether communication exists between the LDAP client and the LDAP server.

- To display all the containers of the DIT on the server, use the ldaplist command without options.
- To display the contents of the specific database, use the ldaplist *database* command, for example, ldaplist passwd *username* or ldaplist host *hostname*.

# **Checking LDAP Server Data From a Non-Client Machine**

To check for information on a system that has no existing LDAP client, use the ldapsearch command. The information that is displayed depends on the filter you use for searching. The following example lists all of the containers in the DIT:

```
# ldapsearch -h server1 -b "dc=west,dc=example,dc=com" -s one "objectclass=*"
```

For a list of options and filters that you can use with the ldapsearch command, see the ldapsearch(1) man page.

### **LDAP Configuration Problems and Solutions**

This section describes possible LDAP configuration problems and solutions.

### **Unresolved Host Name**

The LDAP client software returns fully qualified host names for host lookups, such as host names returned by gethostbyname() and getaddrinfo(). If the name stored is qualified, that is, if it contains at least one dot, the client returns the name as is. For example, if the name stored is hostB.eng, the returned name is hostB.eng.

If the name stored in the LDAP directory is not qualified, that is, it does not contain a dot, the client appends the domain part to the name. For example, if the name stored is hostA, the returned name is hostA. *domain-name*.

# Unable to Reach Systems in the LDAP Domain Remotely

If the DNS domain name is different from the LDAP domain name, then the LDAP naming service cannot be used to serve host names unless the host names are stored as fully qualified names.

### **Login Does Not Work**

LDAP clients use the PAM modules for user authentication during login. When using the standard UNIX PAM module, the password is read from the server and checked on the client side. This process can fail due to one of the following reasons:

- Idap is not associated with the passwd database in the name service switch.
- The proxy agent cannot read the user's userPassword attribute on the server list. You must enable at least the proxy agent to read the password because the proxy agent returns it to the client for comparison. pam ldap does not require read access to the password.
- The proxy agent might not have the correct password.
- The entry does not have the shadowAccount object class.
- No password is defined for the user.

When you use ldapaddent, you must use the -p option to ensure that the password is added to the user entry. If you use ldapaddent without the -p option, the user's password is not stored in the directory unless you also add the /etc/shadow file by using ldapaddent.

- No LDAP servers are reachable.
  - Check the status of the servers.
  - # /usr/lib/ldap/ldap\_cachemgr -g
- pam. conf is configured incorrectly.

- The user is not defined in the LDAP namespace.
- NS\_LDAP\_CREDENTIAL\_LEVEL is set to anonymous for the pam\_unix\_\* modules, and userPassword is not available to anonymous users.
- The password is not stored in crypt format.
- If pam\_ldap is configured to support account management, a login failure could be the result of one of the following causes:
  - The user's password has expired.
  - The user's account is locked out due to too many failed login attempts.
  - The user's account has been deactivated by the administrator.
  - The user tried to log in using a non-password based program, such as ssh or sftp.
- If you are using per-user authentication and sasl/GSSAPI, then some component of Kerberos or the pam\_krb5 configuration might be set up incorrectly. For more information about resolving Kerberos issues, see the *Managing Kerberos and Other Authentication* Services in Oracle Solaris 11.3.

### **Lookup Too Slow**

The LDAP database relies on indexes to improve search performance. You must index a common set of attributes that is included in the LDAP documentation provided by Oracle and other vendors. You can also add your own indexes to improve performance at your site.

### **Idapclient Command Cannot Bind to a Server**

The possible reasons for failure of the ldapclient command to initialize the client when using the init option with the profileName attribute are as follows:

- The incorrect domain name was specified on the command line.
- The nisDomain attribute is not set in the DIT to represent the entry point for the specified client domain.
- Access control information is not set up properly on the server, thus disabling anonymous search in the LDAP database.
- An incorrect server address was passed to the ldapclient command. Use the ldapsearch command to verify the server address.
- An incorrect profile name was passed to the ldapclient command. Use the ldapsearch command to verify the profile name in the DIT.

As a troubleshooting aid, use snoop on the client's network interface to see what sort of traffic is going out, and determine the server to which it is talking.

### Using the Idap\_cachemgr Daemon for Debugging

Running the ldap\_cachemgr daemon with the -g option to view the current client configuration and statistics can be useful for debugging.

This command displays current configuration and statistics to standard output, including the status of all LDAP servers. Note that you do *not* need to become superuser to execute this command.

### **Idapclient Command Hangs During Setup**

If the ldapclient command hangs, press Ctrl-C to exit after restoring the previous environment. In such an event, check with the server administrator to ensure that the server is running.

Also check the server list attributes either in the profile or from the command line and make sure that the server information is correct.

# **Resolving Per-User Credentials Issues**

Using per-user credentials requires configuration such as a Kerberos setup. Refer to the following issues when configuring per-user profiles.

### syslog File Indicates 82 Local Error

The syslog file might contain the following error message:

```
libsldap: Status: 7 Mesg: openConnection: GSSSAPI bind failed -82 Local error
```

Kerberos might not be initialized or its ticket is expired. Use the klist command to browse. Use either the kinit -p command or kinit -R command to reinitialize Kerberos.

### **Kerberos Not Initializing Automatically**

To enable the kinit command to run automatically whenever you log in, add pam\_krb5.so.1 to the /etc/pam.conf file. For example:

```
login auth optional pam_krb5.so.1
rlogin auth optional pam_krb5.so.1
```

other auth optional pam\_krb5.so.1

### syslog File Indicates Invalid Credentials

The syslog file might contain Invalid credential after you use the kinit command. This problem might occur due to one of the following reasons:

- The root host entry or the user entry is not in the LDAP directory.
- Mapping rules are incorrect.

# The Idapclient init Command Fails in the Switch Check

You can use the ldapclient init command to check the LDAP profile for the presence of the self/sasl/GSSAPI configuration. If the switch check fails, the error lies in DNS not being used as the search criteria for the host database. You can resolve this issue as follows:

Use the following commands to check the status of the DNS service and to enable it.

```
# svcs -l dns/client
# svcadm enable dns/client
```

If the failure is in the bind operation of sasl/GSSAPI, check the syslog file to determine the problem.

# · · · CHAPTER 7

### **LDAP Schemas**

This chapter describes LDAP schemas and the different types of schemas supported by Oracle Solaris. It covers the following topics:

- "IETF Schemas for LDAP" on page 83
- "Directory User Agent Profile (DUAProfile) Schema" on page 89
- "Oracle Solaris Schemas" on page 92
- "Internet Print Protocol Information for LDAP" on page 95

### **IETF Schemas for LDAP**

Schemas are definitions that describe what types of information can be stored as entries in a server's directory.

For a directory server to support LDAP naming clients, the schemas defined in this section must be configured in the server unless schema is mapped using the schema mapping feature of the clients.

IETF defines several LDAP schemas: the RFC 2307 Network Information Service (NIS) schema and RFC 2307bis, and a Configuration Profile Schema for LDAP-Based Agents (RFC 4876), and the LDAP Schema for Printer Services. To support NIS services, you must add the definition of these schemas to the directory server. You can access the RFCs on the IETF web site at http://www.ietf.org.

**Note -** Internet drafts, such as RFC 2307bis, are draft documents valid for a maximum of six months and might be updated, or rendered obsolete, by other documents at any time.

### **RFC 2307bis Network Information Service Schema**

You must configure the LDAP servers to support the revised RFC 2307bis schema.

The nisSchema OID is 1.3.6.1.1. The RFC 2307bis attributes are as follows:

```
( nisSchema.1.0 NAME 'uidNumber'
DESC 'An integer uniquely identifying a user in an
  administrative domain'
EQUALITY integerMatch SYNTAX 'INTEGER' SINGLE-VALUE )
( nisSchema.1.1 NAME 'gidNumber'
DESC 'An integer uniquely identifying a group in an
  administrative domain'
EQUALITY integerMatch SYNTAX 'INTEGER' SINGLE-VALUE )
( nisSchema.1.2 NAME 'gecos'
DESC 'The GECOS field; the common name'
EQUALITY caseIgnoreIA5Match
SUBSTRINGS caseIgnoreIA5SubstringsMatch
SYNTAX 'IA5String' SINGLE-VALUE )
( nisSchema.1.3 NAME 'homeDirectory'
DESC 'The absolute path to the home directory'
EQUALITY caseExactIA5Match
SYNTAX 'IA5String' SINGLE-VALUE )
( nisSchema.1.4 NAME 'loginShell'
DESC 'The path to the login shell'
EQUALITY caseExactIA5Match
SYNTAX 'IA5String' SINGLE-VALUE )
( nisSchema.1.5 NAME 'shadowLastChange'
EQUALITY integerMatch
SYNTAX 'INTEGER' SINGLE-VALUE )
( nisSchema.1.6 NAME 'shadowMin'
EQUALITY integerMatch
SYNTAX 'INTEGER' SINGLE-VALUE )
( nisSchema.1.7 NAME 'shadowMax'
EQUALITY integerMatch
SYNTAX 'INTEGER' SINGLE-VALUE )
( nisSchema.1.8 NAME 'shadowWarning'
EQUALITY integerMatch
SYNTAX 'INTEGER' SINGLE-VALUE )
( nisSchema.1.9 NAME 'shadowInactive'
EQUALITY integerMatch
SYNTAX 'INTEGER' SINGLE-VALUE )
( nisSchema.1.10 NAME 'shadowExpire'
EQUALITY integerMatch
SYNTAX 'INTEGER' SINGLE-VALUE )
```

```
( nisSchema.1.11 NAME 'shadowFlag'
EQUALITY integerMatch
SYNTAX 'INTEGER' SINGLE-VALUE )
( nisSchema.1.12 NAME 'memberUid'
EQUALITY caseExactIA5Match
{\tt SUBSTRINGS}\ case {\tt ExactIA5SubstringsMatch}
SYNTAX 'IA5String' )
( nisSchema.1.13 NAME 'memberNisNetgroup'
EQUALITY caseExactIA5Match
SUBSTRINGS caseExactIA5SubstringsMatch
SYNTAX 'IA5String' )
( nisSchema.1.14 NAME 'nisNetgroupTriple'
DESC 'Netgroup triple'
SYNTAX 'nisNetgroupTripleSyntax' )
( nisSchema.1.15 NAME 'ipServicePort'
EQUALITY integerMatch
SYNTAX 'INTEGER' SINGLE-VALUE )
( nisSchema.1.16 NAME 'ipServiceProtocol'
SUP name )
( nisSchema.1.17 NAME 'ipProtocolNumber'
EQUALITY integerMatch
SYNTAX 'INTEGER' SINGLE-VALUE )
( nisSchema.1.18 NAME 'oncRpcNumber'
EQUALITY integerMatch
SYNTAX 'INTEGER' SINGLE-VALUE )
( nisSchema.1.19 NAME 'ipHostNumber'
DESC 'IP address as a dotted decimal, eq. 192.168.1.1
      omitting leading zeros'
SUP name )
( nisSchema.1.20 NAME 'ipNetworkNumber'
DESC 'IP network as a dotted decimal, eg. 192.168,
      omitting leading zeros'
SUP name SINGLE-VALUE )
( nisSchema.1.21 NAME 'ipNetmaskNumber'
DESC 'IP netmask as a dotted decimal, eq. 255.255.255.0,
       omitting leading zeros'
EQUALITY caseIgnoreIA5Match
SYNTAX 'IA5String{128}' SINGLE-VALUE )
( nisSchema.1.22 NAME 'macAddress'
```

```
DESC 'MAC address in maximal, colon separated hex
      notation, eg. 00:00:92:90:ee:e2'
EQUALITY caseIgnoreIA5Match
SYNTAX 'IA5String{128}' )
( nisSchema.1.23 NAME 'bootParameter'
DESC 'rpc.bootparamd parameter'
SYNTAX 'bootParameterSyntax' )
( nisSchema.1.24 NAME 'bootFile'
DESC 'Boot image name'
EQUALITY caseExactIA5Match
SYNTAX 'IA5String' )
( nisSchema.1.26 NAME 'nisMapName'
SUP name )
( nisSchema.1.27 NAME 'nisMapEntry'
EQUALITY caseExactIA5Match
SUBSTRINGS caseExactIA5SubstringsMatch
SYNTAX 'IA5String{1024}' SINGLE-VALUE )
( nisSchema.1.28 NAME 'nisPublicKey'
DESC 'NIS public key'
SYNTAX 'nisPublicKeySyntax' )
( nisSchema.1.29 NAME 'nisSecretKey'
DESC 'NIS secret key'
SYNTAX 'nisSecretKeySyntax' )
( nisSchema.1.30 NAME 'nisDomain'
DESC 'NIS domain'
SYNTAX 'IA5String' )
( nisSchema.1.31 NAME 'automountMapName'
DESC 'automount Map Name'
EQUALITY caseExactIA5Match
SUBSTR caseExactIA5SubstringsMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.26 SINGLE-VALUE )
( nisSchema.1.32 NAME 'automountKey'
DESC 'Automount Key value'
EQUALITY caseExactIA5Match
SUBSTR caseExactIA5SubstringsMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.26 SINGLE-VALUE )
( nisSchema.1.33 NAME 'automountInformation'
DESC 'Automount information'
EQUALITY caseExactIA5Match
SUBSTR caseExactIA5SubstringsMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.26 SINGLE-VALUE )
```

The RFC 2307 objectClasses are as follows:

```
( nisSchema.2.0 NAME 'posixAccount' SUP top AUXILIARY
 DESC 'Abstraction of an account with POSIX attributes'
 MUST ( cn $ uid $ uidNumber $ gidNumber $ homeDirectory )
 MAY ( userPassword $ loginShell $ gecos $ description ) )
( nisSchema.2.1 NAME 'shadowAccount' SUP top AUXILIARY
 DESC 'Additional attributes for shadow passwords'
 MUST uid
 MAY ( userPassword $ shadowLastChange $ shadowMin
       shadowMax $ shadowWarning $ shadowInactive $
       shadowExpire $ shadowFlag $ description ) )
( nisSchema.2.2 NAME 'posixGroup' SUP top STRUCTURAL
 DESC 'Abstraction of a group of accounts'
 MUST ( cn $ gidNumber )
 MAY ( userPassword $ memberUid $ description ) )
( nisSchema.2.3 NAME 'ipService' SUP top STRUCTURAL
 DESC 'Abstraction an Internet Protocol service.
       Maps an IP port and protocol (such as tcp or udp)
       to one or more names; the distinguished value of
       the cn attribute denotes the service's canonical
       name'
 MUST ( cn $ ipServicePort $ ipServiceProtocol )
 MAY ( description ) )
( nisSchema.2.4 NAME 'ipProtocol' SUP top STRUCTURAL
 DESC 'Abstraction of an IP protocol. Maps a protocol number
       to one or more names. The distinguished value of the cn
       attribute denotes the protocol's canonical name'
 MUST ( cn $ ipProtocolNumber )
 MAY description )
( nisSchema.2.5 NAME 'oncRpc' SUP top STRUCTURAL
 DESC 'Abstraction of an Open Network Computing (ONC)
        [RFC1057] Remote Procedure Call (RPC) binding.
       This class maps an ONC RPC number to a name.
       The distinguished value of the cn attribute denotes
       the RPC service's canonical name'
 MUST ( cn $ oncRpcNumber $ description )
 MAY description )
( nisSchema.2.6 NAME 'ipHost' SUP top AUXILIARY
 DESC 'Abstraction of a host, an IP device. The distinguished
       value of the cn attribute denotes the host's canonical
       name. Device SHOULD be used as a structural class'
 MUST ( cn $ ipHostNumber )
 MAY ( l $ description $ manager $ userPassword ) )
```

```
( nisSchema.2.7 NAME 'ipNetwork' SUP top STRUCTURAL
 DESC 'Abstraction of a network. The distinguished value of
        the cn attribute denotes the network's canonical name'
 MUST ipNetworkNumber
 MAY ( cn $ ipNetmaskNumber $ l $ description $ manager ) )
( nisSchema.2.8 NAME 'nisNetgroup' SUP top STRUCTURAL
 DESC 'Abstraction of a netgroup. May refer to other netgroups'
 MUST cn
 MAY ( nisNetgroupTriple $ memberNisNetgroup $ description ) )
( nisSchema.2.9 NAME 'nisMap' SUP top STRUCTURAL
 DESC 'A generic abstraction of a NIS map'
 MUST nisMapName
 MAY description )
( nisSchema.2.10 NAME 'nisObject' SUP top STRUCTURAL
 DESC 'An entry in a NIS map'
 MUST ( cn $ nisMapEntry $ nisMapName )
 MAY description )
( nisSchema.2.11 NAME 'ieee802Device' SUP top AUXILIARY
 DESC 'A device with a MAC address; device SHOULD be
        used as a structural class'
 MAY macAddress )
( nisSchema.2.12 NAME 'bootableDevice' SUP top AUXILIARY
 DESC 'A device with boot parameters; device SHOULD be
 used as a structural class'
 MAY ( bootFile $ bootParameter ) )
( nisSchema.2.14 NAME 'nisKeyObject' SUP top AUXILIARY
 DESC 'An object with a public and secret key'
 MUST ( cn $ nisPublicKey $ nisSecretKey )
 MAY ( uidNumber $ description ) )
( nisSchema.2.15 NAME 'nisDomainObject' SUP top AUXILIARY
 DESC 'Associates a NIS domain with a naming context'
 MUST nisDomain )
( nisSchema.2.16 NAME 'automountMap' SUP top STRUCTURAL
 MUST ( automountMapName )
 MAY description )
( nisSchema.2.17 NAME 'automount' SUP top STRUCTURAL
 DESC 'Automount information'
 MUST ( automountKey $ automountInformation )
 MAY description )
( nisSchema.2.18 NAME 'groupOfMembers' SUP top STRUCTURAL
```

DESC 'A group with members (DNs)'

```
MUST cn
MAY ( businessCategory $ seeAlso $ owner $ ou $ o $
    description $ member ) )
```

### **Mail Alias Schema**

( 0.9.2342.19200300.100.1.3

Mail alias information uses the schema defined by the Internet draft.

The original LDAP mail groups schema contains a large number of attributes and object classes. LDAP clients uses only two attributes and a single object class. The mail alias attributes are as follows:

```
NAME 'mail'
DESC 'RFC822 email address for this person'
EQUALITY caseIgnoreIA5Match
SYNTAX 'IA5String(256)'
SINGLE-VALUE )

( 2.16.840.1.113730.3.1.30
NAME 'mgrpRFC822MailMember'
DESC 'RFC822 mail address of email only member of group'
EQUALITY CaseIgnoreIA5Match
SYNTAX 'IA5String(256)' )

The schema for the mailGroup object class is as follows:
( 2.16.840.1.113730.3.2.4
NAME 'mailGroup'
SUP top
```

```
2.16.840.1.113730.3.2.4
NAME 'mailGroup'
SUP top
STRUCTURAL
MUST mail
MAY ( cn $ mailAlternateAddress $ mailHost $ mailRequireAuth $
   mgrpAddHeader $ mgrpAllowedBroadcaster $ mgrpAllowedDomain $
   mgrpApprovePassword $ mgrpBroadcasterModeration $ mgrpDeliverTo $
   mgrpErrorsTo $ mgrpModerator $ mgrpMsgMaxSize $
   mgrpMsgRejectAction $ mgrpMsgRejectText $ mgrpNoMatchAddrs $
   mgrpRemoveHeader $ mgrpRFC822MailMember ))
```

# Directory User Agent Profile (DUAProfile) Schema

```
The DUAConfSchemaOID is 1.3.6.1.4.1.11.1.3.1.

( DESC 'Default LDAP server host address used by a DUA' EQUALITY caseIgnoreMatch SYNTAX 1.3.6.1.4.1.1466.115.121.1.15 SINGLE-VALUE )
```

```
( DUAConfSchemaOID.1.0 NAME 'defaultServerList'
 DESC 'Default LDAP server host address used by a DUAList'
 SYNTAX 1.3.6.1.4.1.1466.115.121.1.15
 SINGLE-VALUE )
( DUAConfSchemaOID.1.1 NAME 'defaultSearchBase'
 DESC 'Default LDAP base DN used by a DUA'
 EQUALITY distinguishedNameMatch
 SYNTAX 1.3.6.1.4.1.1466.115.121.1.12
 SINGLE-VALUE )
( DUAConfSchemaOID.1.2 NAME 'preferredServerList'
 DESC 'Preferred LDAP server host addresses to be used by a
 DUA'
 EQUALITY caseIgnoreMatch
 SYNTAX 1.3.6.1.4.1.1466.115.121.1.15
 SINGLE-VALUE )
( DUAConfSchemaOID.1.3 NAME 'searchTimeLimit'
 DESC 'Maximum time in seconds a DUA should allow for a
 search to complete'
 EQUALITY integerMatch
 SYNTAX 1.3.6.1.4.1.1466.115.121.1.27
 SINGLE-VALUE )
( DUAConfSchemaOID.1.4 NAME 'bindTimeLimit'
 DESC 'Maximum time in seconds a DUA should allow for the
 bind operation to complete'
 {\bf EQUALITY\ integer Match}
 SYNTAX 1.3.6.1.4.1.1466.115.121.1.27
 SINGLE-VALUE )
( DUAConfSchemaOID.1.5 NAME 'followReferrals'
 DESC 'Tells DUA if it should follow referrals
 returned by a DSA search result'
 EQUALITY caseIgnoreIA5Match
 SYNTAX 1.3.6.1.4.1.1466.115.121.1.7
 SINGLE-VALUE )
( DUAConfSchemaOID.1.6 NAME 'authenticationMethod'
 DESC 'A keystring which identifies the type of
 authentication method used to contact the DSA'
 EQUALITY caseIgnoreMatch
 SYNTAX 1.3.6.1.4.1.1466.115.121.1.15
 SINGLE-VALUE )
( DUAConfSchemaOID.1.7 NAME 'profileTTL'
 DESC 'Time to live before a client DUA
 should re-read this configuration profile'
 SYNTAX 1.3.6.1.4.1.1466.115.121.1.27
```

```
SINGLE-VALUE )
      ( DUAConfSchemaOID.1.9 NAME 'attributeMap'
        DESC 'Attribute mappings used by a DUA'
        EQUALITY caseIgnoreIA5Match
        SYNTAX 1.3.6.1.4.1.1466.115.121.1.26 )
      ( DUAConfSchemaOID.1.10 NAME 'credentialLevel'
        DESC 'Identifies type of credentials a DUA should
        use when binding to the LDAP server'
        EQUALITY caseIgnoreIA5Match
        SYNTAX 1.3.6.1.4.1.1466.115.121.1.26
        SINGLE-VALUE )
      ( DUAConfSchemaOID.1.11 NAME 'objectclassMap'
        DESC 'Objectclass mappings used by a DUA'
        EQUALITY caseIgnoreIA5Match
        SYNTAX 1.3.6.1.4.1.1466.115.121.1.26 )
      ( DUAConfSchemaOID.1.12 NAME 'defaultSearchScope'
        DESC 'Default search scope used by a DUA'
        SYNTAX 1.3.6.1.4.1.1466.115.121.1.15
        SINGLE-VALUE )
      ( DUAConfSchemaOID.1.13 NAME 'serviceCredentialLevel'
        DESC 'Identifies type of credentials a DUA
        should use when binding to the LDAP server for a
        specific service'
        EQUALITY caseIgnoreIA5Match
        SYNTAX 1.3.6.1.4.1.1466.115.121.1.26 )
      ( DUAConfSchemaOID.1.14 NAME 'serviceSearchDescriptor'
        DESC 'LDAP search descriptor list used by Naming-DUA'
        EQUALITY caseIgnoreMatch
        SYNTAX 1.3.6.1.4.1.1466.115.121.1.15 )
      ( DUAConfSchemaOID.1.15 NAME 'serviceAuthenticationMethod'
        DESC 'Authentication Method used by a service of the DUA'
        EOUALITY caseIgnoreMatch
        SYNTAX 1.3.6.1.4.1.1466.115.121.1.15 )
( DUAConfSchemaOID.2.4 NAME 'DUAConfigProfile'
SUP top STRUCTURAL
DESC 'Abstraction of a base configuration for a DUA'
MAY ( defaultServerList $ preferredServerList $
            defaultSearchBase $ defaultSearchScope $
            searchTimeLimit $ bindTimeLimit $
            credentialLevel $ authenticationMethod $
            followReferrals $ serviceSearchDescriptor $
            serviceCredentialLevel $ serviceAuthenticationMethod $
```

```
objectclassMap $ attributeMap $
profileTTL ) )
```

### **Oracle Solaris Schemas**

Oracle Solaris requires the following schemas:

- Projects schema
- Role-based access control and execution profile schemas
- Printer schemas

# **Projects Schema**

The /etc/project file is a local source of attributes associated with projects. For more information, see the user\_attr(4) man page.

The project attributes are as follows:

```
( 1.3.6.1.4.1.42.2.27.5.1.1 NAME 'SolarisProjectID'
  DESC 'Unique ID for a Solaris Project entry'
  EQUALITY integerMatch
  SYNTAX INTEGER SINGLE )
( 1.3.6.1.4.1.42.2.27.5.1.2 NAME 'SolarisProjectName'
  DESC 'Name of a Solaris Project entry'
  EQUALITY caseExactIA5Match
 SYNTAX IA5String SINGLE )
( 1.3.6.1.4.1.42.2.27.5.1.3 NAME 'SolarisProjectAttr'
 DESC 'Attributes of a Solaris Project entry'
  EQUALITY caseExactIA5Match
 SYNTAX IA5String )
( 1.3.6.1.4.1.42.2.27.5.1.30 NAME 'memberGid'
  DESC 'Posix Group Name'
  EQUALITY caseExactIA5Match
 SYNTAX 'IA5String' )
The Project objectClass is as follows:
( 1.3.6.1.4.1.42.2.27.5.2.1 NAME 'SolarisProject'
  SUP top STRUCTURAL
  MUST ( SolarisProjectID $ SolarisProjectName )
 MAY ( memberUid $ memberGid $ description $ SolarisProjectAttr ) )
```

# **Role-Based Access Control and Execution Profile Schema**

The /etc/user\_attr file is the local source of extended attributes associated with users and roles. For more information, see the user\_attr(4) man page.

You can add the SolarisQualifiedUserAttr object class to the existing Oracle Solaris RBAC schema. You can specify multiple values to the attributes of this class and thus enhance the current SolarisUserQualifier class. If you already have an existing LDAP configuration prior to the availability of the SolarisQualifiedUserAttr class, you can use the ldapadd command to add the class to the configuration.

The role-based access control attributes are as follows:

```
( 1.3.6.1.4.1.42.2.27.5.1.4 NAME 'SolarisAttrKeyValue'
 DESC 'Semi-colon separated key=value pairs of attributes'
 EQUALITY caseIgnoreIA5Match
 SUBSTRINGS caseIgnoreIA5Match
 SYNTAX 'IA5String' SINGLE-VALUE )
( 1.3.6.1.4.1.42.2.27.5.1.7 NAME 'SolarisAttrShortDesc'
 DESC 'Short description about an entry, used by GUIs'
 EQUALITY caseIgnoreIA5Match
 SYNTAX 'IA5String' SINGLE-VALUE )
( 1.3.6.1.4.1.42.2.27.5.1.8 NAME 'SolarisAttrLongDesc'
 DESC 'Detail description about an entry'
 EQUALITY caseIgnoreIA5Match
 SYNTAX 'IA5String' SINGLE-VALUE )
( 1.3.6.1.4.1.42.2.27.5.1.9 NAME 'SolarisKernelSecurityPolicy'
 DESC 'Solaris kernel security policy'
 EQUALITY caseIgnoreIA5Match
 SYNTAX 'IA5String' SINGLE-VALUE )
( 1.3.6.1.4.1.42.2.27.5.1.10 NAME 'SolarisProfileType'
 DESC 'Type of object defined in profile'
 EQUALITY caseIgnoreIA5Match
 SYNTAX 'IA5String' SINGLE-VALUE )
( 1.3.6.1.4.1.42.2.27.5.1.11 NAME 'SolarisProfileId'
 DESC 'Identifier of object defined in profile'
 EQUALITY caseExactIA5Match
 SYNTAX 'IA5String' SINGLE-VALUE )
( 1.3.6.1.4.1.42.2.27.5.1.12 NAME 'SolarisUserQualifier'
 DESC 'Per-user login attributes'
 EQUALITY caseIgnoreIA5Match
 SYNTAX 'IA5String' SINGLE-VALUE )
```

```
( 1.3.6.1.4.1.42.2.27.5.1.13 NAME 'SolarisReserved1'
  DESC 'Reserved for future use'
  EQUALITY caseIgnoreIA5Match
  SYNTAX 'IA5String' SINGLE-VALUE )
( 1.3.6.1.4.1.42.2.27.5.1.14 NAME 'SolarisReserved2'
  DESC 'Reserved for future use'
  EQUALITY caseIgnoreIA5Match
  SYNTAX 'IA5String' SINGLE-VALUE )
( 2.16.840.1.113894.1009.2.100.1.1 NAME 'SolarisUserAttrEntry'
  DESC 'user attr file format without username'
  EQUALITY caseExactIA5Match
  SYNTAX 'IA5String' )
( 2.16.840.1.113894.1009.2.100.1.2 NAME 'SolarisUserType'
  DESC 'specifies whether a normal user or a role'
  EQUALITY caseExactIA5Match
  SYNTAX 'IA5String' SINGLE-VALUE )
The role based access control objectClassses are as follows:
( 1.3.6.1.4.1.42.2.27.5.2.3 NAME 'SolarisUserAttr' SUP top AUXILIARY
  DESC 'User attributes'
  MAY ( SolarisUserQualifier $ SolarisAttrReserved1 $ \
        SolarisAttrReserved2 $ SolarisAttrKeyValue ) )
( 1.3.6.1.4.1.42.2.27.5.2.4 NAME 'SolarisAuthAttr' SUP top STRUCTURAL
  DESC 'Authorizations data'
  MUST cn
  MAY ( SolarisAttrReserved1 $ SolarisAttrReserved2 $ \
        SolarisAttrShortDesc $ SolarisAttrLongDesc $ \
        SolarisAttrKeyValue ) )
( 1.3.6.1.4.1.42.2.27.5.2.5 NAME 'SolarisProfAttr' SUP top STRUCTURAL
  DESC 'Profiles data'
  MUST cn
  MAY ( SolarisAttrReserved1 $ SolarisAttrReserved2 $ \
        SolarisAttrLongDesc $ SolarisAttrKeyValue ) )
( 1.3.6.1.4.1.42.2.27.5.2.6 NAME 'SolarisExecAttr' SUP top AUXILIARY
  DESC 'Profiles execution attributes'
  MAY ( SolarisKernelSecurityPolicy $ SolarisProfileType $ \
        SolarisAttrReserved1 $ SolarisAttrReserved2 $ \
        SolarisProfileId $ SolarisAttrKeyValue ) )
( 2.16.840.1.113894.1009.2.100.2.1 NAME 'SolarisQualifiedUserAttr'
  SUP top AUXILIARY
  DESC 'Host or netgroup qualified user attributes'
  MAY ( SolarisUserAttrEntry $ SolarisUserType ) )
```

### Internet Print Protocol Information for LDAP

This section provides information about the attributes and object classes for the internet print protocol and the printer.

### **Internet Print Protocol Attributes**

```
( 1.3.18.0.2.4.1140
NAME 'printer-uri'
DESC 'A URI supported by this printer.
This URI SHOULD be used as a relative distinguished name (RDN).
If printer-xri-supported is implemented, then this URI value
MUST be listed in a member value of printer-xri-supported.'
EQUALITY caseIgnoreMatch
{\tt ORDERING} \ \ case Ignore Ordering Match
SUBSTR caseIgnoreSubstringsMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15 SINGLE-VALUE )
( 1.3.18.0.2.4.1107
NAME 'printer-xri-supported'
DESC 'The unordered list of XRI (extended resource identifiers) supported
by this printer.
Each member of the list consists of a URI (uniform resource identifier)
followed by optional authentication and security metaparameters.'
EQUALITY caseIgnoreMatch
{\tt ORDERING}\ case Ignore Ordering Match
SUBSTR caseIgnoreSubstringsMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15 )
( 1.3.18.0.2.4.1135
NAME 'printer-name'
DESC 'The site-specific administrative name of this printer, more end-user
friendly than a URI.'
EQUALITY caseIgnoreMatch
ORDERING caseIgnoreOrderingMatch
SUBSTR caseIgnoreSubstringsMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{127} SINGLE-VALUE )
(1.3.18.0.2.4.1119
NAME 'printer-natural-language-configured'
DESC 'The configured language in which error and status messages will be
generated (by default) by this printer.
Also, a possible language for printer string attributes set by operator,
system administrator, or manufacturer.
Also, the (declared) language of the "printer-name", "printer-location",
"printer-info", and "printer-make-and-model" attributes of this printer.
For example: "en-us" (US English) or "fr-fr" (French in France) Legal values of
language tags conform to [RFC3066] "Tags for the Identification of Languages".'
```

```
EQUALITY caseIgnoreMatch
ORDERING caseIgnoreOrderingMatch
SUBSTR caseIgnoreSubstringsMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{127} SINGLE-VALUE )
( 1.3.18.0.2.4.1136
NAME 'printer-location'
DESC 'Identifies the location of the printer. This could include
things like: "in Room 123A", "second floor of building XYZ".'
EQUALITY caseIgnoreMatch
ORDERING caseIgnoreOrderingMatch
{\tt SUBSTR}\ case {\tt IgnoreSubstringsMatch}
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{127} SINGLE-VALUE )
( 1.3.18.0.2.4.1139
NAME 'printer-info'
DESC 'Identifies the descriptive information about this printer.
This could include things like: "This printer can be used for
printing color transparencies for HR presentations", or
"Out of courtesy for others, please print only small (1-5 page)
jobs at this printer", or even "This printer is going away on July 1, 1997,
please find a new printer".'
EQUALITY caseIgnoreMatch
ORDERING caseIgnoreOrderingMatch
SUBSTR caseIgnoreSubstringsMatch SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{127}
SINGLE-VALUE )
( 1.3.18.0.2.4.1134
NAME 'printer-more-info'
DESC 'A URI used to obtain more information about this specific printer.
For example, this could be an HTTP type URI referencing an HTML page
accessible to a Web Browser.
The information obtained from this URI is intended for end user consumption.'
{\tt EQUALITY} \ \ case Ignore {\tt Match} \ \ {\tt ORDERING} \ \ case Ignore {\tt Ordering Match}
SUBSTR caseIgnoreSubstringsMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15 SINGLE-VALUE )
( 1.3.18.0.2.4.1138
NAME 'printer-make-and-model'
DESC 'Identifies the make and model of the device.
The device manufacturer MAY initially populate this attribute.'
EQUALITY caseIgnoreMatch
ORDERING caseIgnoreOrderingMatch
SUBSTR caseIgnoreSubstringsMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{127} SINGLE-VALUE )
( 1.3.18.0.2.4.1133
NAME 'printer-ipp-versions-supported'
DESC 'Identifies the IPP protocol version(s) that this printer supports,
including major and minor versions,
i.e., the version numbers for which this Printer implementation meets
the conformance requirements.'
EQUALITY caseIgnoreMatch
```

```
ORDERING caseIgnoreOrderingMatch
SUBSTR caseIgnoreSubstringsMatch SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{127} )
( 1.3.18.0.2.4.1132
NAME 'printer-multiple-document-jobs-supported'
DESC 'Indicates whether or not the printer supports more than one
document per job, i.e., more than one Send-Document or Send-Data
operation with document data.'
FOUALTTY booleanMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.7 SINGLE-VALUE )
( 1.3.18.0.2.4.1109
NAME 'printer-charset-configured'
DESC 'The configured charset in which error and status messages will be
generated (by default) by this printer.
Also, a possible charset for printer string attributes set by operator,
system administrator, or manufacturer.
For example: "utf-8" (ISO 10646/Unicode) or "iso-8859-1" (Latin1).
Legal values are defined by the IANA Registry of Coded Character Sets and
the "(preferred MIME name)" SHALL be used as the tag.
For coherence with IPP Model, charset tags in this attribute SHALL be  \\
lowercase normalized.
This attribute SHOULD be static (time of registration) and SHOULD NOT be
dynamically refreshed attributetypes: (subsequently).'
EQUALITY caseIgnoreMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{63} SINGLE-VALUE )
( 1.3.18.0.2.4.1131
NAME 'printer-charset-supported'
DESC 'Identifies the set of charsets supported for attribute type values of
type Directory String for this directory entry.
For example: "utf-8" (ISO 10646/Unicode) or "iso-8859-1" (Latin1).
Legal values are defined by the IANA Registry of Coded Character Sets and
the preferred MIME name.'
EQUALITY caseIgnoreMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{63})
( 1.3.18.0.2.4.1137
NAME 'printer-generated-natural-language-supported'
DESC 'Identifies the natural language(s) supported for this directory entry.
For example: "en-us" (US English) or "fr-fr" (French in France).
Legal values conform to [RFC3066], Tags for the Identification of Languages.'
EQUALITY caseIgnoreMatch
ORDERING caseIgnoreOrderingMatch SUBSTR caseIgnoreSubstringsMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{63})
( 1.3.18.0.2.4.1130
NAME 'printer-document-format-supported'
DESC 'The possible document formats in which data may be interpreted
and printed by this printer.
Legal values are MIME types come from the IANA Registry of Internet Media Types.'
EQUALITY caseIgnoreMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{127} )
```

```
( 1.3.18.0.2.4.1129
NAME 'printer-color-supported'
DESC 'Indicates whether this printer is capable of any type of color printing
at all, including highlight color.'
EQUALITY booleanMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.7 SINGLE-VALUE )
( 1.3.18.0.2.4.1128
NAME 'printer-compression-supported'
DESC 'Compression algorithms supported by this printer.
For example: "deflate, gzip". Legal values include; "none", "deflate"
attributetypes: (public domain ZIP), "gzip" (GNU ZIP), "compress" (UNIX).'
EQUALITY caseIgnoreMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{255} )
( 1.3.18.0.2.4.1127
NAME 'printer-pages-per-minute'
DESC 'The nominal number of pages per minute which may be output by this
printer (e.g., a simplex or black-and-white printer).
This attribute is informative, NOT a service guarantee.
Typically, it is the value used in marketing literature to describe this printer.'
EQUALITY integerMatch
ORDERING integerOrderingMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.27 SINGLE-VALUE )
( 1.3.18.0.2.4.1126 NAME 'printer-pages-per-minute-color'
DESC 'The nominal number of color pages per minute which may be output by this
printer (e.g., a simplex or color printer).
This attribute is informative, NOT a service guarantee.
Typically, it is the value used in marketing literature to describe this printer.'
EQUALITY integerMatch
ORDERING integerOrderingMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.27 SINGLE-VALUE )
( 1.3.18.0.2.4.1125 NAME 'printer-finishings-supported'
DESC 'The possible finishing operations supported by this printer.
Legal values include; "none", "staple", "punch", "cover", "bind", "saddle-stitch",
"edge-stitch", "staple-top-left", "staple-bottom-left", "staple-top-right",
"staple-bottom-right", "edge-stitch-left", "edge-stitch-top", "edge-stitch-right",
"edge-stitch-bottom", "staple-dual-left", "staple-dual-top", "staple-dual-right",
"staple-dual-bottom".'
EQUALITY caseIgnoreMatch
SUBSTR caseIgnoreSubstringsMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{255} )
( 1.3.18.0.2.4.1124 NAME 'printer-number-up-supported'
DESC 'The possible numbers of print-stream pages to impose upon a single side of
an instance of a selected medium. Legal values include; 1, 2, and 4.
Implementations may support other values.'
EQUALITY integerMatch
ORDERING integerOrderingMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.27 )
```

```
( 1.3.18.0.2.4.1123 NAME 'printer-sides-supported'
DESC 'The number of impression sides (one or two) and the two-sided impression
rotations supported by this printer.
Legal values include; "one-sided", "two-sided-long-edge", "two-sided-short-edge".'
EQUALITY caseIgnoreMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{127} )
( 1.3.18.0.2.4.1122 NAME 'printer-media-supported'
DESC 'The standard names/types/sizes (and optional color suffixes) of the media
supported by this printer.
For example: "iso-a4", "envelope", or "na-letter-white".
Legal values conform to ISO 10175, Document Printing Application (DPA), and any
IANA registered extensions.'
EQUALITY caseIgnoreMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{255} )
( 1.3.18.0.2.4.1117 NAME 'printer-media-local-supported'
DESC 'Site-specific names of media supported by this printer, in the language in
"printer-natural-language-configured".
For example: "purchasing-form" (site-specific name) as opposed to
(in "printer-media-supported"): "na-letter" (standard keyword from ISO 10175).'
EQUALITY caseIgnoreMatch SUBSTR caseIgnoreSubstringsMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{255} )
( 1.3.18.0.2.4.1121 NAME 'printer-resolution-supported'
DESC 'List of resolutions supported for printing documents by this printer.
Each resolution value is a string with 3 fields:
1) Cross feed direction resolution (positive integer), 2) Feed direction
resolution (positive integer), 3) Resolution unit.
Legal values are "dpi" (dots per inch) and "dpcm" (dots per centimeter).
Each resolution field is delimited by ">". For example: "300> 300> dpi>"."
EQUALITY caseIgnoreMatch
SUBSTR caseIgnoreSubstringsMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{255} )
( 1.3.18.0.2.4.1120 NAME 'printer-print-quality-supported'
DESC 'List of print qualities supported for printing documents on this printer.
For example: "draft, normal". Legal values include; "unknown", "draft", "normal",
"high".'
EQUALITY caseIgnoreMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{127} )
( 1.3.18.0.2.4.1110 NAME 'printer-job-priority-supported'
DESC 'Indicates the number of job priority levels supported.
An IPP conformant printer which supports job priority must always support a
full range of priorities from "1" to "100"
(to ensure consistent behavior), therefore this attribute describes the
"granularity".
 Legal values of this attribute are from "1" to "100".'
EQUALITY integerMatch
ORDERING integerOrderingMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.27 SINGLE-VALUE )
```

```
( 1.3.18.0.2.4.1118
NAME 'printer-copies-supported'
DESC 'The maximum number of copies of a document that may be printed as a single job.
A value of "0" indicates no maximum limit.
A value of "-1" indicates unknown.
EQUALITY integerMatch
ORDERING integerOrderingMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.27 SINGLE-VALUE )
( 1.3.18.0.2.4.1111
NAME 'printer-job-k-octets-supported'
DESC 'The maximum size in kilobytes (1,024 octets actually) incoming print job that
this printer will accept.
A value of "0" indicates no maximum limit. A value of "-1" indicates unknown.'
EQUALITY integerMatch
ORDERING integerOrderingMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.27 SINGLE-VALUE )
( 1.3.18.0.2.4.1113
NAME 'printer-service-person'
DESC 'The name of the current human service person responsible for servicing this
printer.
It is suggested that this string include information that would enable other humans
to reach the service person, such as a phone number.'
EQUALITY caseIgnoreMatch
ORDERING caseIgnoreOrderingMatch
SUBSTR caseIgnoreSubstringsMatch SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{127}
SINGLE-VALUE )
( 1.3.18.0.2.4.1114
NAME 'printer-delivery-orientation-supported'
DESC 'The possible delivery orientations of pages as they are printed and ejected
from this printer.
Legal values include; "unknown", "face-up", and "face-down".'
EQUALITY caseIgnoreMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{127} )
( 1.3.18.0.2.4.1115
NAME 'printer-stacking-order-supported'
DESC 'The possible stacking order of pages as they are printed and ejected from
this printer.
Legal values include; "unknown", "first-to-last", "last-to-first".'
EQUALITY caseIgnoreMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{127} )
( 1.3.18.0.2.4.1116
NAME 'printer-output-features-supported'
DESC 'The possible output features supported by this printer.
Legal values include; "unknown", "bursting", "decollating", "page-collating",
"offset-stacking".'
EQUALITY caseIgnoreMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{127} )
```

```
( 1.3.18.0.2.4.1108
NAME 'printer-aliases'
DESC 'Site-specific administrative names of this printer in addition the printer
name specified for printer-name.'
EQUALITY caseIgnoreMatch
ORDERING caseIgnoreOrderingMatch
SUBSTR caseIgnoreSubstringsMatch
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15{127} )
( 1.3.6.1.4.1.42.2.27.5.1.63
NAME 'sun-printer-bsdaddr'
DESC 'Sets the server, print queue destination name and whether the client generates
protocol extensions.
"Solaris" specifies a Solaris print server extension. The value is represented b the
following value: server "," destination ", Solaris".'
SYNTAX '1.3.6.1.4.1.1466.115.121.1.15' SINGLE-VALUE )
( 1.3.6.1.4.1.42.2.27.5.1.64
NAME 'sun-printer-kvp'
DESC 'This attribute contains a set of key value pairs which may have meaning to the
print subsystem or may be user defined.
Each value is represented by the following: key "=" value.'
SYNTAX '1.3.6.1.4.1.1466.115.121.1.15' )
```

### Internet Print Protocol ObjectClasses

```
objectclasses: ( 1.3.18.0.2.6.2549
NAME 'slpService'
DESC 'DUMMY definition'
SUP 'top' MUST (objectclass) MAY ())
objectclasses: ( 1.3.18.0.2.6.254
NAME 'slpServicePrinter'
DESC 'Service Location Protocol (SLP) information.'
AUXILIARY SUP 'slpService')
objectclasses: ( 1.3.18.0.2.6.258
NAME 'printerAbstract'
DESC 'Printer related information.'
ABSTRACT SUP 'top' MAY ( printer-name
$ printer-natural-language-configured
$ printer-location
$ printer-info
$ printer-more-info
$ printer-make-and-model
$ printer-multiple-document-jobs-supported
$ printer-charset-configured
$ printer-charset-supported
$ printer-generated-natural-language-supported
$ printer-document-format-supported
```

```
$ printer-color-supported
$ printer-compression-supported
$ printer-pages-per-minute
$ printer-pages-per-minute-color
$ printer-finishings-supported
$ printer-number-up-supported
$ printer-sides-supported
$ printer-media-supported
$ printer-media-local-supported
$ printer-resolution-supported
$ printer-print-quality-supported
$ printer-job-priority-supported
$ printer-copies-supported
$ printer-job-k-octets-supported
$ printer-current-operator
$ printer-service-person
$ printer-delivery-orientation-supported
$ printer-stacking-order-supported $ printer! -output-features-supported ))
objectclasses: ( 1.3.18.0.2.6.255
NAME 'printerService'
DESC 'Printer information.'
STRUCTURAL SUP 'printerAbstract' MAY ( printer-uri
$ printer-xri-supported ))
objectclasses: ( 1.3.18.0.2.6.257
NAME 'printerServiceAuxClass'
DESC 'Printer information.'
AUXILIARY SUP 'printerAbstract' MAY ( printer-uri $ printer-xri-supported ))
objectclasses: ( 1.3.18.0.2.6.256
NAME 'printerIPP'
DESC 'Internet Printing Protocol (IPP) information.'
AUXILIARY SUP 'top' MAY ( printer-ipp-versions-supported $
printer-multiple-document-jobs-supported ))
objectclasses: ( 1.3.18.0.2.6.253
NAME 'printerLPR'
DESC 'LPR information.'
AUXILIARY SUP 'top' MUST ( printer-name ) MAY ( printer-aliases))
objectclasses: ( 1.3.6.1.4.1.42.2.27.5.2.14
NAME 'sunPrinter'
DESC 'Sun printer information'
SUP 'top' AUXILIARY MUST (objectclass $ printer-name) MAY
(sun-printer-bsdaddr $ sun-printer-kvp))
```

### **Printer Attributes**

```
ATTRIBUTE ( 1.3.6.1.4.1.42.2.27.5.1.63
```

```
NAME sun-printer-bsdaddr
DESC 'Sets the server, print queue destination name and whether the
     client generates protocol extensions. "Solaris" specifies a
     Solaris print server extension. The value is represented by
     the following value: server "," destination ", Solaris".'
EQUALITY caseIgnoreIA5Match
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15
SINGLE-VALUE
)
ATTRIBUTE ( 1.3.6.1.4.1.42.2.27.5.1.64
NAME sun-printer-kvp
DESC 'This attribute contains a set of key value pairs which may have
      meaning to the print subsystem or may be user defined. Each
      value is represented by the following: key "=" value.'
EQUALITY caseIgnoreIA5Match
SYNTAX 1.3.6.1.4.1.1466.115.121.1.15 )
```

# Sun Printer ObjectClasses

```
OBJECTCLASS ( 1.3.6.1.4.1.42.2.27.5.2.14

NAME sunPrinter

DESC 'Sun printer information'

SUP top

AUXILIARY

MUST ( printer-name )

MAY ( sun-printer-bsdaddr $ sun-printer-kvp ))
```



# Transitioning From NIS to LDAP

This chapter describes how to enable support of NIS clients that use naming information stored in the LDAP directory. By following the procedures in this chapter, you can transition from using an NIS naming service to using the LDAP naming service.

For information about the benefits of transitioning to LDAP, see "Overview of the LDAP Naming Service" on page 11.

This chapter covers the following topics:

- "About the NIS-to-LDAP Service" on page 105
- "Transitioning From NIS to LDAP Task Map" on page 109
- "Prerequisites for the NIS-to-LDAP Transition" on page 110
- "Setting Up the NIS-to-LDAP Service" on page 111
- "NIS-to-LDAP Best Practices With Oracle Directory Server Enterprise Edition" on page 117
- "NIS-to-LDAP Restrictions" on page 120
- "NIS-to-LDAP Troubleshooting" on page 120
- "Reverting to NIS" on page 125

### **About the NIS-to-LDAP Service**

The NIS-to-LDAP transition service ("N2L service") replaces existing NIS daemons on the NIS master server with NIS-to-LDAP transition daemons. The N2L service also creates an NIS-to-LDAP mapping file on the NIS server. The mapping file specifies the mapping between NIS map entries and equivalent Directory Information Tree (DIT) entries in LDAP. An NIS master server that has gone through this transition is known as an N2L server. The slave servers do not have an NISLDAPmapping file, so they continue to function in the usual manner. The slave servers periodically update their data from the N2L server as if it were a regular NIS master.

The behavior of the N2L service is controlled by the ypserv and NISLDAPmapping configuration files. The inityp2l script assists the server with the initial setup of these configuration files.

Once the N2L server has been established, you can edit the configuration file to maintain the N2L service.

The N2L service supports the following:

- Import of NIS maps into the LDAP DIT
- Client access to DIT information with the speed and extensibility of NIS

In the context of the N2L service, the term "map" is used in the following ways:

- To refer to a database file in which NIS stores a specific type of information
- To describe the process of mapping NIS information to or from the LDAP DIT

In any naming system, only one source of information can be the authoritative source. In traditional NIS, NIS sources are the authoritative information. When you use the N2L service, the source of authoritative data is the LDAP directory. The directory is managed by using directory management tools. For more information about directory management tools, see Chapter 1, "Introduction to the LDAP Naming Service".

NIS sources are retained for emergency backup or backout only. After you use the N2L service, you must phase out NIS clients. Eventually, all NIS clients should be replaced by LDAP naming service clients.

The Service Management Facility (SMF) manages the NIS and LDAP services. You can perform administrative actions on these services, such as enabling, disabling, or restarting, by using the svcadm command. You can query the status of services by using the svcs command. For more information about using SMF with LDAP and NIS, see "LDAP and the Service Management Facility" on page 64 and "NIS and the Service Management Facility" in *Working With Oracle Solaris 11.3 Directory and Naming Services: DNS and NIS.* For information about SMF, refer to *Managing System Services in Oracle Solaris 11.3*. Also refer to the svcadm(1M) and svcs(1) man pages for more details.

You need to be familiar with NIS and LDAP concepts, terminology, and IDs to perform the procedures in this chapter. For more information about the NIS and LDAP naming service, see the following sections:

- Chapter 5, "About the Network Information Service" in Working With Oracle Solaris 11.3
   Directory and Naming Services: DNS and NIS, for an overview of NIS
- Chapter 1, "Introduction to the LDAP Naming Service", for an overview of LDAP

Additional overview information is provided in the following sections:

- "When Not to Use the NIS-to-LDAP Service" on page 107
- "Effect of Installing the NIS-to-LDAP Service" on page 107
- "NIS-to-LDAP Commands, Files, and Maps" on page 108
- "Supported Standard Mappings" on page 108

### When Not to Use the NIS-to-LDAP Service

The intent of the N2L service is to serve as a transition tool from using NIS to using LDAP. Do not use the N2L service in the following situations:

- In an environment where you do not plan to share data between NIS and LDAP naming service clients
  - In such an environment, an N2L server would serve as an excessively complex NIS master server
- In an environment where NIS maps are managed by tools that modify the NIS source files (other than yppasswd)
  - Regeneration of NIS sources from DIT maps is an imprecise task that requires manual checking of the resulting maps. Once the N2L service is used, regeneration of NIS sources is provided only for backout or reverting to NIS.
- In an environment with no NIS clients
   In such an environment, use LDAP naming service clients and their corresponding tools.

### Effect of Installing the NIS-to-LDAP Service

Installing the files that are related to the N2L service does not change the NIS server's default behavior. While installing the N2L service, you may see some changes to the NIS man pages and the addition of N2L helper scripts, inityp2l and ypmap2src, on the servers. However, as long as inityp2l is not run or the N2L configuration files are not created manually on the NIS server, the NIS components continue to start in traditional NIS mode and function as usual.

After inityp21 is run, users see some changes in server and client behavior. The following table lists the NIS and LDAP user types and a description of what each type of user should notice after the N2L service is deployed.

User Type	Effect of N2L Service
NIS master server administrators	The NIS master server is converted to an N2L server. The NISLDAPmapping and ypserv configuration files are installed on the N2L server. After the N2L server is established, you can use LDAP commands to administer your naming information.
NIS slave server administrators	After the N2L transition, an NIS slave server continues to run NIS in the usual manner. The N2L server pushes updated NIS maps to the slave server when yppush is called by ypmake. For more information, see the ypmake(1M) man page.
NIS clients	NIS read operations are similar to traditional NIS. When an LDAP naming service client changes information in the DIT, the information is copied into the NIS maps. The copy operation is complete after a configurable timeout expires. This behavior is similar to the behavior of a normal NIS client when the client is connected to an NIS slave server.
	If an N2L server cannot bind to the LDAP server for a read, the N2L server returns the information from its own cached copy. Alternatively, the N2L server can return

User Type	Effect of N2L Service
	an internal server error. You can configure the N2L server to respond either way. For more information, see the ypserv(1M) man page.
All users	When an NIS client makes a password change request, the change is immediately visible on the N2L master server and to native LDAP clients.
	If you attempt to change a password on the NIS client and the LDAP server is unavailable, then the change is refused and the N2L server returns an internal server error. This behavior prevents incorrect information from being written into the cache.

### **NIS-to-LDAP Commands, Files, and Maps**

This section describes the utilities, configuration files, and mapping associated with the N2L transition.

The N2L transition uses the following utilities:

- /usr/lib/netsvc/yp/inityp2l Assists with the creation of the NISLDAPmapping and ypserv configuration files but not the management of these files. If you are familiar with the technologies, you can maintain the N2L configuration files or create custom mappings by using a text editor to examine and customize the inityp2l output. For more information, see the inityp2l(1M) man page.
- /usr/lib/netsvc/yp/ypmap2src Converts standard NIS maps to approximations of the equivalent NIS source files. You can use the ypmap2src utility to convert from an N2L transition server to traditional NIS. For more information, see the ypmap2src(1M) man page.

The N2L service uses the following files to transition from NIS to LDAP:

- /var/yp/NISLDAPmapping Specifies the mapping between NIS map entries and equivalent
   DIT entries in LDAP. See the NISLDAPmapping(4) man page.
- /var/yp/ypserv Specifies configuration information for the NIS-to-LDAP transition daemons. For more information, see the ypserv(4) man page.

When the NIS-to-LDAP transition is implemented, the yppasswdd command uses the ageing. byname mapping to read and write password aging information to the DIT.

# **Supported Standard Mappings**

By default, the N2L service supports mappings between its standard maps and LDAP entries based on RFC 2307, RFC 2307bis, and later standards. Standard maps do not require manual modification of the mapping file. Any maps on your system that are not standard N2L service maps are considered custom maps and require manual modification.

The N2L service also supports automatic mapping of the auto.\* maps. However, because most auto.\* file names and contents are specific to each network configuration, those files are not specified in the list of standard maps. The exceptions are the auto.home and auto.master maps, which are supported as standard maps.

The N2L service supports the following standard maps:

```
audit user
auth attr
auto.home
auto.master
bootparams
ethers.byaddr ethers.byname
exec_attr
group.bygid group.byname group.adjunct.byname
hosts.byaddr hosts.byname
ipnodes.byaddr ipnodes.byname
mail.byaddr mail.aliases
netgroup netgroup.byprojid netgroup.byuser netgroup.byhost
netid.byname
netmasks.byaddr
networks.byaddr networks.byname
passwd.byname passwd.byuid passwd.adjunct.byname
prof attr
project.byname project.byprojectid
protocols.byname protocols.bynumber
publickey.byname
rpc.bynumber
services.byname services.byservicename
timezone.byname
user_attr
```

During the NIS-to-LDAP transition, the yppasswdd daemon uses the ageing.byname map to read and write password aging information to the DIT. If you are not using password aging, then the ageing.byname mapping is ignored.

# **Transitioning From NIS to LDAP Task Map**

The following table identifies the procedures needed to install and manage the N2L service with standard and custom NIS-to-LDAP mappings.

Task	Description	For Instructions
Complete all prerequisites.	Be sure that you have properly configured your NIS server and Oracle Directory Server Enterprise Edition (LDAP server).	"Prerequisites for the NIS-to-LDAP Transition" on page 110

Task	Description	For Instructions
Set up the N2L service.	Uses the inityp2l command on the NIS master server to set up either standard mappings or custom or nonstandard mappings.	"How to Set Up the N2L Service With Standard Mappings" on page 112 "How to Set Up the N2L Service With Custom or Nonstandard Mappings" on page 113
Customize a map.	Displays examples of custom maps for the N2L transition.	"Examples of Custom Maps" on page 115
Configure Oracle Directory Server Enterprise Edition with N2L.	Configures Oracle Directory Server Enterprise Edition as your LDAP server for the N2L transition.	"NIS-to-LDAP Best Practices With Oracle Directory Server Enterprise Edition" on page 117
Troubleshoot the system.	Identifies and resolves common N2L issues.	"NIS-to-LDAP Troubleshooting" on page 120
Revert to NIS.	Revert to NIS using the appropriate map:	
	Maps based on NIS source files	"How to Revert to Maps Based on NIS Source Files" on page 126
	Maps based on the DIT	"How to Revert to Maps Based on DIT Contents" on page 126

# **Prerequisites for the NIS-to-LDAP Transition**

Before implementing the N2L service, you must ensure the following items:

- Make sure that the system is set up as a working traditional NIS server before running the inityp2l script to enable N2L mode.
- Configure the LDAP directory server on your system.

The NIS-to-LDAP migration tools support Oracle Directory Server Enterprise Edition and compatible versions of directory servers offered by Oracle. If you use Oracle Directory Server Enterprise Edition, use the idsconfig command to configure the server *before* you set up the N2L service. For more information about the idsconfig command, see Chapter 4, "Setting Up the Oracle Directory Server Enterprise Edition With LDAP Clients" and the idsconfig(1M) man page.

Although other third-party LDAP servers might work with the N2L service, they are not supported by Oracle. If you are using an LDAP server other than Oracle Directory Server Enterprise Edition or compatible Oracle servers, you must manually configure the server to support the schemas of RFC 2307bis, RFC 4876, or later standards *before* you set up the N2L service.

- Use files before dns for the config/host property.
- Ensure that the addresses of the N2L master server and the LDAP server are present in the hosts file on the N2L master server.

An alternative solution is to list the LDAP server address in ypserv, rather than its host name. Because the LDAP server address is listed in another place, changing the address of either the LDAP server or the N2L master server requires additional file modifications.

# **Setting Up the NIS-to-LDAP Service**

You can use the standard mappings or custom mappings to set up the N2L service, as described in the procedures in this section.

As part of the NIS-to -LDAP conversion, you need to run the inityp21 command. This command runs an interactive script for which you must provide configuration information. For more information about the types of information you need to provide for configuration, see the ypserv(1M) man page. This information typically includes:

- The name of the configuration file being created. The default configuration file is /etc/default/ypserv.
- The DN that stores configuration information in LDAP. The default value is ypserv.
- Preferred server list for mapping data to LDAP.
- Preferred server list for mapping data from LDAP.
- Authentication method for mapping data to LDAP.
- Authentication method for mapping data from LDAP.
- TLS method for mapping data to LDAP.
- TLS method for mapping data from LDAP.
- Proxy user bind DN to read or write data from LDAP.
- Proxy user bind DN to read or write data to LDAP.
- Proxy user password to read or write data from LDAP.
- Proxy user password to read or write data to LDAP.
- Timeout value (in seconds) for an LDAP bind operation.
- Timeout value (in seconds) for an LDAP search operation.
- Timeout value (in seconds) for an LDAP modify operation.
- Timeout value (in seconds) for an LDAP add operation.
- Timeout value (in seconds) for an LDAP delete operation.
- Time limit (in seconds) for search operation on the LDAP server.
- Size limit (in bytes) for search operation on the LDAP server.
- Whether N2L should follow LDAP referrals.
- LDAP retrieval error action, number of retrieval attempts, and timeout (in seconds) between each attempt.
- Store error action, number of attempts, and timeout (in seconds) between each attempt.
- Mapping file name.

- Whether to generate mapping information for auto\_direct map.
  - The script places relevant information regarding custom maps at appropriate places in the mapping file.
- The naming context.
- Whether to enable password changes.
- Whether to change the default TTL values for any map.

**Note -** Most LDAP servers, including the Oracle Directory Server Enterprise Edition do not support sasl/cram-md5 authentication. .

# ▼ How to Set Up the N2L Service With Standard Mappings

Use this procedure if you are transitioning the maps listed in "Supported Standard Mappings" on page 108. If you are using custom or nonstandard maps, see "How to Set Up the N2L Service With Custom or Nonstandard Mappings" on page 113.

Before You Begin

Complete the prerequisite steps that are listed in "Prerequisites for the NIS-to-LDAP Transition" on page 110.

1. Become an administrator on the NIS master server.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

2. Convert the NIS master server into an N2L server.

### # inityp2l

Run the inityp2l script on the NIS master server and follow the prompts. inityp2l sets up the configuration and mapping files for standard and auto.\* maps. For information about the list of the information you need to provide, see "Setting Up the NIS-to-LDAP Service" on page 111.

## Determine whether the LDAP DIT is fully initialized for the transition from the NIS source files.

The DIT is fully initialized if it already contains the information necessary to populate all the maps that are listed in the NISLDAPmapping file.

- If the LDAP DIT is fully initialized, initialize the NIS maps.
  - 1. Stop the NIS service.

# svcadm disable network/nis/server:default

2. Initialize the NIS maps from information in the DIT.

```
# ypserv -r
```

Wait for ypserv to exit.

- If the LDAP DIT is not fully initialized, initialize it.
  - 1. Make sure the NIS maps are up to date.

```
# cd /var/yp
# make
```

For more information, see the ypmake(1M) man page.

2. Stop the NIS service.

```
# svcadm disable network/nis/server:default
```

3. Copy the NIS maps to the DIT and then initialize N2L support for the maps.

```
# ypserv -Ir
```

Wait for ypserv to exit.

4. Start the DNS and NIS services to ensure that they use the new maps.

```
# svcadm enable network/dns/client:default
# svcadm enable network/nis/server:default
```

# ▼ How to Set Up the N2L Service With Custom or Nonstandard Mappings

Use this procedure if the following circumstances apply:

- The maps you want to use are not listed in "Supported Standard Mappings" on page 108.
- Standard NIS maps need to be mapped to non-RFC 2307 LDAP mappings.

Before You Begin

Complete the prerequisite steps that are listed in "Prerequisites for the NIS-to-LDAP Transition" on page 110.

1. Become an administrator on the NIS master server.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

2. Configure the NIS master server into the N2L server.

```
# inityp2l
```

Run the inityp2l script on the NIS master server and follow the prompts. For the list of the information that you need to provide, see "Setting Up the NIS-to-LDAP Service" on page 111.

## 3. Modify the /var/yp/NISLDAPmapping file.

For examples of how to modify the mapping file, see "Examples of Custom Maps" on page 115.

## 4. Determine whether the LDAP DIT is fully initialized.

The DIT is fully initialized if it already contains the information necessary to populate all the maps that are listed in the NISLDAPmapping file. If the DIT is fully initialized, skip Step 5.

- 5. Initialize the DIT for the transition from the NIS source files.
  - a. Make sure that the old NIS maps are up-to-date.

```
# cd /var/yp
# make
```

For more information, see the ypmake(1M) man page.

b. Stop the NIS daemons.

```
# svcadm disable network/nis/server:default
```

c. Copy the NIS maps to the DIT, then initialize N2L support for the maps.

```
# ypserv -Ir
```

Wait for ypserv to exit.

**Tip** - The original NIS dbm files are not overwritten. You can recover these files if needed.

d. Start the DNS and NIS service to ensure that they use the new maps.

```
# svcadm enable network/dns/client:default
# svcadm enable network/nis/server:default
```

- e. Skip Step 6 and continue with Step 7.
- 6. Initialize the NIS maps.

Perform this step only if the DIT is fully initialized.

a. Stop the NIS daemons.

# svcadm disable network/nis/server:default

## b. Initialize the NIS maps from information in the DIT.

```
# ypserv -r
```

Wait for ypserv to exit.

**Tip** - The original NIS dbm files are not overwritten. You can recover these files if needed.

## c. Start the DNS and NIS service to ensure that they use the new maps.

```
# svcadm enable network/dns/client:default
# svcadm enable network/nis/server:default
```

## Verify whether the LDAP entries are correct.

If the entries are incorrect, then the entries cannot be found by LDAP naming service clients.

```
# ldapsearch -h server -s sub -b "ou=servdates, dc=..." \ "objectclass=servDates"
```

## Verify the contents of the LDAP maps.

The following sample output shows how to use the makedm command to verify the contents of the hosts.byaddr map.

### # makedbm -u LDAP servdate.bynumber

plato: 1/3/2001

johnson: 2/4/2003,1/3/2001

yeats: 4/4/2002 poe: 3/3/2002,3/4/2000

If the contents are as expected, the transition from NIS to LDAP was successful.

## **Examples of Custom Maps**

Examples in this section show how you might customize maps. Use your preferred text editor to modify the /var/yp/NISLDAPmapping file as needed. For more information about file attributes and syntax, see the NISLDAPmapping(4) man page. For more information about the LDAP naming service, see Chapter 1, "Introduction to the LDAP Naming Service".

## **EXAMPLE 7** Moving Host Entries

This example shows how to move host entries from the default location to another location in the DIT by changing the nisLDAPobjectDN attribute in the NISLDAPmapping file to the new base

LDAP distinguished name (DN). For this example, the internal structure of the LDAP objects is unchanged, so objectClass entries are also unchanged..

#### Change:

```
nisLDAPobjectDN hosts: \
ou=hosts,?one?, \
objectClass=device, \
objectClass=ipHost

to:
nisLDAPobjectDN hosts: \
ou=newHosts,?one?, \
objectClass=device, \
objectClass=ipHost
```

This change causes entries to be mapped under dn: ou=newHosts, dom=domain1, dc=sun, dc=com, instead of dn: ou=hosts, dom=domain1, dc=sun, dc=com.

### **EXAMPLE 8** Implementing a Custom Map

This example shows how to implement a custom map.

In this example the servdate.bynumber map contains information about the servicing dates for systems. This map is indexed by the system's serial number, which in this example is 123. Each entry consists of the system owner's name, a colon, and a comma-separated list of service dates, such as John Smith:1/3/2001,4/5/2003.

The old map structure is to be mapped onto LDAP entries of the following form:

```
dn: number=123,ou=servdates,dc=... \
number: 123 \
userName: John Smith \
date: 1/3/2001 \
date: 4/5/2003 \
.
.
.
objectClass: servDates
```

By examining the NISLDAPmapping file, you can see that the mapping closest to the required pattern is group. The custom mappings can be modeled on the group mapping. Because there is only one map, no nisLDAPdatabaseIdMapping attribute is required. The attributes to be added to NISLDAPmapping are as follows:

```
nisLDAPentryTtl servdate.bynumber:1800:5400:3600
```

```
nisLDAPnameFields servdate.bynumber: \
("%s:%s", uname, dates)

nisLDAPobjectDN servdate.bynumber: \
ou=servdates, ?one? \
objectClass=servDates:

nisLDAPattributeFromField servdate.bynumber: \
dn=("number=%s,", rf_key), \
number=rf_key, \
userName=uname, \
(date)=(dates, ",")

nisLDAPfieldFromAttribute servdate.bynumber: \
rf_key=number, \
uname=userName, \
dates=("%s,", (date), ",")
```

# NIS-to-LDAP Best Practices With Oracle Directory Server Enterprise Edition

The N2L service supports Oracle Directory Server Enterprise Edition. Although other third-party LDAP servers might work with the N2L service, they are not supported by Oracle. If you are using an LDAP server other than an Oracle Directory Server Enterprise Edition server or compatible Oracle servers, you must manually configure the server to support the schemas of RFC 2307, RFC 2307bis and RFC 4876, or later standards.

If you are using Oracle Directory Server Enterprise Edition, you can enhance the directory server to improve performance. To make these enhancements, you must have LDAP administrator privileges on the Oracle Directory Server Enterprise Edition server. In addition, you must coordinate with the LDAP clients if the directory server need to be rebooted. The Oracle Directory Server Enterprise Edition documentation is available at Oracle Directory Server Enterprise Edition documentation.

# Creating Virtual List View Indexes With Oracle Directory Server Enterprise Edition

For large maps, you must use the LDAP virtual list view (VLV) indexes to ensure that LDAP searches return complete results. For information about setting up VLV indexes on Oracle Directory Server Enterprise Edition, see the Oracle Directory Server Enterprise Edition documentation.

VLV search results use a fixed page size of 50000. If you are using VLVs with Oracle Directory Server Enterprise Edition, ensure that both the LDAP server and N2L server are able to handle transfers of this size. If all of your maps are known to be smaller than this limit, you do not need to use VLV indexes. However, if your maps are larger than the size limit or you are unsure of the size of all maps, use VLV indexes to avoid incomplete returns.

If you are using VLV indexes, set up the appropriate size limits as follows:

- On the Oracle Directory Server Enterprise Edition server, ensure that the nsslapd-sizelimit attribute is set to greater than or equal to 50000 or -1. For more information, see the idsconfig(1M) man page.
- On the N2L server, ensure that the nisLDAPsearchSizelimit attribute is set to either greater than or equal to 50000 or zero. For more information, see the NISLDAPmapping(4) man page.

After VLV indexes have been created, activate them by running dsadm with the vlvindex option on the Oracle Directory Server Enterprise Edition server. For more information, see the dsadm(1M) man page.

## **VLVs for Standard Maps**

Use the Oracle Directory Server Enterprise Edition idsconfig command to set up VLVs if the following conditions apply:

- You are using Oracle Directory Server Enterprise Edition.
- You are mapping standard maps to RFC 2307bis LDAP entries.

VLVs are domain specific, so each time idsconfig is run, VLVs are created for one NIS domain. Therefore, during the NIS-to-LDAP transition, you must run idsconfig once for *each* nisLDAPdomainContext attribute included in the NISLDAPmapping file.

## **VLVs for Custom and Nonstandard Maps**

You must manually create new Oracle Directory Server Enterprise Edition VLVs for maps, or copy and modify existing VLV indexes, if the following conditions apply:

- You are using Oracle Directory Server Enterprise Edition.
- You have large custom maps or have standard maps that are mapped to nonstandard DIT locations.

To view existing VLV indexes, type the following command:

```
% ldapsearch -h hostname -s sub -b "cn=ldbm database,cn=plugins,cn=config"
"objectclass=vlvSearch"
```

# **Avoiding Server Timeouts With Oracle Directory Server Enterprise Edition**

When the N2L server refreshes a map, the result might require a lengthy LDAP directory access. If Oracle Directory Server Enterprise Edition is not correctly configured, the refresh operation might time out before completion. To avoid directory server timeouts, modify Oracle Directory Server Enterprise Edition attributes manually or by running the idsconfig command.

For example, you might want to modify the following attributes to increase the minimum amount of time in seconds that the server should spend performing the search request:

```
dn: cn=config
nsslapd-timelimit: -1
```

For testing purposes, you can use an attribute value of -1, which indicates no limit. When you have determined the optimum limit value, change the attribute value. Do *not* maintain any attribute settings at -1 on a production server. With no limits, the server might be vulnerable to Denial of Service attacks.

For more information about configuring Oracle Directory Server Enterprise Edition with LDAP, see Chapter 4, "Setting Up the Oracle Directory Server Enterprise Edition With LDAP Clients".

# **Avoiding Buffer Overruns With Oracle Directory Server Enterprise Edition**

To avoid buffer overruns, modify the Oracle Directory Server Enterprise Edition attributes manually or by running the idsconfig command. For example:

• Modify the following attributes to increase the maximum number of entries that are returned for a client search query:

```
dn: cn=config
nsslapd-sizelimit: -1
```

Modify the following attributes to increase the maximum number of entries that are verified for a client search query:

```
dn: cn=config, cn=ldbm database, cn=plugins, cn=config
nsslapd-lookthroughlimit: -1
```

For testing purposes, you can use an attribute value of -1, which indicates no limit. When you have determined the optimum limit value, change the attribute value. Do *not* maintain any attribute settings at -1 on a production server. With no limits, the server might be vulnerable to Denial of Service attacks.

If VLVs are being used, the sizelimit attribute values should be set as defined in "Creating Virtual List View Indexes With Oracle Directory Server Enterprise Edition" on page 117. If VLVs are not being used, the size limit should be set large enough to accommodate the largest container.

For more information about configuring Oracle Directory Server Enterprise Edition with LDAP, see Chapter 4, "Setting Up the Oracle Directory Server Enterprise Edition With LDAP Clients".

## **NIS-to-LDAP Restrictions**

When the N2L server has been set up, the NIS source files are no longer used. Therefore, do not run ypmake on an N2L server. If ypmake is accidentally run, such as for an existing cron job, the N2L service is unaffected. However, a warning is logged suggesting that yppush should be called explicitly.

## **NIS-to-LDAP Troubleshooting**

This section covers the following areas of troubleshooting:

- "Common LDAP Error Messages" on page 120
- "NIS-to-LDAP Issues" on page 122

## **Common LDAP Error Messages**

The N2L server might log errors that relate to internal LDAP problems, resulting in LDAP-related error messages. Although the errors are nonfatal, they indicate that you need to investigate the problems. The N2L server might continue to operate but provide out-of-date or incomplete results.

This section describes some of the common LDAP error messages that you might encounter when implementing the N2L service. It also inclues error descriptions and possible causes and solutions for the errors.

Administrative limit exceeded Error Number: 11

**Cause:** An LDAP search was larger than the limit allowed by the directory server's nsslapd-sizelimit attribute. The search returns partial information.

**Solution:** Increase the value of the nsslapd-sizelimit attribute or implement a VLV index for the failing search.

```
Invalid DN Syntax
Error Number: 34
```

**Cause:** An attempt has been made to write an LDAP entry with a DN that contains illegal characters. The N2L server attempts to escape illegal characters, such as the + symbol, that are generated in DNs.

**Solution:** Check the LDAP server error log to find out which illegal DNs were written and modify the NISLDAPmapping file that generated the illegal DNs.

```
Object class violation
Error Number: 65
```

**Cause:** An attempt has been made to write an LDAP entry that is invalid. Generally, this error is due to missing MUST attributes that can be caused by either of the following circumstances:

- Bugs in the NISLDAPmapping file that create entries with missing attributes
- Attempts to add an AUXILIARY attribute to an object that does not exist
   For example, if a user name has not yet been created from the passwd.byxxx map, an attempt to add auxiliary information to that user will fail.

**Solution**: For bugs in the NISLDAPmapping file, check the information in the server error log to determine the nature of the problem.

```
Can't contact LDAP server
Error Number: 81
```

**Cause:** The ypserv file might be incorrectly configured to point to the wrong LDAP directory server. Alternatively, the directory server might not be running.

**Solution:** Perform the following actions to resolve the issue:.

- Reconfigure the ypserv file to point to the correct LDAP directory server.
- Type the following command to confirm that the LDAP server is running:

If the server is unavailable, the following message is displayed:

```
no answer from hostname
```

If there are problems with the LDAP server, the following message is displayed:

ldap\_search: Can't connect to the LDAP server - Connection refused

If everything is working, the following message is displayed:

Directory accessible

Timeout

Error Number: 85

**Cause:** An LDAP operation timed out while updating a map from the DIT. The map might now contain out-of-date information.

Solution: Increase the nisLDAPxxxTimeout attributes in the ypserv configuration file.

## NIS-to-LDAP Issues

This section describes problems that could occur while running the N2L server and provides possible causes and solutions.

## Debugging the NISLDAPmapping File

The mapping file, NISLDAPmapping, is complex. Different issues might cause the mapping to behave in unexpected ways. Use the described techniques to resolve such problems.

Console Message Displays When ypserv -ir (or -Ir) Runs

**Description:** A simple message is displayed on the console and the server exits (a detailed description is written to syslog).

Cause: The syntax of the mapping file might be incorrect.

Solution: Check and correct the syntax in the NISLDAPmapping file.

NIS Daemon Exits at Startup

**Description:** When ypserv or other NIS daemons run, an LDAP-related error message is logged and the daemon exits.

**Cause:** The cause might be one of the following:

- The LDAP server cannot be contacted.
- An entry found in an NIS map or in the DIT is incompatible with the mapping specified.
- An attempt to read or write to the LDAP server returns an error.

**Solution:** Examine the error log on the LDAP server. For the information about LDAP errors, see "Common LDAP Error Messages" on page 120.

Unexpected Results From NIS Operations

**Description:** NIS operations do not return the expected results but no errors are logged.

**Cause:** Incorrect entries might exist in the LDAP or NIS maps, which results in mappings not completing as intended.

**Solution:** Check and correct entries in the LDAP DIT and in the N2L versions of the NIS maps.

- 1. Check that the correct entries exist in the LDAP DIT, and fix the entries as needed. If you are using Oracle Directory Server Enterprise Edition, start the management console by running the dsadm startconsole command.
- 2. Check that the N2L versions of the NIS maps in the /var/yp directory contain the expected entries by comparing the newly generated map to the original map. Fix entries as needed.
  - # cd /var/yp/domain-name
    # makedbm -u test.byname

Be aware of the following when checking the output for the maps:

- The order of entries might not be the same in both files.Use the sort command before comparing output.
- The use of white space might not be the same in both files.
   Use the diff -b command when comparing output.

Processing Order of NIS Maps

**Description:** Object class violations have occurred.

**Cause:** When the ypserv -i command is run, each NIS map is read and its contents are written into the DIT. Several maps might contribute attributes to the same DIT object. Generally, one map creates most of the object, including all of the object's MUST attributes. Other maps contribute additional MAY attributes.

Maps are processed in the same order that nisLDAPobjectDN attributes appear in the NISLDAPmapping file. If maps containing MAY attributes get processed before maps containing

MUST attributes, then object class violations occur. For more information about this error, see "Common LDAP Error Messages" on page 120.

**Solution:** Reorder the nisLDAPobjectDN attributes so that maps are processed in the correct order

As a temporary fix, rerun the ypserv -i command several times. Each time the command is executed, the LDAP entry approaches a complete state.

**Note -** Mapping in such a way that all of an object's MUST attributes cannot be created from at least one map is *not* supported.

## **N2L Server Timeout Issue**

The server times out.

**Cause:** When the N2L server refreshes a map, the result might require a single lengthy access of a large LDAP directory. If Oracle Directory Server Enterprise Edition is not correctly configured, this operation might time out before completion.

**Solution:** To avoid directory server timeouts, modify the Oracle Directory Server Enterprise Edition attributes manually or by running the idsconfig command. For more information, see "Common LDAP Error Messages" on page 120 and "NIS-to-LDAP Best Practices With Oracle Directory Server Enterprise Edition" on page 117.

## **N2L Lock File Issue**

The ypserv command starts but does not respond to NIS requests.

**Cause:** The N2L server lock files are not correctly synchronizing access to the NIS maps.

**Solution:** Type the following commands on the N2L server:

- 1. Stop the NIS server.
  - # svcadm disable network/nis/server:default
- 2. Remove the lock files.
  - # rm /var/run/yp\_maplock /var/run/yp\_mapupdate
- 3. Restart the NIS server.
  - # svcadm enable network/nis/server:default

## **N2L Deadlock Issue**

The N2L server deadlocks.

**Cause:** If the addresses of the N2L master server and the LDAP server are not listed properly in the hosts, ipnodes, or ypserv files, a deadlock might result. For more information about address configuration for N2L, see "Prerequisites for the NIS-to-LDAP Transition" on page 110.

For an example of a deadlock scenario, consider the following sequence of events:

- 1. An NIS client tries to look up an IP address.
- 2. The N2L server finds that the hosts entry is out of date.
- 3. The N2L server tries to update the hosts entry from LDAP.
- 4. The N2L server gets the name of its LDAP server from ypserv, then does a search by using libldap.
- 5. libldap tries to convert the LDAP server's name to an IP address by making a call to the name service switch.
- 6. The name service switch might make an NIS call to the N2L server, which deadlocks.

**Solution:** List the addresses of the N2L master server and the LDAP server in the hosts or ipnodes files on the N2L master server. Whether the server addresses must be listed in hosts, ipnodes, or both files depends on how these files are configured to resolve local host names. Also, check that the config/hosts property of the svc:/network/name-service/switch service lists files before nis in the lookup order.

An alternative solution to this deadlock problem is to list the LDAP server address, not its host name, in the ypserv file. Because the LDAP server address would be listed in another place, changing the address of either the LDAP server or the N2L server would require slightly more effort.

# **Reverting to NIS**

A site that has transitioned from NIS to LDAP using the N2L service is expected to gradually replace all NIS clients with LDAP naming services clients. Support for NIS clients eventually becomes redundant. However, if required, the N2L service provides two ways to return to NIS, as explained in the procedures in this section.

**Tip** - Because traditional NIS ignores the N2L versions of the NIS maps if those maps are present, you can safely leave the N2L versions of the maps on the server. Keeping the N2L maps might be useful in case you later decide to re-enable N2L. Note, however that, the N2L maps take up disk space.

# **▼** How to Revert to Maps Based on NIS Source Files

## Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

## 2. Stop the NIS daemons.

# svcadm disable network/nis/server:default

#### 3. Disable N2L.

# mv /var/yp/NISLDAPmapping backup-filename

This command backs up and moves the N2L mapping file.

4. Set the NOPUSH environment variable so the new maps are not pushed by ypmake.

```
# NOPUSH=1
```

5. Make a new set of NIS maps that are based on the NIS sources.

```
# cd /var/yp
# make
```

6. (Optional) Remove the N2L versions of the NIS maps.

```
# rm /var/yp/domain-name/LDAP_*
```

7. Start the DNS and the NIS service.

```
# svcadm enable network/dns/client:default
# svcadm enable network/nis/server:default
```

# How to Revert to Maps Based on DIT Contents

Back up the old NIS source files before performing this procedure.

## 1. Become an administrator.

For more information, see "Using Your Assigned Administrative Rights" in *Securing Users and Processes in Oracle Solaris* 11.3.

## 2. Stop the NIS daemons.

# svcadm disable network/nis/server:default

3. Update the maps from the DIT.

```
# ypserv -r
```

Wait for ypserv to exit.

4. Disable N2L.

```
\# mv /var/yp/NISLDAPmapping backup-filename
```

This command backs up and moves the N2L mapping file.

5. Regenerate the NIS source files.

```
# ypmap2src
```

- 6. Manually check that the regenerated NIS source files have the correct content and structure.
- 7. Move the regenerated NIS source files to the appropriate directories.
- 8. (Optional) Remove the N2L versions of the mapping files.

```
# rm /var/yp/domain-name/LDAP_*
```

9. Start the DNS and NIS service.

```
# svcadm enable network/dns/client:default
```

# svcadm enable network/nis/server:default

# Glossary

## applicationlevel naming service

Application-level naming services are incorporated in applications offering services such as files, mail, and printing. Application-level naming services are bound below enterprise-level naming services. The enterprise-level naming services provide contexts in which contexts of application-level naming services can be bound.

#### attribute

Each LDAP entry consists of a number of named attributes, each of which has one or more values.

Also, the N2L service mapping and configuration files each consist of a number of named attributes. Each attribute has one or more values.

#### authentication

The means by which a server can verify a client's identity.

#### baseDN

The DN where part of the DIT is rooted. When this is the baseDN for an NIS domains entries it is also referred to as a *context*.

#### client

- (1) The client is a principal (system or user) requesting a naming service from a naming server.
- (2) In the client-server model for file systems, the client is a system that remotely accesses resources of a compute server, such as compute power and large memory capacity.
- (3) In the client-server model, the client is an application that accesses services from a "server process." In this model, the client and the server can run on the same system or on separate systems.

## client-server model

A common way to describe network services and the model user processes (programs) of those services. Examples include the name-server/name-resolver paradigm of the *Domain Name System (DNS)*. See also *client*.

### context

For the N2L service, a context is something under which a NIS domain is generally mapped. See also *baseDN*.

## credentials

The authentication information that the client software sends along with each request to a naming server. This information verifies the identity of a user or system.

#### custom map

Any map that is not a standard map and therefore requires manual modifications to the mapping file when transitioning from NIS to LDAP.

An LDAP directory is a container for LDAP objects. In UNIX, a container for files and directory

subdirectories.

directory cache

A local file used to store data associated with directory objects.

directory information tree (DIT)

name (DN)

The DIT is the distributed directory structure for a given network. By default, clients access the information assuming that the DIT has a given structure. For each domain supported by the LDAP server, there is an assumed subtree with an assumed structure.

distinguished

A distinguished name is an entry in an X.500 directory information base (DIB) composed of selected attributes from each entry in the tree along a path leading from the root down to the named entry.

DIT See directory information tree.

DN A distinguished name in LDAP. A tree-like structured addressing scheme of the LDAP

directory which gives a unique name to each LDAP entry.

**DNS** See Domain Name System.

domain (1) In the Internet, a part of a naming hierarchy usually corresponding to a Local Area Network

> (LAN) or Wide Area Network (WAN) or a portion of such a network. Syntactically, an Internet domain name consists of a sequence of names (labels) separated by periods (dots). For

example, sales.example.com.

(2) In International Organization for Standardization's open systems interconnection (OSI), "domain" is generally used as an administrative partition of a complex distributed system, as in

MHS private management domain (PRMD), and directory management domain (DMD).

domain name The name assigned to a group of systems on a local network that share DNS administrative

files. The domain name is required for the network information service database to work

properly. See also domain.

**Domain Name** System (DNS)

A service that provides the naming policy and mechanisms for mapping domain and machine names to addresses outside of the enterprise, such as those on the Internet. DNS is the network

information service used by the Internet.

encryption The means by which the privacy of data is protected.

encryption

key

See data encrypting key.

A single row of data in a database table, such as an LDAP element in a DIT. entry

Internet address

A 32-bit address assigned to hosts using *TCP/IP*. See *decimal dotted notation*.

**LDAP** Lightweight Directory Access Protocol is a standard, extensible directory access protocol used

by LDAP naming service clients and servers to communicate with each other.

**LDAP client** An LDAP client is a system that reads and writes to any LDAP server. An LDAP naming

service client handles a customized subset of naming information.

**mapping** The process of converting NIS entries to or from DIT entries. This process is controlled by a

mapping file.

mapping file The NISLDAPmapping file that establishes how to map entries between NIS and LDAP files.

N2L configuration files The ypserv daemon uses the N2L configuration files, /var/yp/NISLDAPmapping and /var/yp/ypserv, to start the master server in N2L mode. For more information, see the

iles NISLDAPmapping(4) and ypserv(4) man pages.

**N2L server** An NIS master server that is reconfigured as an N2L server by using the N2L service.

Reconfiguration includes replacing NIS daemons and adding new configuration files.

name resolution The process of translating workstation or user names to addresses.

**name server** Servers that run one or more network naming services.

name service switch The svc:/system/name-service/switch service which defines the sources from which an naming client can obtain its network information.

**namespace** (1) A namespace stores information that users, workstations, and applications must have to communicate across the network.

(2) The set of all names in a naming system.

naming service A network service that handles system, user, domain, router, and other network names and addresses.

**NIS** A distributed network information service containing key information about the systems and the users on the network. The NIS database is stored on the *master server* and all the *replica* or

slave servers.

**NIS maps** A file used by NIS that holds information of a particular type, for example, the password

entries of all users on a network or the names of all systems on a network. Programs that are

part of the NIS service query these maps. See also NIS.

nonstandard maps Standard NIS maps that are customized to use mappings between NIS and the LDAP DIT other

than the mappings identified in RFC 2307 or its successor.

preferred server list A client\_info table or a client\_info file. Preferred server lists specify the preferred servers for a client or domain.

**private key** The private component of a pair of mathematically generated numbers, which, when combined

with a private key, generates the DES key. The DES key in turn is used to encode and decode information. The private key of the sender is only available to the owner of the key. Every user

or system has its own public and private key pair.

**public key** The public component of a pair of mathematically generated numbers, which, when combined

with a private key, generates the DES key. The DES key in turn is used to encode and decode information. The public key is available to all users and system. Every user or system has their

own public and private key pair.

**RDN** Relative Distinguished Name. One part of a DN.

**record** See *entry*.

**RFC 2307** RFC specifying a mapping of information from the standard NIS maps to DIT entries. By

default, the N2L service implements the mapping specified in an updated version RFC 2307bis.

SASL The simple authentication and security layer. A framework for negotiating authentication and

security layer semantics in application-layer protocols.

**schema** A set of rules defining what types of data can be stored in any given LDAP DIT.

**searchTriple** A description of where to look for a given attribute in the DIT. The searchTriple is composed of

a base dn, scope, and filter. This is part of the LDAP URL format as defined in RFC 2255.

Secure RPC password

Password required by the secure RPC protocol. This password is used to encrypt the private key. This password should always be identical to the user's login password.

**server** (1) In NIS, DNS, and LDAP a host system providing naming services to a network.

(2) In the *client-server model* for file systems, the server is a machine with computing resources (and is sometimes called the *compute server*), and large memory capacity. Client machines can remotely access and make use of these resources. In the client-server model for window systems, the server is a process that provides windowing services to an application, or "client process." In this model, the client and the server can run on the same machine or on separate machines.

(3) A daemon that actually handles the providing of files.

**server list** *See* preferred server list.

**slave server** A server system that maintains a copy of the NIS database. It has a disk and a complete copy of

the operating environment.

**source** NIS source files

SSL SSL is the Secure Sockets Layer protocol. It is a generic transport-layer security mechanism

designed to make application protocols such as LDAP secure.

**standard** NIS maps that are supported by the N2L service without requiring manual modification to the maps mapping file. For information about the supported standard maps, see "Supported Standard"

Mappings" on page 108.

**subnet** A working scheme that divides a single logical network into smaller physical networks to

simplify routing.

**suffix** In LDAP, the distinguished name (DN) of the DIT.

 ${\bf yp}$  Yellow Pages  $^{\rm TM}$ . The old name for NIS which is still used within the NIS code.

# Index

access control information, 15 account management configuring on directory server, 58 enableShadowUpdate switch, 24 for LDAP clients that use pam_ldap, 59 for LDAP clients that use pam_unix_* modules, 60 LDAP server for pam_unix_* clients, 27 LDAP supported features, 26 PAM modules and LDAP, 26 adminDN attribute described, 65 adminPassword attribute	certificatePath attribute described, 65 client credential level assigning, 17 cn attribute described, 29 credential levels LDAP client, 17 credential storage LDAP client, 19 credentialLevel attribute described, 30
described, 65 anonymous credentials, 17 attributeMap attribute, 36 described, 30 attributes Internet print protocol, 95 authentication definition, 129 authentication methods choosing in LDAP, 20 for services in LDAP, 21 PAM modules, 22 authenticationMethod attribute described, 30 multi-value example, 20 pam_ldap module and, 22 passwd-cmd service and, 25	data population, 35 defaultSearchBase attribute described, 30 defaultSearchScope attribute described, 30 defaultServerList attribute described, 30 directory cache definition, 130 directory information tree, 12 containers, 12 VLVs and, 45 directory user agent schema, 89 distinguished name definition, 130
B bindTimeLimit attribute described, 31 browsing indexes <i>See</i> virtual list view indexes	DIT <i>See</i> directory information tree DN definition, 130 DNS

definition, 130	definition, 130
domain name system See DNS	enabling account management on directory
domainName attribute	server, 58
described, 65	FMRI, 64
	naming service, 11
	reverting to NIS, 125
E	schemas See LDAP schemas
enableShadowUpdate switch, 24	SMF, 64
encryption 24	transitioning from NIS, 105
definition, 130	troubleshooting See LDAP troubleshooting
encryption key	LDAP client
definition, 130	local profile attributes, 65
entry	LDAP client profile
definition, 130	attributes, 29
definition, 150	credential levels, 17
	LDAP commands, 13
F	LDAP schemas, 83
	directory user agent, 89
FMRIs	mail alias, 89
LDAP, 64	project, 92
followReferrals attribute	role based attributes, 93
described, 31	LDAP troubleshooting
	ldapclient cannot bind to server, 79
	login fails, 78
l	lookup too slow, 79
inityp2l command, 107, 108	unable to reach systems in LDAP domain
Internet address	remotely, 78, 78
definition, 130	unresolved host name, 78
	ldapaddent command, 56
	ldapclient command
K	client profile attributes, 65
Kerberos, 15	lightweight directory access protocol See LDAP
keyserv service	
LDAP authentication and, 22	
	M
	mail alias schema, 89
L	mail attributes, 89
LDAP	mailGroup object class, 89
account management, 26	mapping
advantages and limitations, 11	definition, 131
authentication service, 11, 15	mapping file
client credential levels, 17	NIS to LDAP, 105
commands for configuration and	•
administration, 13	
comparing supported PAM modules, 23, 25	N
data interchange format (LDIF), 12	N2L server, 105

N2L service, 105	LDAP and, 20
custom map examples, 115	
setting up, 111	
supported mappings, 108	0
when not to use, 107	objectclassMap attribute, 37
N2L transition See NIS to LDAP transition	described, 30
name resolution	
definition, 131	Oracle Directory Server Enterprise Edition
name server	setup using idsconfig, 44
definition, 131	
name service switch	
definition, 131	Р
namespace	PAM modules
definition, 131	authentication methods, 22
naming service	LDAP, 22
definition, 131	PAM service, 15
network information service schema, 83	pam ldap
network model, 31	account management in LDAP, 59
NIS	pam ldap service
definition, 131	LDAP authentication and, 22
NIS maps	pam unix * modules
definition, 131	account management in LDAP, 27, 60
NIS to LDAP	passwd-cmd service
SMF and, 106	LDAP authentication and, 21
NIS to LDAP transition, 105, 105	password entry
See also N2L	enableShadowUpdate switch, 18
buffer overruns, 119	password management <i>See</i> account management
commands, 108	passwords passwords
configuration files, 108	LDAP, and, 25
deadlock, 125	per-user credentials, 18
debugging the NISLDAPmapping file, 122	Pluggable Authentication Modules, 22
hosts database, 110	preferredServerList attribute
issues, 122	described, 29
LDAP error codes, 120	private key
name service switch configuration, 110	definition, 131
prerequisites, 110	profiles
restrictions, 120	LDAP client, 65
reverting to NIS, 125	
server timeouts, 119	profileTTL attribute
troubleshooting, 120	described, 31 project schema
using idsconfig command, 110	attributes, 92
using virtual list views (VLVs), 117	
with Oracle Directory Server Enterprise	object class, 92
Edition, 117	proxy authentication 15
NISLDAPmapping file, 105, 108	proxy gradentials 17
none authentication method	proxy credentials, 17
none audientication method	proxyDN attribute

described, 65	described, 30
proxyPassword attribute	pam_ldap module and, 22
described, 65	passwd-cmd service and, 25
public key	serviceSearchDescriptor attribute
definition, 132	described, 30
	simple authentication method
	LDAP and, 20
D	slave server
R	definition, 132
record	SMF
definition, 132	and LDAP, 64
referrals, 47	NIS-to-LDAP tools and, 106
reverting to NIS from LDAP, 125	source
RFC 2307	definition, 132
object classes, 87	SSDs, 35
RFC 2307bis	SSL
attributes, 84	definition, 132
RFC2307bis LDAP schema, 83	SSL protocol, 16
role based LDAP schema, 93	subnet
object classes, 94	definition, 132
	suffix
	definition, 133
S	
SASL	
definition, 132	т
sasl authentication methods	T
LDAP and, 20	tls authentication methods
schema	LDAP and, 20
definition, 132	transitioning NIS to LDAP, 105
schemas See LDAP schemas	Transport Layer Security, 16
mapping, 35	troubleshooting
RFC 2307bis, 83	LDAP, 73
search descriptors, 12	
searchTimeLimit attribute	
described, 30	U
searchTriple	/usr/lib/netsvc/yp/inityp2l command, 107, 108
definition, 132	/usr/lib/netsvc/yp/ypmap2src command, 107, 108
secure RPC password	,,,, ,,,,,,,,,,,,,,,,,,,,,,
definition, 132	
secure sockets layer See SSL	
server	V
definition, 132	/var/yp/NISLDAPmapping file, 108
server list	/var/yp/ypserv file
definition, 132	N2L transition and, 108
service search descriptors, 35	virtual list view indexes, 45
serviceAuthenticationMethod attribute 21	VLV See virtual list view indexes

## Υ

yp definition, 133 ypmap2src command, 107, 108 ypserv file N2L transition and, 108