Managing System Services in Oracle® Solaris 11.3



Managing System Services in Oracle Solaris 11.3

Part No: E54799

Copyright © 2013, 2016, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

Référence: E54799

Copyright © 2013, 2016, Oracle et/ou ses affiliés. Tous droits réservés.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf stipulation expresse de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, accorder de licence, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est livré sous licence au Gouvernement des Etats-Unis, ou à quiconque qui aurait souscrit la licence de ce logiciel pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer des dommages corporels. Si vous utilisez ce logiciel ou matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour ce type d'applications.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Xeon sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Opteron, le logo AMD et le logo AMD Opteron sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée d'The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers, sauf mention contraire stipulée dans un contrat entre vous et Oracle. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation, sauf mention contraire stipulée dans un contrat entre vous et Oracle.

Accessibilité de la documentation

Pour plus d'informations sur l'engagement d'Oracle pour l'accessibilité à la documentation, visitez le site Web Oracle Accessibility Program, à l'adresse http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Accès aux services de support Oracle

Les clients Oracle qui ont souscrit un contrat de support ont accès au support électronique via My Oracle Support. Pour plus d'informations, visitez le site http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info ou le site http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs si vous êtes malentendant.

Contents

U	sing This Documentation	. 15
_		
1	Introduction to the Service Management Facility	
	SMF Capabilities	
	New Features in This Release	
	SMF Concepts and Components	
	SMF Service	
	Service Models	
	Service Names	22
	Service States	23
	Service Dependencies	. 24
	Service Restarters	24
	Service Properties and Property Groups	26
	Service Configuration Repository	26
	Configuration Files and SMF Services	30
	Service Management Privileges	32
2	Getting Information About Services	. 33
	Listing Services on the System	
	Showing Service State	
	Showing More Information About Services	
	Showing Selected Service Information	
	Showing Service Dependencies	. 36
	Dependency Groupings	
	Listing Instances That a Service Depends On	
	Listing Instances That Depend on a Service	
	Showing Whether a Service Will Automatically Restart	
	Getting More Information About Service States	
	Viewing Service Log Files	
	Inspecting Service Configuration	

	Showing Descriptions of Properties and Property Groups	44
	Showing Service and Instance Property Values	45
	Showing Properties in a Property Group Type	47
	Showing the Layer Where a Value Is Set	49
	Showing the File that Contributed the Configuration	50
	Showing Values in a Specified Snapshot	50
	Showing Configuration Customizations	51
	Showing Event Notification Parameters	52
3	Administering Services	55
	Managing SMF Service Instances	55
	Starting a Service	55
	Stopping a Service	58
	Restarting a Service	60
	Rereading Service Configuration	62
	Deleting a Service	63
	Configuring Notification of State Transition and FMA Events	64
4	Configuring Services	. 67
	Using the Service Configuration Command	67
	Invoking a Property Editor	68
	Invoking svccfg Interactively or With a File	69
	Setting Property Values	70
	▼ How to Schedule a Periodic or Scheduled Service	72
	▼ How to Modify a ttymon Property Value	74
	▼ How to Modify an Environment Variable for a Service Process	
	Environment	76
	Adding Property Groups, Properties, and Property Values	
	Deleting Property Groups, Properties, and Property Values	
	Deleting Administrative Configuration	
	Deleting Non-Administrative Configuration	
	Adding Service Instances	
	Reverting Snapshots	
	Importing and Applying Manifests and Profiles	
	Modifying Services that are Controlled by inetd	
	▼ How to Change a Property Value for an inetd Controlled Service	
	▼ How to Add a New Instance of a Service that is Controlled by inetd	
	Modifying Services that are Configured by a File	88

5	Configuring Multiple Systems	89
	Managing Configuration of Multiple Systems	89
	Creating SMF Profiles	89
	Conflicting Configuration	90
	▼ How to Create a Profile by Using svccfg	92
	▼ How to Create a Profile by Using sysconfig	93
	▼ How to Create a Profile by Using svcbundle	93
	Delivering Configuration to Multiple Systems	94
Α	SMF Best Practices and Troubleshooting	97
	SMF Best Practices	97
	Troubleshooting Services Problems	98
	Understanding Configuration Changes	99
	Repairing an Instance That Is Degraded, Offline, or in Maintenance	99
	Marking an Instance as Degraded or in Maintenance	103
	Diagnosing and Repairing Repository Problems	104
	Specifying the Amount of Startup Messaging	107
	Specifying the SMF Milestone to Which to Boot	108
	Using SMF to Investigate System Boot Problems	109
	Converting inetd Services to SMF Services	111
In	dex	113

8

Figures

FIGURE 1	Service Management Facility Framework	20
FIGURE 2	Service Dependency Relationships	37

Tables

TABLE 1	Automatically Restarting a Service After a Dependency Stop	41
TABLE 2	SMF Startup Message Logging Levels	107
TABLE 3	SMF Boot Milestones and Corresponding Run Levels	109

12

Examples

EXAMPLE 1	Listing All Enabled Services	33
EXAMPLE 2	Listing All Installed Services	34
EXAMPLE 3	Listing All Instances of a Service	34
EXAMPLE 4	Showing Processes Started by a Contract Service	35
EXAMPLE 5	Showing a Contract Service Restarting Automatically After Process	
	Stop	35
EXAMPLE 6	Listing Instance and Inherited Properties Currently in Use	45
EXAMPLE 7	Listing Specified Properties or Property Groups Currently in Use	45
EXAMPLE 8	Listing Service and Instance Values in the Editing View	46
EXAMPLE 9	Listing Specified Properties or Property Groups in the Editing View	47
EXAMPLE 10	Showing Property Groups and Their Types	47
EXAMPLE 11	Listing Properties of a Property Group Type	48
EXAMPLE 12	Enabling a Service Instance Permanently	57
EXAMPLE 13	Enabling a Service Instance Temporarily	57
EXAMPLE 14	Disabling a Service Instance	60
EXAMPLE 15	Configuring a Global Notification for a Service State Event	65
EXAMPLE 16	Configuring Notification for Multiple State Events	65
EXAMPLE 17	Configuring a Notification for a Specified Service Instance	65
EXAMPLE 18	Configuring a Notification for an FMA Event	66
EXAMPLE 19	Deleting Notification Settings	66
EXAMPLE 20	Setting a Simple Value	70
EXAMPLE 21	Setting a Value that Contains a Colon Character	71
EXAMPLE 22	Setting a Value that Contains Embedded Spaces	71
EXAMPLE 23	Setting a Value that Is a Set of Values	71
EXAMPLE 24	Adding a Value	72
EXAMPLE 25	Scheduling the Compliance Assessment Service	74
EXAMPLE 26	Using addpg to Create a New Property Group	77
EXAMPLE 27	Using setprop to Create a New Property	78
EXAMPLE 28	Using addpropvalue to Create a New Property	78
EXAMPLE 29	Deleting All Values of a Property	79

EXAMPLE 30	Deleting All Matching Values of a Property	80
EXAMPLE 31	Deleting a Property	80
EXAMPLE 32	Deleting a Property Group	80
EXAMPLE 33	Deleting Customizations	81
EXAMPLE 34	Deleting Configuration that has Bundle Support	82
EXAMPLE 35	Unmasking Configuration	82
EXAMPLE 36	Limiting the Number of Concurrent Processes that are Allowed to Run	86

Using This Documentation

- Overview Describes how to use the Oracle Solaris Service Management Facility (SMF) feature. SMF is one of the components of the wider Oracle Solaris Predictive Self Healing capability.
- Audience System administrators who manage system services
- **Required knowledge** Experience administering Oracle Solaris systems

Product Documentation Library

Documentation and resources for this product and related products are available at http://www.oracle.com/pls/topic/lookup?ctx=E53394.

Feedback

Provide feedback about this documentation at http://www.oracle.com/goto/docfeedback.

· · · CHAPTER 1

Introduction to the Service Management Facility

The Oracle Solaris Service Management Facility (SMF) framework manages system and application services. SMF manages critical system services essential to the working operation of the system and manages application services such as a database or Web server. SMF improves the availability of a system by ensuring that essential system and application services run continuously even in the event of hardware or software failures.

SMF replaces the use of configuration files for managing services and is the recommended mechanism to use to start applications. SMF replaces the init scripting start-up mechanism, inetd.conf configurations, and most rc?.d scripts. SMF preserves compatibility with existing administrative practices wherever possible. For example, most customer and ISV-supplied rc scripts still work the same way they worked without SMF.

This chapter describes:

- Capabilities of SMF
- New features in this release
- Concepts and components of SMF
- Configuration files versus SMF services
- How to gain privileges you need to use some SMF commands

For information about developing custom SMF services, see *Developing System Services in Oracle Solaris 11.3*.

SMF Capabilities

The SMF framework is always active on an Oracle Solaris 11 system. SMF provides the following capabilities:

- Boot faster. SMF speeds booting of large systems by starting independent services in parallel.
- Restart failed services. SMF services have well defined dependency relationships with other services. If a service fails, SMF reports any affected dependent services. SMF automatically attempts to restart failed services in dependency order.

- Inspect services. View the relationships between services and processes. View the values of service properties.
- Manage services. Enable, disable, and restart services. These changes can persist through upgrades and reboots, or you can specify temporary changes.
- Configure services.
 - Change the values of service properties.
 - Add and delete custom properties.
- Audit service changes. SMF writes Oracle Solaris audit records for every administrative change to a service or its properties. SMF can show whether a property value or service state was set by an administrator.
- Securely delegate tasks to non-root users, including the ability to modify properties and enable, disable, or restart services.
- Configure how you will be notified of particular software events or hardware faults.
- Debug service problems. Easily display an explanation for why an enabled service is not running or why a service is preventing another service from running.
- Create a new instance of an existing service or modify an existing service instance.
- Create new services. See *Developing System Services in Oracle Solaris 11.3* for more information about the following capabilities:
 - Using the service creation tool.
 - Converting inetd.conf configurations to SMF services.
 - Converting SMF service properties to configuration files. This mechanism provides
 a bridge for services that are managed by SMF but interact with applications that still
 require configuration files.
 - Creating a service that runs periodically rather than continuously, similar to a cron job.

New Features in This Release

The following SMF features are new in this release:

Synchronous restart and refresh operations

A new -s option for the clear, delegate, mark, milestone, refresh, and restart subcommands of the svcadm command specifies synchronous operation similar to the -s option for the enable and disable subcommands. All svcadm subcommands have synchronous behavior.

Periodic services

In contrast to running persistently, a periodic service runs at scheduled intervals.

SMF Concepts and Components

This section defines terms that are used in the remainder of this guide.

The following figure shows the primary components of the SMF framework. When you boot an image, SMF updates the service configuration repository if necessary, reads the repository data, and starts enabled service instances in correct dependency order. Independent services are started in parallel. When you shut down an image, services are shut down in reverse dependency order.

In the following figure, libscf is the library interface that the restarters use to interact with the service configuration repository. Interaction between the service configuration repository and libscf library interfaces is managed by the svc.configd daemon. The svcs, svcprop, svcadm, and svccfg commands are the interface that administrators use to interact with the service configuration repository.




FIGURE 1 Service Management Facility Framework

SMF Service

An SMF *service* is a persistently running application that represents a system entity such as the following:

- Application services such as a database or a Web server
- Essential system services
- The software state of a device
- Kernel configuration information
- Milestones that correspond to a level of system readiness

A *service instance* is a child of a service and provides capabilities and dependency relationships to applications and other service instances. Only instances have a state and can be started and stopped. If an instance fails for any reason, such as a hardware or software fault, SMF automatically detects the failure and restarts the instance and any dependent instances.

Instances of a service allow multiple configurations of a service to run simultaneously. Service instances inherit and customize common service configuration. For example, you can define a Web server service with one instance configured to listen on port 80 and another instance configured to listen on port 1008. Most services have a default instance. A few services do not have instances, such as some services that use SMF to store configurations but not to run programs. For example, the x11/x11-server service does not have any instances.

An SMF service is described in a file called a service *manifest*. The manifest describes service instances, dependencies, configuration properties, and methods. Service *methods* start, stop, and refresh service instances. A method can be a daemon, other binary executable, or an executable script. A service *profile* file enables you to customize an existing service, primarily by adding properties and adding and overriding property values. The new properties and values are layered over the values assigned in the manifest, as described in "Repository Layers" on page 28. See "Service Bundles" on page 27 for more information about manifests and profiles. A profile is also an excellent tool for applying the same custom configuration to multiple systems, as described in "Creating SMF Profiles" on page 89.

Service information is stored in the *service configuration repository*, which is also called the *SMF database*. The service configuration repository stores the current state of each service instance on the system and the configuration data for each service and service instance. The data is stored in *layers* according to how values were modified, as described in "Repository Layers" on page 28.

SMF provides *actions* that you can invoke on a service instance, including enable, disable, refresh, and restart. Each service instance is managed by a *restarter*, which performs these administrative actions. In general, restarters perform actions by executing *methods* to move the service instance from one state to another state. For more information about restarters, see "Service Restarters" on page 24.

A *milestone service* is a special type of service that represents a level of system readiness such as a system init state. A milestone is a service that other service instances depend on to start. For example, run levels are represented by milestone services such as svc:/milestone/multi-user-server. Milestones also can be used to indicate the readiness of a group of services, such as svc:/milestone/devices, svc:/milestone/network, or svc:/milestone/name-services.

Service Models

SMF services are one of the following models:

Transient service

The service does some work and then exits without starting any long running processes.

Child or wait service

The service is restarted whenever its child process exits cleanly. A child process that exits cleanly is not treated as an error.

Contract or daemon service

The service starts a long running daemon or starts several related processes that are tied together as part of a *service contract*. The contract service manages processes that it starts and any dependent services and their start order. You only need to manage the high-level service.

Periodic services are a special case that do not fit any of these models. A *periodic* or *scheduled* service starts short-running processes at regular or scheduled intervals, staying online between runs when no associated contracted processes exist. See Chapter 3, "Creating a Service to Run Periodically" in *Developing System Services in Oracle Solaris 11.3* and Chapter 4, "Creating a Service to Run on a Specific Schedule" in *Developing System Services in Oracle Solaris 11.3* for more information.

Service Names

Each service and service instance is represented by a Fault Management Resource Identifier (FMRI). The full FMRI for a service instance has the following format:

svc:/service_name:instance_name

The <code>service_name</code> is a hierarchical name such as <code>network/dns/client</code> or application/pkg/server. Components of the <code>service_name</code> that precede the final forward slash character (/) are the <code>category</code> of the service. Categories such as application, device, <code>milestone</code>, <code>network</code>, and <code>system</code> help identify the purpose of the service.

The site category is reserved to help you avoid name conflicts when you create your own SMF services. For example, a site-specific service named svc:/site/tool will not conflict with an Oracle Solaris service named svc:/tool.

Service instance names are appended to the parent service name after a colon character. For example, svc:/system/identity:node and svc:/system/identity:domain are instances of the svc:/system/identity service.

In scripts, best practice is to use the full service instance name. Interactively, names can be shortened to the rightmost portions of the name that result in a unique name. For example, svc:/system/identity can be shortened to identity, and svc:/system/identity:domain can be shortened to identity:domain. Instance names must be preceded by some portion of the service name, followed by a colon character.

Service States

At any particular time, an SMF service instance is in one of the following states:

- degraded The instance is running or available to run, but is functioning at a limited capacity.
- disabled The instance is not enabled and is not running or available to run.
- maintenance The instance is enabled but not able to run. The instance might be transitioning through the maintenance state because an administrative action has not yet completed. Otherwise, administrative action is required to resolve the problem.
- offline The instance is enabled but not running or available to run. For example, if the
 dependencies of an enabled service are not satisfied, the service is kept in the offline state.
- online The instance is enabled and running or available to run. The online state is the
 expected operating state for a correctly configured service instance with all dependencies
 satisfied.
- uninitialized This state is the initial state for all services.

A service instance transitions between states depending on conditions such as administrative actions or the state of its dependent services. For example, when you enable an instance that was in the disabled state, the newly-enabled instance first transitions into the offline state, and transitions into the online state when all of its dependencies are satisfied.

In addition to the current state, administrators can show the auxiliary state. Restarters (see "Service Restarters" on page 24) use the auxiliary state to store information about the state. The master restarter uses the auxiliary state to store the reason the instance transitioned to its current state. For example, after a transition to the online state, the value of the auxiliary state is typically dependencies_satisfied. The periodic restarter uses the auxiliary state to store whether the periodic task is currently running, as described in "Creating a Periodic Service" in Developing System Services in Oracle Solaris 11.3.

See the smf(5) man page for more information about these service states and about how service instances transition through these states.

Service Dependencies

A service can have a *dependency* on a service, a service instance, or a file. Service dependencies define relationships between services.

Dependency relationships determine when a service starts and automatically stops. When dependencies of an enabled service are not satisfied, the service is in the offline state. When dependencies of an enabled service are satisfied, the service is started. If the service start is successful, the service transitions to the online state.

Service dependencies are reevaluated as services transition through states. Service dependencies that are satisfied can later become not satisfied. File dependencies are evaluated only one time.

Dependencies can be required or optional. Service dependencies can be required to be running or disabled. A dependent service can be configured to restart or not when one of its service dependencies is stopped or refreshed.

Dependency relationships allow the following capabilities:

- Scalable and reproducible initialization processes
- Faster system startup on systems that have parallel capabilities by starting independent services in parallel
- Precise fault containment and fault recovery by restarting only services that are directly affected by a fault, and restarting those services in correct dependency order

Service Restarters

Each SMF service instance is managed by a *restarter*. The restarter retrieves instance configuration and provides an execution environment. See smf_restarter(5) for information common to all restarters.

Master Restarter Daemon

The svc.startd daemon is the *master restarter* daemon for SMF and the *default restarter* for all service instances. The svc.startd daemon manages states for all service instances and their dependencies. As dependencies are satisfied when instances move to the online state, the master restarter invokes start methods of other instances or directs the delegated restarter to invoke the start method. The master restarter stops a service instance when the dependencies of the instance are no longer satisfied. The restarter attempts to restart an instance if the instance fails. Because an instance cannot be online until all of its dependencies are satisfied, the

dependencies of an instance help determine the restart behavior of the instance. Properties set on each dependency declaration define whether that dependency is required and in what cases the instance will be restarted if the dependency is restarted.

Among other tasks, the svc.startd daemon starts the appropriate /etc/rc*.d scripts at the appropriate run levels, which is work that was previously done by init.

The following example shows that svc.startd is the restarter for the network/ipmp:default service instance. Other output has been omitted from this example.

```
$ svcs -l ipmp:default
restarter svc:/system/svc/restarter:default
```

If the restarter property is empty or set to svc:/system/svc/restarter:default, the service instance is managed by svc.startd. For more information about the svc.startd daemon, see the svc.startd(1M) man page.

Delegated Restarters

Some services have a set of common behaviors on startup. A *delegated restarter* can provide a specific execution environment and application-specific restarting behavior for these services. The delegated restarter specified by the restarter property is responsible for managing the service instance once that restarter is available.

Oracle Solaris includes the following delegated restarters:

inetd

The inetd delegated restarter can start Internet services on demand, rather than having the services always running. The inetd restarter provides its service instances with an environment composed of a network connection as input and output file descriptors. For more information about the inetd daemon, see the inetd(1M) man page. The following example shows that inetd is the restarter for the cups/in-lpd:default service instance. Other output has been omitted from this example.

```
$ svcs -l cups/in-lpd:default
restarter svc:/network/inetd:default
```

svc.periodicd

The periodic restarter daemon, svc.periodicd, is invoked automatically at system startup as part of the svc:/system/svc/periodic-restarter service and is automatically restarted if any failures occur. Services started by the periodic restarter remain online persistently but run their start method tasks only periodically or at scheduled times. Start method tasks of a periodic service are expected to run for a relatively brief period of time and then terminate. For more information about the periodic restarter, see the svc.

periodicd(1M) man page. For more information about periodic services, see Chapter 3, "Creating a Service to Run Periodically" in *Developing System Services in Oracle Solaris* 11.3.

Service Properties and Property Groups

Information about services, including dependencies, methods, state, and application data, is stored in the service configuration repository as a set of *properties*. Properties can be defined on either the service or an instance of the service. Properties that are set on the service are inherited by all instances of that service. Properties that are set on an instance are used only by that instance. Service instances can customize the values of inherited properties and can define additional properties that are not defined for the parent service.

Properties are organized into *property groups*. Some common property groups include:

- general Contains information such as whether the instance is enabled
- restarter Contains runtime information that is stored by the restarter for the service, including the current state of the instance
- start, refresh, stop Contains information such as which program to execute to start, refresh, or stop the service
- config Used by service developers to hold application data.

See the smf(5) man page for more information about properties and property groups.

Service Configuration Repository

Information about each service is stored in the *service configuration repository*, which is also called the *SMF database*. The service configuration repository stores information as services, instances, property groups, and properties. In addition to information defined by service developers, the service configuration repository stores information such as the start time and current state of each service instance on the system.

The repository stores persistent configuration information as well as SMF runtime data for services.

- Persistent configuration information is stored in layers according to the source of the data.
 See "Repository Layers" on page 28.
- Runtime data, or non-persistent configuration information, is not preserved across reboot, and the repository does not store layer information for non-persistent data. Non-persistent data generally hold an active program state.

The repository also stores service template data, such as types, value constraints, and descriptions of properties. Template data is defined in the service manifest. See the smf_template(5) man page for more information about template data.

The service configuration repository can only be manipulated or queried by using SMF interfaces. Use the svcs, svcprop, svcadm, and svccfg commands or the Service Configuration Facility library functions listed in the libscf(3LIB) man page. You can read and write property values and show property values in specified layers and snapshots. For information about layers, see "Repository Layers" on page 28. For information about snapshots, see "Repository Snapshots" on page 29. You can show only the properties of the selected service instance or parent service, or you can show a *composed* view of properties. In a composed view, both properties set on the parent service and properties set on the service instance are shown; values shown are the values set on the service instance.

Service Bundles

A service bundle is an XML file that contains the information that is stored in the service configuration repository for a service or service instance. Information provided in service bundles is stored in the service configuration repository and can be exported from the repository. Service bundles in standard locations are imported into the repository during system boot.

The two types of service bundles are manifests and profiles.

Manifests Manifests contain the complete set of properties associated with a

specific set of services or service instances.

Profiles Profiles typically provide customization of a service or service instance

> that augments or overrides information provided in the manifest. Examples of customizations include additional properties and changed

property values.

The standard location for manifests is /lib/svc/manifest. The standard location for profiles is /etc/svc/profile.

When the system is booted or the manifest import service is restarted, manifests are imported and profiles are applied if they are new or changed. An IPS package that delivers a service bundle can specify that the manifest import service should be restarted when the package is installed.

Local customizations can be provided in profile files with an .xml suffix in the /etc/svc/ profile/site directory. If the same property in the same repository layer for the same service or instance is defined by multiple manifests or profiles, SMF cannot determine which value to use. When this type of conflict is detected, the instance is placed in the maintenance state. See "Repository Layers" on page 28 for more information about layers.

In addition to delivering services into Oracle Solaris, service bundles can also deliver custom configuration across a variety of systems.

A system profile, /etc/svc/profile/generic.xml, is applied during installation. Do not change this profile. Any changes made to this system profile will be overwritten on upgrade. See the smf_bootstrap(5) man page for more information.

Repository Layers

The service configuration repository can store different values for a single property. The repository stores data in *layers* according to the source of the data. The source can be manifests, system profiles, site profiles, and customizations made by using SMF commands and library interfaces. You can view values in different layers to understand the source of the value in the running configuration: whether a value was assigned in the manifest, in a profile, or was changed by an administrator. See "Showing the Layer Where a Value Is Set" on page 49.

Configuration changes made by using SMF commands and library interfaces appear only in the admin layer. Configuration in other layers is defined in profile and manifest files in standard locations. When a property is added to the repository from a file or a property value is changed in a file, you can show the name of the file that provided that configuration by using the -f or -o file options of the svccfg listprop command. See "Showing the File that Contributed the Configuration" on page 50.

If a property has different values assigned at different layers, the value that is used by the service instance is the value in the highest layer of the layer hierarchy. The following table shows the order of layers in the hierarchy. For example, if a property has a value in the site-profile layer, that value overrides the value in the manifest layer or any other lower layer. If a property has a value in the admin layer, that value overrides all other values set in any other layer.

Layer	Content	
admin	Any changes that are made by an administrator using the SMF commands or by an application using SMF library interfaces. The admin layer also includes any changes that are made by importing a manifest or applying a profile from a non-standard location. See "Importing and Applying Manifests and Profiles" on page 84 for caution about the use of non-standard locations.	
site-profile	Any values from profile files in the /etc/svc/profile/site directory or the legacy /etc/svc/profile/site.xml and /var/svc/profile/site.xml profiles. Note that /var/svc/profile is deprecated as a standard location. Do not put new profiles in the /var/svc/profile directory.	
system-profile	Any values from the /etc/svc/profile/generic.xml and /etc/svc/profile/platform.xml system profiles.	
manifest	Values from manifests in the /lib/svc/manifest and /var/svc/manifest directories. Note that /var/svc/manifest is deprecated as a standard location and should not be used for new manifests.	

Configuration conflicts are not permitted within any layer. Configuration that is set by using SMF commands, the sysconfig command, or SMF library interfaces overwrites the previous setting. If conflicting configuration is delivered by multiple files in any single layer, and is not set at a higher layer, the manifest-import service log reports the conflict, and the service with the conflicting configuration is not started. See "Conflicting Configuration" on page 90 for more information.

You can specify the layer of configuration data to view and therefore identify which data are administrative customizations and which data were delivered with the software. When an SMF client does not specify the layer from which to retrieve configuration data, the topmost layer data is provided. The topmost layer is determined by the order shown in the above table, where the admin layer is the topmost layer and the manifest layer is the lowest priority layer. If a property has a value in the admin layer, that is the value that the repository delivers. In this way, local customizations are preferred over the values that were provided when the system was installed.

Repository Snapshots

The repository captures a read-only *snapshot* of each service each time the service is successfully started. These snapshots enable you to easily return to a previous working state if necessary. The following snapshots might be available for any given instance:

initial	Initial configuration when the service and its instances were imported for the first time. An initial snapshot is not created if a profile starts the service or instance before manifest import.
previous	Current configuration captured when a manifest import is performed for a service that has already been delivered. The service could have already been delivered by the manifest being imported or by another manifest.
running	The running configuration of the service instance. When you change configuration data, use the svcadm refresh or svccfg refresh command to promote the new values to the running snapshot.
start	Configuration captured during a successful transition to the online state.

Repository Backups

SMF automatically takes the following *backups* of the service configuration repository:

 The boot backup is taken immediately before the first change to the repository is made during each system startup. ■ The manifest_import backups occur before svc:/system/early-manifest-import: default or svc:/system/manifest-import:default completes, if the service imported any new manifests or ran any upgrade scripts.

Four backups of each type are maintained by the system, with the oldest backups deleted as necessary.

You can restore the repository from one of these backups. See "How to Restore a Repository From Backup" on page 105.

Configuration Files and SMF Services

SMF is the recommended mechanism to use to start applications. In most cases, SMF replaces the use of configuration files for managing services. This section describes how some common legacy configuration scripts and files are handled.

/etc/rc?.d scripts

The /etc/rc?.d directories, where ? represents a run level, contain legacy initialization and termination scripts for managing services that execute on run level transitions. Most services that were formerly implemented by /etc/rc?.d scripts are managed by SMF. Some /etc/rc?.d scripts are retained to enable you to use third-party applications that expect these services as /etc/rc*.d scripts. These scripts are hard linked to files in the /etc/init.d directory. For information about /etc/rc?.d scripts and about run levels, see the /etc/init.d/README file, the README files in the /etc/rc?.d directories, and the inittab(4) man page. For instructions to convert a run control script, see "How to Convert a Run Control Script to an SMF Service" in Developing System Services in Oracle Solaris 11.3. After you convert an rc?d script, rename the script from Sscript to sscript to effectively remove the script.

/etc/init.d scripts

The /etc/init.d directory contains initialization and termination scripts for changing init states. Some of these scripts are hard linked to scripts in the /etc/rc?.d directories. For information about /etc/init.d scripts, see /etc/init.d/README and the init.d(4) man page.

Legacy init.d run control scripts are represented with SMF FMRIs that begin with lrc instead of svc. For example, the /etc/rc2.d/S47pppd PPP configuration script is represented by the lrc:/etc/rc2_d/S47pppd service. The state of these lrc services is legacy_run. As shown in the following example, you can list names and start times of legacy services, but you cannot administer these services by using SMF.

```
legacy_run 9:34:54 lrc:/etc/rc2_d/S89PRESERVE
$ svcs -l lrc:/etc/rc2_d/S47pppd
svcs: Operation not supported for legacy service 'lrc:/etc/rc2_d/S47pppd'
$ svccfg -s lrc:/etc/rc2_d/S47pppd listprop
svccfg: Operation not supported for legacy service 'lrc:/etc/rc2_d/S47pppd'
```

/etc/inittab entries

Entries in the /etc/inittab file control process dispatching by init. Do not edit the /etc/inittab file directly. Instead, modify SMF services. See "How to Modify a ttymon Property Value" on page 74 for an example of how to modify a parameter passed to ttymon.

For information about the format of /etc/inittab file entries, see the inittab(4) man page. For information about run levels, see the inittab(4) man page and /etc/init.d/ README.

/etc/inetd.conf file

Services that were formerly configured by using the inetd.conf file are now configured by using SMF. Configurations in the inetd.conf file must be converted to SMF services to be available for use. See "Converting inetd Services to SMF Services" on page 111. For inetd services that are already converted to SMF services, see "Modifying Services that are Controlled by inetd" on page 84.

```
/etc/nscd.conf file
/etc/nsswitch.conf file
/etc/resolv.conf file
```

Do not edit these files. Edits will be lost. These files are automatically generated from SMF data for backward compatibility with applications that might parse the file. Use the svccfg_setprop command to modify property values as shown in "Setting Property Values" on page 70.

The function of the nscd.conf file is replaced by the svc:/system/name-service-cache SMF service. See the nscd.conf(4) man page to see which name-service-cache properties to configure instead of editing the nscd.conf file.

The function of the nsswitch.conf file is replaced by the svc:/system/name-service/switch SMF service. See the nsswitch.conf(4) man page to see which name-service/switch properties to configure instead of editing the nsswitch.conf file.

The function of the resolv.conf file is replaced by the svc:/network/dns/client SMF service. See the resolv.conf(4) man page to see which dns/client properties to configure instead of editing the resolv.conf file.

These files are examples of configuration files that you should not edit. Other such files exist. In a few cases, editing a configuration file is the correct way to modify configuration, as described in "Modifying Services that are Configured by a File" on page 88. Before editing any configuration file, read any comments in the file and any associated man page to ensure that editing the file is the correct way to modify the configuration for the related service.

Service Management Privileges

Modifying service state and configuration requires increased privilege. Use one of the following methods to gain the privilege you need. See *Securing Users and Processes in Oracle Solaris* 11.3 for more information about roles, profiles, and authorizations, including how to determine which role or profile you need and how to assign privileges.

Roles

Use the roles command to list the roles that are assigned to you. Use the su command with the name of the role to assume that role. As this role, you can execute any commands that are permitted by the rights profiles that are assigned to that role. For example, if the role is assigned the Service Configuration rights profile, you can execute the svccfg and svcadm commands modify service properties and change service state.

Rights profiles

Use the profiles command to list the rights profiles that are assigned to you. Use one of the following methods to execute commands that your rights profiles permit you to execute:

- Use a profile shell such as pfbash or pfksh.
- Use the pfexec command in front of the command that you want to execute. In general, you must specify the pfexec command with each privileged command that you execute.

Authorizations

See the smf_security(7) man page for detailed information about authorizations required for SMF operations. You can also inspect a particular service for properties such as action_authorization, modify_authorization, read_authorization, and value_authorization. Individual services can require their own particular authorizations.

sudo command

Depending on the security policy at your site, you might be able to use the sudo command with your user password to execute a privileged command.



Getting Information About Services

This chapter shows how to get information about services such as the following:

- Service state, dependencies, and other property values
- Processes started by a contract service
- Log file location for troubleshooting
- FMA event and service transition event notification settings

Listing Services on the System

The svcs command is the primary command for listing service instance states and status.

Showing Service State

See "Service States" on page 23 for descriptions of the states shown in these examples.

EXAMPLE 1 Listing All Enabled Services

With no options or arguments, the svcs command lists all service instances that are enabled on this system, as well as instances that are temporarily disabled.

Service instances in the disabled state in this listing will be enabled on the next boot of the system. Instances in the legacy_run state are not managed by SMF. See "Configuration Files and SMF Services" on page 30 for more information about these legacy services. See "Getting More Information About Service States" on page 41 if you have services in the maintenance, degraded, or offline states.

The STIME column shows the time the instance entered the listed state. If the instance entered this state more than 24 hours ago, the STIME column shows the date.

\$ svcs STATE STIME FMRI

```
legacy_run
              Sep_09
                       lrc:/etc/rc2_d/S47pppd
legacy_run
              Sep_09
                       lrc:/etc/rc2_d/S81dodatadm_udaplt
legacy run
              Sep 09
                       lrc:/etc/rc2 d/S89PRESERVE
disabled
              Sep 09
                       svc:/system/vbiosd:default
online
              Sep 09
                       svc:/system/early-manifest-import:default
online
              Sep 09
                       svc:/system/svc/restarter:default
. . .
```

EXAMPLE 2 Listing All Installed Services

To list all service instances that are installed on this system, including disabled instances that will not be enabled automatically on next boot, use the svcs -a command.

```
$ svcs -a
```

An asterisk (*) is appended to the state for service instances that are transitioning from the listed state to another state. For example, offline* probably means the instance is still executing its start method.

A question mark (?) is displayed if the state is absent or unrecognized.

EXAMPLE 3 Listing All Instances of a Service

With a service name specified, the svcs command lists all instances of a service. See "Showing Selected Service Information" on page 36 for information about the -o option.

```
$ svcs -Ho inst identity
node
domain
```

Showing More Information About Services

The svcs -l command shows a long listing for each specified service instance including more detailed information about the instance state, paths to the log file and configuration files for the instance, dependency types, dependency restart attribute values, and dependency state. The following example shows that all of the required dependencies of this service instance are online. The one dependency that is disabled is an optional dependency. For information about dependency types and restart attribute values, see "Showing Service Dependencies" on page 36. In svcs -l output, states other than those described in "Service States" on page 23 are possible for dependencies. See the svcs(1) man page for descriptions. The following example also shows that the specified service instance is temporarily enabled, is online, and the service is a contract type service. See "Service Models" on page 22 for definitions of service types. If the state value has a trailing asterisk, for example offline*, then the instance is in transition, and the next state field shows a state value instead of none. The state time is the time the instance entered the listed state.

\$ svcs -l net-snmp

```
svc:/application/management/net-snmp:default
fmri
name
             net-snmp SNMP daemon
enabled
             true (temporary)
state
             online
next state
            none
state time
            September 17, 2013 05:57:26 PM PDT
             /var/svc/log/application-management-net-snmp: default.log
logfile
restarter
             svc:/system/svc/restarter:default
contract id 160
manifest
            /etc/svc/profile/generic.xml
manifest
            /lib/svc/manifest/application/management/net-snmp.xml
dependency require all/none svc:/system/filesystem/local (online)
dependency optional all/none svc:/milestone/name-services (online)
dependency
            optional all/none svc:/system/system-log (online)
dependency
            optional all/none svc:/network/rpc/rstat (disabled)
            require_all/restart svc:/system/cryptosvc (online)
dependency
dependency
             require_all/restart svc:/milestone/network (online)
dependency
             require_all/refresh file://localhost/etc/net-snmp/snmp/snmpd.conf (online)
dependency
             require all/none svc:/milestone/multi-user (online)
```

EXAMPLE 4 Showing Processes Started by a Contract Service

Use the svcs -p command to show the process IDs and command names of processes started by a contract service instance. The net-snmp service manages the /usr/sbin/snmpd SNMP agent that collects information about a system through a set of Management Information Bases (MIBs).

EXAMPLE 5 Showing a Contract Service Restarting Automatically After Process Stop

Contract service instances are automatically restarted if the contract empties. SMF also attempts to restart processes associated with a contract service instance as part of automatic recovery from hardware or software failure events. The following example shows that after the /usr/sbin/snmpd process is killed, it is automatically restarted with a new process ID. The net-snmp:default instance is still online and has a new start time.

Showing Selected Service Information

Output from the svcs command can be very useful for piping to other commands or using in scripts. The -o option of the svcs command enables you to specify the columns of information you want and the order of the columns. You can output the service name and instance name in separate columns, the current state and next state of the service, and the contract ID, for example. With the -s and -S options, you can specify the sort order of the output for one or more columns. See the COLUMNS section of the svcs(1) man page for a list of available columns. Multiple -s options behave additively.

Three additional pieces of information can be shown for periodic services. For information about periodic services, see Chapter 3, "Creating a Service to Run Periodically" in *Developing System Services in Oracle Solaris* 11.3 and the svc.periodicd(1M) man page.

LRUN The last time the start method of this periodic service instance ran.

Service instances that are not periodic display a hyphen character (-) in

this column.

NRUN The next time the start method of this periodic service instance is

scheduled to run. Service instances that are not periodic display a hyphen

character (-) in this column.

ASTATE The auxiliary state of the service instance. Service instances that are not

periodic instances use this property to show the reason that the instance made its most recent transition. Instances that are not periodic instances almost always show dependencies_satisfied as the value of this property, since this is usually the reason the instance transitioned from the offline to the online state. Periodic service instances can display either running or scheduled in this column to indicate whether the instance is waiting between start method executions. See "Specifying the periodic method Element" in *Developing System Services in Oracle*

Solaris 11.3 for more information.


Showing Service Dependencies

Dependency relationships govern service instance state transitions. See "Service Dependencies" on page 24 for a high-level description of dependencies. See *Developing System Services in Oracle Solaris 11.3* for detailed descriptions and how to specify different kinds of dependencies.

In the following figure, the svc1:default, svc2:default, and svc3:default service instances do not require any other services or any files or other resources to start. These instances can start in parallel, execute their start methods, and move to the online state without waiting on

any other resources. The svc4:default instance cannot execute its start method until the svc2: default instance is online. The svc5:inst1 instance needs both svc2:default resources and svc4:default resources. The dependency that svc5:inst1 has on svc4:default is an optional dependency and is satisfied if svc4:default is in one of the following states: enabled and online, disabled, or not present. The svc5:inst1 instance must wait until svc2:default is online, and if svc4:default is present and enabled, svc5:inst1 must also wait until svc4: default is online. If svc4:default is present and disabled or is not present, svc5:inst1 does not need to wait for svc4:default.

FIGURE 2 Service Dependency Relationships



Dependency Groupings

Each dependency is assigned to one of the following groupings. The grouping defines how dependencies in that grouping are satisfied.

require_all

This dependency is satisfied when both of the following conditions are met:

- All of the service dependencies in this grouping are running, either online or degraded.
- All of the file dependencies in this grouping are present.

require_any

This dependency is satisfied when either of the following conditions is met:

- At least one of the service dependencies in this grouping is running, either online or degraded.
- At least one of the file dependencies in this grouping is present.

optional all

This dependency is satisfied when all of the service dependencies in this group meet either of the following conditions:

- The service is running, either online or degraded.
- The service requires administrative action to run. The service is not present, is incomplete, is disabled, is in maintenance, or is offline waiting for dependencies that require administrative action to start.

File dependencies in this group can be present or not present.

This dependency is not satisfied if the service instance is in transition and does not require administrative intervention to start. In this case, the dependent service waits for this dependency to start or waits for the determination that the dependency cannot start without administrative action.

exclude_all

This dependency is satisfied when both of the following conditions are met:

- All of the service dependencies in this grouping are disabled, in maintenance, or not present.
- All of the file dependencies in this grouping are not present.

Listing Instances That a Service Depends On

The svcs -d command lists the service instances that a given service depends on.

This example shows the service instances that the system-repository service depends on:

\$ svcs -d system-repository

STATE	SITME	FMKI
online	Sep_09	<pre>svc:/milestone/network:default</pre>
online	Sep_09	<pre>svc:/system/filesystem/local:default</pre>
online	Sep_09	<pre>svc:/system/filesystem/autofs:default</pre>

The svcs -l command also lists the services that a given service depends on. In addition to the name and state of the dependency, the -l option output shows the type, or grouping, of the dependency and the value of the restart_on property of the dependency. In this example, two of the dependencies are required and one is optional. See "Dependency Groupings" on page 37 for descriptions of how dependencies in these groupings affect the dependent service. See "Dependency Groupings" on page 37 for descriptions of how different values of the restart_on property of the dependency affect the dependent service.

\$ svcs -l system-repository

svc:/application/pkg/system-repository:default

name IPS System Repository

enabled false state disabled next_state none

restarter svc:/system/svc/restarter:default

manifest /lib/svc/manifest/application/pkg/pkg-system-repository.xml dependency require all/error svc:/milestone/network:default (online) dependency require_all/none svc:/system/filesystem/local:default (online) dependency optional_all/error svc:/system/filesystem/autofs:default (online)

You can also use the sycprop command to list these dependencies. This form shows the grouping and restart on values of the dependency on separate lines, and does not show the state of the dependency.

\$ svcprop -g dependency system-repository:default

network/entities fmri svc:/milestone/network:default network/grouping astring require_all network/restart_on astring error network/type astring service filesystem-local/entities fmri svc:/system/filesystem/local:default filesystem-local/grouping astring require all filesystem-local/restart on astring none filesystem-local/type astring service autofs/entities fmri svc:/system/filesystem/autofs:default autofs/grouping astring optional all autofs/restart_on astring error autofs/type astring service

Listing Instances That Depend on a Service

The svcs -D command lists the service instances that depend on a given service.

This example shows the service instances that depend on the system-repository service:

\$ svcs -D system-repository

STATE STTME

online 16:39:30 svc:/application/pkg/zones-proxyd:default

The following command confirms that zones-proxyd depends on system-repository.

\$ svcs -do svc,desc zones-proxyd

DESC

application/pkg/system-repository IPS System Repository system/filesystem/minimal minimal file system mounts

milestone/network Network milestone The following command shows more information about how zones-proxyd depends on system-repository. The last line of this output shows that the zones-proxyd service requires the system-repository service to be running and shows that system-repository is currently running. This output also shows that the zones-proxyd service will be restarted if the system-repository service is refreshed.

\$ svcs -l zones-proxyd

fmri svc:/application/pkg/zones-proxyd:defaulr

name Zones Proxy Daemon

enabled true
state online
next_state none

state_time January 6, 2014 04:39:30 PM PST
restarter svc:/system/svc/restarter:default

manifest /lib/svc/manifest/application/pkg/zoneproxyd.xml

dependency require_any/none svc:/system/filesystem/minimal (online)

dependency require any/error svc:/milestone/network (online)

dependency require_all/restart svc:/application/pkg/system-repository (online)

Showing Whether a Service Will Automatically Restart

A running service can be configured to restart when one of its dependencies is stopped or refreshed. If dependencies of a running service (online or degraded state) are not satisfied, the service transitions to the offline state. If a service restarts after a dependency stop or refresh, dependencies might again be satisfied and the dependent service transitioned back to a running state.

The following factors determine whether a service is restarted after a require_all, require_any, or optional_all dependency is stopped or refreshed:

- Whether the dependency was stopped or refreshed. If stopped, whether the dependency was stopped because of an error such as a hardware error or a core dump or for some other reason such as an administrative action.
- The value of the restart_on attribute of the dependency. Possible values are none, error, restart, and refresh.

As shown in the following table, if the value of the restart_on attribute of the dependency is none, the dependent service is not restarted when the dependency is stopped or refreshed. If the value of the restart_on attribute of the dependency is refresh, the dependent service is always restarted when the dependency is stopped or refreshed. If the value of restart_on is error, the dependent service is only restarted if the dependency stopped because of an error. If the value of restart_on is restart, the dependent service is only restarted if the dependency was refreshed.

TABLE 1	Automatically Restar	ing a Service After a	Dependency Stop

require_all, require_any, Or optional_all Dependency	Value of Dep	Value of Dependency restart_on Attribute			
Stop or Refresh Event	none	error	restart	refresh	
Stop due to error	No restart	Restart	No restart	Restart	
Other stop	No restart	No restart	No restart	Restart	
Refresh	No restart	No restart	Restart	Restart	

"Listing Instances That a Service Depends On" on page 38 shows that the system-repository service has two require_all dependencies and one optional_all dependency. The following command shows that the system-repository service will be restarted if the milestone/network service or the system/filesystem/autofs service stops due to an error but not if they stop for any other reason or are refreshed. The system-repository service will not be restarted if the system/filesystem/local service is refreshed or stopped for any reason.

Getting More Information About Service States

With no arguments, the svcs -x command gives explanatory information about the following service instances:

- Instances that are enabled but not running.
- Instances that are preventing other enabled services from running.

If all enabled services are running, the svcs -x command produces no output.

In the following example, the pkg/depot service is in the maintenance state because its start method failed.

```
$ svcs -x
svc:/application/pkg/depot:default (IPS Depot)
State: maintenance since September 11, 2013 01:30:42 PM PDT
Reason: Start method exited with $SMF_EXIT_ERR_FATAL.
    See: http://support.oracle.com/msg/SMF-8000-KS
    See: pkg.depot-config(1M)
    See: /var/svc/log/application-pkg-depot:default.log
Impact: This service is not running.
```

The output suggests a Predictive Self-Healing knowledge article from My Oracle Support, a man page, and a log file to reference to determine why the start method failed. See "Viewing

Service Log Files" on page 42 for information about different ways to view log files. See "Repairing an Instance That Is Degraded, Offline, or in Maintenance" on page 99 for information about how to fix a service that is in the maintenance state.

In the following example, the print/server service has dependent services that are not running. The dependent services cannot run because the print/server service has been disabled.

```
$ svcs -x
svc:/application/print/server:default (LP print server)
 State: disabled since Fri Mar 08 14:42:32 2013
Reason: Disabled by an administrator.
  See: http://sun.com/msq/SMF-8000-05
  See: lpsched(1M)
Impact: 2 dependent services are not running. (Use -v for list.)
$ svcs -xv
svc:/application/print/server:default (LP print server)
State: disabled since Fri Mar 08 14:42:32 2013
Reason: Disabled by an administrator.
  See: http://sun.com/msg/SMF-8000-05
  See: man -M /usr/share/man -s 1M lpsched
Impact: 2 dependent services are not running:
       svc:/application/print/rfc1179:default
       svc:/application/print/ipp-listener:default
$ svcs -D print/server
                       FMRI
STATE
              STIME
              Mar 08
                      svc:/milestone/multi-user:default
online
offline
              Mar_08 svc:/application/print/ipp-listener:default
              Mar 08 svc:/application/print/rfc1179:default
offline
```

If an argument given to the svcs -x command does not meet the criteria stated at the beginning of this section, the output does not show any reason for the instance state but still shows resources for more information.

```
$ svcs -x smb
svc:/network/smb:default (SMB properties)
State: online since Thu Sep 12 19:16:56 2013
   See: smb(4)
   See: /var/svc/log/network-smb:default.log
Impact: None.
```

Viewing Service Log Files

SMF records information about significant restarter actions, method standard output, and standard error output to /var/svc/log/service:instance.log for each service instance. Hyphens are substituted for forward slashes in the service name in the log file name. The svcs

command with the -L, -l, or -x option shows the full path name of the log file for the specified service instance. The svcs -xL command shows the last few lines of the log file and tells you to use the svcs -Lv command to view the complete log file. The svcs -Lv command displays the complete file, which could be quite long. If you prefer to view the log file in an editor or view just the last n entries, for example, operate on the output of the svcs -L command.

The following example shows how to use the log file to investigate why the service shown in the svcs listing is temporarily disabled.

```
$ svcs
STATE
               STIME
                        FMRI
              Sep_09 lrc:/etc/rc2_d/S47pppd
legacy_run
              Sep_09 lrc:/etc/rc2_d/S81dodatadm_udaplt
legacy_run
               Sep 09 lrc:/etc/rc2 d/S89PRESERVE
legacy run
               Sep_09 svc:/system/vbiosd:default
disabled
               Sep 09 svc:/system/early-manifest-import:default
online
               Sep_09 svc:/system/svc/restarter:default
online
$ svcs -x vbiosd
svc:/system/vbiosd:default (BIOS call emulation)
 State: disabled since Mon Sep 9 18:42:37 2013
Reason: Temporarily disabled by service method: "vbiosd is not supported on UEFI
 systems."
  See: http://support.oracle.com/msg/SMF-8000-1S
  See: vbiosd(1M)
   See: /var/svc/log/system-vbiosd:default.log
Impact: This service is not running.
$ svcs -xL vbiosd
svc:/system/vbiosd:default (BIOS call emulation)
 State: disabled since Mon Sep 9 18:42:37 2013
Reason: Temporarily disabled by service method: "vbiosd is not supported on UEFI
 systems."
  See: http://support.oracle.com/msg/SMF-8000-1S
   See: vbiosd(1M)
  See: /var/svc/log/system-vbiosd:default.log
Impact: This service is not running.
  Loa:
[ Sep 9 18:42:27 Enabled. ]
[ Sep 9 18:42:37 Executing start method ("/lib/svc/method/svc-vbiosd start"). ]
[ Sep 9 18:42:37 Method "start" exited with status 101. ]
[ Sep 9 18:42:37 "start" method requested temporary disable: "vbiosd is not supported
 on UEFI systems"
  Use: 'svcs -Lv svc:/system/vbiosd:default' to view the complete log.
$ svcs -L vbiosd
/var/svc/log/system-vbiosd:default.log
$ view `svcs -L vbiosd`
```

Other log files that you might find useful include the log for the master restarter daemon and the system log. To see the log file name and view the log file for the svc.startd restarter daemon,

use the service name restarter with the svcs command. To see the log file name and view the log file for the syslogd system log daemon, use the service name system-log.

See "Specifying the Amount of Startup Messaging" on page 107 for instructions to change the amount of messaging you see on system boot. See "Configuring Notification of State Transition and FMA Events" on page 64 for instructions to configure services to notify you when they transition into or out of a service state or when an FMA event occurs.

Inspecting Service Configuration

Service configuration is expressed in properties that are set on services and service instances and stored in layers in the service configuration repository. Properties that are set on a service are inherited by all instances of that service. Properties that are set on an instance are used only by that instance. Service instances can customize the values of inherited properties and can define additional properties that are not defined for the parent service.

This section shows how to retrieve property values and how to identify whether the value is global for the service, is specific to an instance, was delivered with the software, or is an administrative customization.

Showing Descriptions of Properties and Property Groups

The svccfg describe command displays a description of the property groups and properties of a service, including the current values of properties. With no operands, describe shows descriptions of all property groups and properties of the selected service or service instance. Use the -v option to show more information, including a description of the current value and a list of possible values. Use the -t option to show template information.

```
maximum number of values: 1
value: none
  value description: Never restart due to dependency refresh, restart, or failure.
value constraints:
  value name: none
  value name: error
  value name: restart
  value name: refresh
```

Showing Service and Instance Property Values

The examples in this section describe how to view service and instance properties and property groups in different views, layers, and snapshots.

EXAMPLE 6 Listing Instance and Inherited Properties Currently in Use

By default, the svcprop command shows the values assigned to properties in the running snapshot, which are the values currently being used. By default, the svcprop command shows properties in the *composed view* of the running snapshot, which means that both instance-specific properties and inherited properties are shown. If the value of an inherited property is customized in the instance, the value set in the instance is shown. The output lists one line for each property, showing the property group and property name separated by a forward slash character, the data type of the property value, and the property value. If no property or group name is specified, all property values in the running snapshot are shown.

If the FMRI or pattern operand specifies the full service name but does not specify an instance, properties set only on the service are shown. Properties set only on an instance are not shown. The following command shows properties such as service dependencies, the type of the service, and the paths of the profile and manifest files.

\$ svcprop svc:/system/identity

When you specify an instance, you see the composed view of properties customized for that instance and properties inherited from the parent service. The following command lists all the properties in the running snapshot for the specified instance, including properties inherited from the parent service and properties specific to this instance. For inherited properties whose value is customized for this instance, the customized value is shown. This example shows properties such as additional dependencies, the path to the executable that starts this instance, the path to the log file for this instance, and information about the state of this instance.

\$ svcprop svc:/system/identity:domain

EXAMPLE 7 Listing Specified Properties or Property Groups Currently in Use

Use the -p option to show specific properties or all properties in a specific property group.

\$ svcprop -p pkg/port pkg/server svc:/application/pkg/server:oss:properties/pkg/port count 82 svc:/application/pkg/server:s11:properties/pkg/port count 81 svc:/application/pkg/server:default:properties/pkg/port count 80 \$ svcprop -p pkg pkg/server:s11 pkg/inst_root astring /export/ipsrepos/Solaris11 pkg/port count 81 ... pkg/ssl_cert_file astring "" pkg/ssl_key_file astring "" ...

EXAMPLE 8 Listing Service and Instance Values in the Editing View

With options, the svcprop command can show the *editing* view instead of the running snapshot. The editing view shows the most recent changes. The changes in the editing view might or might not have been committed into the running snapshot by refreshing or restarting the instance. The following commands illustrate the difference between the running snapshot and the editing view. The oss and s11 instances have just been created and property values have been changed, but the instances have not yet been refreshed.

The following command shows the composed view of the running snapshot. Because these instances have not been refreshed since they were customized, the values shown are values from the pkg/server service.

\$ svcprop -p pkg/port pkg/server

```
svc:/application/pkg/server:oss/:properties/pkg/port count 80
svc:/application/pkg/server:s11/:properties/pkg/port count 80
svc:/application/pkg/server:default/:properties/pkg/port count 80
```

The -c option shows the composed view of the editing values.

\$ svcprop -c -p pkg/port pkg/server

```
svc:/application/pkg/server:oss/:properties/pkg/port count 82
svc:/application/pkg/server:s11/:properties/pkg/port count 81
svc:/application/pkg/server/:properties/pkg/port count 80
```

The -C option shows the editing values without composition. Because this is not a composed view, no value is found for the instance that has not been customized.

\$ svcprop -C -p pkg/port pkg/server

```
svc:/application/pkg/server:oss/:properties/pkg/port count 82
svc:/application/pkg/server:s11/:properties/pkg/port count 81
svcprop: Couldn't find property 'pkg/port' for instance 'svc:/application/pkg/server:
default'.
```

The svccfg command displays the editing property values by default, not the values in the running snapshot. You can force svccfg to display values in the running snapshot by using the selectsnap subcommand as shown in "Showing Values in a Specified Snapshot" on page 50.

The svccfg command only shows values for the parent service when you specify a parent service and only shows values for an instance when you specify an instance. If you receive no output from the svccfg listprop command, the property you specified might not be set on the parent service or the instance that you specified. If the property was deleted, use listcust -M to view the masked value, as shown in "Showing Configuration Customizations" on page 51.

The following command lists all editing property values for the specified service because no property group or property name is specified. In addition to the output shown by the svcprop svc:/system/identity command, this output includes property group names and types and template data.

```
$ svccfg -s svc:/system/identity listprop
```

The following command lists all editing property values for the specified service instance. Because this command does not show the composed view, this output does not show the paths to the profile and manifest files, for example.

```
$ svccfg -s svc:/system/identity:domain listprop
```

EXAMPLE 9 Listing Specified Properties or Property Groups in the Editing View

The following command lists all editing property values in the specified property group for the specified service instance. The -o option enables you to select the columns to display. See the svccfg(1M) man page for the list of valid column names.

Showing Properties in a Property Group Type

In addition to showing property values by property name or property group name, you can also show property values by property group type.

```
EXAMPLE 10 Showing Property Groups and Their Types
```

The listpg subcommand of the svccfg command shows the name and type of each property group.

\$ svccfg -s pkg/server listpg

application pkg pkg application pkg_bui application pkg_secure application τs dependency autofs dependency fs dependency ntn dependency network dependency general framework manifestfiles framework start method stop method tm common name template \$ svccfg -s pkg/server:s11 listpg

application general framework

NONPERSISTENT restarter framework

Non-persistent property groups generally hold an active program state. Values of properties in non-persistent property groups are cleared during system boot.

Specify a property group name to show the type of only that property group.

```
$ svccfg -s pkg/mirror listpg config
config application
```

EXAMPLE 11 Listing Properties of a Property Group Type

Use the -g option of the svcprop command to show properties in a specific property group

\$ svcprop -g com.sun,fw_configuration smtp

```
firewall_config/apply_to astring ""
firewall_config/exceptions astring ""
firewall_config/policy astring use_global
firewall_config/value_authorization astring solaris.smf.value.firewall.config
```

Multiple -g options show properties from property groups of all specified types.

\$ svcprop -g application -g com.sun,fw_configuration smtp

```
config/include_info boolean false
config/local only boolean true
config/path_to_sendmail_mc astring ""
config/value authorization astring solaris.smf.value.sendmail
firewall config/apply to astring ""
firewall_config/exceptions astring ""
firewall config/policy astring use global
firewall_config/value_authorization astring solaris.smf.value.firewall.config
```

If you use both the -p and -g options, do not specify the name of the property group in the -p option value.

```
$ svcprop -g plugin -p path auditd
audit_binfile/path astring audit_binfile.so
audit_syslog/path astring audit_syslog.so
audit remote/path astring audit remote.so
```

Showing the Layer Where a Value Is Set

The service configuration repository stores property data in layers according to the source of the data. Both the svcprop and svccfg commands can show the layer that is the source of a property value. The -l option of the svcprop and svccfg commands requires an argument to specify the layer for which you want information. Argument values are manifest, system-profile, site-profile, and admin. The output indicates whether a specific property value was set in the service manifest, in a profile, or by an administrator or application. See "Repository Layers" on page 28 for descriptions of the layers. The keyword all is an alias for all layers. If the layer you specify is not the source of the property values you request, no output is shown.

The following command shows that some property values come from the service manifest and some were set by an administrator. Some properties have values in more than one layer. The pkg/readonly property has a value set in the service manifest, and an administrator also set that same value. Values from different layers could be different.

```
$ svcprop -l all -p pkg pkg/server:s11
pkg/port count admin 81
pkg/inst_root astring admin /export/ipsrepos/Solaris11
pkg/address net_address manifest
pkg/cfg_file astring manifest ""
...
pkg/readonly boolean manifest true
pkg/readonly boolean admin true
```

The -l option of the svccfg listprop command can also take the argument current. Using current as the -l argument shows the same property values that are shown when you do not use the -l option. The only difference in the output is that the name of the layer is also shown. The non-persistent data does not show a layer name (the third column displays <none>) because the service configuration repository does not store layer information for non-persistent data. Non-persistent property groups generally hold an active program state, and values of properties in non-persistent property groups are cleared during system boot.

\$ svccfg -s pkg/server:s11 listprop -l current

pkg	applicatio	on admin	
pkg/inst_root	astring	admin	/export/ipsrepos/Solaris11
pkg/port	count	admin	81
general	framework	admin	
general/complete	astring	manifest	
general/enabled	boolean	admin	true
restarter	framework	<none></none>	NONPERSISTENT

```
restarter/logfile
                                astring
                                                       /var/svc/log/application-pkg-
                                             <none>
server:default.log
restarter/contract
                                 count
                                             <none>
restarter/start pid
                                count
                                             <none>
restarter/start method timestamp time
                                                       1379605275.329096000
                                             <none>
restarter/start method waitstatus integer
                                             <none>
restarter/auxiliary_state astring
                                                       dependencies satisfied
                                             <none>
restarter/next_state
                                astring
                                             <none>
                                                       none
restarter/state
                                astring
                                             <none>
                                                       online
restarter/state timestamp
                                time
                                             <none>
                                                       1379605275.332259000
```

Showing the File that Contributed the Configuration

The following commands show that the localtime property is set to UTC in the service manifest and set to US/Pacific in a profile in the /etc/svc/profile/site directory. The value set at the site-profile layer is admin configuration and overrides the value set at the manifest layer.

```
$ svcprop -l all -p timezone/localtime system/timezone:default
timezone/localtime astring manifest UTC
timezone/localtime astring admin US/Pacific
$ svccfg -s system/timezone:default listprop -l all -o propname,layer,value \
> timezone/localtime
localtime admin US/Pacific
localtime manifest UTC
```

Use either the -f option or the -o file option of the svccfg listprop command to show the name of the file that contributed the configuration:

Showing Values in a Specified Snapshot

The following command lists the snapshots that are available for this service instance. Use these snapshot names with either svcprop or svccfg to show the values of properties that were set in that snapshot. Only instances have snapshots. Services do not have snapshots. See "Repository Snapshots" on page 29 for information about snapshots of the service configuration repository.

```
$ svccfg -s pkg/server:default listsnap
initial
previous
running
start
$ svccfg -s pkg/server:s11 listsnap
previous
running
start
```

The following commands show that the value of the pkg/inst_root property was different in the previous snapshot.

```
$ svcprop -s previous -p pkg/inst_root pkg/server:s11
/var/share/pkg/repositories/solaris
$ svccfg -s pkg/server:s11
svc:/application/pkg/server:s11> selectsnap previous
[previous]svc:/application/pkg/server:s11> listprop pkg/inst_root
pkg/inst_root astring /var/share/pkg/repositories/solaris
[previous]svc:/application/pkg/server:s11> exit
```

Showing Configuration Customizations

The svccfg listcust command displays customizations at the admin layer for the specified service. Use the -L option to also show customizations in the site-profile layer.

The following command shows all customizations at the admin layer of the pkg/server: solaris service:

\$ svccfg -s pkg/server:solaris listcust

general	framework	admin	
general/complete	astring	admin	
general/enabled	boolean	admin	true
pkg	application	admin	
pkg/inst_root	astring	admin	/export/pkgrepos/
solaris			
pkg/port	count	admin	83
pkg/readonly	boolean	admin	true
pkg/standalone	boolean	admin	false

The following command shows that the definition of the property config/nodename is provided at the manifest layer, but the value solaris is set at the admin layer.

The following command shows only admin layer customizations of the identity: node service:

```
$ svccfg -s identity:node listcust
config/loopback astring admin solaris
```

The following command shows all customizations of the identity:node service:

The svccfg listcust command also displays all *masked* entities. Use the -M option to list only masked entities. Before you use the svccfg delcust command, use the svccfg listcust command to verify what will be deleted. See "Deleting Property Groups, Properties, and Property Values" on page 79 and the smf(5) man page for a description of masked entities.

Showing Event Notification Parameters

The svcs -n command displays the FMA events notification parameters, system wide SMF state transition notification parameters, and service instance state transition notification parameters. See "Notification Parameters" in the smf(5) man page for information about these parameters.

```
$ svcs -n
Notification parameters for FMA Events
   Event: problem-diagnosed
       Notification Type: smtp
           Active: true
           reply-to: root@localhost
           to: root@localhost
       Notification Type: snmp
           Active: true
       Notification Type: syslog
           Active: true
   Event: problem-repaired
       Notification Type: snmp
           Active: true
   Event: problem-resolved
       Notification Type: snmp
           Active: true
```

System wide notification parameters:

```
svc:/system/svc/global:default:
    Event: to-maintenance
    Notification Type: smtp
         Active: true
         to: sysadmins@example.com

svc:/application/pkg/mirror:default:
    Event: to-maintenance
    Notification Type: smtp
         Active: true
         to: installteam@example.com
```

Three FMA events are shown: problem-diagnosed, problem-repaired, and problem-resolved. Notification parameters can also be configured for a fourth event: problem-updated.

For the system wide state transition notification setting, the service that stores these global settings is also listed. This system wide setting is a custom setting. System wide, or global, values apply to all service instances that do not have custom values set.

The last setting shown is a custom setting for a particular service instance.

Use the svccfg listnotify command to show notification parameters for only the specified event. For state transition events, use the -g option to show global settings. The output also shows the source of the notification parameter values.

```
$ svccfg listnotify problem-resolved
    Event: problem-resolved (source: svc:/system/fm/notify-params:default)
    Notification Type: snmp
    Active: true

$ svccfg listnotify -g to-maintenance
    Event: to-maintenance (source: svc:/system/svc/global:default)
    Notification Type: smtp
    Active: true
    to: sysadmins@example.com

$ svccfg -s pkg/mirror listnotify to-maintenance
    Event: to-maintenance (source: svc:/application/pkg/mirror)
    Notification Type: smtp
    Active: true
    to: installteam@example.com
```

See "Configuring Notification of State Transition and FMA Events" on page 64 for information about configuring event notification.



Administering Services

This chapter describes:

- How to start, stop, and restart a service
- How to reread service configuration
- How to configure the system to notify you of FMA events or service state transitions

The command that changes service state is svcadm. The svcadm command operates on a service instance. If you provide a service name with no instance specified, and that service has only a single instance, svcadm operates on that instance. If you provide a service name with no instance specified, and that service has multiple instances, or if you specify any other pattern that matches multiple instances, svcadm issues an error message.

Managing SMF Service Instances

A service instance is always in one of the states described in "Service States" on page 23. This section discusses how to cause an instance to transition to a different state, how to commit updated property values to the running snapshot, and how to delete instances from normal view.

Starting a Service

A service instance that is in any of the following states is already enabled and does not need to be started: degraded, maintenance, offline, online. If the instance you want to start is in the degraded, maintenance, or offline state, see "Repairing an Instance That Is Degraded, Offline, or in Maintenance" on page 99. If the instance you want to start is in the disabled state, enable the instance as shown in the following procedure. When you enable an instance, the restarter for that instance attempts to transition the instance to the online state.

▼ How to Enable a Service Instance

1. Check the instance state and dependencies.

Check that the instance is currently disabled and that all of its required dependencies are running (in the online or degraded state).

\$ svcs -l FMRI

2. Enable the instance.

The restarter for the service attempts to bring the specified instance to the online state.

An instance can be permanently or temporarily enabled. Permanent enable is persistent across system reboot and is the default. Temporary enable lasts only until reboot.

Permanently enable the instance.

\$ svcadm enable FMRI

Temporarily enable the instance.

Use the -t option to specify temporary enable.

\$ svcadm enable -t FMRI

If you want an instance to run now but not run on next reboot, make sure the instance is disabled, and then temporarily enable the instance. To verify that the instance is temporarily enabled, use the svcs -l command and check the enabled row:

enabled true (temporary)

Synchronously enable the instance.

If you specify the -s option, svcadm enables the instance and waits for the instance to enter the online or degraded state before returning. The svcadm command returns when the instance reaches an online state or when it determines that the instance requires administrator intervention to reach an online state.

Use the -T option with the -s option to specify an upper bound in seconds to make the transition or determine that the transition cannot be made.

\$ svcadm enable -sT 10 FMRI

3. Verify that the instance is online.

\$ svcs FMRI

If the instance is in the degraded, maintenance, or offline state, see "Repairing an Instance That Is Degraded, Offline, or in Maintenance" on page 99.

Example 12 Enabling a Service Instance Permanently

The following command shows that the pkg/mirror:default service instance is currently disabled, and all of its required dependencies are online.

\$ svcs -l pkg/mirror

```
fmri
             svc:/application/pkg/mirror:default
name
             IPS Repository Mirror
enabled
             false
            disabled
state
next_state none
state time September 17, 2013 07:16:52 AM PDT
restarter
             svc:/system/svc/restarter:default
manifest
            /lib/svc/manifest/application/pkg/pkg-mirror.xml
dependency require all/error svc:/milestone/network:default (online)
            require_all/none svc:/system/filesystem/local:default (online)
dependency
dependency
            optional all/error svc:/system/filesystem/autofs:default (online)
dependency
            require_all/none svc:/application/pkg/repositories-setup (online)
```

The following command enables the pkg/mirror:default instance. In this case, the svcadm command returns because the pkg/mirror:default instance is successfully enabled.

```
$ svcadm enable -sT 10 pkg/mirror:default
$ svcs pkg/mirror
```

STATE STIME FMRI

online 22:03:53 svc:/application/pkg/mirror:default

Example 13 Enabling a Service Instance Temporarily

The following command shows that the net-snmp:default service instance is currently disabled, and all of its required dependencies are online. The one dependency that is disabled is an optional dependency.

\$ svcs -l net-snmp

```
fmri
             svc:/application/management/net-snmp:default
name
             net-snmp SNMP daemon
enabled
             false
             disabled
state
next state
state time
            September 17, 2013 05:56:39 PM PDT
logfile
             /var/svc/log/application-management-net-snmp:default.log
restarter
             svc:/system/svc/restarter:default
contract id
manifest
             /etc/svc/profile/generic.xml
manifest
             /lib/svc/manifest/application/management/net-snmp.xml
dependency require all/none svc:/system/filesystem/local (online)
dependency
            optional all/none svc:/milestone/name-services (online)
dependency
            optional_all/none svc:/system/system-log (online)
dependency
            optional all/none svc:/network/rpc/rstat (disabled)
dependency
             require all/restart svc:/system/cryptosvc (online)
dependency
             require all/restart svc:/milestone/network (online)
```

```
dependency require_all/refresh file://localhost/etc/net-snmp/snmpd.conf (online)
dependency require all/none svc:/milestone/multi-user (online)
```

After enabling the instance using the -t option as shown in the following example, the instance is temporarily enabled, is online, and has a contract ID because it has started the snmpd process, as shown by the svcs -p command.

```
$ svcadm enable -t net-snmp:default
$ svcs -l net-snmp
            svc:/application/management/net-snmp:default
fmri
            net-snmp SNMP daemon
name
enabled
           true (temporary)
state
            online
next state none
state time September 17, 2013 05:57:26 PM PDT
logfile
            /var/svc/log/application-management-net-snmp:default.log
restarter
            svc:/system/svc/restarter:default
contract_id 160
            /etc/svc/profile/generic.xml
manifest
manifest
            /lib/svc/manifest/application/management/net-snmp.xml
dependency require_all/none svc:/system/filesystem/local (online)
dependency
            optional_all/none svc:/milestone/name-services (online)
dependency
            optional_all/none svc:/system/system-log (online)
dependency
            optional_all/none svc:/network/rpc/rstat (disabled)
            require_all/restart svc:/system/cryptosvc (online)
dependency
dependency
            require all/restart svc:/milestone/network (online)
dependency
            require all/refresh file://localhost/etc/net-snmp/snmp/snmpd.conf (online)
dependency
            require_all/none svc:/milestone/multi-user (online)
$ svcs -p net-snmp
        STIME
STATE
                       FMRT
              17:57:26 svc:/application/management/net-snmp:default
online
              17:57:26
                           5022 snmpd
```

Stopping a Service

Use the svcadm disable command to disable an enabled or temporarily disabled service instance. A disabled instance cannot be restarted. You must first enable the instance.

Note - Security best practice recommends that you periodically review your online services to assess whether any of them are no longer used and no longer need to be running.

How to Disable a Service Instance

- 1. Check whether other services depend on this instance.
 - a. List services that depend on this instance.

\$ svcs -D FMRI

b. Check whether the dependent service requires this instance.

For each result from the svcs -D command, use the svcs -l command to check whether the dependency is a required dependency.

You should not disable this instance if this instance is a required dependency of another service. See "Showing Service Dependencies" on page 36 for information about dependency groupings and restart on values.

2. Disable the instance.

The restarter for the service attempts to bring the specified instance to the disabled state. In general, the restarter for the service attempts to run the stop method if a stop method exists. The periodic restarter does not attempt to run any stop method because processes contracted by a periodic instance do not run persistently. Periodic instances run short-lived processes and then wait until the next scheduled time to run. See Chapter 3, "Creating a Service to Run Periodically" in *Developing System Services in Oracle Solaris 11.3* for more information.

An instance can be permanently or temporarily disabled. Permanent disable is persistent across system reboot and is the default. Temporary disable lasts only until reboot.

Permanently disable the instance.

\$ svcadm disable FMRI

■ Temporarily disable the instance.

Use the -t option to specify temporary disable.

```
\$ svcadm disable -t FMRI
```

If you want an instance to be disabled now but run on next reboot, make sure the instance is running (in the online or degraded state), and then temporarily disable the instance. To verify that the instance is temporarily disabled, use the svcs -l command and check the enabled row:

enabled false (temporary)

Synchronously disable the instance.

If you specify the -s option, svcadm disables the instance and waits for the instance to enter the disabled state before returning. The svcadm command returns when the instance reaches the disabled state or when it determines that the instance requires administrator intervention to reach the disabled state.

Use the -T option with the -s option to specify an upper bound in seconds to make the transition or determine that the transition cannot be made.

\$ svcadm disable -sT 10 FMRI

3. Verify that the instance is disabled.

\$ svcs FMRI

Example 14 Disabling a Service Instance

The following commands show that the Generic Security Service, rpc/gss, is online, and services that depend on the rpc/gss service are disabled:

The following command shows that even if the dependents were online, the rpc/gss service is an optional dependency and no attempt will be made to start the rpc/gss service if any of these three dependent services is refreshed or stopped for any reason:

The svcadm disable command is successful, the instance is currently in the disabled state, and the restart attempt fails.

Restarting a Service

The restart operation only restarts instances that are currently running (in the online or degraded state). You might need to restart a running instance because you have made a configuration change that cannot be effected while the instance is running, for example.

Restarting a service instance does not refresh configuration. In general, the svcadm restart command runs the stop method of the instance and then runs the start method of the instance. The periodic restarter runs only the start method. The svcadm restart command does not commit property changes into the running snapshot and does not run the refresh method of the instance. See "Rereading Service Configuration" on page 62 for information about committing configuration changes into the running snapshot.

Restarting the manifest-import service is a special case. Restarting the manifest-import service imports any changed manifests or profiles in standard locations, commits the changes into the service configuration repository, takes a new running snapshot, and runs the refresh method of changed instances if a refresh method exists.

▼ How to Restart a Service Instance

1. Check the instance state.

The instance must be in the online or degraded state.

\$ svcs FMRI

2. Restart the instance.

The restarter for the service attempts to bring the specified instance to the online state. Most restarters implement the restart operation as a stop operation followed by a start operation.

Restart the instance.

\$ svcadm restart FMRI

Synchronously restart the instance.

If you specify the -s option, svcadm restarts the instance and waits for the instance to enter the online, degraded, or maintenance state before returning. The svcadm command returns when the instance reaches one of these states or when it determines that the instance requires administrator intervention to reach one of these states.

Use the -T option with the -s option to specify an upper bound in seconds to make the transition or determine that the transition cannot be made.

\$ svcadm restart -sT 10 FMRI

3. Verify that the instance is started.

If the restart is successful, the instance is in the online, degraded, or maintenance state. If the instance is in the degraded or maintenance state, see "Repairing an Instance That Is Degraded, Offline, or in Maintenance" on page 99.

\$ svcs FMRI

Rereading Service Configuration

You can use the following methods to change service configuration:

- Use the svccfg setprop command.
- Edit the service manifest file.
- Edit a profile or provide a new profile associated with the service.

When you change service configuration or provide new configuration, those changes do not immediately appear in the running snapshot. To apply configuration changes, refresh the service instances. This implementation enables you to make multiple changes to multiple services and then apply all the changes at once.

To apply changes you made by using the svccfg setprop command, you must use either the svcadm refresh or svccfg refresh command. The service instance must have a refresh method and must be in the online or degraded state.

To apply changes you made by modifying or adding manifest files or profiles, you can use either the svcadm refresh or svccfg refresh command, or you can restart the manifest-import service. The service instance must be in the online or degraded state. The manifest-import service updates the configuration of all running instances whose manifests or profiles have changed. The manifest-import service does not apply configuration changes that you made by using the svccfg setprop command. In addition to manually restarting the manifest-import service, booting the system and many pkg operations also restart the manifest-import service.

The sycadm refresh and syccfg refresh commands both perform the following steps:

- 1. Create a new running snapshot to commit the editing properties into the running snapshot.
- 2. Run the refresh method of the instance, if a refresh method exists and the instance is in the online or degraded state. The refresh method should notify the application that changes have been made. The refresh method might reread property values from the running snapshot. Even if no refresh method exists, the configuration in the running snapshot is updated.

The periodic restarter does not attempt to run any refresh method. When a periodic instance is refreshed, the periodic restarter rereads the values of the properties in the periodic property group described in "Storing Periodic Service Data in the Service Configuration Repository" in *Developing System Services in Oracle Solaris* 11.3.

The svcadm refresh command operates on a service instance. The svccfg refresh command operates on a service instance or on a parent service. If a service is specified, the svccfg refresh command refreshes all instances of that service. While snapshots are taken only for service instances and not for parent services, parent service properties are inherited by service instances. Changed parent service properties appear in a service instance snapshot if the instance does not override those changes.

Some changes, such as dependency changes, take effect immediately. Other changes do not become effective until the service is restarted as described in "Restarting a Service" on page 60. Changes that cannot be made while the application is running require a refresh followed by a restart. Examples of changes that cannot be made while the application is running include closing or opening a socket or resetting an environment variable.

If you specify the -s option with the svcadm refresh command, svcadm refreshes the instance and waits for the instance to enter the online, degraded, or maintenance state before returning. The svcadm command returns when the instance reaches one of these states or when it determines that the instance requires administrator intervention to reach one of these states. Use the -T option with the -s option to specify an upper bound in seconds to make the transition or determine that the transition cannot be made.

Deleting a Service

The svccfg delete command does not remove a service instance from the system. Instead, the svccfg delete command masks the instance. After you run the svccfg delete command, the service manifest still exists in /lib/svc/manifest. SMF keeps the service configuration repository in sync with file system content. Since the manifest still exists on the file system in a standard location, that service information is still stored in the repository and is only masked from normal view. Any administrative customizations are deleted from a masked instance. See the smf(5) man page for a description of masked entities.

Files that support a service instance are updated when you use pkg commands, even if that service instance is masked. When files that support a service instance are updated by pkg commands, the SMF data store is updated even though the service is still masked from view. If the service instance is unmasked, that service instance is already updated from the files delivered by pkg with no further intervention needed. To unmask a service instance, see "How to Undo Deletion of a Service Instance" on page 64.

▼ How to Delete a Service Instance

1. Check the dependents of the instance to be deleted.

Use the svcs -D command to show instances that depend on this instance. After you delete this instance, dependent instances might not be able to run. Use the svcs -l command to check whether this instance is a required dependency of the dependent instance.

2. Mask the instance.

Use the svccfg delete command to mask the instance from normal view. Use the svcs command to show the state of the instance. If the instance is running (is in the online or degraded state), use the svccfg delete -f command to mask the instance from normal view.

```
$ svcs -H my-svc
disabled 7:25:37 svc:/site/my-svc:default
$ svccfg delete svc:/site/my-svc:default
```

3. Verify that the instance is masked.

Use the svccfg listcust -M command to confirm that the instance is masked. Commands such as svcs should display an error message that no matching instance is found.

▼ How to Undo Deletion of a Service Instance

1. Confirm that the instance is masked.

Use the svccfg listcust -M command as shown in the previous procedure.

2. Unmask the instance.

```
$ svccfg -s svc:/site/my-svc:default delcust
Deleting customizations for instance: default
```

Reimporting the manifest does not remove a mask.

3. Verify that the instance is unmasked.

Use the svccfg listcust -M command to confirm that the instance is not masked. The svcs command should display the state of the instance.

Configuring Notification of State Transition and FMA Events

You can configure the system to notify you when a service changes state or when an FMA event occurs. You can specify either Simple Mail Transfer Protocol (SMTP) or Simple Network Management Protocol (SNMP) notification.

SMF uses the system SNMP configuration. No SNMP configuration is required in SMF unless you want to change the default notification. By default, SNMP traps are sent on maintenance transitions. If you use SNMP for transition notification, you can configure additional traps for other state transitions. See snmp-notify(1M) for examples.

The following examples show how to set notification parameters for SMF and FMA events and how to delete notification parameters. If you receive a notification of a service in the maintenance, offline, or degraded state, use the svcs command to investigate, as described in "Repairing an Instance That Is Degraded, Offline, or in Maintenance" on page 99.

EXAMPLE 15 Configuring a Global Notification for a Service State Event

The following command creates a notification that sends email when services go into the maintenance state.

\$ svccfg setnotify -g to-maintenance mailto:sysadmins@example.com

-g The -g option sets this notification parameter for all service instances

that do not have custom values set. All modified service instances are refreshed. The -g option can only be used when setting notification for

service state transitions, not with FMA events.

to-maintenance The to-maintenance argument is a state transition event as described in

"Notification Parameters" in the smf(5) man page. Specifying only the state name includes both to-state and from-state transitions. This event

can also be a comma separated list of transitions.

mailto: The mailto argument specifies the notification you want to receive for

the specified event. This argument could also specify snmp. An snmp notification value must be either snmp:active or snmp:inactive. A mailto notification value can be either mailto:active or mailto:inactive, in addition to the form shown in this example. Setting a notification parameter overwrites any existing value for that event. The active and inactive settings do not overwrite existing values but toggle

whether the existing notification is in effect for the specified event.

EXAMPLE 16 Configuring Notification for Multiple State Events

This example notifies whenever the system shuts down, successfully boots, or fails to boot. The following command creates a notification that sends email when services transition into the online state, out of the online state, or into the maintenance state. Specifying online is equivalent to specifying both to-online and from-online.

\$ svccfg setnotify -g online,to-maintenance mailto:sysadmins@example.com

EXAMPLE 17 Configuring a Notification for a Specified Service Instance

The following command creates a notification that sends email when the pkg/mirror service transitions into the maintenance state.

\$ svccfq -s pkg/mirror setnotify to-maintenance mailto:installteam@example.com

The following command creates a notification that sends email when the http:apache22 service transitions out of the online state.

\$ svccfg -s http:apache22 setnotify from-online mailto:webservices@example.com

EXAMPLE 18 Configuring a Notification for an FMA Event

The problem-diagnosed argument is an FMA event. This argument can be a comma separated list of FMA events. See the list of FMA events in "Notification Parameters" in the smf(5) man page.

\$ svccfg setnotify problem-diagnosed mailto:IT@example.com

EXAMPLE 19 Deleting Notification Settings

The following commands delete the notification settings set in the previous examples.

- \$ svccfg delnotify -g to-maintenance
- \$ svccfg -s pkg/mirror delnotify to-maintenance
- \$ svccfg setnotify problem-diagnosed mailto:root@localhost

· · · CHAPTER 4

Configuring Services

SMF stores configuration data in the service configuration repository. Configuring SMF services means modifying the data in the configuration repository and then committing the modifications into the running snapshot. This chapter describes how to modify the data in the configuration repository. For viewing data in the configuration repository, see "Inspecting Service Configuration" on page 44. For committing configuration modifications into the running snapshot, see "Rereading Service Configuration" on page 62.

Each service and service instance stores configuration data in properties, which are organized into property groups. Modifying the data in the configuration repository includes modifying service property values, creating custom property groups and properties, creating new instances of a service, and applying a profile. Modifying configuration also includes deleting customizations and reverting repository snapshots.

This chapter describes:

- Adding and modifying property values
- Adding and deleting properties and property groups
- Adding service instances
- Reverting snapshots
- Importing and applying service manifests and profiles
- Modifying services that are controlled by inetd
- Modifying services that are configured by a file

SMF configuration changes can be logged by using the Oracle Solaris auditing framework. Refer to "Configuring the Audit Service" in *Managing Auditing in Oracle Solaris 11.3* for more information.

Using the Service Configuration Command

The svccfg command manipulates data in the service configuration repository. Changes made with the svccfg command are recorded in the admin layer. See "Repository Layers" on page 28 for information about layers. Changes made with the svccfg command are stored in the service

configuration repository as current, or editing, property values, and do not immediately appear in the running snapshot. When you change configuration data, use the svcadm refresh or svccfg refresh command to commit the new values into the running snapshot.

Keeping newly changed data separate from the running snapshot enables you to make multiple changes, and then commit all the changes to the running snapshot together. While you are in the process of making multiple changes, some property values might be incompatible or inconsistent, but the running snapshot is unmodified. When you are finished making changes, perform a refresh.

You can use the svccfg command in any of the following ways:

- Use the svccfg editprop command to invoke an editor on the property groups and properties of the currently selected entity.
- Enter a full svccfg command on the command line, specifying subcommands such as setprop.
- Enter only syccfg or syccfg -s *FMRI* on the command line to start an interactive session.
- Specify the -f option to read svccfg commands from a file.

Invoking a Property Editor

Invoking the svccfg command as shown in the following example opens an editor on the properties of the selected entity. This form of the svccfg command can be very fast and convenient for modifying several property values. For the editprop subcommand, you must specify an entity with the -s option.

```
$ svccfg -s pkg/server:s11 editprop
```

A file of setprop commands for the current values of each property of the specified entity opens in the editor specified by the VISUAL environment variable. If VISUAL is not defined, the editor specified by EDITOR is opened. If neither VISUAL nor EDITOR is defined, the property file is opened in vi.

Each line of the file is preceded by a comment character. To change the value of a property in the svccfg editing configuration, remove the comment character, change the value, and save the file. To change the value of a property in the running snapshot, remove the comment character from the last line of the file, which is the refresh subcommand.

The following listing shows a partial example of a file created by the editprop subcommand:

```
##
## Change property values by removing the leading '#' from the
## appropriate lines and editing the values. svccfg subcommands
## such as delprop can also be added to the script.
```

```
##
## Property group "pkg"
## The following properties are defined in the selected instance
## (svc:/application/pkg/server:s11)

# setprop pkg/port = count: 81
# setprop pkg/inst_root = astring: /export/ipsrepos/Solaris11

## The following properties inherit from the parent service
## (svc:/application/pkg/server)

# ...

## Property group "pkg_bui"

# ...

## Property group "pkg_secure"

# ...

## Uncomment to apply these changes to this instance.
# refresh
```

As the instructions in the file state, you can add subcommands other than setprop. For example, you could add a delprop command. Some property groups, such as framework and dependency, are not displayed by default. Specify editprop -a to show all properties.

The uncommented commands in this temporary file are executed when you save and quit the editing session.

Invoking svccfg Interactively or With a File

Invoking the svccfg command interactively as shown in the following example can be convenient when you want to perform several configuration operations.

```
$ svccfg
svc:> select pkg/server
svc:/application/pkg/server> list
:properties
default
svc:/application/pkg/server> add s11
svc:/application/pkg/server> select s11
svc:/application/pkg/server:s11> setprop pkg/inst_root=/export/ipsrepos/Solaris11
svc:/application/pkg/server:s11> setprop pkg/port=81
svc:/application/pkg/server:s11> unselect
svc:/application/pkg/server> add oss
svc:/application/pkg/server> select oss
```

```
svc:/application/pkg/server:oss> setprop pkg/inst_root=/export/ipsrepos/SolarisStudio
svc:/application/pkg/server:oss> setprop pkg/port=82
svc:/application/pkg/server:oss> unselect
svc:/application/pkg/server> list
:properties
default
s11
055
svc:/application/pkg/server> refresh
svc:/application/pkg/server> select pkg/mirror:default
svc:/application/pkg/mirror:default> listprop config/crontab_period
config/crontab_period astring
                                  "30 2 25 * *"
svc:/application/pkg/mirror:default> setprop config/crontab_period="00 3 25 * *"
svc:/application/pkg/mirror:default> refresh
svc:/application/pkg/mirror:default> exit
```

The same commands given at the interactive prompts in the preceding example could also be provided in a file and executed with a command such as the following command.

```
$ svccfg -f cfgpkgrepos
```

Setting Property Values

The following commands set property values:

```
svccfg setprop
Changes the value of a property.

svccfg addpropvalue
Adds a value to a multi-value property.

svccfg setenv
```

Changes the value of an environment variable for a service process execution environment.

Remember to use the svccfg refresh command or svcadm refresh command to commit configuration changes into the running snapshot.

```
EXAMPLE 20 Setting a Simple Value
```

In the simplest use of setprop, specify a *pg/name* for the selected service or instance, where *pg* is the name of the property group and *name* is the name of the property, and specify the new value after an equals symbol. If the property already exists or is templated, you do not need to specify the property type.

\$ svccfg -s pkg/server:sll setprop pkg/port=81

EXAMPLE 21 Setting a Value that Contains a Colon Character

If the property value contains a colon character (:), then specify the property type as shown in the following example where the type is astring:

```
$ svccfg -s system-repository:default setprop config/http_proxy = astring: https:
//proxyURI
```

Use the listprop subcommand to find the type of the property you want to set.

```
$ svccfg -s system-repository:default listprop config/http_proxy
config/http_proxy astring
```

EXAMPLE 22 Setting a Value that Contains Embedded Spaces

Use double quotation marks to set a value that contains embedded spaces. Depending on your shell, you might need to enclose the double-quoted string in single quotation marks.

```
$ svccfg -s pkg/mirror setprop config/crontab_period = "00 3 25 * *"
$ svccfg -s pkg/mirror setprop config/crontab_period = '"00 3 25 * *"'
```

Use quotation marks to set a value that contains double quotation marks or backslash characters, and use a backslash character to escape any double quotation marks or backslash characters.

EXAMPLE 23 Setting a Value that Is a Set of Values

Use parentheses to specify a set of values as a single value. Depending on your shell, you might need to enclose the value set in single quotation marks as well.

```
$ svccfg -s dns/client setprop config/nameserver = (10.0.0.1 192.168.0.1)
$ svccfg -s dns/client setprop config/nameserver = '(10.0.0.1 192.168.0.1)'
$ svccfg -s dns/client listprop config/nameserver
config/nameserver net address 10.0.0.1 192.168.0.1
```

Use the describe subcommand to find the number of values allowed in the set of values.

```
$ svccfg -s dns/client describe -v config/nameserver
config/nameserver net_address 10.0.0.1 192.168.0.1
   type: net_address
   required: false
   The IP address of a DNS nameserver to be used by the resolver.
   visibility: readwrite
   minimum number of values: 1
   maximum number of values: 3
   value: 10.0.0.1
```

value: 192.168.0.1

EXAMPLE 24 Adding a Value

Use the addpropvalue subcommand to add the given value to the specified property of the selected service or service instance. The new value is appended to the end of the existing list of property values for the property.

```
$ svcprop -p keymap/layout keymap:default
US-English
$ svccfg -s keymap:default addpropvalue keymap/layout UK-English
$ svccfg -s keymap:default listprop keymap/layout
keymap/layout astring "US-English" "UK-English"
```

In the previous setprop example, all values in the set of values must be specified at once. If only one value is specified, that value becomes the new set of one value. In this addpropvalue example, the added values are distinct. To access these added values, you must use the libscf function scf_iter_property_values() to iterate over the values. While listprop lists both values, describe lists only the first value and reports that the maximum allowed number of values for this property is one.

\$ svccfg -s keymap:default describe -v keymap/layout

```
keymap/layout astring US-English
type: astring
required: true
The keyboard layout
visibility: readwrite
minimum number of values: 1
maximum number of values: 1
value: US-English
```

▼ How to Schedule a Periodic or Scheduled Service

A periodic or scheduled service runs its start method on a cadence or at a time that you specify by setting property values of the service.

1. Confirm that the service you want to schedule is a periodic or scheduled service.

The following command lists all periodic and scheduled services on the system because it lists all instances whose restarter is the periodic-restarter service:

```
$ svcs -R svc:/system/svc/periodic-restarter:default
```

You could also use svcs -l, svcprop, or svccfg to show the value of the general/restarter property.

2. Show the current schedule for the service.

The following command shows whether the instance is a periodic service or a scheduled service. A periodic service has a periodic property group, and a scheduled service has a scheduled property group:

\$ svcprop -p periodic -p scheduled FMRI

If *FMRI* is a periodic service, the values of the periodic/period property and any other periodic properties that are set are shown. An error message is shown for the scheduled property group.

If *FMRI* is a scheduled service, the values of the scheduled/interval and scheduled/frequency properties and any other scheduled properties that are set are shown. An error message is shown for the periodic property group.

3. Change the schedule.

Properties that have no value are not shown by the svcprop or svccfg listprop commands. Use the following references to decide which properties to set to achieve the schedule you want:

- For periodic services, see "Specifying the periodic_method Element" in *Developing System Services in Oracle Solaris 11.3* and "Scheduling Executions of a Periodic Service Start Method" in *Developing System Services in Oracle Solaris 11.3*. Only the periodic/period property is required to schedule a periodic service. Other properties are optional.
- For scheduled services, see "Specifying the scheduled_method Element" in *Developing System Services in Oracle Solaris 11.3* and "Scheduling Executions of a Scheduled Service Start Method" in *Developing System Services in Oracle Solaris 11.3*. The scheduled/interval and scheduled/frequency properties are required to schedule a scheduled service.

If you set a property that has not been set before, you must specify the property type as shown in Example 21, "Setting a Value that Contains a Colon Character," on page 71. If you reset that property value, you do not need to specify the property type again. Also, if you set a property that has not been set before, you will see the following message:

Type required for new properties.

4. Read the modified property values.

Use the svcadm or svccfg command to refresh the service instance. Use the svcprop command again to verify that the periodic or scheduled property values are updated.

5. Verify that the service instance is online.

The instance might have been disabled while you were modifying property values, or the instance might have gone into maintenance when you performed the refresh. If the instance is in maintenance, view the log file as described in "Viewing Service Log Files" on page 42. Possible problems include the following:

 Conflicting properties are set. For example, you cannot set both the scheduled/ day of month and scheduled/day property values. Not all required properties are set. For example, you cannot set just the day and minute, you
must also set the hour.

For more information about moving a service out of the maintenance state, see "How to Repair an Instance That Is in Maintenance" on page 100.

6. Verify the schedule.

The following command shows the next time the service will run:

```
\$ svcs -o nrun FMRI
```

If no schedule is shown, make sure the instance is online.

Example 25 Scheduling the Compliance Assessment Service

The following command shows that the compliance assessment service is currently scheduled to run once each week:

```
$ svcprop -p scheduled compliance:default
scheduled/frequency integer 1
scheduled/interval astring week
```

With this schedule, the instance can run at any time on any day the first week. Subsequent runs will then occur some time that same day in future weeks.

The following commands set the instance to invoke its start method some time between 3am and 4am every Wednesday:

```
$ svccfg -s compliance:default
```

▼ How to Modify a ttymon Property Value

This procedure shows how to modify parameters passed to ttymon.

1. Identify the service to modify.

The ttymon(1M) man page states that the service to modify is svc:/system/console-login. The ttymon(1M) man page also contains descriptions of the properties in the ttymon property group.

The following command shows multiple instances of the console-login service in this image and shows that the default instance is the only instance currently online:

\$ svcs console-login

```
STATE STIME FMRI
disabled 10:49:43 svc:/system/console-login:terma
disabled 10:49:43 svc:/system/console-login:termb
online 10:50:54 svc:/system/console-login:default
```

2. Identify the property to modify.

The following command shows the name, data type, value, and a brief description of each property in the ttymon property group in the default instance:

\$ svccfg -s console-login:default describe ttymon ttymon application ttymon/device astring /dev/console The terminal device to be used for the console login prompt. ttymon/terminal_type astring Sets the initial value of the TERM environment variable

The preceding output shows no value for the terminal_type property. The following command confirms that the value of the ttymon/terminal_type property of the console-login:default instance is currently null:

```
$ svcprop -p ttymon/terminal_type console-login:default
""
```

3. Modify the property value.

Enter the following command to change the value of the ttymon/terminal_type property of the console-login:default instance to xterm:

```
$ svccfg -s system/console-login:default setprop ttymon/terminal_type=xterm
```

4. Commit the new value into the running snapshot.

The following output shows that the value of the terminal_type property is changed in the editing configuration but not in the running snapshot:

After you refresh the service instance, the property value is changed in the running snapshot:

```
$ svcadm refresh console-login:default
```

```
$ svcprop -p ttymon/terminal_type console-login:default
xterm
```

▼ How to Modify an Environment Variable for a Service Process Environment

This procedure shows how to set a value for an environment variable in the environment where processes started by the service will run.

The example in this procedure shows how to modify cron environment variables to help with debugging.

1. Verify that the service is running.

The following output shows that the cron service is online and a cron process is running.

2. Set environment variables.

The setenv subcommand sets an environment variable for the environment where a process started by a service or service instance will run.

Use the following command to check the current values of the environment variables you want to set:

```
$ pargs -e `pgrep -f /usr/sbin/cron`
```

The environment variables that are set in this example do not have any current values. The following commands set the UMEM_DEBUG and LD_PRELOAD environment variables for the /usr/sbin/cron process started by the svc:/system/cron:default service instance:

```
$ svccfg -s system/cron:default setenv UMEM_DEBUG default
$ svccfg -s system/cron:default setenv LD_PRELOAD libumem.so
```

3. Refresh and restart the service.

Changing an environment variable value requires a restart as well as a refresh to take effect.

```
$ svcadm refresh system/cron:default
$ svcadm restart system/cron:default
```

4. Verify that the change has been made.

The following output shows that the service has been restarted, the process has a new process ID, and the two environment variables are set for that process environment.

```
$ svcs -p cron
        STIME FMRI
STATE
online
               9:24:39 svc:/system/cron:default
               9:24:39
                           5601 cron
$ svcprop -g method -p environment system/cron:default
start/environment astring LD_PRELOAD=libumem.so UMEM_DEBUG=default
$ pargs -e `pgrep -f /usr/sbin/cron`
5601: /usr/sbin/cron
envp[0]: LOGNAME=root
envp[1]: LD PRELOAD=libumem.so
envp[2]: PATH=/usr/sbin:/usr/bin
envp[3]: SMF_FMRI=svc:/system/cron:default
envp[4]: SMF METHOD=start
envp[5]: SMF RESTARTER=svc:/system/svc/restarter:default
envp[6]: SMF ZONENAME=global
envp[7]: UMEM DEBUG=default
```

See Also The unsetenv subcommand unsets an environment variable for a process started by a service or service instance.

Adding Property Groups, Properties, and Property Values

The following commands add properties and property groups:

```
svccfg setprop
svccfg addpropvalue
```

Adds the property whose value is being set if the property does not already exist.

svccfg addpg

Adds a new property group to a service or service instance.

Remember to use the svccfg refresh command or svcadm refresh command to commit configuration changes into the running snapshot.

EXAMPLE 26 Using addpg to Create a New Property Group

Use the addpg subcommand to add a property group to the selected service or service instance.

```
svccfg -s FMRI addpg name type [flags]
```

type By convention, the value of *type* is usually application. See *Developing*

System Services in Oracle Solaris 11.3 for more information about

property group types.

flags

Specify P for the value of *flags* to store the property group and any added properties as non-persistent. If P is specified, this property group and contained properties will be automatically removed on reboot, The value P is an alias for SCF_PG_FLAG_NONPERSISTENT. See the scf service add pg(3SCF) man page.

```
$ svccfg -s svc:/site/my-svc addpg config application
$ svccfg -s my-svc listprop config
config application
$ svccfg -s my-svc:default listprop config
```

In this example, the administrator added the config property group to the parent service, my-svc, but not to the instance, my-svc:default. The listprop command shows that the config property group does not exist in the service instance.

EXAMPLE 27 Using setprop to Create a New Property

Use the setprop subcommand to set a property value as described in "Setting Property Values" on page 70. If the property group does not already exist in the selected instance or service, the property group is created if the type and flags are found in the template definitions. If the property does not already exist in the selected instance or service, you must specify the property *type*.

```
$ svccfg -s my-svc:default setprop config/vendor = astring: vendora
$ svccfg -s my-svc:default listprop config/vendor
config/vendor astring vendora
```

EXAMPLE 28 Using addpropralue to Create a New Property

Use the addpropvalue subcommand to add a property value as described in "Setting Property Values" on page 70. If the property group does not already exist in the selected instance or service, the property group is created if the type and flags are found in the template definitions. If the property does not already exist in the selected instance or service, you must specify the property *type*.

```
$ svccfg -s my-svc:default addpropvalue config/vendor astring: vendorb
$ -s my-svc:default addpropvalue config/customer astring: acustomer
$ svccfg -s my-svc:default listprop config
config application
config/vendor astring "vendora" "vendorb"
config/customer astring acustomer
```

Deleting Property Groups, Properties, and Property Values

The following commands delete property values, properties, and property groups:

```
svccfg setprop
```

Delete all values of a property.

svccfg delpropvalue

Delete all values of the specified property that match the specified pattern.

svccfg delprop

Delete a property.

svccfg delpg

Delete a property group.

svccfg delcust

Delete administrative customizations.

Remember to use the svccfg refresh command or svcadm refresh command to commit configuration changes into the running snapshot.

Deleting Administrative Configuration

Configuration modifications made by using svccfg commands or libscf calls modify only the admin layer of the service configuration repository. See "Repository Layers" on page 28 for information about layers. When you delete configuration that is only defined in the admin layer and does not exist in any other layer, that configuration is gone. Commands that display configuration no longer show the deleted configuration, even when you use the -l option to show all layers of the service configuration repository. See "Deleting Non-Administrative Configuration" on page 81 for information about deleting configuration that exists in other layers.

EXAMPLE 29 Deleting All Values of a Property

Use the setprop subcommand as described in "Setting Property Values" on page 70. To delete all values of a property, do not specify any type or value. The values are deleted, but the property still exists.

```
$ svccfg -s my-svc:default setprop config/vendor =
$ svccfg -s my-svc:default listprop config/vendor
config/vendor astring
```

EXAMPLE 30 Deleting All Matching Values of a Property

Use the delpropvalue subcommand to delete all values of the named property that match the given pattern.

```
$ svccfg -s my-svc:default setprop config/tool = astring: '(hammer tongs wrench)'
$ svccfg -s my-svc:default listprop config
               application
config/customer astring acustomer
config/vendor astring
                          "vendora" "vendorb"
config/tool astring
                          "hammer tongs wrench"
$ svccfg -s my-svc:default delpropvalue config/vendor '*b'
$ svccfg -s my-svc:default delpropvalue config/tool 'tong*'
$ svccfg -s my-svc:default listprop config
confia
               application
config/customer astring acustomer
config/vendor astring vendora
config/tool astring
                          "hammer tongs wrench"
$ # config/tool is a single value that is a value set
$ svccfg -s my-svc:default delpropvalue config/tool '*tong*'
$ svccfg -s my-svc:default listprop config
confia
              application
config/customer astring
                          acustomer
config/vendor astring
                          vendora
config/tool
              astring
```

EXAMPLE 31 Deleting a Property

Use the delprop subcommand to delete the named property of the selected service or service instance.

```
$ svccfg -s my-svc:default delprop config/tool
$ svccfg -s my-svc:default listprop config
config application
config/customer astring acustomer
config/vendor astring vendora
```

EXAMPLE 32 Deleting a Property Group

The delpg and delprop subcommands both can delete a property group. The delpg subcommand deletes the named property group of the selected service or service instance. The delprop subcommand deletes the named property group if no property is named.

```
$ svccfg -s my-svc:default delpg config
$ svccfg -s my-svc:default listprop config
$
```

EXAMPLE 33 Deleting Customizations

The delcust subcommand deletes administrative customizations on the selected service or service instance. Before you use the delcust subcommand, use the listcust subcommand with the same pattern or option to see what will be deleted. If a pattern is given, the pattern must match a property or property group.

\$ svccfg -s my-svc:default listcust application admin confia config/customer astring admin acustomer "vendora" "vendorb" config/vendor astring admin config/tool astring admin "hammer tongs wrench" \$ svccfg -s my-svc:default listcust '*tool' config/tool astring admin "hammer tongs wrench" \$ svccfg -s my-svc:default delcust '*tool' Deleting customizations for property: config/tool \$ svccfg -s my-svc:default listcust '*tool' \$ svccfg -s my-svc:default listcust config application admin config/customer astring admin acustomer config/vendor astring admin "vendora" "vendorb"

Deleting Non-Administrative Configuration

Configuration that exists in the site-profile, system-profile, and manifest layers of the service configuration repository is defined in service manifests and profile files. See "Repository Layers" on page 28 for information about layers. SMF keeps the service configuration repository in sync with file system content. Any configuration that is defined in a manifest or profile file in a standard location still exists on the file system after administrative customization, including after being deleted, and is still stored in the service configuration repository. Configuration that is defined in a manifest or profile is said to have bundle support. When you delete configuration that has bundle support, the information is not deleted from the file system but is *masked* so that it is not seen in the normal view. See the smf(5) man page for a description of masked entities.

Deleting configuration that has bundle support is an administrative customization. In this case, the delcust subcommand *unmasks* the configuration, rather than deleting anything. Use the listcust -M subcommand to view masked configuration. Use the delcust -M subcommand to unmask configuration, or undo the deletion or masking of the configuration.

EXAMPLE 34 Deleting Configuration that has Bundle Support

In "Deleting Administrative Configuration" on page 79, the config property group of the my-svc service only existed in the admin layer. The config property group did not exist in any manifest or profile. When those properties were deleted, they were gone from the system. This example shows the different result when you delete configuration that has bundle support.

The property is defined in the service manifest:

After deletion, the property is not displayed by using listprop with no options. Because the property has bundle support, the property still exists in the service configuration repository and can be displayed by using the -l or -M options with the listprop subcommand.

```
$ svccfg -s pkg/server listprop pkg/inst_root
$ svccfg -s pkg/server listprop -l all pkg/inst_root
pkg/inst_root astring admin MASKED /export/ipsrepos/Solaris11
pkg/inst_root astring manifest MASKED /var/pkgrepo
$ svccfg -s pkg/server listcust -M
pkg/inst_root astring admin MASKED /export/ipsrepos/Solaris11
```

EXAMPLE 35 Unmasking Configuration

When you unmask the property, both customizations are gone:

- The property is no longer masked or hidden.
- The property no longer has its customized value.

```
$ svccfg -s pkg/server delcust -M
Deleting customizations for property: pkg/inst_root
$ svccfg -s pkg/server listprop -l all pkg/inst_root
pkg/inst_root astring manifest /var/pkgrepo
$ svccfg -s pkg/server listprop pkg/inst_root
pkg/inst_root astring /var/pkgrepo
```

Adding Service Instances

Instances of a service allow multiple configurations of a service to run simultaneously. Service instances inherit and customize common service configuration.

Use the add subcommand to create a new entity with the given name as a child of the selected service.

```
$ svcs -Ho inst pkg/server
default
$ svccfg -s pkg/server add s11
$ svcs -Ho inst pkg/server
default
s11
```

Reverting Snapshots

Each of the following operations creates a new running snapshot:

- svcadm restart manifest-import
- svcadm refresh
- svccfg refresh

The revert subcommand reverts the administrative customizations (admin layer) of the instance specified by the -s option and its service to the values recorded in the named snapshot or the currently selected snapshot. Use the listsnap subcommand to view a list of possible snapshots for this service instance. Use the selectsnap subcommand to select a snapshot in interactive mode.

```
$ svcprop -p pkg/inst_root pkg/server:default
pkg/inst_root astring /export/ipsrepos/Solaris11
$ svccfg -s pkg/server:default listsnap
initial
previous
running
start
$ svcprop -s previous -p pkg/inst_root pkg/server:default
pkg/inst_root astring /var/pkgrepo
```

Because the revert subcommand reverts all administrative customizations, list all administrative customizations and examine their values before you revert.

```
$ svcprop -s previous -l admin pkg/server:default
pkg/inst_root astring /var/pkgrepo
$ svccfg -s pkg/server:default revert previous
$ svcadm refresh pkg/server:default
$ svcprop -p pkg/inst_root pkg/server:default
pkg/inst_root astring /var/pkgrepo
```

Importing and Applying Manifests and Profiles

When you restart the manifest-import service, manifests in standard locations are imported and profiles in standard locations are applied if they are new or changed. See "Service Bundles" on page 27 for manifest and profile standard locations. If importing a manifest or applying a profile results in the service being started or stopped, the appropriate method is executed if one exists.

Specifying a file in a standard location to the svccfg import command restarts the manifest-import service.

Recommended best practice is to put your manifest and profile files in the standard locations and restart the manifest-import service rather than use the svccfg import or svccfg apply commands.

\$ svcadm restart manifest-import

When you restart the manifest-import service, the configuration in profiles and manifests in standard locations is applied to the manifest, system-profile, or site-profile layer of affected instances, affected instances are refreshed and validated, and a new snapshot is created.

When you import or apply profiles and manifests in non-standard locations, configuration is applied to the admin layer of affected instances. Using non-standard locations is strongly discouraged for default or initial configuration delivery. For making a large number of configuration changes, importing or applying from a non-standard location might be easier than issuing many commands, but you lose the benefit of the automated management mechanisms of the manifest-import service. To manage service delivery, the manifest-import service requires known locations and expected states.

The svccfg apply command applies all configuration to the admin layer, even for manifests and profiles in standard locations.

Modifying Services that are Controlled by inetd

A service that is controlled by inetd is an SMF service that was converted from a configuration in the inetd.conf file. The inetd command is the delegated restarter for these services.

The following procedure shows how to change property values of services that are controlled by inetd.

To confirm that the service you want to modify is controlled by inetd, use either the inetadm command or the svcs -R command as shown in the following examples to list all inetd controlled services. The following examples show only a partial list:

\$ inetadm

ENABLED STATE FMRI
enabled online svc:/application/cups/in-lpd:default
...
disabled disabled svc:/application/x11/xfs:default
\$ svcs -R network/inetd:default
STATE STIME FMRI
online 8:11:10 svc:/application/cups/in-lpd:default
...
online 8:11:11 svc:/network/rpc/smserver:default

The -l option of the inetadm command lists all the properties of the inetd controlled service. In the following example, the error message indicates that the specified service is not an inetd controlled service. "No restarter property" means that the master restarter, svc.startd, manages the service instance.

\$ inetadm -l ssh

Error: Specified service instance "svc:/network/ssh:default" has no restarter property. inetd is not the delegated restarter of this instance.

Similarly, in the following example, the message "Couldn't find property 'general/restarter" indicates that the default restarter, svc.startd, manages the service instance.

\$ svcprop -p general/restarter ssh

```
svcprop: Couldn't find property 'general/restarter' for instance
'svc:/network/ssh:default'.
```

If a service is controlled by inetd, its restarter is inetd, as shown in the following example:

\$ svcprop -p general/restarter cups/in-lpd

svc:/network/inetd:default

The svcs -1 command also shows the restarter. The following example shows only partial output:

\$ svcs -l cups/in-lpd

restarter svc:/network/inetd:default

▼ How to Change a Property Value for an inetd Controlled Service

1. List the properties for the service.

Use the -l option of the inetadm command to list all the properties of the specified service. Inspect the current values of the properties.

\$ inetadm -l FMRI

2. Change a property value.

Use the -m option of the inetadm command to change the value of a specified property. Specific information about the properties for a service should be covered in the man page associated with the service.

```
$ inetadm -m FMRI property-name=value
```

To delete a property value, specify an empty value.

```
$ inetadm -m svc property=""
```

3. Verify that the property value is changed.

List the properties again to make sure that the appropriate change has occurred.

```
$ inetadm -l FMRI
```

4. Confirm that the change has taken effect.

Confirm that the property change has the expected effect.

Example 36 Limiting the Number of Concurrent Processes that are Allowed to Run

This example shows how to limit the number of finger processes that are allowed to run concurrently.

Security best practice recommends limiting the number of processes that are allowed to run concurrently for each system service that is controlled by inetd. In addition, if a service that is controlled by inetd is not needed, disable that service as described in "Stopping a Service" on page 58.

The property to configure to limit the number of processes that are allowed to run concurrently is the max_copies property. The inetadm -p command lists the properties common to all services managed by inetd and their default values. The following example shows only partial output:

```
$ inetadm -p
NAME=VALUE
...
max_copies=-1
...
```

The inetadm -l command lists all the properties of the specified service so that you can inspect the current value of the max copies property for that service.

```
$ inetadm -l finger | grep copies
```

```
default max_copies=-1
```

Use the -m option of the inetadm command to change the value of the property:

```
$ inetadm -m finger max_copies=5
```

Verify that the property value is changed.

```
$ inetadm -l finger | grep copies
max_copies=5
```

Notice that the scope of "default" is no longer displayed for this property.

▼ How to Add a New Instance of a Service that is Controlled by inetd

Determine the location of the manifest for the service.

```
$ svcs -l FMRI
...
manifest /lib/svc/manifest/path/file.xml
```

- 2. Edit the manifest file to add a new instance with appropriate property values.
 - a. Copy and paste an existing instance element.
 - b. Give the new instance element a unique instance name.
 - c. Change the property values as necessary.
- Add the new instance to the profile file.

Edit the file /etc/svc/profile/generic.xml to add a new instance element inside the service element for the appropriate service.

4. Restart the manifest import service.

```
$ svcadm restart manifest-import
```

5. Verify that the new instance has been added.

Search for the FMRI in the output of the svcs -a or inetadm command.

6. Verify the property values of the new instance.

```
$ inetadm -l FMRI
```

Modifying Services that are Configured by a File

A few SMF services that are not managed by inetd get some of their configuration from a file rather than from service properties. To modify this configuration, edit the configuration file and use SMF commands to restart the service. These configuration files can be changed while the service is running, but the content of the files is only read when the service is started.

Before you edit a configuration file directly, check the following conditions:

- Make sure the configuration file does not contain a message telling you not to directly edit it.
- Make sure the service does not have a property group of type configfile.

\$ svcprop -g configfile network/ntp

If the service has a property group of type configfile, modify the properties in those property groups and not the configuration file. See Chapter 6, "Using a Stencil to Create a Configuration File" in *Developing System Services in Oracle Solaris 11.3*.

For example, to add a new NTP server to support your NTP clients, add a new entry for the server to the /etc/inet/ntp.conf file and then restart the NTP service as shown in the following command:

\$ svcadm restart svc:/network/ntp:default

To enable IKEv2, modify the /etc/inet/ike/ikev2.config file to configure the IKEv2 daemon, and then enable the IKEv2 service as shown in the following command. To edit the ikev2.config file, use the pfedit command as a user who is assigned the Network IPsec Management profile. Editing the file in this way preserves the correct file ownership. See the pfedit(1M) man page for information about using pfedit.

\$ svcadm enable svc:/network/ipsec/ike:ikev2



Configuring Multiple Systems

This chapter describes the recommended way to manage configuration change across multiple systems.

The most accurate, efficient way to deliver consistent system configuration to multiple systems across system updates is to deliver SMF profiles in IPS packages.

This chapter describes:

- How to manage the configuration of multiple systems
- How to create SMF profiles
- How to deliver configuration to multiple systems

Managing Configuration of Multiple Systems

The following steps summarize how to manage configuration of multiple systems:

- Create SMF profiles that specify the services you want enabled and the values of their properties. Profiles can add and set properties for existing services and instances and specify new service instances. Profiles can specify almost anything that a manifest can specify.
- Create IPS packages to install those profiles in the /etc/svc/profile/site directory on each system. See "Repository Layers" on page 28 for a description of the site-profile configuration layer.

Creating SMF Profiles

The following steps summarize how to create SMF profile files:

1. Use any of the following methods to create SMF profile files:

- Use the svccfg extract command to capture profile information from an existing service as described in "How to Create a Profile by Using svccfg" on page 92.
- Use the sysconfig create-profile command to create a new profile file as described in "How to Create a Profile by Using sysconfig" on page 93.
- Use the svcbundle command with bundle-type=profile to create a new profile file as described in "How to Create a Profile by Using svcbundle" on page 93.
- 2. Customize property values in the profile file, and include comments about the reason for each customization. Ensure that you do not specify conflicting configuration. See "Conflicting Configuration" on page 90 for more information.
- 3. To test the profile, copy the profile file to the /etc/svc/profile/site directory, and restart the manifest-import service.

Use one of the following commands to verify that the configuration described in profile files has been applied:

- svccfg listcust -L
- svccfg listprop -l all
- svcprop -l all

Conflicting Configuration

When you create a profile, ensure that the configuration defined does not conflict with configuration defined in the same layer in any other profile for the same service or service instance.

Examples of conflicting configuration include different values for the same property and different types for the same property or property group.

If conflicting configuration is delivered by multiple files in any single layer, and is not set at a higher layer, the manifest-import service log reports the conflict and the service with the conflicting configuration is not started and is placed in the maintenance state.

If you create two profile files, each of which specify different values for the same property, place both of these profile files in the /etc/svc/profile/site directory, and reboot the system, you get results similar to the following:

• If you have notifications configured, the notification reports the conflict. The following example is a service state transition notification:

HOSTNAME: host

TIMESTAMP: June 27, 2016 at 04:15:43 PM PDT

FMRI: svc:/site/example:default FROM-STATE: uninitialized TO-STATE: maintenance

```
DESCRIPTION: The indicated service has transitioned to the maintenance state REASON: the instance is in conflict
```

The following example is an FMA event notification. Note the information in the Impact and Recommended Action sections.

```
SUNW-MSG-ID: SMF-8001-02, TYPE: Defect, VER: 1, SEVERITY: Major
EVENT-TIME: Mon Jun 27 16:14:07 PDT 2016
PLATFORM: Ultra 24, CSN: 0817FMB003, HOSTNAME: host
SOURCE: software-diagnosis, REV: 0.2
EVENT-ID: c46b48bb-484d-4c9f-a82b-e1349a0ddce6
DESC: The Solaris Service manager tried to import a manifest or apply a profile
defining
the service, but detected one or more entities with conflicting definitions.
AUTO-RESPONSE: The service may have been placed into the maintenance state.
IMPACT: The service is not running. It will not be started until the conflict is
and the maintenance state is cleared. Services with require-type dependencies on the
service will not be started. (Use 'svcs -xv svc:/site/nm example:default' to see a
of services waiting for the service to start.)
REC-ACTION: Edit the problematic manifest or profile to resolve the conflict and
or reapply it, or use svccfg to administratively override the conflicting
 definitions.
Then clear the maintenance state. Please refer to the associated reference document
http://support.oracle.com/msg/SMF-8001-02 for the latest service procedures and
policies
regarding this diagnosis.
```

■ The svcs -x command reports the conflict.

\$ svcs -x

```
svc:/site/example:default (site/example)
State: maintenance since Mon Jun 27 16:32:36 2016
Reason: Instance has conflicts.
Conflicting value: FMRI="svc:/site/example"; Name of conflicting property="config/prop1"; from file="/etc/svc/profile/site/example_prof1.xml";
    See: http://support.oracle.com/msg/SMF-8001-02
    See: /var/svc/log/site-example:default.log
Impact: This service is not running.
```

■ The manifest-import service log file reports the conflict.

\$ tail `svcs -L manifest-import`

```
Applying profile to admin layer: /etc/svc/profile/site/example_prof2.xml Applying profile to admin layer: /etc/svc/profile/site/example_prof1.xml svccfg: svc:/site/example: property group "config" has a conflict.
```

```
Conflicting value: FMRI="svc:/site/example"; Name of conflicting property="config/prop1"; from file="/etc/svc/profile/site/example_prof1.xml";
```

You can also use the -l, -f, and -o options of the svccfg listprop command to investigate the cause of a conflict. See "Showing the Layer Where a Value Is Set" on page 49 and "Showing the File that Contributed the Configuration" on page 50.

▼ How to Create a Profile by Using svccfg

1. Create the profile.

The svccfg extract command displays a service profile for the specified service or instance. To extract values from specific layers, use the -l option. The -l option argument can be a layer name or a comma-separated list of layer names. See the svccfg(8) man page for the complete list of layer names, and see "Repository Layers" on page 28 for descriptions of the layers. The current and all layer names both mean select the highest-layer value for each property.

The following command extracts the highest-layer setting for each property for the network/dns/client service into the dnsclientprofile.xml file:

\$ svccfg extract -l current network/dns/client > dnsclientprofile.xml

2. Make any necessary changes to the profile.

Change the name of the profile to a meaningful name. By default, the name is set to extract, as shown in the following example:

```
<service_bundle type='profile' name='extract'>
```

Make any changes that are necessary for the target systems.

3. Copy the profile to the correct directory.

The following command indicates that this profile is for all systems at a given locale or site:

```
$ cp dnsclientprofile.xml /etc/svc/profile/site/
```

Change the ownership and permissions of the profile as necessary.

4. Restart the manifest import service to apply the profile to the system.

\$ svcadm restart manifest-import

Check the manifest-import service log file for messages about property value conflicts or any other error messages.

```
$ svcs -Lv manifest-import
```

Use the svcs -x command to check that no services are in maintenance.

▼ How to Create a Profile by Using sysconfig

1. Create the profile.

Run the SCI Tool and create a system configuration profile. The default location for the profile is /system/volatile/profile/sc_profile.xml. Use the -o option to specify a different directory for the profile file.

The following command creates a new profile in the siteAprofiles directory that includes network and naming_services configuration. See the sysconfig(8) man page for the complete list of functional groupings (-g) that can be configured.

\$ sysconfig create-profile -g network,naming_services -o ./siteAprofiles

The SCI tool opens and prompts you for the configuration values.

2. Make any necessary changes to the profile.

The profile is in ./siteAprofiles/sc_profile.xml. You might want to change sc_profile.xml to a more meaningful and unique name.

\$ cp ./siteAprofiles/sc_profile.xml ./siteAprofiles/netnamingSiteA.xml

Make any changes that are necessary for the target systems.

Copy the profile to the correct directory.

The following command indicates that this profile is for all systems at a given locale or site:

\$ cp ./siteAprofiles/netnamingSiteA.xml /etc/svc/profile/site/

Change the ownership and permissions of the profile as necessary.

4. Restart the manifest import service to apply the profile to the system.

\$ svcadm restart manifest-import

Check the manifest-import service log file for messages about property value conflicts or any other error messages.

\$ svcs -Lv manifest-import

Use the svcs -x command to check that no services are in maintenance.

▼ How to Create a Profile by Using svcbundle

1. Create the profile.

The following command creates a new profile in example.com.xml:

```
$ svcbundle -o example.com.xml -s service-name=site/example.com \
> -s bundle-type=profile -s instance-property=pg_name:prop_name:prop_type:value \
> -s service-property=pg_name:prop_name:prop_type:value
```

- 2. Make any changes that are necessary for the target systems.
- 3. Copy the profile to the correct directory.

The following command indicates that this profile is for all systems:

```
$ cp example.com.xml /etc/svc/profile/site/
```

4. Restart the manifest import service to apply the profile to the system.

```
$ svcadm restart manifest-import
```

Check the manifest-import service log file for messages about property value conflicts or any other error messages.

```
$ svcs -Lv manifest-import
```

Use the svcs -x command to check that no services are in maintenance.

Delivering Configuration to Multiple Systems

The best way to deliver profiles to your systems depends on how configuration information is controlled in your organization. Common ways of dividing the information into different packages is by site, by network, and by system function. For example, DNS and NTP configuration might be the same for all systems in a DMZ, but would be different from the configurations used in internal development groups. In that same DMZ environment, the systems that act as web servers might all share a common configuration, which might be different from the configuration of systems serving other functions.

Dependencies can be used to build complete configurations out of smaller sets of configuration information. Using dependencies reduces duplication of information across packages.

Create at least one package for each group of systems that require the same configuration. A package can deliver multiple profiles.

- Configuration for different SMF layers must be delivered in different profile files in different directories.
- Within a single layer, you probably want to deliver configuration for different services in different profile files.
- Different groups of systems require different configuration and therefore different profiles.

You might want multiple profile packages per system group, for example to separately deliver configuration that you expect to change more frequently. Multiple profile packages for the same group of systems could be group dependencies in one package. A group package also is an easy way to deliver new profile packages for that group.

When a profile needs to change, rebuild the package with the updated profile and increment the package version number. If you are using a group package, update the group package as well. The updated configuration is then installed by pkg_update.

See *Packaging and Delivering Software With the Image Packaging System in Oracle Solaris 11.3* for information about how to create your profile packages. The following instructions are specific to SMF profile packages:

- Do not package the /etc, /etc/svc, or /etc/svc/profile directories or any of the standard subdirectories of the /etc/svc/profile directory: Those directories are already delivered by system packages.
- Include a restart fmri actuator on each profile or manifest file action.

Consider using a periodic service to check whether updates are available for installed profile packages. See *Developing System Services in Oracle Solaris 11.3* for information about creating a periodic service.

If you want to provide individual system administrators with a choice of configuration, deliver mediated links into the /etc/svc/profile/site directory and the target profiles elsewhere. See "Delivering Multiple Implementations of an Application" in *Packaging and Delivering Software With the Image Packaging System in Oracle Solaris 11.3* for more information.

+++ APPENDIX A

SMF Best Practices and Troubleshooting

This appendix describes best practices and troubleshooting, including:

- Repairing a service instance that is degraded, offline, or in maintenance
- Diagnosing and repairing SMF repository problems
- Specifying the amount of SMF startup messaging
- Specifying the SMF milestone to which to boot
- Investigating system boot problems
- Converting inetd services to SMF services

SMF Best Practices

Most services describe configuration policy. If the configuration you want is not implemented, modify the policy description by modifying the service. Modify the values of service properties or create new service instances with different property values. Do not disable service instances and edit configuration files that are intended to be managed by an SMF service. An increasing number of fundamental Oracle Solaris features are configured by SMF service properties, not by editing configuration files.

Do not modify manifests and system profiles that are delivered by Oracle or by third-party software vendors. These manifests and profiles might be replaced when you upgrade your system, and then your changes to these files will be lost. Instead, do one of the following:

- Add a new service instance with different property values as described in "Adding Service Instances" on page 82.
- Create a profile to customize the service. Use the svcbundle command or the svccfg extract command to create a profile file. Customize property values in that file, and include comments about the reason for each customization. Copy the profile file to /etc/svc/profile/site, and restart the manifest-import service.

To apply the same custom configuration to multiple systems, copy the same profile file to /etc/svc/profile/site on each system, and restart the manifest-import service on each system. To automate delivering the profile to each system, package the profile. See Chapter 5, "Configuring Multiple Systems".

■ Use the svccfg command or the inetadm command to manipulate the properties directly. If you use the svccfg command to modify property values, be sure to refresh the service instance as explained in "Understanding Configuration Changes" on page 99. For information about modifying, adding, and deleting service configuration, see Chapter 4, "Configuring Services". To see configuration that has already been modified, see "Showing Configuration Customizations" on page 51. To delete custom configuration, see Example 33, "Deleting Customizations," on page 81 and Example 35, "Unmasking Configuration," on page 82.

When you create a site profile, make sure the configuration defined does not conflict with configuration defined in another site profile for the same service or service instance. Configuration conflicts are not permitted within any layer. If conflicting configuration is delivered by multiple files in any single layer, and is not set at a higher layer, the manifest-import service log reports the conflict and the service with the conflicting configuration is not started. See "Conflicting Configuration" on page 90 for more information.

Do not use non-standard locations for manifest and profile files. See "Service Bundles" on page 27 for manifest and profile standard locations.

When you create a service for your own use, use site at the beginning of the service name: svc:/site/service_name:instance_name.

Do not modify the configuration of the master restarter service, svc:/system/svc/restarter: default, except to configure logging levels as described in "Specifying the Amount of Startup Messaging" on page 107.

Before you use the svccfg delcust command, use the svccfg listcust command with the same options. The delcust subcommand can potentially remove all administrative customizations on a service. Use the listcust subcommand to verify which customizations will be deleted by the delcust subcommand.

In scripts, use the full service instance FMRI: svc:/service_name:instance_name.

Troubleshooting Services Problems

This section discusses the following topics:

- Committing configuration changes into the running snapshot
- Fixing services that are reported to have problems
- Manually transitioning an instance to the degraded or maintenance state
- Fixing a corrupt service configuration repository
- Configuring the amount of messaging to display or store on system startup
- Transitioning or booting to a specified milestone
- Using SMF to investigate booting problems
- Converting inetd services to SMF services

Understanding Configuration Changes

In the service configuration repository, SMF stores property changes separately from properties in the running snapshot. When you change service configuration, those changes do not immediately appear in the running snapshot.

The refresh operation updates the running snapshot of the specified service instance with the values from the editing configuration.

By default, the svcprop command shows properties in the running snapshot, and the svccfg command shows properties in the editing configuration. If you have changed property values but not performed a configuration refresh, the svcprop and svccfg commands show different property values. After you perform a configuration refresh, the svcprop and svccfg commands show the same property values.

Rebooting does not change the running snapshot. The svcadm restart command does not refresh configuration. Use the svcadm refresh or svccfg refresh command to commit configuration changes into the running snapshot.

Repairing an Instance That Is Degraded, Offline, or in Maintenance

Use the svcs -x command with no arguments to display explanatory information about any service instances that match either of the following descriptions:

- The service is enabled but is not running.
- The service is preventing another enabled service from running.

The following list summarizes how to approach service problems:

1. Diagnose the problem, starting with viewing the service log file.

Log files located in /var/svc/log and /system/volatile. The service log file shows time stamps and method exit reasons.

The location of the log file for a particular service is given by the following command:

\$ svcs -L service-name

The following command displays the end of the log file for a particular service:

\$ svcs -Lx service-name

- 2. Fix the problem.
 - If multiple service failures are identified, start by looking at the first failure to occur, using the time stamps in the service log files.
 - Use the following command to show impacted dependencies of the failed service:

```
$ svcs -l service-name
```

Use the following command to show services on which *service-name* depends:

```
$ svcs -d service-name
```

- If fixing the problem involves modifying service configuration, refresh the service.
- 3. Move affected services to a running state.

▼ How to Repair an Instance That Is in Maintenance

A service instance that is in maintenance is enabled but not able to run.

1. Determine why the instance is in maintenance.

The instance might be transitioning through the maintenance state because an administrative action has not yet completed. If the instance is transitioning, its state should be shown as maintenance* with an asterisk at the end.

An instance that is configured to restart after failure might be placed in maintenance because it was restarting too frequently. In this case you need to determine the cause of the consistent failure.

If an instance is in maintenance because it has conflicts, or conflicting property values, see "Conflicting Configuration" on page 90.

In the following example, the "State" and "Reason" lines show that the pkg/depot service is in the maintenance state because its start method failed.

```
$ svcs -x
svc:/application/pkg/depot:default (IPS Depot)
State: maintenance since September 11, 2013 01:30:42 PM PDT
Reason: Start method exited with $SMF_EXIT_ERR_FATAL.
    See: http://support.oracle.com/msg/SMF-8000-KS
    See: pkg.depot-config(1M)
    See: /var/svc/log/application-pkg-depot:default.log
Impact: This service is not running.
```

Log in to the Oracle support site to view the referenced Predictive Self-Healing knowledge article. In this case, the article tells you to view the log file to determine why the start method failed. The svcs output gives the name of the log file. See "Viewing Service Log Files" on page 42 for information about how to view the log file. In this example, the log file shows the start method invocation and the fatal error message.

```
[ Sep 11 13:30:42 Executing start method ("/lib/svc/method/svc-pkg-depot start"). ] pkg.depot-config: Unable to get publisher information: The path '/export/ipsrepos/Solaris11' does not contain a valid package repository.
```

2. Fix the problem.

One or more of the following steps might be needed.

Update service configuration.

If fixing the reported problem required modifying service configuration, use the svccfg refresh or svcadm refresh command for any services whose configuration changed. Verify that the configuration is updated in the running snapshot by using the svcprop command to check property values or by other tests specific to this service.

Ensure dependencies are running.

Sometimes the "Impact" line in the svcs -x output tells you that services that depend on the service that is in the maintenance state are not running. Use the svcs -l command to check the current state of dependent services. Ensure that all required dependencies are running. Use the svcs -x command to verify that all enabled services are running.

■ Ensure contract processes are stopped.

If the service that is in the maintenance state is a contract service, determine whether any processes that were started by the service have not stopped. When a contract service instance is in a maintenance state, the contract ID should be blank, as shown in the following example, and all processes associated with that contract should have stopped. Use svcs -l or svcs -o ctid to check that no contract exists for a service instance in maintenance. Use svcs -p to check whether any processes associated with this service instance are still running. Any processes shown by svcs -p for a service instance in maintenance should be killed.

\$ svcs -l system-repository

```
fmri
            svc:/application/pkg/system-repository:default
name
            IPS System Repository
enabled
            true
state
            maintenance
next state none
state time September 17, 2013 07:18:19 AM PDT
logfile
            /var/svc/log/application-pkg-system-repository:default.log
restarter
            svc:/system/svc/restarter:default
contract id
manifest
            /lib/svc/manifest/application/pkg/pkg-system-repository.xml
dependency require all/error svc:/milestone/network:default (online)
            require all/none svc:/system/filesystem/local:default (online)
dependency
            optional_all/error svc:/system/filesystem/autofs:default (online)
dependency
```

3. Notify the restarter that the instance is repaired.

When the reported problem is fixed, use the svcadm clear command to return the service to the online state. For services in the maintenance state, the clear subcommand tells the restarter for that service that the service is repaired.

```
$ svcadm clear pkg/depot:default
```

If you specify the -s option, the svcadm command waits to return until the instance reaches the online state or until it determines that the instance cannot reach the online state without administrator intervention. Use the -T option with the -s option to specify an upper bound in seconds to make the transition or determine that the transition cannot be made.

4. Verify that the instance is repaired.

Use the svcs command to verify that the service that was in maintenance is now online. Use the svcs -x command to verify that all enabled services are running.

▼ How to Repair an Instance That Is Offline

A service instance that is offline is enabled but not running or available to run.

1. Determine why the instance is offline.

The instance might be transitioning through the offline state because its dependencies are not yet satisfied. If the instance is transitioning, its state should be shown as offline*.

2. Fix the problem.

■ Enable service dependencies.

If required dependencies are disabled, enable them with the following command:

\$ svcadm enable -r FMRI

■ Fix dependency file.

A dependency file might be missing or unreadable. You might want to use pkg fix or pkg revert to fix this type of problem. See the pkg(1) man page.

3. Restart the instance if necessary.

If the instance was offline because a required dependency was not satisfied, fixing or enabling the dependency might cause the offline instance to restart and come online with no further administrative action needed.

If you made some other fix to the service, then restart the instance.

 $\$ \ {\rm svcadm} \ {\rm restart} \ FMRI$

4. Verify that the instance is repaired.

Use the svcs command to verify that the instance that was offline is now online. Use the svcs -x command to verify that all enabled services are running.

▼ How to Repair an Instance That Is Degraded

A service instance that is degraded is enabled and running or available to run, but is functioning at a limited capacity.

1. Determine why the instance is degraded.

2. Fix the problem.

3. Request the restarter to online the instance.

When the reported problem is fixed, use the svcadm clear command to return the instance to the online state. For instances in the degraded state, the clear subcommand requests that the restarter for that instance transition the instance to the online state.

\$ svcadm clear pkg/depot:default

4. Verify that the instance is repaired.

Use the svcs command to verify that the instance that was degraded is now online. Use the svcs -x command to verify that all enabled services are running.

Marking an Instance as Degraded or in Maintenance

You can mark a service instance as being in either the degraded state or the maintenance state. You might want to do this if the application is stuck in a loop or is deadlocked, for example. The information about the state change propagates to the dependencies of the marked instance, which can help debug other related instances.

Specify the -I option to request an immediate state change.

When you mark an instance as maintenance, you can specify the -t option to request a temporary state change. Temporary requests last only until reboot.

If you specify the -s option with the svcadm mark command, svcadm marks the instance and waits for the instance to enter the degraded, or maintenance state before returning. Use the -T option with the -s option to specify an upper bound in seconds to make the transition or determine that the transition cannot be made.

Diagnosing and Repairing Repository Problems

On system startup, the repository daemon, svc.configd, performs an integrity check of the configuration repository stored in /etc/svc/repository.db. If the svc.configd integrity check fails, the svc.configd daemon writes a message to the console similar to the following:

```
svc.configd: smf(5) database integrity check of:
   /etc/svc/repository.db

failed. The database might be damaged or a media error might have prevented it from being verified. Additional information useful to your service provider is in:
   /system/volatile/db_errors

The system will not be able to boot until you have restored a working database. svc.startd(1M) will provide a sulogin(1M) prompt for recovery purposes. The command:
   /lib/svc/bin/restore_repository

can be run to restore a backup version of your repository. See http://support.oracle.com/msg/SMF-8000-MY for more information.
```

The svc.configd daemon then exits. That exit is detected by the svc.startd daemon, and svc. startd then starts sulogin.

At the sulogin prompt, enter Ctrl-D to exit sulogin. The svc.startd daemon recognizes the sulogin exit and restarts the svc.configd daemon, which checks the repository again. The problem might not reappear after this additional restart.



Caution - Do not directly invoke the svc.configd daemon. The svc.startd daemon starts the svc.configd daemon.

If svc.configd again reports a failed integrity check and you are again at the sulogin prompt, ensure that required file systems are not full. Using the root password, log in either remotely or at the sulogin prompt. Check that space is available on both the root and system/volatile file systems. If either of these file systems is full, clean up and start the system again. If neither of these file systems is full, follow the procedure "How to Restore a Repository From Backup" on page 105.

The service configuration repository can become corrupted for any of the following reasons:

Disk failure

- Hardware bug
- Software bug
- Accidental overwrite of the file

The following procedure shows how to replace a corrupt repository with a backup copy of the repository.

How to Restore a Repository From Backup



Caution - Only restore a corrupt repository. Do not use this repository restore procedure to delete unwanted configuration changes. To undo configuration changes, see "Showing Configuration Customizations" on page 51, Example 33, "Deleting Customizations," on page 81, and Example 35, "Unmasking Configuration," on page 82.

1. Log in.

Using the root password, log in either remotely or at the sulogin prompt.

2. Run the repository restore command:

/lib/svc/bin/restore_repository

Running this command takes you through the necessary steps to restore a non-corrupt backup. SMF automatically takes backups of the repository as described in "Repository Backups" on page 29.

SMF maintains persistent and non-persistent configuration data. See "Service Configuration Repository" on page 26 for descriptions of these two repositories. The restore_repository command only restores the persistent repository. The restore_repository command also reboots the system, which destroys the non-persistent configuration data. The non-persistent data is runtime data that is not needed across system reboot.

When started, the /lib/svc/bin/restore_repository command displays a message similar to the following:

See http://support.oracle.com/msg/SMF-8000-MY for more information on the use of this script to restore backup copies of the smf(5) repository.

If there are any problems which need human intervention, this script will give instructions and then exit back to your shell.

After the root (/) file system is mounted with write permissions, or if the system is a local zone, you are prompted to select the repository backup to restore:

The following backups of /etc/svc/repository.db exists, from oldest to newest:

```
... list of backups ...
```

Backups are given names, based on type and the time the backup was taken. Backups beginning with boot are completed before the first change is made to the repository after system boot. Backups beginning with manifest_import are completed after svc:/system/manifest-import:default finishes its process. The time of the backup is given in YYYYMMDD HHMMSS format.

3. Enter the appropriate response.

Typically, the most recent backup option is selected.

Please enter either a specific backup repository from the above list to restore it, or one of the following choices:

CHOICE	ACTION
boot	restore the most recent post-boot backup
${\tt manifest_import}$	restore the most recent manifest_import backup
-seed-	restore the initial starting repository (All
	customizations will be lost, including those
	made by the install/upgrade process.)
-quit-	cancel script and quit

Enter response [boot]:

If you press Enter without specifying a backup to restore, the default response, enclosed in [] is selected. Selecting -quit- exits the restore_repository script, returning you to your shell prompt.



Caution - Selecting -seed- restores the seed repository. This repository is designed for use during initial installation and upgrades. Only use the seed repository for recovery purposes when no other service configuration change or backup service repository will work. All configuration changes will be lost, including changes to fundamental Oracle Solaris features that were delivered by installing or updating packages. Using the seed repository for recovery purposes should be a last resort.

After you have selected the backup that you want to restore, that backup is validated and its integrity is checked. If any problems are discovered, the restore_repository command prints error messages and prompts you for another selection. Once you have selected a valid backup, the following information is printed, and you are prompted for final confirmation.

```
After confirmation, the following steps will be taken:

svc.startd(1M) and svc.configd(1M) will be quiesced, if running.

/etc/svc/repository.db

-- renamed --> /etc/svc/repository.db_old_YYYYMMDD_HHMMSS

/system/volatile/db_errors

-- copied --> /etc/svc/repository.db_old_YYYYMMDD_HHMMSS_errors
```

```
repository_to_restore
    -- copied --> /etc/svc/repository.db
and the system will be rebooted with reboot(1M).
Proceed [yes/no]?
```

4. Type yes to remedy the fault.

The system reboots after the restore repository command executes all of the listed actions.

Specifying the Amount of Startup Messaging

By default, each service that starts during system boot does not display a message on the console. Use one of the following methods to change which messages appear on the console and which are recorded only in the svc.startd log file. The value of *logging-level* can be one of the values shown in the table below.

■ When booting a SPARC system, specify the -m option to the boot command at the ok prompt. See "Messages options" in the kernel(1M) man page.

```
ok boot -m logging-level
```

- When booting an x86 system, edit the GRUB menu to specify the -m option. See "Adding Kernel Arguments by Editing the GRUB Menu at Boot Time" in *Booting and Shutting Down Oracle Solaris 11.3 Systems* and "Messages options" in the kernel(1M) man page.
- Prior to rebooting a system, use the svccfg command to change the value of the options/ logging property. If this property has never been changed on this system, then it will not exit and you will have to add it. The following example changes to verbose messaging. The change takes effect on the next restart of the svc.startd daemon.

```
$ svccfg -s system/svc/restarter:default listprop options/logging
$ svccfg -s system/svc/restarter:default addpg options application
$ svccfg -s system/svc/restarter:default setprop options/logging=verbose
$ svccfg -s system/svc/restarter:default listprop options/logging
options/logging astring verbose
```

TABLE 2 SMF Startup Message Logging Levels

Logging Level Keyword	Description
quiet	Display on the console any error messages that require administrative intervention. Also record these messages in syslog and in /var/svc/log/svc.startd.log.
verbose	In addition to the messaging provided at the quiet level, display on the console a single message for each service started, and record in /var/svc/log/svc.startd.log information about errors that do not require administrative intervention.

Logging Level Keyword	Description
debug	In addition to the messaging provided at the quiet level, display on the console a single message for each service started, and record any svc.startd debug messages in /var/svc/log/svc.startd.log.

Specifying the SMF Milestone to Which to Boot

When you boot a system, you can specify the SMF milestone to which to boot.

By default, all services for which the value of the general/enabled property is true are started at system boot. To change the milestone to which to boot a system, use one of the following methods. The value of *milestone* can be the FMRI of a milestone service or a keyword as shown in Table 3, "SMF Boot Milestones and Corresponding Run Levels," on page 109.

■ When booting a SPARC system, specify the -m option to the boot command at the ok prompt. See the -m option in the kernel(1M) man page.

ok **boot** -m milestone=milestone

- When booting an x86 system, edit the GRUB menu to specify the -m option. See "Adding Kernel Arguments by Editing the GRUB Menu at Boot Time" in *Booting and Shutting Down Oracle Solaris 11.3 Systems* and the -m option in the kernel(1M) man page.
- Prior to rebooting a system, use the svcadm milestone command with the -d option. Note that with or without the -d option, this command restricts and restores running services immediately. With the -d option, the command also makes the specified milestone the default boot milestone. This new default is persistent across reboots.

\$ svcadm milestone -d milestone

This command does not change the current run level of the system. To change the current run level of the system, use the init command.

If you specify the -s option, svcadm changes the milestone and then waits for the transition to the specified milestone to complete before returning. The svcadm command returns when all instances have transitioned to the state necessary to reach the specified milestone or when it determines that administrator intervention is required to make a transition. Use the -T option with the -s option to specify an upper bound in seconds to complete the milestone change operation or return.

The following table describes SMF boot milestones, including any corresponding Oracle Solaris run level. A system's *run level* defines what services and resources are available to users. A system can be in only one run level at a time. For information about run levels,see "How Run Levels Work" in *Booting and Shutting Down Oracle Solaris 11.3 Systems*, the inittab(4) man page, and the /etc/init.d/README file. For more information about SMF boot milestones, see the milestone subcommand in the svcadm(1M) man page.

TABLE 3 SMF Boot Milestones and Corresponding Run Levels

SMF Milestone FMRI or Keyword	Correspond Run Level	ngescription
none		The none keyword represents a milestone where no services are running except for the master restarter. When none is specified, all services except for svc:/system/svc/restarter:default are temporarily disabled.
		The none milestone can be useful when for debugging startup problems. See "How to Investigate Problems Starting Services at System Boot" on page 110 for specific instructions.
all		The all keyword represents a milestone that depends on every service. When all is specified, temporary enable and disable requests are ignored for all services. This is the default milestone used by svc.startd.
svc:/milestone/single-user	s or S	Ignore temporary enable and disable requests for svc:/milestone/single-user:default and all services on which it depends either directly or indirectly. Temporarily disable all other services.
svc:/milestone/multi-user	2	Ignore temporary enable and disable requests for svc:/milestone/multi-user:default and all services on which it depends either directly or indirectly. Temporarily disable all other services.
svc:/milestone/multi-user-server	3	Ignore temporary enable and disable requests for svc:/milestone/multi-user-server:default and all services on which it depends either directly or indirectly. Temporarily disable all other services.

To determine the milestone to which a system is currently booted, use the svcs command. The following example shows that the system is booted to run level 3, milestone/multi-user-server:

```
$ svcs 'milestone/*'
STATE
        STIME
                      FMRI
online
              9:08:05 svc:/milestone/unconfig:default
online
              9:08:06 svc:/milestone/config:default
online
              9:08:07 svc:/milestone/devices:default
online
               9:08:25 svc:/milestone/network:default
online
               9:08:31 svc:/milestone/single-user:default
online
               9:08:51 svc:/milestone/name-services:default
online
               9:09:13 svc:/milestone/self-assembly-complete:default
online
               9:09:23 svc:/milestone/multi-user:default
               9:09:24 svc:/milestone/multi-user-server:default
online
```

Using SMF to Investigate System Boot Problems

This section describes actions to take if your system hangs during boot or if a key service fails to start during boot.

▼ How to Investigate Problems Starting Services at System Boot

If problems occur when starting services at system boot, sometimes the system will hang during boot. This procedure shows how to investigate services problems that occur at boot time.

1. Boot without starting any services.

The following command instructs the svc.startd daemon to temporarily disable all services and start sulogin on the console.

```
ok boot -m milestone=none
```

See "Specifying the SMF Milestone to Which to Boot" on page 108 for a list of SMF milestones that you can use with the boot -m command.

- 2. Log in to the system as root.
- 3. Enable all services.

svcadm milestone all

4. Determine where the boot process is hanging.

When the boot process hangs, determine which services are not running by running svcs -a. Look for error messages in the log files in /var/svc/log.

- 5. After fixing the problems, verify that all services have started.
 - a. Verify that all needed services are online.

svcs -x

b. Verify that the console-login service dependencies are satisfied.

This command verifies that the login process on the console will run.

svcs -l system/console-login:default

6. Continue the normal booting process.

▼ How to Force Single-User Login if the Local File System Service Fails During Boot

Local file systems that are not required to boot the system are mounted by the svc:/system/filesystem/local:default service. When any of those file systems cannot be mounted,

the filesystem/local service enters a maintenance state. System startup continues, and any services that do not depend on filesystem/local are started. Services that have a required dependency on the filesystem/local service are not started.

This procedure explains how to change the configuration of the system so that a sulogin prompt appears immediately after the service fails instead of allowing system startup to continue.

Modify the system/console-login service.

```
$ svccfg -s svc:/system/console-login
svc:/system/console-login> addpg site,filesystem-local dependency
svc:/system/console-login> setprop site,filesystem-local/entities = fmri: svc:/system/
filesystem/local
svc:/system/console-login> setprop site,filesystem-local/grouping = astring: require_all
svc:/system/console-login> setprop site,filesystem-local/restart_on = astring: none
svc:/system/console-login> setprop site,filesystem-local/type = astring: service
svc:/system/console-login> end
```

2. Refresh the service.

\$ svcadm refresh console-login

When a failure occurs with the system/filesystem/local:default service, use the svcs -vx command to identify the failure. After the failure has been fixed, use the following command to clear the error state and allow the system boot to continue:

```
$ svcadm clear filesystem/local
```

Converting inetd Services to SMF Services

The inetd.conf file on your system should contain no entries. The inetd.conf file should contain only comments that this is a legacy file no longer directly used. If the inetd.conf file contains any entries, follow the instructions in this section to convert these configurations to SMF services. Services that are configured in the inetd.conf file but are not configured as an SMF service are not available for use. Services that are configured in the inetd.conf file are not restarted by the inetd command directly. Rather, the inetd command is the delegated restarter for the converted services.

During initial system boot, configurations in the inetd.conf file are automatically converted to SMF services. After initial system boot, entries might be added to the inetd.conf file by installing additional software that is not delivered by Image Packaging System (IPS) packages. Software that is delivered by IPS packages includes any required SMF manifest, and that SMF manifest instantiates that service instance with the correct property values.

If the inetd.conf file on your system contains any entries, use the inetconv command to convert those configurations to SMF services. The inetconv command converts inetd.conf entries into SMF service manifest files and imports those manifests into the SMF repository to instantiate the service instances. See the inetconv(1M) man page for information about command options and to see examples of using the command.

The name of the new SMF manifest incorporates the <code>service_name</code> from the <code>inetd.conf</code> entry. The entry from the <code>inetd.conf</code> file is saved as a property of the new service instance. The new SMF manifest specifies property groups and properties to define the actions listed in the <code>inetd.conf</code> entry. After running the <code>inetconv</code> command, use the <code>svcs</code> and <code>svcprop</code> commands to ensure the new service instance was created and has the correct property values.

The inetd command is the delegated restarter for SMF internet services. Do not use the inetd command directly to manage these services. Use the inetadm command with no options or operands to see a list of services that are controlled by inetd. Use the inetadm, svcadm, and svccfg commands to configure and manage these converted services.

The inetconv command does not modify the input inetd.conf file. You should manually delete any entries in the inetd.conf file after successfully running inetconv.

For information about configuring inetd services that are already converted to SMF services, see "Modifying Services that are Controlled by inetd" on page 84.

Index

A actions, 20 admin layer, 28, 51 authorizations, 32 auxiliary service state, 23	masking, 81 modifying, 67 refreshing, 62 setting property values, 70 unmasking, 81 configuration files, 17, 18, 30 configuration repository <i>See</i> service configuration repository
B	contract service, 22
backups, 29	customizations
boot backups, 29 boot command	listing, 51
milestone option, 108	
none milestone, 110	E .
booting	D
current milestone, 109	daemon service, 22 default restarter, 24
logging levels, 107 milestones, 108 to an SMF milestone, 110 without starting services, 110	degraded service state, 23, 99, 103 delegated restarters, 25 delete a service, 63
bundles support, 81 bundles, 27	dependencies, 23, 24 effect on the state of a dependent service, 40 groupings, 37 instances that a service depends on, 38 instances that depend on a service, 39
С	listing, 36
child service, 22	describe subcommand
composed view, 26, 45	svccfg command, 44 disable a service, 58
config property group, 26	disabled service, 36 disabled service state, 23
configuration	disabled service state, 23
adding property groups and properties, 77 adding property values, 70 deleting bundle-supported configuration, 81 deleting customizations, 79, 81 deleting properties, 79 deleting property groups, 79 deleting property values, 79	E editing view, 47 enable a service, 55 environment variables modifying in methods, 76

error logging, 42	libscf library, 26
/etc/inetd.conf file, 30, 88, 111	batch operation functions, 18
/etc/init.d scripts, 30	listcust subcommand
/etc/inittab entries, 30	svccfg command, 47,51
/etc/rc?.d scripts, 30	listpg subcommand
event notification, 64	svccfg command,47
	listprop subcommand
	svccfg command, 47
F	listsnap subcommand
Fault Management Resource Identifier See FMRI	svccfg command, 50
FMRI	log files, 42
service and instance, 22	lrc services, 30
G	••
	M
general property group, 26	maintenance service state, 23, 99, 103
	manifest layer, 28,51
	manifest-import backups, 29
	manifest-import service configuration refresh, 62
inetadm command, 111	manifests, 20
examples, 84	standard location, 27
inetconv command, 111	masked configuration, 81
inetd command, 111	masked entities, 51, 63
inetd Internet services restarter daemon, 25	master restarter daemon, 24 methods, 20
inetd service	milestone services, 20
adding instances, 84	milestones
convert to SMF service, 111	booting, 108
modifying properties, 84	corresponding run levels, 108
inetd.conf file, 30, 111	currently booted, 109
init states <i>See</i> run levels	none, 110
init.d scripts, 30	,
initial snapshot, 29	
inittab entries, 30	N
instances, 20	
adding, 82 naming, 22	non-persistent properties, 49 non-persistent property groups, 48
nanning, 22	notification configuration, 64
	notification parameters
1	displaying, 52
L laws 20	
layers, 28	
admin layer, 51	0
manifest layer, 51	0
site-profile layer, 51	offline service state, 23, 99
legacy run service state. 33	online service state. 23

P	current, 109
periodic service, 22	default level, 108
scheduling, 72	running snapshot, 29, 45
periodic-restarter periodic services restarter	
service, 25	
permissions, 32	S
previous snapshot, 29	scheduled service, 22
privileges, 32	scheduling, 72
profiles, 20	security
creating, 89	disabling unneeded services, 58
packaging, 94	limiting concurrent processes, 86
site directory, 27	rights, 32
standard location, 27	selectsnap subcommand
properties, 26, 26, 44	svccfg command, 46
composed view of, 26, 45	service bundles
editing view of, 47	standard locations, 27
in the running snapshot, 45	Service Configuration Facility library, libscf, 26
non-persistent, 48	service configuration repository, 20, 26
property groups, 26, 44	backups, 29
non-persistent, 48	layers, 28
type, 47	library interfaces, 26
	modifying, 67
	repairing, 104
D.	snapshots, 29
R	svc.configd daemon, 104
rc?.d scripts, 30	template data, 26
refresh service configuration, 62	service contract, 22
remove a service, 63	service instances, 20
repository <i>See</i> service configuration repository	adding, 82
resolv.conf file, 30	service models, 22
restart a service, 60	service properties, 26, 26, 44
restart the manifest-import service, 60	service property groups, 26, 44
restarter property group, 26	service restarter, 24
restarters, 20, 24	service states
default restarter, 24	auxiliary state, 23
delegated restarters, 25	changing manually, 99, 103
inetd Internet services restarter daemon, 25	description, 23
svc.periodicd periodic services restarter	listing, 33
daemon, 25	transitions, 23
svc.startd master restarter daemon, 24	services, 20
restore_repository command, 105	deleting, 63
rights profiles, 32	disabling, 58
roles, 32	enabling, 55
run control scripts, 30	modifying configuration, 67
run levels	naming, 22
corresponding SMF milestones, 108	refreshing configuration, 62

restarting, 60	add subcommand, 82
starting, 55	addpg subcommand, 77
stopping, 58	addpropvalue subcommand, 70, 77
single-user login, 104	apply subcommand, 84
site-profile layer,28, 51	command input file, 70
SMF database <i>See</i> service configuration repository	delcust -M subcommand, 81
snapshots, 46, 50	delcust subcommand, 79, 81
initial, 29	delete subcommand, 63
previous, 29	delpg subcommand, 79
reverting, 83	delprop subcommand, 79
running, 29	delpropvalue subcommand, 79
running snapshot, 45	describe subcommand, 44
start, 29	editprop subcommand, 68
updating running configuration, 62	extract subcommand, 92
start a service, 55	import subcommand, 84
start property group,26	interactive use, 69
start snapshot,29	listcust -M subcommand, 63, 81
STATE column, 33	
state transition notification, 64	listcust subcommand, 47, 51
stencil files, 18	listpg subcommand, 47
stop a service, 58	listprop subcommand, 47
sulogin command,104	listsnap subcommand, 50
svc.configd repository daemon, 104	refresh subcommand, 62
svc.periodicd periodic services restarter daemon, 25	revert subcommand, 83
svc.startd master restarter daemon, 24, 104	selectsnap subcommand, 46, 83
svc:/network/inetd Internet services restarter	setenv subcommand, 70, 76
service, 25	setprop subcommand, 70, 77, 79
svc:/system/svc/periodic-restarter periodic	showing properties, 44
services restarter service, 25	unsetenv subcommand, 76
svc:/system/svc/restarter:default master	svcio utility, 18
restarter daemon, 24	svcprop command
svcadm command, 55	showing properties, 44, 45
clear subcommand, 99	svcs command, 33
disable subcommand, 58	sysconfig command
enable subcommand, 55	create-profile subcommand, 93
mark subcommand, 103	system-profile layer, 28
milestone subcommand, 108, 110	
refresh subcommand, 62	
restart manifest-import subcommand, 60,63	Т
restart subcommand, 60, 99	template data, 26
synchronous options, 18	transient service, 22
sycbundle command	
creating profiles, 93	
svccfg command	U
J	uninitialized service state. 23

update service configuration, 62

W

wait service, 22