

Speed and Velocity.

- distribution of speed

$$\int_0^\infty f(v) dv = 1$$

- distribution of velocity

$$\int_{-\infty}^{\infty} \int_{-\infty}^{\infty} \int_{-\infty}^{\infty} F(v_x, v_y, v_z) dv^3 = 1$$

- Isotropic Velocity Distribution

Isotropic means the same in all directions.

$$\text{eg. } \langle v_x^2 \rangle = \langle v_y^2 \rangle = \langle v_z^2 \rangle = \frac{1}{3} \langle v^2 \rangle.$$

$$\langle v_x \rangle = \langle v_y \rangle = \langle v_z \rangle = 0.$$

volume element in the spherical coordinate.

$$dv (v d\theta) (v \sin\theta d\phi)$$

$$= v^2 \sin\theta dv d\theta d\phi.$$

Since isotropic. ϕ doesn't matter.

$$f_{sp} = \frac{1}{4\pi} f(v) \sin\theta.$$

Normalisation:

$$\frac{1}{4\pi} \int_0^\infty f(v) dv \cdot \int_0^\pi \sin\theta d\theta \int_0^{2\pi} d\phi = 1.$$

$$\int_0^\infty f(v) dv = 1$$

$f(v)$ is the speed distribution

$$f_{sp}(v, \theta, \phi) dv d\theta d\phi = F(v_x, v_y, v_z) dv_x dv_y dv_z$$

For any distribution

$$f_{sp}(v, \theta, \phi) = v^2 \sin\theta F(v_x, v_y, v_z).$$