Configure the Kafka Client & Gateway

Configure the Gravitee Kafka Gateway and Kafka client to proxy a Kafka cluster, including TLS, broker mapping, mTLS authentication, and producing and consuming messages.

Overview

To use Gravitee to proxy a Kafka cluster, configure the Gravitee Kafka Gateway and Kafka client.

Configure the Kafka Gateway

Running the Kafka Gateway requires an Enterprise license with the Kafka Gateway feature included. This does not come by default with a Gravitee license. It must be purchased separately from Gravitee.

To run the Kafka Gateway, enable the Gateway server in `gravitee.yml`. The full example of the configuration is defined [below](). The baseline required configuration is:

```
kafka:
  enabled: true

  routingMode: host # Default is host. Supported values: host, port. For port-based routing, # Routing Port Mode
  # Routing Host Mode
  domainPattern: "broker-*.# Default is broker-*. Wildcard (*) is required. Example: broker-*.kafka.gravitee.io"
  advertisedListeners: "*:9092" # Default is public port for Kafka API. Default is 9092
```

Bootstrap server domain

- The Gateway runs multiple APIs on different **domains**. The Kafka client connects to the API using the bootstrap server domain (`bootstrapDomainPrefix`), where `bootstrap` is host prefix defined for each API.



The Kafka client routes to the correct API through Progressive Routing (SNI routing).

- To route to the correct API, the Gateway uses SNI routing, in which is part of the TLS protocol. Consequently, all client connections must support version 1.2, with at least `TLS_RSA_WITH_AES_128_CBC_SHA` in the client cipher configuration.
- The client must trust the certificate presented by the Gateway. To handle the variable host in the proxy bootstrap server URL, you likely need to request a wildcard SAN to use as the certificate presented by the Gateway.
- With the default configuration, you need a wildcard DNS entry so that you don't need a new DNS entry for every API. In this example, the DNS and wildcard certificate are for `*.kafka.gravitee.io`.

- When 1 Kafka restrictions on the domains I can use?

If you have restrictions on the domain names you can use for APIs, you can override the default hostname by updating the Gateway configuration. For example, instead of `localhost.{bootstrapDomain}`, on the hostname, you can set the pattern to `my-hostname-{apiHost}.mycompany.org` by configuring the variables below:

```
kafka:
  enabled: true

  routingMode: host # Default is host. Only host is supported for now.
  # Routing Host Mode
  domainPattern: "broker-*.# Default is broker-*. Wildcard (*) is required. Example: broker-*.kafka.gravitee.io"
  bootstrapPrefix: "bootstrap-" # Default is bootstrap-. Example: bootstrap-kafka.gravitee.io
  # The default domain where the Kafka APIs are exposed, ex: 'myapi' will be exposed as 'myapi.mycompany.org'. Default is the same as the bootstrap host.
  defaultDomain: "kafka.gravitee.io" # Default public port for Kafka APIs. Default is 9092

  # Customize the host domain.
  # The {bootstrapDomain} token that will be evaluated at runtime, when the API is :
  # {bootstrapDomain} will be replaced with the bootstrap.host value
  # {apiHost} will be replaced with the host value of the API
  bootstrapDomainPattern: "my-hostname-{apiHost}.mycompany.org"
```

With this, if there are three brokers in the upstream cluster, the client must be able to route to `api1-broker-0.my-hostname-api1.mycompany.org`, `api1-broker-1.my-hostname-api1.mycompany.org`, and `api1-broker-2.my-hostname-api1.mycompany.org`, along with `my-hostname-api1.mycompany.org`.

- What if I don't have a valid DNS entry?

If you do not have a valid DNS entry for your Gateway hierarchy, for example, you're running the [Docker image]() on your machine, you may need to update your `/etc/hosts` file.

If you are running the Gateway locally or testing with the `defaultDomain` as `kafka.local`, you can update your `/etc/hosts` file with the following entries:

```
127.0.0.1   localhost kafka.local api1.kafka.local bootstrap.kafka.local
127.0.0.1   localhost broker-0.api1.kafka.local broker-1.api1.kafka.local broker-2
127.0.0.1   localhost broker-0.api2.kafka.local broker-1.api2.kafka.local broker-2
127.0.0.1   localhost broker-0.api3.kafka.local broker-1.api3.kafka.local broker-2
```

To add more APIs, you will need to add another API host to the first line and two more entries for each new API (`api2` and `api3` in this example).

Port allocation for port-based routing

When using port-based routing, each plan requires three port values:

- **Bootstrap port**: The entry point clients use to connect (range: 9234–65535)
- **Broker range start**: The beginning of the contiguous port range allocated for backend Kafka brokers (range: 9234–65535)
- **Broker range end**: The end of the contiguous port range allocated for backend Kafka brokers (range: 9234–65535)

The broker range must not overlap with the bootstrap port or with port allocations from other plans in the same environment.

Port conflict detection

The Gateway enforces four conflict rules within each environment to prevent port allocation conflicts:

- Broker ranges from different plans cannot overlap.
- A plan's bootstrap port cannot fall within another plan's broker range.
- A plan's broker range cannot contain another plan's bootstrap port.
- Bootstrap ports must be unique across all plans.

Conflict detection runs before plan creation or update and blocks operations that would violate these rules.

Configure mTLS authentication

All Kafka plans already use TLS for transport encryption by default. The configuration below is **only** required when a Kafka client must authenticate with mutual TLS (mTLS) using a client certificate.

To require client certificate authentication for Kafka Kafka APIs, add the following TLS properties to `gravitee.yml`. This is an infrastructure-level configuration that applies globally to all Kafka Kafka APIs deployed on the gateway:

Property	Description	Example
`kafka.ssl.clientAuth`	Requires client certificate authentication	`required`
`kafka.ssl.trustStore.type`	Truststore type for verifying client certificates	`jks`
`kafka.ssl.trustStore.password`	Gateway truststore password	`gravitee`
`kafka.ssl.trustStore.path`	Path to gateway truststore containing CA that signed client certificates	`/path/to/secrets/truststore.jks`
`kafka.ssl.keyStore.type`	Gateway keystore type	`jks`
`kafka.ssl.keyStore.password`	Gateway keystore password	`gravitee`
`kafka.ssl.keyStore.path`	Path to gateway keystore	`/path/to/secrets/keystore.jks`

The gateway truststore must contain the CA certificate that signed the client certificates. The gateway keystore contains the gateway's identity certificate.

To reject connections from clients whose certificates have been revoked, add a `kafka.ssl.crl` block to `gravitee.yml`. For more information about the HTTP server's CRL options — see [Reject revoked client certificates with a CRL]() for the full reference and behavior.

Configure mTLS authorization

By default, clients talk to Kafka APIs by using the bootstrap server as `localhost.{bootstrapDomain}`. This is set in `gravitee.yml`, but for convenience, when developing APIs in the UI, you can set the client advertised listener property in the hostname. You can also leave this value blank and respecify the full hostname in the API.

To configure the APIM Console to use the Kafka domain and port values for your Organization:

1. Log in to your Management Console
2. Select **Organizations**
3. Select **Entrypoints & Rewriting Tags**
4. In the **Entrypoints Configuration** section, confirm that the **Default Kafka domain** and **Default Kafka port** values match those of your Kafka API.

This value is then displayed on the entrypoint page of your APIs.



Configure the Kafka client

Configure the Kafka client. Gravitee can use a regular Kafka client. There are many implementations of the Kafka client, and you can use any client that supports the Kafka protocol.

As of the v0.6.0 release, the Kafka Gateway requires the Kafka client to be version 3.0 or above.

The default client for talk to Kafka is packaged within the Kafka library and is based on Java. The prerequisite for using this client is a JRE. See the [Java documentation]() for more information on how to install a JRE.

1. Download Kafka. Gravitee Kafka Gateway is compatible with the source code or either binary download of Apache Kafka distribution. For more information about downloading Kafka, go to [Kafka download page]().
2. Store the downloaded file structure in a secure place. You'll need the path to your existing directory when calling your Kafka API.

The client has a handy tool, its `/bin` directory contains messages, create a `.properties` file in this root folder, as described in the [Example]() section.

At this point, you can begin creating and deploying APIs in the Gravitee Kafka Gateway.

Configure Kafka clients for mTLS authentication

When using an mTLS plan, Kafka clients must present a client certificate during the TLS handshake in addition to the standard TLS configuration. Add the following TLS properties to the client's `.properties` file:

Property	Description	Example
`ssl.keystore.location`	Path to client keystore containing the certificate	`/path/to/client.keystore.jks`
`ssl.keystore.type`	Client keystore type	`JKS`
`ssl.keystore.password`	Client keystore password	`gravitee`

Produce and consume messages

Use the Gravitee Kafka Gateway and client to call your Kafka API and, as a primary use case, produce or consume messages. You can also proxy requests to create and manage topics, update partitions, and manage consumer groups.

Prerequisites

The following prerequisites must be met before you can produce messages to Gravitee Kafka API.

- You must have an active subscription to a published API plan belonging to your Gravitee Kafka API.
- If you are subscribed to an OAuth2 or JWT plan, your application must reference the same client-id that you use for authentication.
- When using [Gravitee Access Management (AM)]() as the authorization server, the client-id is generated when you create an application. For more information, see Gravitee resources. If you are not, then any client-id can be used.

For plan, application, subscription, and resource information, see the following:

- For information on how to create and manage plans, see [Plans]().
- To learn how to create an application for a Gravitee plan, see [Applications]().
- For more information on how subscriptions work in Gravitee, see [Subscriptions]().
- To learn how to create a resource, see [Resources]().

Plan security must exclusion

Gravitee Kafka APIs enforce strict separation between plan security types. You can't mix Keyless, mTLS, and authentication plans such as OAuth2, JWT, and API Key in published plans. When you publish a plan of one type, all published plans of conflicting types are automatically closed. Multiple plans of the same security type can coexist. For example, two mTLS plans can coexist.

The following table summarizes plan type coexistence rules:

Plan Type	Can Coexist With	Conflicts With
Keyless	Other Keyless plans	mTLS, API Key, OAuth2, JWT
mTLS	Other mTLS plans	Keyless, API Key, OAuth2, JWT
API Key, OAuth2, JWT	Other authentication plans	Keyless, mTLS

If you need to support multiple security types simultaneously, create separate APIs for each security model.

Certificate-based subscription rejection

The gateway extracts the client certificate from the TLS session, computes its SHA1 hash, and uses the hash as a security token to look up the subscription. The subscription must be registered in the gateway's local store manager.

On successful validation, the gateway populates the connection context with the following attributes for policies and analytics:

- `plan`id
- `application`id
- `subscription`id

Example

The following example provides a template for how to produce and consume messages using the Kafka Gateway, Kafka client, and the prerequisites mentioned above.

1. In the top-level folder of your Kafka download, create an empty `.properties` file named `connect.properties`.
2. Go to the Developer Portal and find your API.
3. After selecting your API, click the **My Subscriptions** tab.
4. Copy the script in the **Gravitee Kafka Properties** section, and then paste it into your `connect.properties` file.

Gravitee Kafka Properties
Paste the `connect.properties` to set your values by API.

```
security.protocol=SSL_SSL
ssl.endpoint.identification.algorithm=
ssl.truststore.location=/path/to/gravitee_kafka_truststore.jks
ssl.truststore.password=GRAVITEE_KAFKA_TRUSTSTORE_PASSWORD
ssl.keystore.location=/path/to/gravitee_kafka_keystore.jks
ssl.keystore.password=GRAVITEE_KAFKA_KEYSTORE_PASSWORD
client.dns.lookup=use_all_dns_ips
# Configure your truststore if you are using a self-signed certificate
# ssl.truststore.location=/path/to/truststore.jks
# ssl.truststore.password=TRUSTSTORE_PASSWORD
```

5. Copy either the producer or consumer command from the **Calling the API** section.

Calling the API
Use the following command as example for calling the API.

Producer

```
./bin/kafka-console-producer.sh \
  --bootstrap-server \
  --producer.config connect.properties
```

Consumer

```
./bin/kafka-console-consumer.sh \
  --bootstrap-server \
  --consumer.config connect.properties
```

6. In a terminal, change your working directory to the top-level folder of your Kafka download.
7. Paste the commands you copied, and then execute them to produce or consume messages.

Appendix: Full Gateway Configuration

The following is the full server configuration for the Kafka gateway and listeners:

```
kafka:
  enabled: false

  routingMode: host # Default is host. Only host is supported for now.
  # Routing Host Mode
  domainPattern: "broker-*.# Default is broker-*. Wildcard (*) is required. Example: broker-*.kafka.gravitee.io"
  bootstrapPrefix: "bootstrap-" # Default is bootstrap-. Example: bootstrap-kafka.gravitee.io
  # The default domain where the Kafka APIs are exposed, ex: 'myapi' will be exposed as 'myapi.mycompany.org'. Default is the same as the bootstrap host.
  defaultDomain: "kafka.gravitee.io" # Default public port for Kafka APIs. Default is 9092

  # With the open Redirect configuration, the Gravitee Gateway yields bootstrap and 9
  # Customize the host domain.
  # The {bootstrapDomain} token that will be evaluated at runtime, when the API is :
  # {bootstrapDomain} will be replaced with the bootstrap.host value
  # {apiHost} will be replaced with the host value of the API
  bootstrapDomainPattern: "my-hostname-{apiHost}.mycompany.org"

  # Use to override to fit your DNS configuration.
  # Only to return APIs pointing to the url, as well as 'default/host'. Please note that
  # Default is false
  # defaultOnly: false
  # bootstrapAdvertisedListeners: bootstrap:localhost:9092
  # advertisedListeners: localhost:9092

  # mTLS configuration
  # clientAuth: required
  # ssl:
  #   keystore:
  #     password: gravitee
  #     path: /path/to/keystore.jks
  #   watch: true
  #   trustStore:
  # mTLS configuration
  # ssl:
  #   keystore:
  #     # Supports either JKS or PEM
  #     type: jks
  #     path: /path/to/secrets/gateway/ssl/server.keystore.jks
  #     password: secret
  #   watch: true
  #   trustStore:
  #     type: jks
  #     path: /path/to/secrets/my-certificates
  #     password: gravitee
```