

Node Management API v 1.0 Provisioning

Release Date: June 27, 2019
Protection Level: Confidential

CCH® Tagetik

Via Roosevelt 103, 55100 Lucca, Italy
Ph. +39 0583 96811 • **M.** info@cchtagetik.com
VAT IT 01234830469

We get Finance. You get Results.

Introduction

This file is a technical document that can be used by a developer in order to implement an integration with the CPM node management services. A basic understanding of REST services and HTTP protocol is required.

As of version 5.3 SP8 CCH Tagetik exposes node management REST API, designed to monitor the state of a node and manage its configuration.

Readers of this manual should have some experience in configuring and managing the JEE application server being used to deploy the CCH Tagetik application.

Please contact CCH Tagetik Software above concerning any questions or comments related to the contents of this document.

Technical Details

In order to enable the SCIM endpoints, the system property **com.tagetik.rest.management.v1.ws.enabled** must be set to **true**. This can be set configuring properly the application server. In order to modify this behavior the application server restart is required.

All the endpoint operations within the application are administration features, so they can be accessed only by users with administration credentials. The endpoints are protected by **Basic Authentication,** that is a standard simple authentication scheme built into the HTTP protocol. More details about this standard are provided at the following link: https://tools.ietf.org/html/rfc1945#section-11.1

Endpoints

Server Status endpoint

This endpoint allows to list all the diagnostic controls on the server.
https://<host>:<port>/<context-root>/api/management/v1/serverstatus/

Basic Authentication

Operations:

Operation	Http Method	Request Body	Path Variable	Query String Parameters	Response Body	HTTP Response Status	Response Status (Exception)
Read	GET	-	-	-	ServerStatusInfoVo	200 (Success)	401 (Unauthorized)

Invocation examples:

OPERATION	HTTP Method	URL	Request Body
Read	GET	***https://<host>:<port>/<context-root>/api/management/v1/serverstatus/***	-

Exceptions:

Http Status	Description
401 (Unauthorized)	It occurs when the user is not authorized.

Response Body Sample:


```
{
  "connectedUsers": [
    {
      "number": 1,
      "clientType": "BROWSER"
    }
  ],
  "runningElaborations": [],
  "systemUptime": {
    "years": 0,
    "months": 0,
    "days": 0,
    "hours": 0,
    "minutes": 20,
    "seconds": 5
  },
  "memoryStatus": {
    "S0C": "206848,0",
    "S1C": "151040,0",
```

```
      "S0U": "0,0",
      "S1U": "0,0",
      "EC": "972288,0",
      "EU": "119060,4",
      "OC": "2796544,0",
      "OU": "2325686,8",
      "MC": "988544,0",
      "MU": "956459,5",
      "CCSC": "111232,0",
      "CCSU": "104754,5",
      "YGC": "245",
      "YGCT": "23,710",
      "FGC": "11",
      "FGCT": "11,077",
      "GCT": "34,787"
   },
   "schedulingStatus": {
      "enabled": true
   }
}
```


ServerStatusInfoVo

Name	Schema	Description
connectedUsers	<ConnectedUsersVo> array	List of connected users
memoryStatus	MemoryStatusVo	JVM memory status
runningElaborations	<ElaborationVo> array	List of running elaborations
schedulingStatus	SchedulingStatusVo	Scheduling Status
systemUptime	UptimeSystemVo	Server uptime information

Connected Users endpoint

This endpoint allows to list the currently logged users on the server.
https://<host>:<port>/<context-root>/api/management/v1/serverstatus/connectedUsers

Basic Authentication

Operations:

Operation	Http Method	Request Body	Path Variable	Query String Parameters	Response Body	HTTP Response Status	Response Status (Exception)
Read	GET	-	-	-	ConnectedUserVo	200 (Success)	401 (Unauthorized)

Invocation examples:

OPERATION	HTTP Method	URL	Request Body
Read	GET	***https://<host>:<port>/<context-root>/api/management/v1/serverstatus/connectedUsers***	-

Exceptions:

Http Status	Description
401 (Unauthorized)	It occurs when the user is not authorized.

Response Body Sample:


```
[
  {
    "number": 1,
    "clientType": "BROWSER"
  }
]
```


ConnectedUsersVo

Name	Schema	Description
clientType	string	Connected client type
number	Integer (int64)	Number of client connected

Memory Status endpoint

This endpoint allows to list the information about the server Java Virtual Machine memory parameters. They are retrieved executing a **jstat** command on the node.

https://<host>:<port>/<context-root>/api/management/v1/serverstatus/memoryStatus

Basic Authentication

Operations:

Operation	Http Method	Request Body	Path Variable	Query String Parameters	Response Body	HTTP Response Status	Response Status (Exception)
Read	GET	-	-	-	MemoryStatusVo	200 (Success)	401 (Unauthorized)

Invocation examples:

OPERATION	HTTP Method	URL	Request Body
Read	GET	***https://<host>:<port>/<context-root>/api/management/v1/serverstatus/memoryStatus***	-

Exceptions:

Http Status	Description
401 (Unauthorized)	It occurs when the user is not authorized.

Response Body Sample:


```
{
   "S0C": "206848,0",
   "S1C": "228352,0",
   "S0U": "2240,0",
   "S1U": "0,0",
   "EC": "941056,0",
   "EU": "613649,6",
   "OC": "2796544,0",
   "OU": "2325694,8",
   "MC": "988544,0",
   "MU": "956652,7",
   "CCSC": "111232,0",
   "CCSU": "104792,0",
   "YGC": "246",
   "YGCT": "23,757",
   "FGC": "11",
   "FGCT": "11,077",
   "GCT": "34,834"
}
```


MemoryStatusVo

Name	Schema
CCSC	string
CCSU	string
EC	string
EU	string
FGC	string
FGCT	string
GCT	string
MC	string
MU	string
OC	string
OU	string
S0C	string

S0U	string
S1C	string
S1U	string
YGC	string
YGCT	string

Running Elaborations endpoint

This endpoint allows to list elaborations currently running on the server
https://<host>:<port>/<context-root>/api/management/v1/serverstatus/runningElaborations

Basic Authentication

Operations:

Operation	Http Method	Request Body	Path Variable	Query String Parameters	Response Body	HTTP Response Status	Response Status (Exception)
Read	GET	-	-	-	ElaborationVo	200 (Success)	401 (Unauthorized)

Invocation examples:

OPERATION	HTTP Method	URL	Request Body
Read	GET	***https://<host>:<port>/<context-root>/api/management/v1/serverstatus/runningElaborations***	-

Exceptions:

Http Status	Description
401 (Unauthorized)	It occurs when the user is not authorized.

Response Body Sample:

```
[
  {
    "username":"YOUNG",
    "oid":"123",
    "elaboration":"EXP_ELABORATION"
  }
]
```

ElaborationVo

Name	Schema	Description
elaboration	String	Elaboration type
oid	string	Elaboration identifier
username	string	The user that launched the elaboration

Scheduling Status endpoint

This endpoint allows to retrieve information about and to set the scheduling status
https://<host>:<port>/<context-root>/api/management/v1/serverstatus/schedulingStatus

Basic Authentication

Operations:

Operation	Http Method	Request Body	Path Variable	Query String Parameters	Response Body	HTTP Response Status	Response Status (Exception)
Read	GET	-	-	-	SchedulingStatusVo	200 (Success)	401 (Unauthorized)
Update	PUT	SchedulingStatusVo (required)	-	-	-	200 (OK)	

Invocation examples:

OPERATION	HTTP Method	URL	Request Body
Read	GET	***https://<host>:<port>/<context-root>/api/management/v1/serverstatus/schedulingStatus***	-
Update	PUT	***https://<host>:<port>/<context-root>/api/management/v1/serverstatus/schedulingStatus***	SchedulingStatusVo

Exceptions:

Http Status	Description
401 (Unauthorized)	It occurs when the user is not authorized.

GET Response Body Sample:

```
{
   "enabled": true
}
```

PUT Request Body Sample:

```
{
   "enabled": false
}
```

SchedulingStatusVo

Name	Schema	Description
enabled	boolean	The node scheduling status

System Uptime endpoint

This endpoint allows to retrieve server uptime information
https://<host>:<port>/<context-root>/api/management/v1/serverstatus/systemUptime

Basic Authentication

Operations:

Operation	Http Method	Request Body	Path Variable	Query String Parameters	Response Body	HTTP Response Status	Response Status (Exception)
Read	GET	-	-	-	UptimeStatusVo	200 (Success)	401 (Unauthorized)

Invocation examples:

OPERATION	HTTP Method	URL	Request Body
Read	GET	***https://<host>:<port>/<context-root>/api/management/v1/serverstatus/systemUptime***	-

Exceptions:

Http Status	Description
401 (Unauthorized)	It occurs when the user is not authorized.

Response Body Sample:

```
{
  "years": 1,
  "months": 3,
  "days": 25,
  "hours": 23,
  "minutes": 58,
  "seconds": 59
}
```

SystemUptimeVo

Name	Schema	Description
years	int	Uptime years
months	int	Uptime months
days	int	Uptime days
hours	int	Uptime hours
minutes	int	Uptime minutes
seconds	int	Uptime seconds

Messages endpoint

This endpoint allows to send a message to a specific user.

https://<host>:<port>/<context-root>/api/management/v1/messages

Basic Authentication

Operations:

Operation	Http Method	Request Body	Path Variable	Query String Parameters	Response Body	HTTP Response Status	Response Status (Exception)
Create	POST	DirectMessage	-	-	-	201 (Created)	400 (Bad Request) 401 (Unauthorized)

Invocation examples:

OPERATION	HTTP Method	URL	Request Body
Create	POST	***https://<host>:<port>/<context-root>/api/management/v1/messages***	DirectMessage

Exceptions:

Http Status	Description
400 (Bad Request)	It occurs when the request is not correct.
401 (Unauthorized)	It occurs when the user is not authorized.

Request Body Sample:

```
{
  "recipient": “YOUNG”,
  "subject": “UPDATE”,
  "text": “TEST”,
  "priority": “HIGH”
}
```

DirectMessage

Name	Schema	Description
recipient	String	Recipient user
subject	String	Message subject
text	String	Message text
priority	String	Message priority

Broadcast endpoint

This endpoint allows to send a broadcast message to all users.

https://<host>:<port>/<context-root>/api/management/v1/messages/broadcast/all

Basic Authentication

Operations:

Operation	Http Method	Request Body	Path Variable	Query String Parameters	Response Body	HTTP Response Status	Response Status (Exception)
Create	POST	Message	-	-	sentMessagesCount	201 (Created)	400 (Bad Request) 401 (Unauthorized)

Invocation examples:

OPERATION	HTTP Method	URL	Request Body
Create	POST	***https://<host>:<port>/<context-root>/api/management/v1/messages/broadcast/all***	Message

Exceptions:

Http Status	Description
400 (Bad Request)	It occurs when the request is not correct.
401 (Unauthorized)	It occurs when the user is not authorized.

Request Body Sample:

```
{
  "subject": “UPDATE”,
  "text": “TEST”,
  "priority": “HIGH”
}
```

Response Body Sample:

2

Message

Name	Schema	Description
subject	String	Message subject
text	String	Message text
priority	String	Message priority

sentMessagesCount

Name	Schema	Description
sentMessagesCount	int	Number of delivered messages

Glossary

The following table provides a short glossary for the terminology used in this manual.

JVM	Java Virtual Machine
RFC	Request for comments

Notes and Copyright

Tagetik Software S.r.l with a sole quota holder reserves the right to change the contents of this document without prior notice. All trademarks are the property of the trademark owners.

This document and its contents are the sole property of Tagetik Software S.r.l with a sole quota holder; and are protected by Italian Copyright Law no. 633/1941 and by any applicable international agreements and treaties concerning intellectual property rights. All rights, including the intellectual property rights, are reserved to Tagetik Software S.r.l with a sole quota holder. The user of this document is authorized by Tagetik Software S.r.l with a sole quota holder to make copies of this document for private purposes only in paper and/or electronic formats for the sole purpose of training in relation to the use of CCH® Tagetik software for the benefit of the staff/employees of the above-mentioned company. Any other use is hereby expressly forbidden.