


Packet Tracer - Configuring IPv4 Static and Default Routes

Topology



Addressing Table

Device	Interface	IPv4 Address	Subnet Mask	Default Gateway
R1	G0/0	172.31.1.1	255.255.255.128	N/A
	S0/0/0	172.31.1.194	255.255.255.252	N/A
R2	G0/0	172.31.0.1	255.255.255.0	N/A
	S0/0/0	172.31.1.193	255.255.255.252	N/A
	S0/0/1	172.31.1.197	255.255.255.252	N/A
R3	G0/0	172.31.1.129	255.255.255.192	N/A
	S0/0/1	172.31.1.198	255.255.255.252	N/A
PC1	NIC	172.31.1.126	255.255.255.128	172.31.1.1
PC2	NIC	172.31.0.254	255.255.255.0	172.31.0.1
PC3	NIC	172.31.1.190	255.255.255.192	172.31.1.129

Objectives

Part 1: Examine the Network and Evaluate the Need for Static Routing

Part 2: Configure Static and Default Routes

Part 3: Verify Connectivity

Packet Tracer - Configuring IPv4 Static and Default Routes

Background

In this activity, you will configure static and default routes. A static route is a route that is entered manually by the network administrator to create a reliable and safe route. There are four different static routes that are used in this activity: a recursive static route, a directly attached static route, a fully specified static route, and a default route.

Part 1: Examine the Network and Evaluate the Need for Static Routing

- Looking at the topology diagram, how many networks are there in total? Total 5 Networks
- How many networks are directly R1 and R3 have 2 networks and R2 has 3 networks directly connected.
- How many static routes are required by each router to reach networks that are not directly connected? R1 and R1 need 3 and R2 need 2 static routes.
- Test connectivity to the R2 and R3 LANs by pinging PC2 and PC3 from PC1.
Why were you unsuccessful? Because routers are not configured the static routes to reach those remote networks and to get the reply back.

Part 2: Configure Static and Default Routes

Step 1: Configure recursive static routes on R1.

- What is recursive static route? It points the IP of the next hop to reach destination network.
- Why does a recursive static route require two routing table lookups? One lookup to find the destination IP address and another lookup to find the exit pathway with the next hop IP.
- Configure a recursive static route to every network not directly connected to R1, including the WAN link between R2 and R3.
- Test connectivity to the R2 LAN and ping the IP addresses of PC2 and PC3.
Why were you unsuccessful? No, because R2 doesnt have a return route configured back to R1 LAN.

Step 2: Configure directly attached static routes on R2.

- How does a directly attached static route differ from a recursive static route? A directly attached static route state the exit interface instead of the next hop IP address.
- Configure a directly attached static route from R2 to every network not directly connected.

- c. Which command only displays directly connected networks? sh ip route connected
- d. Which command only displays the static routes listed in the routing table? sh ip route static
- e. When viewing the entire routing table, how can you distinguish between a directly attached static route and a directly connected network? Directly connected network has a label "C" whereas static route are labeled as "S."

© 2013 Cisco and/or its affiliates. All rights reserved. This document is Cisco Public. Page 2 of 4

Packet Tracer - Configuring IPv4 Static and Default Routes

Step 3: Configure a default route on R3.

- a. How does a default route differ from a regular static route? A default route works like a backup plan and matches all destination networks not specifically in the routing table using 0.0.0.0 0.0.0.0 address. On the other hand, a regular static route points a specific network.
- b. Configure a default route on R3 so that every network not directly connected is reachable.
- c. How is a static route displayed in the routing table? A static route is labeled as "S" whereas a default static route is labeled as "S*"

Step 4: Document the commands for fully specified routes.

Note: Packet Tracer does not currently support configuring fully specified static routes. Therefore, in this step, document the configuration for fully specified routes.

- a. Explain a fully specified route. A fully specified route consists both the next hop ip address and the exit interface.
- b. Which command provides a fully specified static route from R3 to the R2 LAN? ip route 172.31.0.0 255.255.255.0 s0/0/1 172.31.1.197
- c. Write a fully specified route from R3 to the network between R2 and R1. Do not configure the route; just calculate it. ip route 172.31.1.192 255.255.255.252 s0/0/1 172.31.1.197
- d. Write a fully specified static route from R3 to the R1 LAN. Do not configure the route; just calculate it. ip route 172.31.1.0 255.255.255.128 s0/0/1 172.31.1.197

Step 5: Verify static route configurations.

Use the appropriate **show** commands to verify correct configurations.

Which **show** commands can you use to verify that the static routes are configured correctly? sh ip route, sh ip route static, show running-config

Part 3: Verify Connectivity

Every device should now be able to ping every other device. If not, review your static and default route configurations.

© 2013 Cisco and/or its affiliates. All rights reserved. This document is Cisco Public. Page 3 of 4

Packet Tracer - Configuring IPv4 Static and Default Routes

Suggested Scoring Rubric

Activity Section	Question Location	Possible Points	Earned Points
Part 1: Examine the Network and Evaluate the Need for Static Routing	a - d	10	
Part 1 Total		10	
Part 2: Configure Static and Default Routes	Step 1	7	
	Step 2	7	
	Step 3	3	
	Step 4	10	
	Step 5	3	
Part 2 Total		30	
Packet Tracer Score		60	
Total Score		100	

© 2013 Cisco and/or its affiliates. All rights reserved. This document is Cisco Public. Page 4 of 4