Potentials

Michael Brodskiy

Professor: D. Wood

October 2, 2023

$$\oint \vec{E} \cdot d\vec{a} = \frac{q_{enc}}{\varepsilon_o} \Leftrightarrow \vec{\nabla} \cdot \vec{E} = \frac{\rho}{\varepsilon_o}$$

This means that, in a region with no charge, $\vec{\nabla} \cdot \vec{E} = 0$, which also means $\nabla^2 V = 0$ (the Laplacian) Rectangular Coordinates:

$$\nabla^{2}V = 0 \qquad \frac{\partial^{2}V}{\partial x^{2}} + \frac{\partial^{2}V}{\partial y^{2}} + \frac{\partial^{2}V}{\partial z^{2}} = 0$$
$$V(x, y, z) = X(x)Y(y)Z(z) \Rightarrow \frac{\partial^{2}X}{\partial x^{2}}YZ + \frac{\partial^{2}Y}{\partial y^{2}}XZ + \frac{\partial^{2}Z}{\partial z^{2}}XY = 0$$

If we divide by the respective functions, we get:

$$\frac{\partial^2}{\partial x^2} \frac{1}{X} + \frac{\partial^2}{\partial y^2} \frac{1}{Y} + \frac{\partial^2}{\partial z^2} \frac{1}{Z} = 0$$

$$\frac{d^2 X}{dx^2} = c_1 X(x) \Rightarrow c_1 > 0:$$

$$X(x) = \begin{cases} Ae^{\pm kx} & c_1 = k^2 \\ A\sin(kx) & c_1 = -k^2 \\ A\cos(kx) & c_1 = -k^2 \end{cases}$$

• — Repeating this for each variable, we find

$$\frac{d^{2}Y}{dy^{2}} = c_{2}Y(y) \qquad \frac{d^{2}Z}{dz^{2}} = c_{2}Z(z)$$
$$c_{1} + c_{2} + c_{3} = 0$$

• Fourier Inversion

$$\int_0^a \sin\left(\frac{n\pi y}{a}\right) \sin\left(\frac{m\pi y}{a}\right) dy = \frac{a}{2}\delta_{nm}$$

This is used to define the terms for Fourier analysis

- A semi-infinite square tube, with the four walls grounded:
 - The boundary conditions are (with V = 0) given by:

$$\begin{cases} x = 0, & 0 < y < b \\ x = a, & 0 < y < b \\ y = 0, & 0 < x < a \\ y = b, & 0 < x < a \end{cases}$$

- This would mean:

$$X = \sin\left(\frac{n\pi x}{a}\right) \qquad Y \propto \sin\left(\frac{m\pi y}{b}\right) \qquad Z = e^{-k_z z}$$
$$V = \sum_{n,m} B_{n,m} e^{-k_z z} \sin\left(\frac{n\pi x}{a}\right) \sin\left(\frac{m\pi y}{b}\right)$$

– Because we know $c_1 + c_2 + c_3 = 0$, we know:

$$-\left(\frac{n\pi}{a}\right)^2 - \left(\frac{m\pi}{b}\right) + k_z^2 = 0$$
$$k_z = \sqrt{\left(\frac{n\pi}{a}\right)^2 + \left(\frac{m\pi}{b}\right)^2}$$

• Poisson's Equation

$$\nabla^2 V = -\frac{\rho}{\varepsilon_o}$$

- When the charge density is zero, we get Laplace's Equation:

$$\nabla^2 V = 0$$

• Given a box in three dimensions with lengths a, b, c, we know:

$$c_1 + c_2 + c_3 = 0 \longrightarrow \begin{cases} c > 0, & \text{Exponential} \\ c < 0, & \text{Sinusoidal} \end{cases}$$

- We know the voltage is of the form

$$V = f(z)\sin\left(\frac{n\pi x}{a}\right)\sin\left(\frac{m\pi y}{a}\right)$$

- The function, f(z), must then be of the form:

$$f(z) = Ae^{kz} + Be^{-kz}$$

- If V = 0, then z = 0, so:

$$A + B = 0 \rightarrow A = -B$$
$$f(z) = Ae^{kz} - Ae^{-kz}$$
$$= A(e^{kz} - e^{-kz})$$
$$= 2A\sinh(kz)$$

- Thus, we can set up the function as:

$$V(x, y, z) = \sum_{m,n} c_{m,n} \sin\left(\frac{n\pi x}{a}\right) \sin\left(\frac{m\pi y}{b}\right) \sinh(kz)$$

• Spherical Coordinates

$$\nabla^2 V = \frac{1}{r^2} \frac{\partial}{\partial r} \left(r^2 \frac{\partial V}{\partial r^2} \right) + \frac{1}{r^2 \sin(\theta)} \frac{\partial}{\partial \theta} \left(\sin(\theta) \frac{\partial V}{\partial \theta} \right) = 0$$

- In Quantum Mechanics, we have spherical harmonics:

$$Y_{lm}(\theta, \phi) = P_l(\cos(\theta)) f_{ml}(\phi)$$

- For our purposes, we can find:

$$V(r,\theta) = \sum_{l=0,1,\dots} \left(A_l r^l + \frac{B_l}{r^{l+1}} \right) P_e(\cos(\theta))$$

- A typical problem for this would be:
 - * Given some potential, $V(\theta)$ on a spherical surface, find V_{in} and V_{out}

$$R_e(r) = A_l r^l + \frac{B_l}{r^{l+1}}$$

$$V_{in} = A_l r^l P_l(\cos(\theta))$$

$$V_{out} = \frac{B_l}{r^{l+1}} P_l(\cos(\theta))$$

* We know the following boundary conditions:

$$r \to \infty, V \to 0$$

* We can integrate the function:

$$\int_{-1}^{1} V(R,\theta) P_l(\cos(\theta)) d(\cos(\theta)) = \frac{2R^l A_l}{2l+1}$$

- Example: Given $V(R, \theta) = E_o R \cos(\theta) = E_o R P_1(\cos(\theta))$

* This gives us:

$$\begin{cases} \text{Inside:} & V = A_1 r^2 \cos(\theta) \\ \text{Outside:} & V = \frac{B_1}{r^2} P_1(\cos(\theta)) \end{cases}$$

- For a sphere
 - We find $E_oR\cos(\theta)$:

$$\begin{cases}
Inside: & V = E_o r \cos(\theta) = E_o z \\
Outside: & V = \frac{E_o R^3}{r^2} (\cos(\theta))
\end{cases}$$

- We know:

$$\vec{E}_{in} = -\vec{\nabla}V_{in} = -\frac{\partial V}{\partial z}\hat{\mathbf{z}} = -E_o\hat{\mathbf{z}} = E_o(-\cos(\theta)\hat{\mathbf{r}} + \sin(\theta)\hat{\theta})$$
$$\vec{E}_{out} = -\vec{\nabla}V_{out} = -\frac{\partial V}{\partial r}\hat{\mathbf{r}} = -\frac{1}{r}\frac{\partial V_{out}}{\partial \theta} = \frac{E_oR^3}{r^3}(2\cos(\theta)\hat{\mathbf{r}} + \sin(\theta)\hat{\theta})$$

 To confirm our calculation, we can take the partial derivative with respect to the angle:

$$E_{in_{\theta}}(R) = E_o \sin(\theta)$$
$$E_{out_o}(R) = E_o \cos(\theta)$$

- We can then use Gauss's law:

$$\frac{\sigma A}{\varepsilon_o} = A(E_{out_r} - E_{in_r})$$

$$\sigma = \varepsilon_o(E_{out}(R, \theta) - E_{in}(R, \theta))$$

$$\sigma = 3\varepsilon_o(E_o \cos(\theta))$$

- This implies there is a positive charge at the north pole, a negative charge at the south pole, and no charge at the equator
- To find the total charge we can do the following:

$$Q = \int_0^{\pi} R^2 \sin(\theta) d\theta (3\varepsilon_o E_o \cos(\theta)) = 0$$

- Poles:
 - We can determine that:

$$\begin{cases} \text{Monopole:} & V \propto \frac{1}{r} \\ \text{Dipole:} & V \propto \frac{1}{r^2} \\ \text{Quadrupole:} & V \propto \frac{1}{r^3} \\ \text{Octopole:} & V \propto \frac{1}{r^4} \end{cases}$$

- The arrangement increases in dimension each time we go up an order; that, is, the shape is a single point charge for monopole, two equal but opposite charges along a line for dipole, a square with aggregate charge of zero for quadrupole, and a cube with aggregate charge zero for octopole
- The energy per positron may be expressed as $E_{e^+} = 2m_e c^2$
- Multipole Expansion

$$V(\vec{r}) = \frac{1}{4\pi\varepsilon_o} \sum_{n=0}^{\infty} \frac{1}{r^{n+1}} \int P_n(\cos(\alpha)) (r')^n \rho(\vec{r}') d\tau'$$

- For a sphere, the surface charge may be distributed according to:

$$\sigma = \sigma_o (1 - \cos(\theta))^2$$
$$\int \rho(\vec{r}') d\vec{\tau} \int \sigma(R, \theta) da'$$

where

$$da' = r' \sin(\theta') d\theta' d\phi' = 2\pi r' \sin(\theta') dr' d\theta'$$

can be made easier with

$$\int_0^{\pi} \sin(\theta') d\theta' \longleftrightarrow \int_{-1}^1 d(\cos(\theta'))$$

• Electric Field of a Dipole

$$\vec{E} = -\vec{\nabla}V = -\vec{\nabla}\left(\frac{\cos(\theta)}{4\pi\varepsilon_o r^2}\right)$$

- This assumes the z-axis is aligned with \vec{p}

$$\vec{E}_r = \frac{p\cos(\theta)}{2\pi\varepsilon_o r^3}$$

$$\vec{E}_{\theta} = \frac{p \sin(\theta)}{4\pi\varepsilon_{o} r^{3}}$$

- Thus, we get:

$$\vec{E} = \frac{p}{4\pi\varepsilon_o r^3} \left(2\cos(\theta)\hat{\mathbf{r}} + \sin(\theta)\hat{\theta} \right)$$