

HighRes Runner Suite

How to use GitHub to install and update the suite on any machine

Private repository: <https://github.com/MFFOTO/runner-suite-stage6>

The suite auto-detects the hardware at startup and picks the backend, model, worker count and image size on its own. On each machine you only set the input/output folders.

1. Set up a NEW machine

a) Install git (once per machine):

- Normal Windows (Intel/AMD): run `winget install --id Git.Git -e`
- Snapdragon / Windows-on-ARM: same command (Git for Windows has an ARM64 build)
- Or download from <https://git-scm.com/download/win>

b) Clone the repository (the first clone opens a browser login, because the repo is private):

```
cd D:\
git clone https://github.com/MFFOTO/runner-suite-stage6.git
cd runner-suite-stage6
```

c) Run setup - builds the Python environment and installs everything, and creates your settings.json from the template:

```
setup_runner_suite.bat
```

d) Set your paths - open settings.json and set `input_folder` and `output_folder`. Always use forward slashes (D:/events/originals), never backslashes - a single backslash breaks JSON.

e) Run:

```
run_elite_suite.bat
```

2. Update ANY machine (the whole point)

From the project folder:

```
cd D:\runner-suite-stage6
git pull
```

Only code updates land. Your settings.json and downloaded models are never touched.

3. Convert an EXISTING folder into a clone

If a machine already has a working project folder and you want `git pull` to work there without re-downloading everything:

```
cd D:\runner_suite_stage6_highres_plus
git init
git remote add origin https://github.com/MFFOTO/runner-suite-stage6.git
git fetch origin
del yolov8m-pose.pt yolov8n-pose.onnx 2>nul
```

```
git reset --hard origin/master
```

settings.json, the .venv and the extra model weights are git-ignored, so they stay as-is. The del line lets the reset restore the repo's model copies without an error (they come back from the local fetch - no re-download).

Simpler alternative (recommended if unsure): just clone fresh into a new folder (Section 1), copy your old settings.json in, and delete the old folder once it works.

4. How settings are handled

- **settings.json** - per machine, git-ignored. Your paths live here.
- **settings.example.json** - the tracked template; setup copies it to settings.json on first run.
- Because settings.json is ignored, git pull never conflicts on it.

5. Notes & gotchas

Windows paths in settings.json:

Use forward slashes, e.g. "D:/events/originals". A single backslash is an invalid JSON escape and crashes on load.

Microsoft Store Python (common on Copilot+ / Snapdragon laptops):

- A bare 'python' command may point at the sandboxed Store Python, not the venv. run_elite_suite.bat already calls the venv's python explicitly.
- Store-Python venvs leak the per-user packages into the path, which can hide venv packages. run_elite_suite.bat sets PYTHONNOUSERSITE=1 to block that.

Snapdragon / ARM GPU (DirectML):

- The suite runs on the Adreno GPU when yolov8n-pose.onnx is present and onnxruntime-directml is installed (pip install onnxruntime-directml).
- yolov8n-pose.onnx is included in the repo, so a clone/pull already has it - no need to export it (on-device export is often blocked by Smart App Control).
- Confirm the GPU in the [AUTO-TUNE] block: Backend: onnxruntime / DirectML (GPU).

Speed on CPU-only machines:

'pip install opencv' gives a faster x86 CPU backend (auto-selected). Lowering image_quality.target_height (e.g. 4000 to 3000) is the biggest speed lever on weak machines.