LAB 05

Working with Data related Operator and Directives, Addressing



STUDENT NAME	ROLL NO	$\overline{\text{SEC}}$
	I AD ENGINEEDIC CIONATUDE	

MARKS AWARDED: /

NATIONAL UNIVERSITY OF COMPUTER AND EMERGING SCIENCES (NUCES), KARACHI

Prepared by: Muhammad Nadeem

Lab Session 05: Working with Data Related Operators and Directives, Addressing

OBJECTIVES:

Observing effect of Arithmetic Instructions on Flag

Register Direct-offset operands

OFFSET operator

PTR operator

TYPE operator

LENGTHOF operator

SIZEOF operator

Indirect operands

Indexed operands

Effect of Arithmetic Instructions on Flag Registers

Status flags are updated to indicate certain properties of the result

Once a flag is set, it remains in that state until another instruction that affects the flags is executed

Z-Zero Flag:

The Zero flag is set when the result of an operation produces zero in the destination operand.

```
mov cx,1

sub cx,1 ; CX = 0, ZF = 1

mov ax,0FFFFh

inc ax ; AX = 0, ZF = 1

inc ax ; AX = 1, ZF = 0
```

Remember...

- A flag is set when it equals 1.
- · A flag is clear when it equals 0.

C-Carry Flag:

This flag is set, when there is a carry out of MSB in case of addition and borrow in case of subtraction.

The Carry flag is set when the result of an operation generates an unsigned value that is out of range (too big or too small for the destination operand).



LAB: 5 [Fall 2022] [COAL LAB]

```
mov al,0FFh
add al,1 ; CF = 1, AL = 00

; Try to go below zero:

mov al,0
sub al,1 ; CF = 1, AL = FF
```

S-Sign Flag:

This flag indicates the sign of the result of an operation. A 0 for positive number and 1 for a negative number.

mov	AL, 15	mov	AL,15
add	AL,97	sub	AL,97
clears the sign flag as		sets the sign flag as	
the result is 112		the result is -82	
(or 0111000 in binary)		(or 10101110 in binary)	

AC-Auxilary Carry Flag:

This flag is set, if there is a carry from the lowest nibble, i.e., bit three during addition, or borrow for the lowest nibble, i.e. bit three, during subtraction.

Suppose we add 1 to 0Fh. The sum (10h) contains a 1 in bit position 4 that was carried out of bit position 3:

```
mov al,0Fh add al,1 ; AC = 1
```

P Parity Flag:

The Parity flag (PF) is set when the least significant byte of the destination has an even number of 1 bits. The following ADD and SUB instructions alter the parity of AL:

```
mov al,10001100b
add al,00000010b ; AL = 10001110, PF = 1
sub al,10000000b ; AL = 00001110, PF = 0
```

O-Over flow Flag:



The Overflow flag is set when the result of a signed arithmetic operation over-flows or

underflows the destination operand. For example, the largest possible integer signed byte value is +127; adding 1 to it causes overflow:

Similarly, the smallest possible negative integer byte value is 128. Subtracting 1 from it causes underflow. The destination operand value does not hold a valid arithmetic result, and the Over-flow flag is set:

Direct-offset Operands:

You can add a displacement to the name of a variable, creating a direct-offset operand.

Example:

```
.data
arrayB BYTE 10h,20h,30h,40h
arrayW WORD 100h,200h,300h

.code
mov al,arrayB ; AL = 10h
mov al,[arrayB+1] ; AL = 20h
mov ax,arrayW ; AX = 100h
mov ax,[arrayW+2] ; AX = 200h
```

Similarly, the second element in a doubleword array is 4 bytes beyond the first one.

DATA-RELATED OPERATORS AND DIRECTIVES

OFFSET Operator:

The OFFSET operator returns the offset of a data label.

Syntax:

MOV reg32, OFFSET mem ; reg32 points to count



LAB: 5 [Spring 2022] [COAL LAB]

Example:

```
.data
bVal BYTE?
wVal WORD?
dVal DWORD?
dVal2 DWORD?
```

If bVal is located at offset 00404000h, we would get:

mov esi, OFFSET bval ; ESI = mov esi, OFFSET wVal ; ESI = mov esi, OFFSET dVal ; ESI = mov esi, OFFSET dVal2 ; ESI =

PTR Operator:

We can use the PTR operator to override the declared size of an operand. Note PTR must be used in combination with one of the standard assembler data types.

For example, that we would like to move the lower 16 bits of a doubleword variable named myDouble into AX. The assembler will not permit the following move because the operand sizes do not match:

```
.data
myDouble DWORD 12345678h
.code
mov ax, myDouble ; error
```

But the WORD PTR operator makes it possible to move the low-order word (5678h) to AX:

```
mov ax, word ptr myDouble ; AX = 5678H and higher word (1234h) to AX:
```

mov dx, word ptr myDouble+2 ; DX = 1234H

Moving Smaller Values into Larger Destinations

We might want to move two smaller values from memory to a larger destination operand. In the next example, the first word is copied to the lower half of EAX and the second word is copied to the upper half.

The DWORD PTR operator makes this possible:



```
.data
wordList WORD 5678h, 1234h
.code
mov eax, DWORD PTR wordList ; EAX = 12345678h
```

TYPE Operator:

The TYPE operator returns the size, in bytes, of a single element of a variable.

Syntax:

```
MOV reg16, TYPE mem
```

Example 1:

```
.data
var1 BYTE ? ; TYPE var1 = 1
var2 WORD ? ; TYPE var2 = 2
var3 DWORD ? ; TYPE var3 = 4
var4 QWORD ? ; TYPE var =8
```

Example 2:

```
.data
var1 BYTE 20h
var2 WORD 1000h
var3 DWORD ?
var4 BYTE 10, 20, 30, 40, 50
msg BYTE 'File not found', 0
.code
                          ; AX = 0001
mov ax, type var1
                          AX = 0002
mov ax, type var2
                          : AX = 0004
mov ax, type var3
mov ax, type var4
                          AX = 0001
mov ax, type msg
                          AX = 0001
```

LENGTHOF Operator:

The LENGTHOF operator counts the number of individual elements in a variable that has been defined using DUP.

Syntax:



LAB: 5 [Spring 2022] [COAL LAB]

MOV reg16, LENGTHOF mem

Example:

```
.data
val1 WORD 1000h
val2 SWORD 10, 20, 30
array WORD 10 DUP(?),0
array2 WORD 5 DUP(3 DUP(0))
msg BYTE 'File not found', 0

.code
mov ax, LENGTHOF val1 ; AX = 1
mov ax, LENGTHOF val2 ; AX = 3
mov ax, LENGTHOF array ; AX = 11
mov ax, LENGTHOF array2 ; AX = 15
mov ax, LENGTHOF msg; AX=15
```

SIZEOF Operator:

The SIZEOF operator returns the number of bytes an array takes up. It is similar in effect to multiplying LENGTHOF with TYPE.

Syntax:

```
MOV reg16/32, SIZEOF mem
```

Example:

```
.data
intArray WORD 32 DUP(0)
.code
mov eax,SIZEOF intArray ; EAX =64
```

Indirect Operands

In protected mode, an indirect operand can be any 32-bit general-purpose register (EAX, EBX, ECX, EDX, ESI, EDI, EBP, and ESP) surrounded by brackets. The register is assumed to contain the address of some data.

Example:

```
.data
byteVal BYTE 10h
.code
mov esi,OFFSET byteVal
mov al,[esi]; AL = 10h
```



If the destination operand uses indirect addressing, a new value is placed in memory at the location pointed to by the register.

mov [esi],bl

Using PTR with Indirect Operands

inc [esi]

; error: operand must have size

The assembler does not know whether ESI points to a byte, word, doubleword, or some other size. The PTR operator confirms the operand size:

inc BYTE PTR [esi]

Arrays

Indirect operands are ideal tools for stepping through arrays.

Example:

.data

arrayB BYTE 10h,20h,30h

.code

mov esi,OFFSET arrayB

mov al, [esi]; AL = 10h

inc esi

mov al, [esi]; AL = 20h

If we use an array of 16-bit integers, we add 2 to ESI to address each subsequent array element.

.data

arrayW WORD 1000h,2000h,3000h

.code

mov esi,OFFSET arrayW

mov ax, [esi]; AX = 1000h

add esi,2

mov ax, [esi]; AX = 2000h



LAB: 5 [FALL 2022] [COAL LAB]

If we use an array of 32-bit integers, we add 4 to ESI to address each subsequent array element.

Indexed Operands

An indexed operand adds a constant to a register to generate an effective address. Any of the 32-bit general-purpose registers may be used as index registers.

```
SYNTAX:
constant [reg32]
                    ; reg32 can be any of the 32-bit general registers
[ constant + reg32 ]
EXAMPLE:
.data
arrayB BYTE 20, 40, 60, 80
.code
mov esi, 1
mov al, arrayB[esi]
inc esi
mov al, arrayB[esi]
mov esi, 3
mov al, [arrayB + esi]
Adding Displacements: The second type of indexed addressing combines a register with a constant
offset. The index register holds the base address of an array.
INCLUDE Irvine32.inc
.data
arrayW WORD 1000h,2000h,3000h
.code
main PROC
mov eax,0
```

mov ebx,0

```
mov esi,OFFSET arrayW
```

mov ax,[esi]; AX = 1000h

mov bx,[esi+2]; AX = 2000h

mov cx,[esi+4]; AX = 3000h

Scale Factors in Indexed Operands

Indexed operands must take into account the size of each array element when calculating offsets.

SYNTAX:

constant [reg32 * TYPE constant]

EXAMPLE:

INCLUDE Irvine32.inc

.data

arrayW WORD 1000h, 2000h, 3000h, 4000h

.code

main PROC

mov eax,0

mov ebx,0

mov ecx,0

mov esi, 1

mov ax, arrayW[esi * TYPE arrayW]

mov esi, 2

mov bx, arrayW[esi * TYPE arrayW]

mov esi, 3

mov cx, arrayW[esi * TYPE arrayW]

call DumpRegs



Exercises:

- 1. Declare a 32-bit signed integer val1 and initialize it with the eight thousand. If val1 is incremented by 1 using the ADD instruction, what will be the values of the Carry and Sign flags?
- 2. Write down the values of the Carry, Sign, Zero, and Overflow flags after each instruction has executed:

```
\begin{array}{ll} mov\ ax,7FF0h\\ add\ al,10h\\ add\ ah,1\\ add\ ax,2 \end{array} \hspace{0.5cm} ; \ a.\ CF=SF=ZF=OF=\\ i.\ b.\ CF=SF=ZF=OF=\\ i.\ c.\ CF=SF=ZF=OF=\\ \end{array}
```

- 3. Initialize a Byte array consisting of elements 61,43,11,52, 25. Sort the given array in ascending order directly with the help of registers (you do not need to use a loop here). Use direct-offset addressing to access the array elements. (Hint: Use new array for sorted elements). What would be changes in code if declared array was of WORD and DWORD size?
- 4. Use following array declarations:

```
arrayB BYTE 10, 20, 30 arrayW WORD 150, 250, 350 arrayD DWORD 600, 1200, 1800
```

Now initialize three double word variables SUM1, SUM2, SUM3 and perform following operations (expressed in pseudo-code here):

```
SUM1 = arrayB[0] + arrayW[0] + arrayD[0] SUM2 = arrayB[1] + arrayW[1] + arrayD[1] SUM3 = arrayB[2] + arrayW[2] + arrayD[2]
```

5. Initialize two arrays: array1 BYTE 10, 20, 30, 40

array2 BYTE 4 DUP (?)

Copy elements of array1 into array2 in reverse order using either indirect addressing or direct-offset addressing.Use ESI and EDI Registers. (Hint: INC and DEC of OFFSET).

- 6. Subtract an array of 5 doublewords using indirect operands. Save the final result in a variable.
 - 7. Use following array declarations:



arrayB BYTE 60, 70, 80 arrayW WORD 150, 250, 350 arrayD DWORD 600, 1200, 1800

For each array, add its 1st and last element using scale factors and display the result in a separate register. (Hint: Use ESI and TYPE Operator).