

Support Chat — Mobile Dev Guide

Guest ↔ Admin chat · base route `/api/v1/support-chat` · har endpoint pe `[Authorize]` lagi hai

Zaroori baat: Koi b start kar sakta hai conversation — guest ho ya admin/staff. Guest ki hamesha ek he conversation hoti hai (auto get-or-create, guest ka message bhejte he ban jati hai agar na ho). Admin b directly guest ki conversation open/reply kar sakta hai — alag se "create" call ki zaroorat nahi.

1. Guest Endpoints Guest JWT

Method	Path	Kya karta hai
GET	<code>my/conversations</code>	Apni conversation lo (0 ya 1 item)
GET	<code>my/messages?</code> <code>PageNumber&PageSize&SearchTerm&SortBy&SortDescending</code>	Messages paginated milte hen, per page oldest-first
POST	<code>my/messages</code>	Message bhejo (agar conversation nahi hai to khud he ban jaegi). Body: <code>SendSupportMessageRequest</code>
POST	<code>my/messages/read</code>	Admin→guest sare messages read mark karo

2. Admin/Staff Endpoints Permission-based

Method	Path	Permission	Kya karta hai
GET	<code>conversations?</code> <code>OnlyUnread&Status&PageNumber&PageSize&SearchTerm</code>	SupportChat.View	Inbox list — pehle unread, phir LastMessageAt desc se sort
GET	<code>conversations/{conversationId}/messages</code>	SupportChat.View	Message history
POST	<code>conversations/{conversationId}/messages</code>	SupportChat.Manage	Existing conversation me reply
POST	<code>conversations/by-guest/{guestId}/messages</code>	SupportChat.Manage	Admin side se chat start karna — guest ki conversation na ho to bana deta hai, closed ho to reopen kar k message bhej deta hai
POST	<code>conversations/{conversationId}/read</code>	SupportChat.Manage	Guest→admin sare messages read mark karo
POST	<code>conversations/{conversationId}/close</code>	SupportChat.Manage	Conversation close karo
POST	<code>conversations/{conversationId}/reopen</code>	SupportChat.Manage	Closed conversation reopen karo

Har `{conversationId}` / `{guestId}` = **PublicId (GUID)** hota hai, internal int ID nahi. Send/reply endpoints rate-limited hen: 20 request/min.

3. Request / Response Shapes

SendSupportMessageRequest

- `body` string, max 4000 characters (required, jab tak attachment na ho)
- `attachmentUrl` string (optional)
- `attachmentType` string (optional)

SupportMessageResponse

- `id` (Guid), `conversationId` (Guid), `body`, `fromGuest` (bool)
- `sentAt`, `isRead`, `readAt`
- `attachmentUrl`, `attachmentType`, `senderName`

SupportConversationSummaryResponse

- `id`, `guestId`, `guestName`, `guestEmail`
- `status`: Open / Closed
- `lastMessagePreview` (200 characters tak, HTML strip hoti hai, body khali ho to "Photo/Attachment" show hota hai)
- `lastMessageAt`, `lastMessageFromGuest`, `unreadCount`

Attachments: fields (DB, DTO) mojud hen, lekin is controller me alag se koi upload endpoint nahi hai — pehle file existing generic media/upload endpoint se upload karo, phir jo URL mile wo `attachmentUrl` me bhej do.

4. Read / Unread Count — Kaise Kaam Karta Hai

Do alag counter hen har conversation pe: `UnreadByAdminCount` (admin ke liye kitne naye guest-messages parhe nahi gaye) aur `UnreadByGuestCount` (guest ke liye kitne naye admin-messages parhe nahi gaye). Dono ek dusre se independent hen.

Guest se Admin ki taraf (guest message bhejta hai)

1. Guest `POST my/messages` call karta hai.
2. Server message save karta hai, `UnreadByAdminCount += 1` ho jata hai (line-by-line increment, per message).
3. SignalR event `support-message-new` admin ke pass jata hai (jo `SupportChat.Manage` rakhte hen).
4. Admin inbox list (`GET conversations`) me ye conversation unread count k sath dikhta hai, aur `OnlyUnread=true` filter se bhi milega.
5. Jab admin `POST conversations/{conversationId}/read` call kare, tab `UnreadByAdminCount = 0` reset ho jata hai — sab guest messages read mark ho jate hen.

Admin se Guest ki taraf (admin reply/start-chat karta hai)

1. Admin `POST conversations/{conversationId}/messages` ya `POST conversations/by-guest/{guestId}/messages` call karta hai.
2. Server message save karta hai, `UnreadByGuestCount += 1` ho jata hai.
3. SignalR event `support-message-new` guest ke pass jata hai (group `guest:{guestId}`).
4. Guest jab `GET my/conversations` call kare to `unreadCount` field me ye number milega.
5. Jab guest `POST my/messages/read` call kare, tab `UnreadByGuestCount = 0` reset ho jata hai.

Mobile app implementation tip: Har naye message aane pe (`support-message-new` event) local badge count +1 karo. Chat screen open hote he read-endpoint call karo taake server-side count 0 ho jae aur agli baar list me unread na dikhe. Read-receipt push abhi wire nahi hai (`support-conversation-read` event defined hai par kahin call nahi hota) — matlab "seen" status ka realtime push abhi nahi milega, sirf apna read-mark API se update hoga.

5. ID Chain — Konsi ID Kahan Se Milegi, Kahan Use Hogi

Is feature me 3 alag GUID chalte hen: **guestId**, **conversationId**, **messageId**. Teeno alag jagah se milte hen, alag jagah use hote hen. Neeche step-by-step chain hai.

(a) Guest apni khud ki id (login se)

1. Guest app `POST /api/v1/vipapp/auth/verify-otp` call karta hai (OTP verify pe login).
2. Response me `Guest.Id` (Guid = guest ka **PublicId**) milta hai, sath `AccessToken` .
3. Ye `Guest.Id` guest app khud kahin use nahi karta — chat endpoints me guest ki id URL me nahi jati, JWT token he identity carry karta hai (server token se andar he guest resolve kar leta hai).

4. Matlab: guest side `my/...` endpoints me koi ID path me daalne ki zaroorat nahi, sirf token header me bhejo.

(b) Admin ko guestId kahan se milegi (chat start karne k liye)

1. Admin app `GET /api/v1/guest` (full list) ya `GET /api/v1/guest/picker` (halka list, chat-start UI k liye) call karta hai.
2. Response k har item me `Id` (Guid) hota hai — ye guest ka **PublicId** hai.
3. Isi `Id` ko `guestId` ki jagah use karo: `POST conversations/by-guest/{guestId}/messages`.
4. Server internally ye Guid se guest dhoond k uska internal int id nikalta hai, phir uski conversation get/create karta hai — front-end ko is internal id ki koi zaroorat nahi, bas Guid pass karo.

(c) conversationId kahan se milegi

1. Guest side: `GET my/conversations` response me `Id` (Guid) milta hai — yehi conversation ki **PublicId** hai (agar list khali hai to abhi tak koi conversation nahi bani, pehla message bhejte he ban jaegi).
2. Admin side: `GET conversations` (inbox list) response me har item ka `Id` (Guid) milta hai.
3. Ye `Id` aage in sab me `{conversationId}` ki jagah use hoti hai: `messages` (GET/POST), `read`, `close`, `reopen`.
4. Pehli martaba admin ne agar `by-guest/{guestId}/messages` use kiya, to uske response me b conversation ka `Id` milega — agli baar seedha usi `conversationId` wale endpoints use karo, dobara by-guest call ki zaroorat nahi (jab tak nayi conversation na ho).

(d) messageId kahan se milegi

1. Har message send/list response me `Id` (Guid) hota hai — ye `conversationId` se alag, khud message ki apni **PublicId** hai.
2. Abhi kisi endpoint ka path-parameter nahi banti (koi "edit/delete single message" API nahi hai) — sirf UI list render/key aur duplicate-detect k liye use karo (list refresh pe already-shown message dobara na dikhe).

6. Realtime (SignalR)

- Hub URL: `/realtimehub`
- Guest apne aap group `guest:{guestId}` me join hota hai (guest JWT claim se). Admin apne `userId` group me auto-join hota hai.
- Event `support-message-new` : naya guest-message aane pe admins ko jata hai; admin reply/start-chat pe guest ko jata hai.
Client handler: `(title: string, message: string, data: NotificationResponse)` — `data.data.conversationId` is me milta hai.
- Event `notification-new` / `notification-count-changed` : general notification bell channel, support messages k liye bhi fire hota hai.

7. Auth Summary

- Guest: sirf apni conversation, guest JWT se resolve hoti hai — kisi aur guest ko address nahi kar sakta.
- Admin/staff: `SupportChat.Manage` wala koi b reply/close/reopen kar sakta hai; `SupportChat.View` sirf read k liye.
- Kisi ek fixed admin account tak restrict nahi — permission wala koi b staff kisi b conversation ko pick kar sakta hai.