>Maestro CLI
Reference Guide

M3RG-01

November 2025

Version 1

Introduction

`Maestro CLI`, also known as `M3-CLI`, is a robust command-line interface (CLI) tool designed to provide a powerful alternative to user interfaces (UI). It allows you to perform cloud infrastructure management operations, as well as manage related assets, by sending respective calls to Maestro cloud management platform. This Reference Guide provides users the overview of the available `M3 CLI` commands, their purpose, parameters, and usage examples.

Table of Contents

The table below gives the list of available `M3 CLI` commands and their brief descriptions. Click a command name to get to the command details section.

Command	Description
m3 health-check(status)	Describes system status
m3 describe-insights(dins)	Describes insights for an instance in specific region for a specific tenant
m3 describe-resources(drsc)	Describes resources existing in a specific region for a specific tenant
m3 describe-instances(din)	Describes instances existing in a specific region for a specific tenant
m3 publish-platform-service(pubservice)	Publishes a new service based on the specified template to the catalog
m3 delete-platform-service(delservice)	Removes the specified service from the catalog
m3 describe-service-section(dssec)	Describes the section content of the certain published service
m3 delete-service-section(delsersec)	Deletes the section content of the certain published service
m3 add-service-section(addsers)	Adds usage/support section to the certain published service
m3 update-platform-service(updpfs)	Updates specified elements of the platform service
m3 generate-platform-service-varfile(genpfsvar)	“Generates a file with variables for the specified platform service, or fills it with missing parameters if the file already exists.
m3 activate-platform-service(actpfs)	Activates a platform service for your tenant
m3 deactivate-platform-service(dactpfs)	Deactivates a platform service running for your tenant
m3 describe-platform-service-stacks(dplstack)	Provides details about platform service stacks activated for a customer
m3 describe-platform-services(dplservice)	Provides details about the configuration of platform services:
m3 run-instances(run)	Creates instances of the specified configuration
m3 stop-instances(stop)	Stops a virtual instance
m3 backup(bkup)	Provides assistance with using the Backup Platform Service for data backup and recovery
m3 terminate-instances(kill)	Terminates a virtual instance
m3 describe-images(dim)	Describes images available in a specific region for a specific tenant
m3 describe-storages(dstor)	Describes instance storages existing in the specific tenant
m3 create-attach-storage(addattstor)	Creates the storage and attaches to an existing instance
m3 detach-storage(detstor)	Detaches the specified storage from an existing instance
m3 delete-storage(delstor)	Removes the specified storage
m3 decrypt-password(dp)	Decrypts the password for windows instances

Command	Description
m3 describe-schedules(dsch)	Describes the schedules set to instances in your tenant
m3 create-schedule(csch)	Creates a new schedule for automatic instance state management
m3 delete-schedule(delsch)	Deletes a schedule from your tenants schedule library
m3 total-report(treport)	Gets a total billing report for a tenant
m3 subtotal-report(streport)	Gets subtotal billing report for the specified tenant
m3 budgets-report(bgreport)	Gets budgets billing report for the specified tenant
m3 cost-usage-report(cureport)	Gets cost and usage optimization report
m3 untagged-resource-report(untagresreport)	Provides the report by untagged resources within the specified tenant
m3 resource-report(resreport)	Gets resource billing report for the specified tenant
m3 cost-object-report(cosobreport)	Gets cost object report for the specified tenant:
m3 hourly-report(hreport)	Gets hourly billing report for the specified tenant
m3 aws-management-console(awsmc)	Provides access to AWS management console for the specified tenant. The credentials are shared via an email access
m3 azure-management-console(azuremc)	Provides access to Azure management console for the specified tenant. (Access type DEFAULT)
m3 google-management-console(gcpmc)	Provides access to Google Cloud management console for the specified tenant. The credentials are shared via an email
m3 upload-script(upscr)	Uploads an init script to tenant's library in Maestro
m3 delete-scripts(delscr)	Deletes an init script from your library in Maestro
m3 describe-script(dscript)	Describes the script files uploaded to Maestro and available for your tenant
m3 price(price)	Describes the pricing policy
m3 create-image(cim)	Creates an image based on an existing instance
m3 delete-image(delim)	Deletes an image created from a project instance
m3 delete-key(delkey)	Deletes a SSH key from your account
m3 describe-keys(dkey)	Describes your SSH keys existing for a specific tenant
m3 import-key(ikey)	Imports SSH keys for a specific cloud, region and tenant to Maestro
m3 describe-events(dev)	Lists the events that took place in your virtual infrastructure
m3 upload-terraform-template-from-git(upltplgit)	Uploads a Terraform template from Git
m3 describe-terraform-templates(dtpl)	Describes Terraform and AWS_CLOUD_FORMATION templates general info
m3 describe-terraform-stacks(dterstack)	Describes a Terraform stack
m3 reboot-instances(reboot)	Reboots the specified virtual instance
m3 start-instances(start)	Starts a virtual instance that has been previously stopped
m3 manage-termination-protection	Manages termination protection for public cloud instances
m3 delete-terraform-template(deltpl)	Deletes a Terraform template
m3 plan-terraform-template(plantpl)	Plans the selected Terraform template
m3 apply-terraform-template(applytpl)	Applies a Terraform template
m3 lock-terraform-template(locktpl)	Lock a Terraform template to prevent any actions from other users

Command	Description
m3 prolong-terraform-template-lock(ptplock)	Prolong a Terraform template lock to prevent any actions from other users
m3 unlock-terraform-template(unlocktpl)	Unlock a Terraform template to allow actions from other users
m3 destroy-terraform-stack(dtrterstack)	Destroys resources related to a Terraform template or stack
m3 create-instance-quota(cinquota)	Sets up a number of instances allowed for creation on a specific tenant within a specific interval
m3 describe-instance-quota(dinquota)	Describes the limitation for the number of instances allowed for creation on a specific tenant within a specific interval
m3 delete-instance-quota(delinquota)	Deletes the limitation for the number of instances allowed for creation on a specific tenant within a specific interval
m3 create-storage-quota(cstorquota)	Sets up an amount and size of storages allowed for creation on a specific tenant within a specific interval
m3 describe-storage-quota(dstorquota)	Describes the limitation for the number and size of storages allowed for creation on a specific tenant within a specific interval
m3 delete-storage-quota(delstorquota)	Deletes the limitations for an amount and size of storages allowed for creation on a specific tenant within a specific interval
m3 create-key(ckey)	Creates a SSH key used to access instances without need to provide login credentials
m3 manage-key(mkey)	Manage your SSH keys. Adds or deletes an SSH key in a region
m3 describe-tenants(dtn)	Describes the tenants available for the user
m3 describe-regions(dr)	Describes the regions available for a tenant in the specified cloud
m3 describe-shapes(dsh)	Describes the shapes available for your tenant
m3 add-schedule-instances(addschin)	Adds an existing schedule to one or several instances
m3 delete-schedule-instances(delschin)	Deletes a schedule from one or several instances
m3 delete-tags(deltag)	Deletes one or several tags from an instance in public or private cloud
m3 describe-tags(dtag)	Describes tags on an instance in public or private cloud
m3 set-tags(stag)	Updates instance tags. Applicable in public and private clouds
m3 upload-terraform-template(upltpl)	Uploads a Terraform template
m3 export-terraform-template(exptpl)	Exports a Terraform template as a signed URL
m3 multitenant-report(mreport)	Gets multitenant billing report
m3 billing-region-types(brtypes)	Gets billing region types
m3 describe-user-permissions(duserperm)	Describes the permission groups assigned to you in the specified tenant
m3 allocate-ip(alip)	Allocate static ip in the specified region in tenant:
m3 release-ip(rip)	Release static ip in the specified region in tenant:
m3 describe-ip(dip)	Describe static ips in the specified region in tenant:
m3 describe-vlans(dvlans)	Describe available VLANs in the specified region in tenant:
m3 deactivate-vlan(dvlan)	Deactivate specified VLAN in the specified region in tenant:
m3 activate-vlan(avlan)	Activate specified VLAN in the specified region in tenant:
m3 move-to-vlan(mvlan)	Move specific instance to another VLAN:

Command	Description
m3 associate-ip(asip)	Associate specific static IP with instance:
m3 disassociate-ip(dsip)	Disassociate specific static IP from the instance:
m3 report(report)	This command serves as a single point of entry for report-related commands:‘total-report’, ‘subtotal-report’, ‘resource-report’, and ‘hourly-report’
m3 create-recommendation-settings(crset)	Create recommendation settings for cost optimization recommendations
m3 update-recommendation-settings(urset)	Update recommendation settings for cost optimization recommendations
m3 describe-recommendation-settings(drset)	Describe recommendation settings for cost optimization recommendations
m3 remove-recommendation-settings(rrset)	Remove recommendation settings for cost optimization recommendations

m3 health-check

Description:

Describes system status

Usage: m3 health-check(status) [parameters]

Parameters:

```
--help            Shows the short help for the command

--full-help       Shows the detailed help for the command

--verbose         Controls the verbosity of command output

--json            Returns the server response in the JSON format

--table           Returns the server response in the table form (default)

--full            Shows the full response from the server without any specific
formatting (can be used with --json)

--raw             Shows raw response from the server (can be used with --json)
```

Example:

```
    m3 health-check
```

Related commands:

1. Describes the permission groups assigned to you in the specified tenant:

```
    m3 describe-user-permissions -tn <tenant> -c <cloud> -env <environment>
```

m3 describe-insights

Description:

Describes insights for an instance in specific region for a specific tenant

Usage: m3 describe-insights(dins) [parameters]

Parameters:

```
--help                              Shows the short help for the command

--full-help                         Shows the detailed help for the command

--verbose                           Controls the verbosity of command output

--json                              Returns the server response in the JSON format

--table                             Returns the server response in the table form
(default)

--full                              Shows the full response from the server without
any specific formatting (can be used with --json)

--raw                               Shows raw response from the server (can be used
with --json)

--cloud,              -c,       *   The cloud.

                                    Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--instance-id,        -iid,     *   The IDs of the instances

--region,             -r,       *   The region name

--tenant,             -tn,      *   The tenant name

--availability-zone,  -az,          The availability zone name (required for Google)

--resource-group,     -rgname,      The resource group name (required for Azure)
```

Example:

```
m3 describe-insights --instance-id <instance_id> --cloud <cloud_name> --region
<region_name> --tenant <tenant_name> --availability_zone <required_for_google> --
resource_group <required_for_azure>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Associate static IP with instance:

```
m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

4. Creates instances of the specified configuration:

```
m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

5. Deactivate specified VLAN on specified region in tenant:

```
m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

6. Describe available VLANs on specified region in tenant:

```
m3 describe-vlans -tn <tenant> -r <region>
```

7. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

8. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

9. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

10. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

11. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

12. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

13. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

14. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

15. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 describe-resources

Description:

Describes resources existing in a specific region for a specific tenant

Usage: m3 describe-resources(drsc) [parameters]

Parameters:

```
--help                Shows the short help for the command

--full-help           Shows the detailed help for the command

--verbose             Controls the verbosity of command output

--json                Returns the server response in the JSON format

--table               Returns the server response in the table form (default)

--full                Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                 Shows raw response from the server (can be used with --json)

--region,    -r,   *  The region name

--tenant,    -tn,  *  The tenant name

--group,     -g,      Filter for instances by insights group. Default value: ALL.

                      Allowed values: ['ALL', 'UNTAGGED']

--tag,                The tag to be used as a filter: test1key:test1value. Would not
have an effect if 'group' parameter specified as 'UNTAGGED'
```

Example:

```
m3 describe-resources --region <region_name> --tenant <tenant_name>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Associate static IP with instance:

```
m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

4. Creates instances of the specified configuration:

```
m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

5. Deactivate specified VLAN on specified region in tenant:

```
m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

6. Describe available VLANs on specified region in tenant:

```
m3 describe-vlans -tn <tenant> -r <region>
```

7. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

8. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

9. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

10. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

11. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

12. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

13. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

14. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

15. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 describe-instances

Description:

Describes instances existing in a specific region for a specific tenant

Usage: m3 describe-instances(din) [parameters]

Parameters:

```
--help                      Shows the short help for the command

--full-help                 Shows the detailed help for the command

--verbose                   Controls the verbosity of command output

--json                      Returns the server response in the JSON format

--table                     Returns the server response in the table form (default)

--full                      Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                       Shows raw response from the server (can be used with --
json)

--region,        -r,    *   The region name

--tenant,        -tn,   *   The tenant name

--group,         -g,        Filter for instances by insights group.

                            Allowed values if 'insights' flag applied: ['ALL',
'INSTANCE_COSTS', 'SCHEDULES', 'TAGS', 'LIFE_TIME', 'OWNERSHIP', 'VULNERABLE'].

                            Allowed values if 'insights' flag NOT applied ['ALL',
'UNTAGGED`]

--insights,      -I,        Instance criticality factor flag

--instance-id,   -iid,      The IDs of the instances.

                            For several instances, specify the IDs one by one,
separated by a comma without space (e.g., vmo00000001,vmo00000002).

                            Required for Azure cloud

--owner,         -own,      Owner name. Allows get all instances by owner

--resource-tag,  -tag,      The tag to be used as a filter: test1key:test1value

--risk-factor,   -rf,       Filter for instances by specific risk factor. Note: could
be applied only with 'insights' flag

--running,       -R,        A flag. Show only running instances
```

```
--stopped,        -S,        A flag. Show only stopped instances
```

Examples:

1. Describe all instances belonging to the tenant in a specific region:

```
m3 describe-instances --region <region> --tenant <tenant>
```

2. Describe instances with a specific tag:

```
m3 describe-instances --region <region> --tenant <tenant> --resource-tag
<key:value>
```

3. Describe instances with provided owner:

```
m3 describe-instances --region <region> --tenant <tenant> --owner <owner>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Associate static IP with instance:

```
m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

4. Creates instances of the specified configuration:

```
m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

5. Deactivate specified VLAN on specified region in tenant:

```
m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

6. Describe available VLANs on specified region in tenant:

```
m3 describe-vlans -tn <tenant> -r <region>
```

7. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

8. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

9. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

10. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

11. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

12. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

13. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

14. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

15. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 publish-platform-service

Description:

Publishes a new service based on the specified template to the catalog

Usage: m3 publish-platform-service(pubservice) [parameters]

Parameters:

```
--help                                  Shows the short help for the command

--full-help                             Shows the detailed help for the command

--verbose                               Controls the verbosity of command output

--json                                  Returns the server response in the JSON
format

--table                                 Returns the server response in the table form
(default)

--full                                  Shows the full response from the server
without any specific formatting (can be used with --json)

--raw                                   Shows raw response from the server (can be
used with --json)

--cloud,                -c,          *  The cloud name. Specifies which cloud the
template belongs to. Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--discoverable-url,     -durl,       *  The URL where service description can be
found

--provider-version,     -providerv,  *  The version of the provider. The version of
provider used in the template should be indicated with the letter 'v'. For example
v0.14.9

--service,              -sn,         *  The service name

--service-version,      -servicev,   *  The version of the product

--supported-cloud,      -supcloud,   *  The list of the cloud providers that support
this service. It is a description for UI. Pass several values in the following
format: value1,value2,value3

--template,             -tpl,        *  The template name

--tenant,               -tn,         *  The tenant display name. Specifies which
tenant the template belongs to

--title,                -t,          *  Official name of the service

--all-tenants,          -AT,            Register service for all tenants of the
```

```
customer

--category,              -cat,           The categories names

                                         Pass several values in the following format:
value1,value2,value3

--delivery-method,       -dm,            An identifier who provide this service.
Maestro by default

--description,           -d,             The description of the service

--icon-path,             -ipath,         Path to the service icon file. The image
extension should be .png. The size of the image should be: width<=190px,
height<=130px

--operating-system,      -os,            The name of the Operating System

--price,                 -p,             The pricing of the service

--summary-description,   -sd,            The summary description of the service
```

Example:

```
    m3 publish-platform-service --service <name> --delivery-method <delivery_method>
--operating-system <os_name> --service-version <version>

                        --template <name> --discoverable-url <dis_url> --title <title>
--supported-cloud <cloud1,cloudN>

                        --icon-path <path> --cloud <cloud> --tenant

                        <tenant_name> --all-tenants
```

Related commands:

1. Activates a platform service for your tenant:

```
    m3 activate-platform-service -sn <service> -c <cloud> -tn <tenant> -r <region>
```

2. Adds usage/support section to the certain published service:

```
    m3 add-service-section -sn <service> -sec <section> -bt <block_title>
```

3. Deactivates a platform service running for your tenant:

```
    m3 deactivate-platform-service -sid <service_id> -c <cloud> -tn <tenant> -r
   <region>
```

4. Deletes the section content of the certain published service:

```
    m3 delete-service-section -sn <service> -sec <section>
```

5. Deletes the specified service from the catalog:

```
    m3 delete-platform-service -sn <service>
```

6. Describes the section content of the certain published service:

```
    m3 describe-service-section -sn <service> -sec <section>
```

7. List of the platform service stacks activated for a tenant:

```
m3 describe-platform-service-stacks -c <cloud> -tn <tenant> -r <region>
```

8. Provides assistance with using the Backup Platform Service for data backup and recovery:

```
m3 backup -c <cloud> -tn <tenant> -r <region> -bsid <backup_server_id>
```

9. Provides details about the configuration of platform service available in a tenant:

```
m3 describe-platform-services
```

10. Updates specified elements of the platform service:

```
m3 update-platform-service -sn <service>
```

m3 delete-platform-service

Description:

Removes the specified service from the catalog

Usage: m3 delete-platform-service(delservice) [parameters]

Parameters:

```
--help                Shows the short help for the command

--full-help           Shows the detailed help for the command

--verbose             Controls the verbosity of command output

--json                Returns the server response in the JSON format

--table               Returns the server response in the table form (default)

--full                Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                 Shows raw response from the server (can be used with --json)

--service,   -sn,  *  The service name
```

Example:

```
    m3 delete-platform-service --service <name>
```

Related commands:

1. Activates a platform service for your tenant:

```
    m3 activate-platform-service -sn <service> -c <cloud> -tn <tenant> -r <region>
```

2. Adds usage/support section to the certain published service:

```
    m3 add-service-section -sn <service> -sec <section> -bt <block_title>
```

3. Deactivates a platform service running for your tenant:

```
    m3 deactivate-platform-service -sid <service_id> -c <cloud> -tn <tenant> -r
   <region>
```

4. Deletes the section content of the certain published service:

```
    m3 delete-service-section -sn <service> -sec <section>
```

5. Describes the section content of the certain published service:

```
    m3 describe-service-section -sn <service> -sec <section>
```

6. List of the platform service stacks activated for a tenant:

```
    m3 describe-platform-service-stacks -c <cloud> -tn <tenant> -r <region>
```

7. Provides assistance with using the Backup Platform Service for data backup and recovery:

```
    m3 backup -c <cloud> -tn <tenant> -r <region> -bsid <backup_server_id>
```

8. Provides details about the configuration of platform service available in a tenant:

```
m3 describe-platform-services
```

9. Publishes a new service based on the specified template to the catalog:

```
m3 publish-platform-service -sn <service> -servicev <service_version> -tpl
<template> -durl <discoverable_url> -tn <tenant> -c <cloud> -t <title> -supcloud
<supported_cloud1>,<supported_cloudN> -providerv <provider_version>
```

10. Updates specified elements of the platform service:

```
m3 update-platform-service -sn <service>
```

m3 describe-service-section

Description:

Describes the section content of the certain published service

Usage: m3 describe-service-section(dssec) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --
json)

--section,      -sec,  *  The section name. Allowed values: [USAGE, SUPPORT]

--service,      -sn,   *  The service name

--block-title,  -bt,      The title of the block
```

Example:

```
m3 describe-service-section --service <service_name> --section <section_name> --
block-title <title>
```

Related commands:

1. Activates a platform service for your tenant:

```
m3 activate-platform-service -sn <service> -c <cloud> -tn <tenant> -r <region>
```

2. Adds usage/support section to the certain published service:

```
m3 add-service-section -sn <service> -sec <section> -bt <block_title>
```

3. Deactivates a platform service running for your tenant:

```
m3 deactivate-platform-service -sid <service_id> -c <cloud> -tn <tenant> -r
<region>
```

4. Deletes the section content of the certain published service:

```
m3 delete-service-section -sn <service> -sec <section>
```

5. Deletes the specified service from the catalog:

```
m3 delete-platform-service -sn <service>
```

6. List of the platform service stacks activated for a tenant:

```
m3 describe-platform-service-stacks -c <cloud> -tn <tenant> -r <region>
```

7. Provides assistance with using the Backup Platform Service for data backup and recovery:

```
m3 backup -c <cloud> -tn <tenant> -r <region> -bsid <backup_server_id>
```

8. Provides details about the configuration of platform service available in a tenant:

```
m3 describe-platform-services
```

9. Publishes a new service based on the specified template to the catalog:

```
m3 publish-platform-service -sn <service> -servicev <service_version> -tpl
<template> -durl <discoverable_url> -tn <tenant> -c <cloud> -t <title> -supcloud
<supported_cloud1>,<supported_cloudN> -providerv <provider_version>
```

10. Updates specified elements of the platform service:

```
m3 update-platform-service -sn <service>
```

m3 delete-service-section

Description:

Deletes the section content of the certain published service

Usage: m3 delete-service-section(delsersec) [parameters]

Parameters:

```
--help                      Shows the short help for the command

--full-help                 Shows the detailed help for the command

--verbose                   Controls the verbosity of command output

--json                      Returns the server response in the JSON format

--table                     Returns the server response in the table form (default)

--full                      Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                       Shows raw response from the server (can be used with --
json)

--section,       -sec,  *   The section name. Allowed values: [USAGE, SUPPORT]

--service,       -sn,   *   The service name

--block-title,   -bt,       The title of the block which will be deleted

--delete-all,    -A,        A flag. Deletes all blocks in a section

--delete-empty,  -E,        A flag. Deletes all text in section without titles
```

Example:

1. Deletes the section content and title:

```
m3 delete-service-section --section <section_name> --service <service_name> --
block-title <title>
```

2. Deletes blocks without a title in the section:

```
m3 delete-service-section --section <section_name> --service <service_name> --
delete-empty
```

3. Deletes all the content of the section:

```
m3 delete-service-section --section <section_name> --service <service_name> --
delete-all
```

Related commands:

1. Activates a platform service for your tenant:

```
m3 activate-platform-service -sn <service> -c <cloud> -tn <tenant> -r <region>
```

2. Adds usage/support section to the certain published service:

```
m3 add-service-section -sn <service> -sec <section> -bt <block_title>
```

3. Deactivates a platform service running for your tenant:

```
m3 deactivate-platform-service -sid <service_id> -c <cloud> -tn <tenant> -r
<region>
```

4. Deletes the specified service from the catalog:

```
m3 delete-platform-service -sn <service>
```

5. Describes the section content of the certain published service:

```
m3 describe-service-section -sn <service> -sec <section>
```

6. List of the platform service stacks activated for a tenant:

```
m3 describe-platform-service-stacks -c <cloud> -tn <tenant> -r <region>
```

7. Provides assistance with using the Backup Platform Service for data backup and recovery:

```
m3 backup -c <cloud> -tn <tenant> -r <region> -bsid <backup_server_id>
```

8. Provides details about the configuration of platform service available in a tenant:

```
m3 describe-platform-services
```

9. Publishes a new service based on the specified template to the catalog:

```
m3 publish-platform-service -sn <service> -servicev <service_version> -tpl
<template> -durl <discoverable_url> -tn <tenant> -c <cloud> -t <title> -supcloud
<supported_cloud1>,<supported_cloudN> -providerv <provider_version>
```

10. Updates specified elements of the platform service:

```
m3 update-platform-service -sn <service>
```

m3 add-service-section

Description:

Adds usage/support section to the certain published service

Usage: m3 add-service-section(addsers) [parameters]

Parameters:

```
--help                              Shows the short help for the command

--full-help                         Shows the detailed help for the command

--verbose                           Controls the verbosity of command output

--json                              Returns the server response in the JSON format

--table                             Returns the server response in the table form
(default)

--full                              Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                               Shows raw response from the server (can be used
with --json)

--block-title,       -bt,      *    The title of the block

--section,           -sec,     *    The section name. Allowed values: [USAGE, SUPPORT]

--service,           -sn,      *    The service name

--block-value,       -bv,           The value of the block Usage or Support

--block-value-path,  -bvpath,       The path to the file with a value of the block
Usage or Support
```

Example:

```
    m3 add-service-section --service <name> --section <section_name> --block-title
<title> --block-value <value>
```

Related commands:

1. Activates a platform service for your tenant:

```
    m3 activate-platform-service -sn <service> -c <cloud> -tn <tenant> -r <region>
```

2. Deactivates a platform service running for your tenant:

```
    m3 deactivate-platform-service -sid <service_id> -c <cloud> -tn <tenant> -r
   <region>
```

3. Deletes the section content of the certain published service:

```
    m3 delete-service-section -sn <service> -sec <section>
```

4. Deletes the specified service from the catalog:

```
m3 delete-platform-service -sn <service>
```

5. Describes the section content of the certain published service:

```
m3 describe-service-section -sn <service> -sec <section>
```

6. List of the platform service stacks activated for a tenant:

```
m3 describe-platform-service-stacks -c <cloud> -tn <tenant> -r <region>
```

7. Provides assistance with using the Backup Platform Service for data backup and recovery:

```
m3 backup -c <cloud> -tn <tenant> -r <region> -bsid <backup_server_id>
```

8. Provides details about the configuration of platform service available in a tenant:

```
m3 describe-platform-services
```

9. Publishes a new service based on the specified template to the catalog:

```
m3 publish-platform-service -sn <service> -servicev <service_version> -tpl
<template> -durl <discoverable_url> -tn <tenant> -c <cloud> -t <title> -supcloud
<supported_cloud1>,<supported_cloudN> -providerv <provider_version>
```

10. Updates specified elements of the platform service:

```
m3 update-platform-service -sn <service>
```

m3 update-platform-service

Description:

Updates specified elements of the platform service

Usage: m3 update-platform-service(updpfs) [parameters]

Parameters:

```
--help                                  Shows the short help for the command

--full-help                             Shows the detailed help for the command

--verbose                               Controls the verbosity of command output

--json                                  Returns the server response in the JSON format

--table                                 Returns the server response in the table form
(default)

--full                                  Shows the full response from the server
without any specific formatting (can be used with --json)

--raw                                   Shows raw response from the server (can be
used with --json)

--service,              -sn,        *   The service name

--category,             -cat,           The categories names

                                        Pass several values in the following format:
value1,value2,value3

--data-bag-name,        -dbagname,      The databag name

--delivery-method,      -dm,            The type of delivery

--description,          -d,             The description of the service

--discoverable-url,     -durl,          The URL where service description can be found

--icon-path,            -ipath,         Path to the service icon file. The image
extension should be .png. The size of the image should be: width<=190px,
height<=130px

--operating-system,     -os,            The name of the Operating System

--price,                -p,             The pricing of the service

--provider-version,     -poviderv,      The version of the provider. The version of
provider used in the template should be indicated with the letter 'v'. For example
v0.14.9

--service-provider,     -sprov,         The service provider
```

```
--service-version,      -servicev,     The version of the product

--summary-description,  -sd,           The summary description of the service

--support-proxy,        -P,            A flag. Supports proxy if specified

--supported-cloud,      -supcloud,     The list of the cloud names. Should be
specified if you need

                                       Pass several values in the following format:
value1,value2,value3

--template,             -tpl,          The template name

--template-type,        -tpltype,      The type of template that will be used for
registering service. Allowed values: [TERRAFORM]

--title,                -t,            Official name of the service
```

Example:

```
m3 update-platform-service --service<name>
```

Related commands:

1. Activates a platform service for your tenant:

```
m3 activate-platform-service -sn <service> -c <cloud> -tn <tenant> -r <region>
```

2. Adds usage/support section to the certain published service:

```
m3 add-service-section -sn <service> -sec <section> -bt <block_title>
```

3. Deactivates a platform service running for your tenant:

```
m3 deactivate-platform-service -sid <service_id> -c <cloud> -tn <tenant> -r
<region>
```

4. Deletes the section content of the certain published service:

```
m3 delete-service-section -sn <service> -sec <section>
```

5. Deletes the specified service from the catalog:

```
m3 delete-platform-service -sn <service>
```

6. Describes the section content of the certain published service:

```
m3 describe-service-section -sn <service> -sec <section>
```

7. List of the platform service stacks activated for a tenant:

```
m3 describe-platform-service-stacks -c <cloud> -tn <tenant> -r <region>
```

8. Provides assistance with using the Backup Platform Service for data backup and recovery:

```
m3 backup -c <cloud> -tn <tenant> -r <region> -bsid <backup_server_id>
```

9. Provides details about the configuration of platform service available in a tenant:

```
m3 describe-platform-services
```

10. Publishes a new service based on the specified template to the catalog:

```
m3 publish-platform-service -sn <service> -servicev <service_version> -tpl
<template> -durl <discoverable_url> -tn <tenant> -c <cloud> -t <title> -supcloud
<supported_cloud1>,<supported_cloudN> -providerv <provider_version>
```

m3 generate-platform-service-varfile

Description:

“Generates a file with variables for the specified platform service, or fills it with missing parameters if the file already exists.

The template is prefilled with default values if available”

Usage: m3 generate-platform-service-varfile(genpfsvar) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form
(default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with -
-json)

--cloud,           -c,      *   The cloud.

                                Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--region,          -r,      *   The region name

--service,         -sn,     *   The service name

--tenant,          -tn,     *   The tenant name

--variables-file,  -vfile,      The path to a file with variables. The path is the
current working directory by default with the filename '<service>.varfile.json'
```

Example:

```
    m3 generate-platform-service-varfile --cloud <cloud> --region <region> --tenant
<tenant_name> --service <service_name>
```

m3 activate-platform-service

Description:

Activates a platform service for your tenant

Usage: m3 activate-platform-service(actpfs) [parameters]

Parameters:

```
--help                              Shows the short help for the command

--full-help                         Shows the detailed help for the command

--verbose                           Controls the verbosity of command output

--json                              Returns the server response in the JSON format

--table                             Returns the server response in the table form
(default)

--full                              Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                               Shows raw response from the server (can be used
with --json)

--cloud,              -c,       *   The cloud.

                                    Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--region,             -r,       *   The region name

--service,            -sn,      *   The service name

--tenant,             -tn,      *   The tenant name

--destroy-after,      -expire,      The number of hours after service will be expired
automatically

--interactive-mode,   -I,           A flag. If specified the service-specific
parameters will be asked interactively

--variables-file,     -vfile,       The path to a file with variables for activation of
a platform service
```

Examples:

1. Activate a specific service without additional parameters:

```
   m3 activate-platform-service --cloud <cloud> --region <region> --tenant
  <tenant_name> --service <service_name>
```

Related commands:

1. Adds usage/support section to the certain published service:

```
m3 add-service-section -sn <service> -sec <section> -bt <block_title>
```

2. Deactivates a platform service running for your tenant:

```
m3 deactivate-platform-service -sid <service_id> -c <cloud> -tn <tenant> -r
<region>
```

3. Deletes the section content of the certain published service:

```
m3 delete-service-section -sn <service> -sec <section>
```

4. Deletes the specified service from the catalog:

```
m3 delete-platform-service -sn <service>
```

5. Describes the section content of the certain published service:

```
m3 describe-service-section -sn <service> -sec <section>
```

6. List of the platform service stacks activated for a tenant:

```
m3 describe-platform-service-stacks -c <cloud> -tn <tenant> -r <region>
```

7. Provides assistance with using the Backup Platform Service for data backup and recovery:

```
m3 backup -c <cloud> -tn <tenant> -r <region> -bsid <backup_server_id>
```

8. Provides details about the configuration of platform service available in a tenant:

```
m3 describe-platform-services
```

9. Publishes a new service based on the specified template to the catalog:

```
m3 publish-platform-service -sn <service> -servicev <service_version> -tpl
<template> -durl <discoverable_url> -tn <tenant> -c <cloud> -t <title> -supcloud
<supported_cloud1>,<supported_cloudN> -providerv <provider_version>
```

10. Updates specified elements of the platform service:

```
m3 update-platform-service -sn <service>
```

m3 deactivate-platform-service

Description:

Deactivates a platform service running for your tenant

Usage: m3 deactivate-platform-service(dactpfs) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --json)

--cloud,       -c,    *   The cloud.

                          Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--region,      -r,    *   The region name

--service-id,  -sid,  *   The ID of the service to be deactivated

--tenant,      -tn,   *   The tenant name
```

Example:

```
    m3 deactivate-platform-service --cloud <cloud> --region <region> --tenant
<tenant_name> --service-id <service_id>
```

Related commands:

1. Activates a platform service for your tenant:

```
    m3 activate-platform-service -sn <service> -c <cloud> -tn <tenant> -r <region>
```

2. Adds usage/support section to the certain published service:

```
    m3 add-service-section -sn <service> -sec <section> -bt <block_title>
```

3. Deletes the section content of the certain published service:

```
    m3 delete-service-section -sn <service> -sec <section>
```

4. Deletes the specified service from the catalog:

```
    m3 delete-platform-service -sn <service>
```

5. Describes the section content of the certain published service:

```
m3 describe-service-section -sn <service> -sec <section>
```

6. List of the platform service stacks activated for a tenant:

```
m3 describe-platform-service-stacks -c <cloud> -tn <tenant> -r <region>
```

7. Provides assistance with using the Backup Platform Service for data backup and recovery:

```
m3 backup -c <cloud> -tn <tenant> -r <region> -bsid <backup_server_id>
```

8. Provides details about the configuration of platform service available in a tenant:

```
m3 describe-platform-services
```

9. Publishes a new service based on the specified template to the catalog:

```
m3 publish-platform-service -sn <service> -servicev <service_version> -tpl
<template> -durl <discoverable_url> -tn <tenant> -c <cloud> -t <title> -supcloud
<supported_cloud1>,<supported_cloudN> -providerv <provider_version>
```

10. Updates specified elements of the platform service:

```
m3 update-platform-service -sn <service>
```

m3 describe-platform-service-stacks

Description:

Provides details about platform service stacks activated for a customer

Usage: m3 describe-platform-service-stacks(dplstack) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --json)

--cloud,       -c,    *   The cloud.

                          Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--region,      -r,    *   The region name

--tenant,      -tn,   *   The tenant name

--all,         -A,        A flag. If specified, the services activated in all tenants
of the current customer are displayed

--service,     -sn,       The service name

--service-id,  -sid,      Service ID
```

Examples:

1. Provides details about platform service stacks activated in all tenants:

```
m3 describe-platform-service-stacks --cloud <cloud> --tenant <tenant_name> --
region <region_name> --service <service_name> --all
```

2. Provides details about a platform services stack available in a tenant:

```
m3 describe-platform-service-stacks --cloud <cloud> --tenant <tenant_name> --
region <region_name> --service <service_name>
```

3. Provides details about platform services stack by service-id:

```
m3 describe-platform-service-stacks --cloud <cloud> --tenant <tenant_name> --
region <region_name> --service-id <service_id>
```

Related commands:

1. Activates a platform service for your tenant:

```
m3 activate-platform-service -sn <service> -c <cloud> -tn <tenant> -r <region>
```

2. Adds usage/support section to the certain published service:

```
m3 add-service-section -sn <service> -sec <section> -bt <block_title>
```

3. Deactivates a platform service running for your tenant:

```
m3 deactivate-platform-service -sid <service_id> -c <cloud> -tn <tenant> -r
<region>
```

4. Deletes the section content of the certain published service:

```
m3 delete-service-section -sn <service> -sec <section>
```

5. Deletes the specified service from the catalog:

```
m3 delete-platform-service -sn <service>
```

6. Describes the section content of the certain published service:

```
m3 describe-service-section -sn <service> -sec <section>
```

7. Provides assistance with using the Backup Platform Service for data backup and recovery:

```
m3 backup -c <cloud> -tn <tenant> -r <region> -bsid <backup_server_id>
```

8. Provides details about the configuration of platform service available in a tenant:

```
m3 describe-platform-services
```

9. Publishes a new service based on the specified template to the catalog:

```
m3 publish-platform-service -sn <service> -servicev <service_version> -tpl
<template> -durl <discoverable_url> -tn <tenant> -c <cloud> -t <title> -supcloud
<supported_cloud1>,<supported_cloudN> -providerv <provider_version>
```

10. Updates specified elements of the platform service:

```
m3 update-platform-service -sn <service>
```

m3 describe-platform-services

Description:

Provides details about the configuration of platform services:

Usage: m3 describe-platform-services(dplservice) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form
(default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with -
-json)

--cloud,          -c,           The cloud.

                                Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--service,        -sn,          The service name. Required if --tenant and --cloud are
not specified

--template-type,  -tpltype,     The template type. Allowed values: [CLOUD_FORMATION,
TERRAFORM]. If specified, displays services by template type

--tenant,         -tn,          Displaying the list of the available platform services
in the tenant
```

Examples:

1. Provides details about platform services available in a tenant:

```
m3 describe-platform-services --tenant <tenant_name> --cloud <cloud> --template-
type <template_type>
```

2. Provides details about a platform service:

```
m3 describe-platform-services --service <service_name> --json
```

Related commands:

1. Activates a platform service for your tenant:

```
m3 activate-platform-service -sn <service> -c <cloud> -tn <tenant> -r <region>
```

2. Adds usage/support section to the certain published service:

```
m3 add-service-section -sn <service> -sec <section> -bt <block_title>
```

3. Deactivates a platform service running for your tenant:

```
m3 deactivate-platform-service -sid <service_id> -c <cloud> -tn <tenant> -r
<region>
```

4. Deletes the section content of the certain published service:

```
m3 delete-service-section -sn <service> -sec <section>
```

5. Deletes the specified service from the catalog:

```
m3 delete-platform-service -sn <service>
```

6. Describes the section content of the certain published service:

```
m3 describe-service-section -sn <service> -sec <section>
```

7. List of the platform service stacks activated for a tenant:

```
m3 describe-platform-service-stacks -c <cloud> -tn <tenant> -r <region>
```

8. Provides assistance with using the Backup Platform Service for data backup and recovery:

```
m3 backup -c <cloud> -tn <tenant> -r <region> -bsid <backup_server_id>
```

9. Publishes a new service based on the specified template to the catalog:

```
m3 publish-platform-service -sn <service> -servicev <service_version> -tpl
<template> -durl <discoverable_url> -tn <tenant> -c <cloud> -t <title> -supcloud
<supported_cloud1>,<supported_cloudN> -providerv <provider_version>
```

10. Updates specified elements of the platform service:

```
m3 update-platform-service -sn <service>
```

m3 run-instances

Description:

Creates instances of the specified configuration

Usage: m3 run-instances(run) [parameters]

Parameters:

```
--help                                  Shows the short help for the command

--full-help                             Shows the detailed help for the command

--verbose                               Controls the verbosity of command output

--json                                  Returns the server response in the JSON format

--table                                 Returns the server response in the table form
(default)

--full                                  Shows the full response from the server without
any specific formatting (can be used with --json)

--raw                                   Shows raw response from the server (can be used
with --json)

--cloud,                -c,        *    The cloud.

                                        Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE, VMWARE, YANDEX]

--image,                -imname,   *    The name of the image that will be used to the
instance configuration

--name,                 -n,        *    The name of the instance

--region,               -r,        *    The region name

--tenant,               -tn,       *    The tenant name

--additional-storage,   -storage,       The size of an additional storage storage in GB

--instance-type,        -itype,         Required in case of Shape not specified.
Instance type is a native attribute of instance used to determine the types and
amount of hardware resources available to the instance

--key-name,             -kname,         The SSH key name of the key pair. Optional for
Azure cloud

--number-of-instances,  -count,         Number of the instances that will be run. If
parameter is not specified, default value will be equal to 1

--script,               -scname,        The name of the script that will be applied
```

```
--shape,                -shname,      Required in case of InstanceType not specified.
Instance shape is a Maestro name of mapped to InstanceType and corresponding
attributes in other CPs. Some possible values: LARGE, MICRO, SMALL, etc

--stop-after,           -safter,      Expiration parameter which specifies when the
machine will stop

--tag,                  -tag,         Tags. Pass several values in the following
format: key1:val1,key2:val2,key3:val3

--terminate-after,      -tafter,      Termination parameter which specifies when the
machine will terminate
```

Examples:

1. Runs a single instance:

```
m3 run-instances --image <image_name> ---name <instance_name> --key-name
<key_name> --number-of-instances <number> --cloud <cloud> --tenant <tenant_name>
--region <region_name> --shape <shape_name> --script <script_name> --tag
<tag_key1:val1,tag_key2:val2>
```

2. Runs several instances from one image:

```
m3 run-instances --image <image_nam> --name <instance_name> --key-name
<key_name> --number-of-instances <number> --cloud <cloud> --tenant <tenant_name>
--region <region_name> --shape <shape_name> --script <script_name> --tag
<tag_key1:val1,tag_key2:val2>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Associate static IP with instance:

```
m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

4. Deactivate specified VLAN on specified region in tenant:

```
m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

5. Describe available VLANs on specified region in tenant:

```
m3 describe-vlans -tn <tenant> -r <region>
```

6. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

7. Describes images:

```
m3 describe-images -tn <tenant> -r <region>
```

8. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

9. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

10. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

11. Describes the regions available for a tenant in the specified cloud:

```
m3 describe-regions -tn <tenant> -c <cloud>
```

12. Describes the shapes available for your tenant:

```
m3 describe-shapes -tn <tenant> -c <cloud> -r <region>
```

13. Describes the tenants available for the user:

```
m3 describe-tenants
```

14. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

15. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

16. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

17. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

18. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

19. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

20. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 stop-instances

Description:

Stops a virtual instance

Usage: m3 stop-instances(stop) [parameters]

Parameters:

```
--help                      Shows the short help for the command

--full-help                 Shows the detailed help for the command

--verbose                   Controls the verbosity of command output

--json                      Returns the server response in the JSON format

--table                     Returns the server response in the table form (default)

--full                      Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                       Shows raw response from the server (can be used with --
json)

--instance-id,  -iid,  *  The IDs of the instances. For several instances, specify
the IDs one by one, separated by a comma without space (e.g.,
vmo00000001,vmo00000002)

--region,       -r,    *  The region name

--tenant,       -tn,   *  The tenant name
```

Example:

```
    m3 stop-instances --instance-id <instance_id> --tenant <tenant_name> --region
<region_name>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
    m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
    m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Associate static IP with instance:

```
    m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

4. Creates instances of the specified configuration:

```
    m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

5. Deactivate specified VLAN on specified region in tenant:

```
    m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

6. Describe available VLANs on specified region in tenant:

```
m3 describe-vlans -tn <tenant> -r <region>
```

7. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

8. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

9. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

10. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

11. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

12. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

13. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

14. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

15. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 backup

Description:

Provides assistance with using the Backup Platform Service for data backup and recovery

Usage: m3 backup(bkup) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form
(default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with
--json)

--backup-server-id,  -bsid,  *  The ID of the backup server

--cloud,             -c,     *  The cloud.

                                Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--region,            -r,     *  The region name

--tenant,            -tn,    *  The tenant name

--instance-id,       -iid,      The IDs of the instances.

                                For several instances, specify the IDs one by one,
separated by a comma without space (e.g., vmo00000001,vmo00000002)

--service-id,        -sid,      Service ID
```

Example:

```
m3 backup --tenant <tenant_name> --region <region_name> --cloud <cloud> --service-id
<service-id> --instance-id <instance-id> --backup-server-id <backup-server-id>
```

Related commands:

1. Activates a platform service for your tenant:

```
m3 activate-platform-service -sn <service> -c <cloud> -tn <tenant> -r <region>
```

2. Adds usage/support section to the certain published service:

```
m3 add-service-section -sn <service> -sec <section> -bt <block_title>
```

3. Deactivates a platform service running for your tenant:

```
m3 deactivate-platform-service -sid <service_id> -c <cloud> -tn <tenant> -r
<region>
```

4. Deletes the section content of the certain published service:

```
m3 delete-service-section -sn <service> -sec <section>
```

5. Deletes the specified service from the catalog:

```
m3 delete-platform-service -sn <service>
```

6. Describes the section content of the certain published service:

```
m3 describe-service-section -sn <service> -sec <section>
```

7. List of the platform service stacks activated for a tenant:

```
m3 describe-platform-service-stacks -c <cloud> -tn <tenant> -r <region>
```

8. Provides details about the configuration of platform service available in a tenant:

```
m3 describe-platform-services
```

9. Publishes a new service based on the specified template to the catalog:

```
m3 publish-platform-service -sn <service> -servicev <service_version> -tpl
<template> -durl <discoverable_url> -tn <tenant> -c <cloud> -t <title> -supcloud
<supported_cloud1>,<supported_cloudN> -providerv <provider_version>
```

10. Updates specified elements of the platform service:

```
m3 update-platform-service -sn <service>
```

m3 terminate-instances

Description:

Terminates a virtual instance

Usage: m3 terminate-instances(kill) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --
json)

--instance-id,  -iid,  *  The IDs of the instances. For several instances, specify
the IDs one by one, separated by a comma without space (e.g.,
vmo00000001,vmo00000002)

--region,       -r,    *  The region name

--tenant,       -tn,   *  The tenant name
```

Example:

```
    m3 terminate-instances --instance-id <instance_id> --region <region_name> --
tenant <tenant_name>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
    m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
    m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Associate static IP with instance:

```
    m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

4. Creates instances of the specified configuration:

```
    m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

5. Deactivate specified VLAN on specified region in tenant:

```
    m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

6. Describe available VLANs on specified region in tenant:

```
m3 describe-vlans -tn <tenant> -r <region>
```

7. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

8. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

9. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

10. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

11. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

12. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

13. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

14. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

15. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

m3 describe-images

Description:

Describes images available in a specific region for a specific tenant

Usage: m3 describe-images(dim) [parameters]

Parameters:

```
--help                Shows the short help for the command

--full-help           Shows the detailed help for the command

--verbose             Controls the verbosity of command output

--json                Returns the server response in the JSON format

--table               Returns the server response in the table form (default)

--full                Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                 Shows raw response from the server (can be used with --json)

--region,    -r,   *  The region name

--tenant,    -tn,  *  The tenant name
```

Example:

```
    m3 describe-images --region <region> --tenant <tenant>
```

Related commands:

1. Creates an image based on an existing instance:

```
    m3 create-image -tn <tenant> -r <region> -iid <instance_id> -n <name> -d
   <description>
```

2. Deletes an image created from a project instance:

```
    m3 delete-image -tn <tenant> -r <region> -imid <image_id>
```

m3 describe-storages

Description:

Describes instance storages existing in the specific tenant

Usage: m3 describe-storages(dstor) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form (default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with --
json)

--region,       -r,       *   The region name

--tenant,       -tn,      *   The tenant name

--instance-id,  -iid,         The ID of the instance. Use to see the storages of the
specified instance

--storage-id,   -storid,      Storage IDs. Use to see the descriptions of the specific
storages

                              For several storages, specify the IDs one by one,
separated by a comma without space (e.g., vmo00000001,vmo00000002)
```

Examples:

1. Describes all storages on the user's tenant and region:

```
m3 describe-storages --region <region_name> --tenant <name>
```

2. Describes the storages on a specified instance:

```
m3 describe-storages --region <region_name> --tenant <name> --instance-id
<instance_id>
```

3. Describes the specific storage:

```
m3 describe-storages --region <region_name> --tenant <name> --storage-id
<storage_id1>,<storage_idN>
```

Related commands:

1. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

2. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

3. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

4. Describes the shapes available for your tenant:

```
m3 describe-shapes -tn <tenant> -c <cloud> -r <region>
```

5. Sets up an amount and size of storages allowed for creation on a specific tenant within a specific interval:

```
m3 create-storage-quota -tn <tenant> -r <region> -storsize <storage_max_size> -h
<creation_interval_hours> -amount <storage_amount>
```

m3 create-attach-storage

Description:

Creates the storage and attaches to an existing instance

Usage: m3 create-attach-storage(addattstor) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --
json)

--instance-id,  -iid,  *  The ID of the instance to which the storage will be added

--name,         -n,    *  The storage name

--region,       -r,    *  The region name

--size,         -s,    *  The maximum size of a storage at creation, in GB

--tenant,       -tn,   *  The tenant name
```

Example:

```
    m3 create-attach-storage --name <storage_name> --instance-id <instance_id> --
tenant <tenant_name> --region <region_name> --size <size_GB>
```

Related commands:

1. Deletes the specified storage:

```
    m3 delete-storage -tn <tenant> -r <region> -storid <storage_id>
```

2. Detaches the specified storage from instance:

```
    m3 detach-storage -tn <tenant> -r <region> -iid <instance_id> -storid
   <storage_id>
```

m3 detach-storage

Description:

Detaches the specified storage from an existing instance

Usage: m3 detach-storage(detstor) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form (default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with --
json)

--instance-id,  -iid,     *  The ID of the instance from which the storage will be
detached

--region,       -r,       *  The region name

--storage-id,   -storid,  *  The ID of the storage

--tenant,       -tn,      *  The tenant name
```

Example:

```
    m3 detach-storage --tenant <tenant_name> --region <region_name> --instance-id
<instance_id> --storage-id <storage_id>
```

Related commands:

1. Creates the storage and attaches to the specified instance:

```
    m3 create-attach-storage -tn <tenant> -r <region> -iid <instance_id> -n <name> -
    s <size>
```

2. Deletes the specified storage:

```
    m3 delete-storage -tn <tenant> -r <region> -storid <storage_id>
```

m3 delete-storage

Description:

Removes the specified storage

Usage: m3 delete-storage(delstor) [parameters]

Parameters:

```
--help                              Shows the short help for the command

--full-help                         Shows the detailed help for the command

--verbose                           Controls the verbosity of command output

--json                              Returns the server response in the JSON format

--table                             Returns the server response in the table form
(default)

--full                              Shows the full response from the server without
any specific formatting (can be used with --json)

--raw                               Shows raw response from the server (can be used
with --json)

--region,             -r,       *   The region name

--storage-id,         -storid,  *   The ID of storage

--tenant,             -tn,      *   The tenant name

--availability-zone,  -az,          The availability zone name (for Google)
```

Example:

```
    m3 delete-storage --tenant <tenant_name> --region <region_name> --storage-id
<storage_id>
```

Related commands:

1. Creates the storage and attaches to the specified instance:

```
    m3 create-attach-storage -tn <tenant> -r <region> -iid <instance_id> -n <name> -
   s <size>
```

2. Detaches the specified storage from instance:

```
    m3 detach-storage -tn <tenant> -r <region> -iid <instance_id> -storid
   <storage_id>
```

m3 decrypt-password

Description:

Decrypts the password for windows instances

Usage: m3 decrypt-password(dp) [parameters]

Parameters:

```
--help                              Shows the short help for the command

--full-help                         Shows the detailed help for the command

--verbose                           Controls the verbosity of command output

--json                              Returns the server response in the JSON format

--table                             Returns the server response in the table form
(default)

--full                              Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                               Shows raw response from the server (can be used
with --json)

--instance-id,        -iid,    *    The ID of the instance for which the password
should be decrypted

--private-key-path,   -kpath,  *    The path to the file with the private key part

--region,             -r,      *    The region name

--tenant,             -tn,     *    The tenant name

--availability-zone,  -az,         The availability zone name (for Google)
```

Example:

```
m3 decrypt-password --tenant <tenant_name> --region <region_name> --instance-id
<instance_id> --private-key-path <private-key-path-to-file> --availability-zone
<zone_name>
```

m3 describe-schedules

Description:

Describes the schedules set to instances in your tenant

Usage: m3 describe-schedules(dsch) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form
(default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with
--json)

--cloud,          -c,       *   The cloud.

                                Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--tenant,         -tn,      *   The tenant name

--region,         -r,           The region name

--schedule-name,  -schname,     The name of the schedule

--schedule-type,  -schtype,     The schedule type. Allowed values: [Specified
instances, My instances with tag, All my instances in region]
```

Examples:

1. Describes schedules within a specific cloud and region:

```
m3 describe-schedules --cloud <cloud> --tenant <tenant_name> --region
<region_name>
```

2. Describe schedules applied for a specific instance:

```
m3 describe-schedules --cloud <cloud> --tenant <tenant_name> --region
<region_name> --instance-id <instance_id>
```

Related commands:

1. Adds an existing schedule to one or several instances:

```
m3 add-schedule-instances -tn <tenant> -c <cloud> -r <region> -n <name> -iid
<instance_id1>,<instance_idN>
```

2. Creates a new schedule for automatic instance state management:

```
m3 create-schedule -r <region> -tn <tenant> -n <name> -cron <cron> -d
<description> -a <action> -schtype <schedule_type> -c <cloud>
```

3. Deletes a schedule from one or several instances:

```
m3 delete-schedule-instances -tn <tenant> -c <cloud> -r <region> -n <name> -iid
<instance_id1>,<instance_idN>
```

4. Deletes a schedule from your tenants schedule library:

```
m3 delete-schedule -r <region> -tn <tenant> -n <name>
```

5. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

6. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

7. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

m3 create-schedule

Description:

Creates a new schedule for automatic instance state management

Usage: m3 create-schedule(csch) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form
(default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with
--json)

--action,         -a,       *   The action for the schedule. Allowed values: [START,
STOP]

--cloud,          -c,       *   The cloud.

                                Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--cron,           -cron,    *   The cron rule that will be used by the schedule. It
should contain these parameters separated by spaces, in given order: seconds
(optional), minutes, hours, days of month, months, days of weeks, year (optional).
Example: s m d M d/w y. Accepted placeholders: * (all values), ? (no specific value),
/ (increments), - (range)

--description,    -d,       *   The description of the schedule

--name,           -n,       *   The display name of the schedule

--region,         -r,       *   The region name

--schedule-type,  -schtype, *   The schedule type. Allowed values: [Specified
instances, My instances with tag, All my instances in region]

--tenant,         -tn,      *   The tenant name

--instance-id,    -iid,         The IDs of the instances.

                                For several instances, specify the IDs one by one,
```

```
separated by a comma without space (e.g., vmo00000001,vmo00000002)

--tag-key,        -tkey,        The key of the tag of the instance to which the
schedule is to be applied.

                                Required for schedule type "My instances with tag"

--tag-value,      -tvalue,      The value of the tag of the instance to which the
schedule is to be applied.

                                Required for schedule type "My instances with tag"
```

Examples:

1. Creates a new schedule to start or stop explicit instances:

```
m3 create-schedule --action <action> --cloud <cloud> --region <region> --cron
<"cron expression"> --description <"schedule description"> --name <name> --
schedule-type <"schedule type"> --instance-id <instance_id> --tenant
<tenant_name>
```

2. Creates a new schedule to start or stop instances with tag:

```
m3 create-schedule --action <action> --cloud <cloud> --region <region> --cron
<"cron expression"> --description <"schedule description"> --name <name> --
schedule-type <"schedule type"> --tenant <tenant_name> --tag-key <key> --tag-
value <value>
```

Related commands:

1. Adds an existing schedule to one or several instances:

```
m3 add-schedule-instances -tn <tenant> -c <cloud> -r <region> -n <name> -iid
<instance_id1>,<instance_idN>
```

2. Deletes a schedule from one or several instances:

```
m3 delete-schedule-instances -tn <tenant> -c <cloud> -r <region> -n <name> -iid
<instance_id1>,<instance_idN>
```

3. Deletes a schedule from your tenants schedule library:

```
m3 delete-schedule -r <region> -tn <tenant> -n <name>
```

4. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

5. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

6. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

7. Describes the schedules set to instances in your tenant:

```
m3 describe-schedules -tn <tenant> -c <cloud>
```

m3 delete-schedule

Description:

Deletes a schedule from your tenants schedule library

Usage: m3 delete-schedule(delsch) [parameters]

Parameters:

```
--help                  Shows the short help for the command

--full-help             Shows the detailed help for the command

--verbose               Controls the verbosity of command output

--json                  Returns the server response in the JSON format

--table                 Returns the server response in the table form (default)

--full                  Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                   Shows raw response from the server (can be used with --json)

--name,      -n,    *   The name of the schedule used for reference

--region,    -r,    *   The region name

--tenant,    -tn,   *   The tenant name
```

Example:

```
    m3 delete-schedule --region <region> --name <name> --tenant <tenant_name>
```

Related commands:

1. Adds an existing schedule to one or several instances:

```
    m3 add-schedule-instances -tn <tenant> -c <cloud> -r <region> -n <name> -iid
   <instance_id1>,<instance_idN>
```

2. Creates a new schedule for automatic instance state management:

```
    m3 create-schedule -r <region> -tn <tenant> -n <name> -cron <cron> -d
   <description> -a <action> -schtype <schedule_type> -c <cloud>
```

3. Deletes a schedule from one or several instances:

```
    m3 delete-schedule-instances -tn <tenant> -c <cloud> -r <region> -n <name> -iid
   <instance_id1>,<instance_idN>
```

4. Describes insights for an instance in specific region for a specific tenant:

```
    m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

5. Describes instances existing in a specific region for a specific tenant:

```
    m3 describe-instances -tn <tenant> -r <region>
```

6. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

7. Describes the schedules set to instances in your tenant:

```
m3 describe-schedules -tn <tenant> -c <cloud>
```

m3 total-report

Description:

Gets a total billing report for a tenant

Usage: m3 total-report(treport) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form (default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with --
json)

--tenant-group,  -tg,    *      The tenant group

--adjustment,    -A,            A flag. If specified, only adjustments will be shown

--cloud,         -c,            The list of the cloud names. Should be specified if you
need

                                Pass several values in the following format:
value1,value2,value3

--day,           -d,            Day. Format (dd). Use with 'year' and 'month' for a 1-day
range

--from,          -from,         Start date. Format (dd.mm.yyyy). Use with 'to' for a
custom range

--month,         -m,            Month. Format (mm). Use with 'year' for a 1-month range,
or with 'day' for a 1-day range

--region,        -r,            The region name.  Specify this parameter to filter report
records by region

--report,        -R,            A flag. If specified the report will be sent by email

--tag,           -tag,          Collects only records with a specified tag. Use the
following format: tag=value

--to,            -to,           End date. Format (dd.mm.yyyy). Use with 'from' for a
custom range
```

```
--url,          -U,        A flag. If specified, the presigned URL will be generated

--year,         -y,        Year. Format (yyyy). Use with 'month' for a 1-month
range, or with 'month' and 'day' for a 1-day range
```

Examples:

```
1. For the current month (specify year and month):

    m3 total-report --tenant-group <tenant_group_name> --year <yyyy> --month <mm>

2. For a specific day (specify year, month, and day):

    m3 total-report --tenant-group <tenant_group_name> --year <yyyy> --month <mm> --
day <dd>

3. For a date range (from - to):

    m3 total-report --tenant-group <tenant_group_name> --from <dd.mm.yyyy> --to
<dd.mm.yyyy>

4. Show only adjustments:

    m3 total-report --tenant-group <tenant_group_name> --year <yyyy> --month <mm> --
day <dd> --adjustment
```

Note: Use either ‘year’ and ‘month’ (and optionally ‘day’), OR ‘from’ and ‘to’

Related commands:

1. Cost and usage optimization report. Command sends the report only to email:

```
m3 cost-usage-report -date <dd.mm.yyyy> -tn <tenant> -r <region> -rt
<resource_type>
```

2. Gets a budgets billing report for a tenant:

```
m3 budgets-report -tg <tenant_group> -y <year> -m <month>
```

3. Gets billing region types:

```
m3 billing-region-types
```

4. Gets cost object report for the specified tenant:

```
m3 cost-object-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

5. Gets hourly billing report for the specified tenant:

```
m3 hourly-report -tg <tenant_group>
```

6. Gets multitenant billing report:

```
m3 multitenant-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -rtype <report_type>
```

7. Gets resource billing report for the specified tenant:

```
m3 resource-report -tg <tenant_group>
```

8. Gets subtotal billing report for the specified tenant:

```
m3 subtotal-report -tg <tenant_group>
```

9. Gets untagged resource billing report:

```
m3 untagged-resource-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

10. This command is a single point of entry for report-related commands: ‘total-report’, ‘subtotal-report’, ‘resource-report’, ‘budgets-report’ and ‘hourly-report’:

```
m3 report -tg <tenant_group> -y <year> -m <month>
```

m3 subtotal-report

Description:

Gets subtotal billing report for the specified tenant

Usage: m3 subtotal-report(streport) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form (default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with --
json)

--tenant-group,  -tg,    *      The tenant group

--adjustment,    -A,            A flag. If specified, only adjustments will be shown

--cloud,         -c,            The list of the cloud names. (Can not be used with '--
region' parameter)

                                Pass several values in the following format:
value1,value2,value3

--day,           -d,            Day. Format (dd). Use with 'year' and 'month' for a 1-day
range

--from,          -from,         Start date. Format (dd.mm.yyyy). Use with 'to' for a
custom range

--month,         -m,            Month. Format (mm). Use with 'year' for a 1-month range,
or with 'day' for a 1-day range

--region,        -r,            The region name. (Can not be used with '--cloud'
parameter)

--report,        -R,            A flag. If specified the report will be sent by email

--tag,           -tag,          Collects only records with a specified tag. Use the
following format: tag=value

--to,            -to,           End date. Format (dd.mm.yyyy). Use with 'from' for a
custom range
```

```
--url,           -U,        A flag. If specified, the presigned URL will be generated

--year,          -y,        Year. Format (yyyy). Use with 'month' for a 1-month
range, or with 'month' and 'day' for a 1-day range
```

Examples:

```
1. For the current month (specify year and month):

    m3 subtotal-report --tenant-group <tenant_group_name> --year <yyyy> --month <mm>

2. For a specific day (specify year, month, and day):

    m3 subtotal-report --tenant-group <tenant_group_name> --year <yyyy> --month <mm>
--day <dd>

3. For a date range (from - to):

    m3 subtotal-report --tenant-group <tenant_group_name> --from <dd.mm.yyyy> --to
<dd.mm.yyyy>

4. Show only adjustments:

    m3 subtotal-report --tenant-group <tenant_group_name> --year <yyyy> --month <mm>
--day <dd> --adjustment
```

Note: Use either ‘year’ and ‘month’ (and optionally ‘day’), OR ‘from’ and ‘to’

Related commands:

1. Cost and usage optimization report. Command sends the report only to email:

```
m3 cost-usage-report -date <dd.mm.yyyy> -tn <tenant> -r <region> -rt
<resource_type>
```

2. Gets a budgets billing report for a tenant:

```
m3 budgets-report -tg <tenant_group> -y <year> -m <month>
```

3. Gets a total billing report for a tenant:

```
m3 total-report -tg <tenant_group>
```

4. Gets billing region types:

```
m3 billing-region-types
```

5. Gets cost object report for the specified tenant:

```
m3 cost-object-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

6. Gets hourly billing report for the specified tenant:

```
m3 hourly-report -tg <tenant_group>
```

7. Gets multitenant billing report:

```
m3 multitenant-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -rtype <report_type>
```

8. Gets resource billing report for the specified tenant:

```
m3 resource-report -tg <tenant_group>
```

9. Gets untagged resource billing report:

```
m3 untagged-resource-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

10. This command is a single point of entry for report-related commands: ‘total-report’, ‘subtotal-report’, ‘resource-report’, ‘budgets-report’ and ‘hourly-report’:

```
m3 report -tg <tenant_group> -y <year> -m <month>
```

m3 budgets-report

Description:

Gets budgets billing report for the specified tenant

Usage: m3 budgets-report(bgreport) [parameters]

Parameters:

```
--help                      Shows the short help for the command

--full-help                 Shows the detailed help for the command

--verbose                   Controls the verbosity of command output

--json                      Returns the server response in the JSON format

--table                     Returns the server response in the table form (default)

--full                      Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                       Shows raw response from the server (can be used with --
json)

--tenant-group,  -tg,  *    The tenant group

--year,          -y,   *    Year. Format (yyyy). Use with 'month' for a 1-month range

--month,         -m,   *    Month. Format (mm). Use with 'year' for a 1-month range

--region,        -r,        The region name. Specify this parameter to filter report
records by region

--tag,                      Collects only records with a specified tag. Use the
following format: tag=value

--filter,        -f,        Filter by criteria.

                            Allowed values: [ALL(default), DEPLETED, ACTUAL, DISABLED]
```

Examples:

```
m3 budgets-report --tenant-group <tenant_group_name> --year <yyyy> --month <mm>
```

Related commands:

1. Cost and usage optimization report. Command sends the report only to email:

```
m3 cost-usage-report -date <dd.mm.yyyy> -tn <tenant> -r <region> -rt
<resource_type>
```

2. Gets a total billing report for a tenant:

```
m3 total-report -tg <tenant_group>
```

3. Gets billing region types:

```
m3 billing-region-types
```

4. Gets cost object report for the specified tenant:

```
m3 cost-object-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

5. Gets hourly billing report for the specified tenant:

```
m3 hourly-report -tg <tenant_group>
```

6. Gets multitenant billing report:

```
m3 multitenant-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -rtype <report_type>
```

7. Gets resource billing report for the specified tenant:

```
m3 resource-report -tg <tenant_group>
```

8. Gets subtotal billing report for the specified tenant:

```
m3 subtotal-report -tg <tenant_group>
```

9. Gets untagged resource billing report:

```
m3 untagged-resource-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

10. This command is a single point of entry for report-related commands: ‘total-report’, ‘subtotal-report’, ‘resource-report’, ‘budgets-report’ and ‘hourly-report’:

```
m3 report -tg <tenant_group> -y <year> -m <month>
```

m3 cost-usage-report

Description:

Gets cost and usage optimization report

Usage: m3 cost-usage-report(cureport) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form (default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with --
json)

--date,           -date,   *    The date. Format "dd.mm.yyyy"

--region,         -r,      *    The region name for the AWS cloud provider

--resource-type,  -rt,     *    The type of the resource. Allowed values:
"HIGH_UTILIZED_WORKSPACES", "IDLE_ELBS", "IDLE_NAT_GATEWAYS", "IDLE_VPC_ENDPOINTS",

                                "LOW_UTILIZED_ELBS", "LOW_UTILIZED_NAT_GATEWAYS",
"LOW_UTILIZED_VPNS", "EBS_VOLUMES_MODERNIZE_GP2_TO_GP3", "EBS_SNAPSHOT_TRENDS",
"S3_BUCKET_TRENDS_AND_OPTIMIZATIONS"

--tenant,         -tn,     *    The tenant name

--report,         -R,           A flag. If specified the report will be sent by email
```

Example:

```
    m3 cost-usage-report --cloud <cloud> --date <dd.mm.yyyy> --region <region_name> -
-resource-type <resource_type> --tenant <tenant_name>
```

Related commands:

1. Gets a budgets billing report for a tenant:

```
    m3 budgets-report -tg <tenant_group> -y <year> -m <month>
```

2. Gets a total billing report for a tenant:

```
    m3 total-report -tg <tenant_group>
```

3. Gets billing region types:

```
m3 billing-region-types
```

4. Gets cost object report for the specified tenant:

```
m3 cost-object-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

5. Gets hourly billing report for the specified tenant:

```
m3 hourly-report -tg <tenant_group>
```

6. Gets multitenant billing report:

```
m3 multitenant-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -rtype <report_type>
```

7. Gets resource billing report for the specified tenant:

```
m3 resource-report -tg <tenant_group>
```

8. Gets subtotal billing report for the specified tenant:

```
m3 subtotal-report -tg <tenant_group>
```

9. Gets untagged resource billing report:

```
m3 untagged-resource-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

10. This command is a single point of entry for report-related commands: ‘total-report’, ‘subtotal-report’, ‘resource-report’, ‘budgets-report’ and ‘hourly-report’:

```
m3 report -tg <tenant_group> -y <year> -m <month>
```

m3 untagged-resource-report

Description:

Provides the report by untagged resources within the specified tenant

Usage: m3 untagged-resource-report(untagresreport) [parameters]

Parameters:

```
--help                  Shows the short help for the command

--full-help             Shows the detailed help for the command

--verbose               Controls the verbosity of command output

--json                  Returns the server response in the JSON format

--table                 Returns the server response in the table form (default)

--full                  Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                   Shows raw response from the server (can be used with --json)

--from,      -from,  *  The start range date. Format "dd.mm.yyyy"

--tenant,    -tn,    *  The tenant name

--to,        -to,    *  The end range date. Format "dd.mm.yyyy"

--cloud,     -c,        The list of the cloud names. Pass several values in the
following format: value1,value2,value3

--region,    -r,        The region name.  Specify this parameter to filter report
records by region

--report,    -R,        A flag. If specified the report will be sent by email
```

Examples:

1. Provides the general report for the tenant:

```
m3 untagged-resource-report --tenant <tenant_name> --from <dd.mm.yyyy> --to
<dd.mm.yyyy>
```

2. Provides the report for specific clouds:

```
m3 untagged-resource-report --tenant <tenant_name> --from <dd.mm.yyyy> --to
<dd.mm.yyyy> --cloud-list <cloud1>,<cloudN>
```

Related commands:

1. Cost and usage optimization report. Command sends the report only to email:

```
 m3 cost-usage-report -date <dd.mm.yyyy> -tn <tenant> -r <region> -rt
<resource_type>
```

2. Gets a budgets billing report for a tenant:

```
m3 budgets-report -tg <tenant_group> -y <year> -m <month>
```

3. Gets a total billing report for a tenant:

```
m3 total-report -tg <tenant_group>
```

4. Gets billing region types:

```
m3 billing-region-types
```

5. Gets cost object report for the specified tenant:

```
m3 cost-object-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

6. Gets hourly billing report for the specified tenant:

```
m3 hourly-report -tg <tenant_group>
```

7. Gets multitenant billing report:

```
m3 multitenant-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -rtype <report_type>
```

8. Gets resource billing report for the specified tenant:

```
m3 resource-report -tg <tenant_group>
```

9. Gets subtotal billing report for the specified tenant:

```
m3 subtotal-report -tg <tenant_group>
```

10. This command is a single point of entry for report-related commands: ‘total-report’, ‘subtotal-report’, ‘resource-report’, ‘budgets-report’ and ‘hourly-report’:

```
m3 report -tg <tenant_group> -y <year> -m <month>
```

m3 resource-report

Description:

Gets resource billing report for the specified tenant

Usage: m3 resource-report(resreport) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form (default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with --
json)

--tenant-group,  -tg,    *      The tenant group

--cloud,         -c,            The list of the cloud names. Can not be provided with "--
region" parameter.

                                Pass several values in the following format:
value1,value2,value3

--day,           -d,            Day. Format (dd). Use with 'year' and 'month' for a 1-day
range

--from,          -from,         Start date. Format (dd.mm.yyyy). Use with 'to' for a
custom range

--instance-id,   -iid,          The IDs of the instances by which a report will be
generated.

                                For several instances, specify the IDs one by one,
separated by a comma without space (e.g., vmo00000001,vmo00000002)

--month,         -m,            Month. Format (mm). Use with 'year' for a 1-month range,
or with 'day' for a 1-day range

--region,        -r,            The region name. Specify this parameter to filter report
records by region.

                                Can not be provided with "--cloud" parameter

--report,        -R,            A flag. If specified the report will be sent by email
```

```
--tag,           -tag,      Collects only records with a specified tag. Use the
following format: tag=value

--to,            -to,       End date. Format (dd.mm.yyyy). Use with 'from' for a
custom range

--url,           -U,        A flag. If specified, the presigned URL will be generated

--year,          -y,        Year. Format (yyyy). Use with 'month' for a 1-month
range, or with 'month' and 'day' for a 1-day range
```

Examples:

```
1. For the current month (specify year and month):

   m3 resource-report --tenant-group <tenant_group_name> --year <yyyy> --month <mm>

2. For a specific day (specify year, month, and day):

   m3 resource-report --tenant-group <tenant_group_name> --year <yyyy> --month <mm> -
-day <dd>

3. For a date range (from - to):

   m3 resource-report --tenant-group <tenant_group_name> --from <dd.mm.yyyy> --to
<dd.mm.yyyy>
```

Note: Use either ‘year’ and ‘month’ (and optionally ‘day’), OR ‘from’ and ‘to’

Related commands:

1. Cost and usage optimization report. Command sends the report only to email:

```
m3 cost-usage-report -date <dd.mm.yyyy> -tn <tenant> -r <region> -rt
<resource_type>
```

2. Gets a budgets billing report for a tenant:

```
m3 budgets-report -tg <tenant_group> -y <year> -m <month>
```

3. Gets a total billing report for a tenant:

```
m3 total-report -tg <tenant_group>
```

4. Gets billing region types:

```
m3 billing-region-types
```

5. Gets cost object report for the specified tenant:

```
m3 cost-object-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

6. Gets hourly billing report for the specified tenant:

```
m3 hourly-report -tg <tenant_group>
```

7. Gets multitenant billing report:

```
m3 multitenant-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -rtype <report_type>
```

8. Gets subtotal billing report for the specified tenant:

```
m3 subtotal-report -tg <tenant_group>
```

9. Gets untagged resource billing report:

```
m3 untagged-resource-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

10. This command is a single point of entry for report-related commands: ‘total-report’, ‘subtotal-report’, ‘resource-report’, ‘budgets-report’ and ‘hourly-report’:

```
m3 report -tg <tenant_group> -y <year> -m <month>
```

m3 cost-object-report

Description:

Gets cost object report for the specified tenant:

Usage: m3 cost-object-report(cosobreport) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form (default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with --
json)

--from,           -from,   *    The start range date. Format "dd.mm.yyyy"

--tenant,         -tn,     *    The tenant name

--to,             -to,     *    The end range date. Format "dd.mm.yyyy"

--cloud,          -c,           The list of the cloud names. Pass several values in the
following format: value1,value2,value3

--product,        -pn,          The product name. If not specified, 'All' will be used

--region,         -r,           The region name.  Specify this parameter to filter
report records by region

--report,         -R,           A flag. If specified the report will be sent by email

--resource-type,  -rt,          The resource type. If not specified, 'All' will be used

--tag,            -tag,         Collects only records with a specified tag. Use the
following format: tag=value

--usage-type,     -ut,          The usage type. If not specified, 'All' will be used
```

Example:

```
    m3 cost-object-report --tenant <tenant_name> --from <dd.mm.yyyy> --to
<dd.mm.yyyy>
```

Related commands:

1. Cost and usage optimization report. Command sends the report only to email:

```
m3 cost-usage-report -date <dd.mm.yyyy> -tn <tenant> -r <region> -rt
<resource_type>
```

2. Gets a budgets billing report for a tenant:

```
m3 budgets-report -tg <tenant_group> -y <year> -m <month>
```

3. Gets a total billing report for a tenant:

```
m3 total-report -tg <tenant_group>
```

4. Gets billing region types:

```
m3 billing-region-types
```

5. Gets hourly billing report for the specified tenant:

```
m3 hourly-report -tg <tenant_group>
```

6. Gets multitenant billing report:

```
m3 multitenant-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -rtype <report_type>
```

7. Gets resource billing report for the specified tenant:

```
m3 resource-report -tg <tenant_group>
```

8. Gets subtotal billing report for the specified tenant:

```
m3 subtotal-report -tg <tenant_group>
```

9. Gets untagged resource billing report:

```
m3 untagged-resource-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

10. This command is a single point of entry for report-related commands: ‘total-report’, ‘subtotal-report’, ‘resource-report’, ‘budgets-report’ and ‘hourly-report’:

```
m3 report -tg <tenant_group> -y <year> -m <month>
```

m3 hourly-report

Description:

Gets hourly billing report for the specified tenant

Usage: m3 hourly-report(hreport) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form (default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with --
json)

--tenant-group,   -tg,     *    The tenant group

--date,           -date,        Date. Format (dd.mm.yyyy). Or specify 'year, month and
day' instead

--day,            -d,           Day. Format (dd). Use with 'year' and 'month'

--instance-id,    -iid,         The ID of the instance

--month,          -m,           Month. Format (mm). Use with 'year' and 'day'

--region,         -r,           The region name. Specify this parameter to filter report
records by region

--tag,            -tag,         Collects only records with a specified tag. Use the
following format: tag=value

--url,            -U,           A flag. If specified, the presigned URL will be generated

--year,           -y,           Year. Format (yyyy). Use with 'month' and 'day'
```

Example:

```
    1. Specify year, month and day:

    m3 hourly-report --year <yyyy> --month <mm> --day <dd> --tenant-group
<tenant_group_name>

    2. Specify date:
```

```
m3 hourly-report --date <date> --tenant-group <tenant_group_name>
```

Note: Use either ‘year’, ‘month’, and ‘day’, OR ‘date’

Related commands:

1. Cost and usage optimization report. Command sends the report only to email:

```
m3 cost-usage-report -date <dd.mm.yyyy> -tn <tenant> -r <region> -rt
<resource_type>
```

2. Gets a budgets billing report for a tenant:

```
m3 budgets-report -tg <tenant_group> -y <year> -m <month>
```

3. Gets a total billing report for a tenant:

```
m3 total-report -tg <tenant_group>
```

4. Gets billing region types:

```
m3 billing-region-types
```

5. Gets cost object report for the specified tenant:

```
m3 cost-object-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

6. Gets multitenant billing report:

```
m3 multitenant-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -rtype <report_type>
```

7. Gets resource billing report for the specified tenant:

```
m3 resource-report -tg <tenant_group>
```

8. Gets subtotal billing report for the specified tenant:

```
m3 subtotal-report -tg <tenant_group>
```

9. Gets untagged resource billing report:

```
m3 untagged-resource-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

10. This command is a single point of entry for report-related commands: ‘total-report’, ‘subtotal-report’, ‘resource-report’, ‘budgets-report’ and ‘hourly-report’:

```
m3 report -tg <tenant_group> -y <year> -m <month>
```

m3 aws-management-console

Description:

Provides access to AWS management console for the specified tenant. The credentials are shared via an email access

Usage: m3 aws-management-console(awsmc) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form (default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with --
json)

--access-type,  -atype,  *  The type of the access to be provided. Allowed values:
[IAM_USER, ASSUME_ROLE, FEDERATED_USER, CLOUD_ADMIN_USER]

--tenant,       -tn,     *  The tenant name
```

Example:

```
m3 aws-management-console --tenant <tenant_name> --access-type <access_type>
```

Related commands:

1. Azure management console access:

```
m3 azure-management-console -tn <tenant>
```

2. Google management console access:

```
m3 google-management-console -tn <tenant>
```

m3 azure-management-console

Description:

Provides access to Azure management console for the specified tenant. (Access type DEFAULT)

The credentials are shared via an email

Usage: m3 azure-management-console(azuremc) [parameters]

Parameters:

```
--help                Shows the short help for the command

--full-help           Shows the detailed help for the command

--verbose             Controls the verbosity of command output

--json                Returns the server response in the JSON format

--table               Returns the server response in the table form (default)

--full                Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                 Shows raw response from the server (can be used with --json)

--tenant,    -tn,  *  The tenant name
```

Example:

```
    m3 azure-management-console --tenant-name <tenant_name>
```

Related commands:

1. AWS management console access:

```
    m3 aws-management-console -tn <tenant> -atype <access_type>
```

2. Google management console access:

```
    m3 google-management-console -tn <tenant>
```

m3 google-management-console

Description:

Provides access to Google Cloud management console for the specified tenant. The credentials are shared via an email

Usage: m3 google-management-console(gcpmc) [parameters]

Parameters:

```
--help                Shows the short help for the command

--full-help           Shows the detailed help for the command

--verbose             Controls the verbosity of command output

--json                Returns the server response in the JSON format

--table               Returns the server response in the table form (default)

--full                Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                 Shows raw response from the server (can be used with --json)

--tenant,    -tn,  *  The tenant name
```

Example:

```
    m3 google-management-console --tenant-name <tenant_name>
```

Related commands:

1. AWS management console access:

```
    m3 aws-management-console -tn <tenant> -atype <access_type>
```

2. Azure management console access:

```
    m3 azure-management-console -tn <tenant>
```

m3 upload-script

Description:

Uploads an init script to tenant's library in Maestro

Usage: m3 upload-script(upscr) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form (default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with --
json)

--cloud,        -c,       *  The cloud.

                                Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--script,       -scname,  *  The name of the script to be uploaded. The file
extension(.sh, .cmd, ...) will be taken from 'spath'

--source-path,  -spath,   *  The path to the script file. The file extension should
be either '.sh', '.bat', 'cmd' or '.ps1'

--tenant,       -tn,      *  The tenant name
```

Example:

```
    m3 upload-script --cloud <cloud_name> --source-path <path> --script <script_name>
--tenant <tenant_name>
```

Related commands:

1. Deletes the user script from the specific tenant in Maestro:

```
    m3 delete-scripts -tn <tenant> -c <cloud> -scname <script1>,<scriptN>
```

2. Describes the script files uploaded to Maestro and available for the specific tenant:

```
    m3 describe-script -tn <tenant> -c <cloud>
```

m3 delete-scripts

Description:

Deletes an init script from your library in Maestro

Usage: m3 delete-scripts(delscr) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --
json)

--cloud,     -c,       *  The cloud.

                          Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--script,    -scname,  *  List of the name of the file to be deleted. Pass several
values in the following format: value1,value2,value3

--tenant,    -tn,      *  The tenant name
```

Example:

```
m3 delete-scripts --cloud <cloud_name> --file <file_name> --tenant <tenant_name>
```

Related commands:

1. Describes the script files uploaded to Maestro and available for the specific tenant:

```
m3 describe-script -tn <tenant> -c <cloud>
```

2. Uploads the user script to the specific tenant in Maestro:

```
m3 upload-script -tn <tenant> -c <cloud> -spath <source_path> -scname <script>
```

m3 describe-script

Description:

Describes the script files uploaded to Maestro and available for your tenant

Usage: m3 describe-script(dscript) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form
(default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with -
-json)

--cloud,          -c,       *   The cloud.

                                Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--tenant,         -tn,      *   The tenant name

--presigned-url,  -purl,        A flag. Allows user to download script by presigned
URL. Works only with `--full` flag

--script,         -scname,      The file name. If this parameter is specified, the
content of the script will be returned
```

Examples:

1. Describes all available script files:

```
m3 describe-script --cloud <cloud> --tenant <tenant_name>
```

2. Provides the content of the specific file:

```
m3 describe-script --cloud <cloud> --tenant <tenant_name> --script <script_name>
```

Related commands:

1. Deletes the user script from the specific tenant in Maestro:

```
m3 delete-scripts -tn <tenant> -c <cloud> -scname <script1>,<scriptN>
```

2. Uploads the user script to the specific tenant in Maestro:

```
m3 upload-script -tn <tenant> -c <cloud> -spath <source_path> -scname <script>
```

m3 price

Description:

Describes the pricing policy

Usage: m3 price(price) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form (default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with --
json)

--policy-type,  -ptype,  *      The pricing policy type. Allowed values: [DEFAULT,
PROJECT, PERSONAL]

--region,       -r,      *      The region name

--from,         -from,         The start range date. Format "dd.mm.yyyy"

--inactive,     -N,            A flag. If specified the price model for inactive
resources will be returned

--shape,        -sh,           A shape name. Can be used to filter instance price model
by specified shape

--to,           -to,           The end range date. Format "dd.mm.yyyy"
```

Example:

```
    m3 price --policy-type <policy> --zone-name <zone_name> --from <dd.mm.yyyy> --to
<dd.mm.yyyy>
```

Related commands:

1. Cost and usage optimization report. Command sends the report only to email:

```
    m3 cost-usage-report -date <dd.mm.yyyy> -tn <tenant> -r <region> -rt
   <resource_type>
```

2. Gets a budgets billing report for a tenant:

```
    m3 budgets-report -tg <tenant_group> -y <year> -m <month>
```

3. Gets a total billing report for a tenant:

```
m3 total-report -tg <tenant_group>
```

4. Gets billing region types:

```
m3 billing-region-types
```

5. Gets cost object report for the specified tenant:

```
m3 cost-object-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

6. Gets hourly billing report for the specified tenant:

```
m3 hourly-report -tg <tenant_group>
```

7. Gets multitenant billing report:

```
m3 multitenant-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -rtype <report_type>
```

8. Gets resource billing report for the specified tenant:

```
m3 resource-report -tg <tenant_group>
```

9. Gets subtotal billing report for the specified tenant:

```
m3 subtotal-report -tg <tenant_group>
```

10. Gets untagged resource billing report:

```
m3 untagged-resource-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

11. This command is a single point of entry for report-related commands: ‘total-report’, ‘subtotal-report’, ‘resource-report’, ‘budgets-report’ and ‘hourly-report’:

```
m3 report -tg <tenant_group> -y <year> -m <month>
```

m3 create-image

Description:

Creates an image based on an existing instance

Usage: m3 create-image(cim) [parameters]

Parameters:

```
--help                      Shows the short help for the command

--full-help                 Shows the detailed help for the command

--verbose                   Controls the verbosity of command output

--json                      Returns the server response in the JSON format

--table                     Returns the server response in the table form (default)

--full                      Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                       Shows raw response from the server (can be used with --
json)

--description,  -d,    *    The description for the image

--instance-id,  -iid,  *    The ID of the instance

--name,         -n,    *    The image name.  Length: 3-63.

                            Restrictions for Google regions: lowercase alphanumeric
characters including hyphens if not on first or last place.

                            EPAM, Azure and AWS regions: alphanumeric characters
including .()[]-@_

--region,       -r,    *    The region name

--tenant,       -tn,   *    The tenant name
```

Example:

```
    m3 create-image --name <image_name> --instance-id <instance_id> --region <region>
--tenant <tenant_name> --description <"new image description">
```

Related commands:

1. Deletes an image created from a project instance:

```
    m3 delete-image -tn <tenant> -r <region> -imid <image_id>
```

2. Describes images:

```
    m3 describe-images -tn <tenant> -r <region>
```

3. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

4. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

5. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

m3 delete-image

Description:

Deletes an image created from a project instance

Usage: m3 delete-image(delim) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --json)

--image-id,  -imid,  *    The ID of the image to be deleted

--region,    -r,     *    The region name

--tenant,    -tn,    *    The tenant name
```

Example:

```
m3 delete-image --image-id <image_id> --region <region> --tenant <tenant_name>
```

Related commands:

1. Creates an image based on an existing instance:

```
m3 create-image -tn <tenant> -r <region> -iid <instance_id> -n <name> -d
<description>
```

2. Describes images:

```
m3 describe-images -tn <tenant> -r <region>
```

m3 delete-key

Description:

Deletes a SSH key from your account

Usage: m3 delete-key(delkey) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --json)

--key-name,  -kname,  *   The SSH key name of the key to be deleted
```

Example:

```
    m3 delete-key --key-name <key_name>
```

Related commands:

1. Creates a SSH key used to access instances without need to provide login credentials:

```
    m3 create-key -kname <key_name>
```

2. Describes your SSH keys existing for a specific tenant:

```
    m3 describe-keys -tn <tenant>
```

3. Imports public part of SSH keys for a specific cloud, region and tenant to Maestro:

```
    m3 import-key -kname <key_name> -fpath <file_path>
```

4. Manage your SSH keys. Adds or deletes an SSH key in a region:

```
    m3 manage-key -kname <key_name> -tn <tenant> -a <action> -c <cloud>
```

m3 describe-keys

Description:

Describes your SSH keys existing for a specific tenant

Usage: m3 describe-keys(dkey) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --json)

--tenant,    -tn,     *   The tenant name

--cloud,     -c,          The cloud to which the key is applied.

                          Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK]

--key-name,  -kname,      The SSH key name of the keypair to be described

--region,    -r,          The name of the region where the key is applied
```

Examples:

1. Describe all keypairs belonging to the tenant:

```
m3 describe-keys --region <region> --tenant <tenant>
```

2. Describe keypairs applied in a specific cloud and region:

```
m3 describe-keys --cloud <cloud> --region <region> --tenant <tenant>
```

Related commands:

1. Creates a SSH key used to access instances without need to provide login credentials:

```
m3 create-key -kname <key_name>
```

2. Deletes a SSH key from your account:

```
m3 delete-key -kname <key_name>
```

3. Imports public part of SSH keys for a specific cloud, region and tenant to Maestro:

```
m3 import-key -kname <key_name> -fpath <file_path>
```

4. Manage your SSH keys. Adds or deletes an SSH key in a region:

```
m3 manage-key -kname <key_name> -tn <tenant> -a <action> -c <cloud>
```

m3 import-key

Description:

Imports SSH keys for a specific cloud, region and tenant to Maestro

Usage: m3 import-key(ikey) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form (default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with --
json)

--file-path,    -fpath,  *      The path to the RSA public key file

--key-name,     -kname,  *      The SSH key name of the new key.

                                SSH key names must be 6-32 characters long, and include
only these characters - '0-9', 'a-z', 'A-Z', '-_'

--all-tenants,  -AT,            A flag. If specified the key pair for all tenants will be
imported

--cloud,        -c,             The cloud name where the key will be imported.

                                Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK]

--region,       -r,             The region name where the key will be imported

--tenant,       -tn,            The tenant name where the key will be imported
```

Example:

```
    m3 import-key --file-path <path> --key-name <keypair name> --cloud <cloud_name> -
-region <region_name> --tenant <tenant_name>
```

Related commands:

1. Creates a SSH key used to access instances without need to provide login credentials:

```
    m3 create-key -kname <key_name>
```

2. Deletes a SSH key from your account:

```
    m3 delete-key -kname <key_name>
```

3. Describes your SSH keys existing for a specific tenant:

```
m3 describe-keys -tn <tenant>
```

4. Manage your SSH keys. Adds or deletes an SSH key in a region:

```
m3 manage-key -kname <key_name> -tn <tenant> -a <action> -c <cloud>
```

m3 describe-events

Description:

Lists the events that took place in your virtual infrastructure

Usage: m3 describe-events(dev) [parameters]

Parameters:

```
--help                              Shows the short help for the command

--full-help                         Shows the detailed help for the command

--verbose                           Controls the verbosity of command output

--json                              Returns the server response in the JSON format

--table                             Returns the server response in the table form
(default)

--full                              Shows the full response from the server without
any specific formatting (can be used with --json)

--raw                               Shows raw response from the server (can be used
with --json)

--tenant,             -tn,      *   The tenant name

--cloud,              -c,           The cloud.

                                    Allowed values: [AWS, AZURE, ENTERPRISE, GOOGLE,
HARDWARE, NUTANIX, OPEN_STACK, VSPHERE]

--event-id,           -evid,        Event ID. Use it to see more details about a
specific event

--latest-event-date,  -evdate,      The latest event date. Format "dd.mm.yyyy"

--number-of-events,   -count,       The number of events to be displayed.

                                    Allowed values: 1-100. The default value: 10

--region,             -r,           The region name

--resource-id,        -rid,         The ID of the resource for which the events should
be retrieved. Required in case the RELATED search-type is specified

--search-type,        -stype,       Search type.

                                    Allowed values: [ALL(default), TENANT, SECURITY,
BILLING, MANAGEMENT, AZURE_BICEP, TERRAFORM, CLOUD_FORMATION, VIOLATION]
```

Examples:

1. Describes all events in a specific tenant:

```
    m3 describe-events --tenant <tenant_name> --cloud <cloud> --number-of-events
  <number> --search-type <type>
```

2. Describes events related to a specific resource:

```
    m3 describe-events --tenant <tenant_name> --cloud <cloud> --number-of-events
  <number> --search-type <type> --resource-id <resource> --region <region>
```

m3 upload-terraform-template-from-git

Description:

Uploads a Terraform template from Git

Usage: m3 upload-terraform-template-from-git(upltplgit) [parameters]

Parameters:

```
--help                                  Shows the short help for the command

--full-help                             Shows the detailed help for the command

--verbose                               Controls the verbosity of command output

--json                                  Returns the server response in the JSON format

--table                                 Returns the server response in the table form
(default)

--full                                  Shows the full response from the server without
any specific formatting (can be used with --json)

--raw                                   Shows raw response from the server (can be used
with --json)

--branch,             -b,          *    The name of a Git branch

--cloud,              -c,          *    The cloud.

                                        Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--git-url,            -url,        *    URL of the Git project with the template

--provider-type,      -ptype,      *    The Git service provider. Allowed values:
[GITHUB, GITLAB]

--template,           -tpl,        *    The name of the template that will be uploaded

--tenant,             -tn,         *    The tenant name

--terraform-version,  -terv,       *    The version of Terraform used in the template
should be indicated with the letter 'v'. For example v0.14.9

--token,              -tkn,        *    The personal access token to access the Git
project

--webhook,            -wh,         *    The Terraform action executed after receiving
the push-webhook. Allowed values: [NONE, AUTO_PLAN, AUTO_APPLY]

--approval-policy,    -aprpolicy,       The approval rule. Allowed values: [ALL, ONE]

--approver,           -apr,             Template Approvers. For several template
```

```
approvers, please specify each approver's email individually, separated by a comma
without a space. For example: email1,email2

--description,        -d,             The description for the Terraform template

--folder,             -f,             The path to the Terraform template in the Git
project

--multistack,         -M,             Flag. If specified the template can be used to
create multiple stacks

--variables,          -var,           Provide the variables along with their values.
The format should be:

                                      "key1:value1" for strings,
"key2:\"value2_1,value2_2\"" for lists and "key3:\"key3_1=value3_1,key3_2=value3_2\""
for objects.

                                      Simultaneous use is possible:
"key1:value1,key2:\"value2_1,value2_2\",key3:\"key3_1=value3_1,key3_2=value3_2\""

                                      Note: the example uses cmd syntax. If you use
bash or powershell, update the parameter value specification accordingly

--variables-file,     -vfile,         Specify the path to the JSON file that contains
the variables. Supported types: STRING, MAP, LIST, BOOL, NUMBER
```

Example:

```
m3 upload-terraform-template-from-git --branch <branch_name> --cloud <cloud> --git-
url <project_url> --storage <storage-type> --tenant <tenant>

                                    --template <name> --terraform-version <version> -
-token <personal_access_token> --webhook <action>

                                    --variables
"key1:\"value1_1,value1_2\",key2:value2,key3:\"key3_1=value3_1\"" OR --variables-file
<path_to_file>
```

Related commands:

1. Applies a Terraform template:

```
m3 apply-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

2. Deletes a Terraform template:

```
m3 delete-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

3. Describes Terraform template:

```
m3 describe-terraform-templates -c <cloud> -tn <tenant>
```

4. Describes a Terraform stack:

```
m3 describe-terraform-stacks -c <cloud> -tn <tenant>
```

5. Destroys resources related to a Terraform template or stack:

```
m3 destroy-terraform-stack -c <cloud> -tn <tenant> -tpl <template>
```

6. Exports a Terraform template as a signed URL:

```
m3 export-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

7. Lock a Terraform template to prevent any actions from other users:

```
m3 lock-terraform-template -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

8. Plans the selected Terraform template:

```
m3 plan-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

9. Prolong a Terraform template lock to prevent any actions from other users:

```
m3 prolong-terraform-template-lock -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

10. Unlock a Terraform template to allow actions from other users:

```
m3 unlock-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

11. Uploads a Terraform template:

```
m3 upload-terraform-template -fpath <file_path> -terv <terraform_version> -c
<cloud> -tn <tenant> -tpl <template>
```

m3 describe-terraform-templates

Description:

Describes Terraform and AWS_CLOUD_FORMATION templates general info

Usage: m3 describe-terraform-templates(dtpl) [parameters]

Parameters:

```
--help                  Shows the short help for the command

--full-help             Shows the detailed help for the command

--verbose               Controls the verbosity of command output

--json                  Returns the server response in the JSON format

--table                 Returns the server response in the table form (default)

--full                  Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                   Shows raw response from the server (can be used with --json)

--cloud,     -c,    *   The cloud.

                        Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--tenant,    -tn,   *   The tenant name

--template,  -tpl,      Names of templates.

                        Pass several values in the following format:
value1,value2,value3
```

Examples:

1. Describes Terraform templates existing on the tenant:

```
m3 describe-terraform-templates --cloud <cloud_name> --tenant <tenant_name>
```

2. Describes listed Terraform templates on the tenant:

```
m3 describe-terraform-templates --cloud <cloud_name> --tenant <tenant_name> --
template <name1>,<nameN>
```

Related commands:

1. Applies a Terraform template:

```
m3 apply-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

2. Deletes a Terraform template:

```
m3 delete-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

3. Describes a Terraform stack:

```
m3 describe-terraform-stacks -c <cloud> -tn <tenant>
```

4. Destroys resources related to a Terraform template or stack:

```
m3 destroy-terraform-stack -c <cloud> -tn <tenant> -tpl <template>
```

5. Exports a Terraform template as a signed URL:

```
m3 export-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

6. Lock a Terraform template to prevent any actions from other users:

```
m3 lock-terraform-template -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

7. Plans the selected Terraform template:

```
m3 plan-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

8. Prolong a Terraform template lock to prevent any actions from other users:

```
m3 prolong-terraform-template-lock -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

9. Unlock a Terraform template to allow actions from other users:

```
m3 unlock-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

10. Uploads a Terraform template from Git:

```
m3 upload-terraform-template-from-git -c <cloud> -tn <tenant> -tpl <template> -
url <git_url> -tkn <token> -b <branch> -wh <webhook> -ptype <provider_type> -terv
<terraform_version>
```

11. Uploads a Terraform template:

```
m3 upload-terraform-template -fpath <file_path> -terv <terraform_version> -c
<cloud> -tn <tenant> -tpl <template>
```

m3 describe-terraform-stacks

Description:

Describes a Terraform stack

Usage: m3 describe-terraform-stacks(dterstack) [parameters]

Parameters:

```
--help                  Shows the short help for the command

--full-help             Shows the detailed help for the command

--verbose               Controls the verbosity of command output

--json                  Returns the server response in the JSON format

--table                 Returns the server response in the table form (default)

--full                  Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                   Shows raw response from the server (can be used with --json)

--cloud,     -c,     *  The cloud.

                        Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--tenant,    -tn,    *  The tenant name

--stack-id,  -stid,     The list of stack identifiers. For several stacks, specify
the IDs one by one, separated by a comma without space (e.g., st00000001,st00000002)
```

Example:

```
    m3 describe-terraform-stacks --cloud <cloud> --tenant <tenant_name> --stack-id
<stack_id1>,<stack_idN>
```

Related commands:

1. Applies a Terraform template:

```
    m3 apply-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

2. Deletes a Terraform template:

```
    m3 delete-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

3. Describes Terraform template:

```
    m3 describe-terraform-templates -c <cloud> -tn <tenant>
```

4. Destroys resources related to a Terraform template or stack:

```
    m3 destroy-terraform-stack -c <cloud> -tn <tenant> -tpl <template>
```

5. Exports a Terraform template as a signed URL:

```
m3 export-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

6. Lock a Terraform template to prevent any actions from other users:

```
m3 lock-terraform-template -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

7. Plans the selected Terraform template:

```
m3 plan-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

8. Prolong a Terraform template lock to prevent any actions from other users:

```
m3 prolong-terraform-template-lock -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

9. Unlock a Terraform template to allow actions from other users:

```
m3 unlock-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

10. Uploads a Terraform template from Git:

```
m3 upload-terraform-template-from-git -c <cloud> -tn <tenant> -tpl <template> -
url <git_url> -tkn <token> -b <branch> -wh <webhook> -ptype <provider_type> -terv
<terraform_version>
```

11. Uploads a Terraform template:

```
m3 upload-terraform-template -fpath <file_path> -terv <terraform_version> -c
<cloud> -tn <tenant> -tpl <template>
```

m3 reboot-instances

Description:

Reboots the specified virtual instance

Usage: m3 reboot-instances(reboot) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --
json)

--instance-id,  -iid,  *  The IDs of the instances. For several instances, specify
the IDs one by one, separated by a comma without space (e.g.,
vmo00000001,vmo00000002)

--region,       -r,    *  The region name

--tenant,       -tn,   *  The tenant name
```

Example:

```
    m3 reboot-instances --instance-id <instance_id> --region <region_name> --tenant
<tenant_name>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
    m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
    m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Associate static IP with instance:

```
    m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

4. Creates instances of the specified configuration:

```
    m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

5. Deactivate specified VLAN on specified region in tenant:

```
    m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

6. Describe available VLANs on specified region in tenant:

```
m3 describe-vlans -tn <tenant> -r <region>
```

7. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

8. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

9. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

10. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

11. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

12. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

13. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

14. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

15. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 start-instances

Description:

Starts a virtual instance that has been previously stopped

Usage: m3 start-instances(start) [parameters]

Parameters:

```
--help                      Shows the short help for the command

--full-help                 Shows the detailed help for the command

--verbose                   Controls the verbosity of command output

--json                      Returns the server response in the JSON format

--table                     Returns the server response in the table form (default)

--full                      Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                       Shows raw response from the server (can be used with --
json)

--instance-id,  -iid,  *  The IDs of the instances. For several instances, specify
the IDs one by one, separated by a comma without space (e.g.,
vmo00000001,vmo00000002)

--region,       -r,    *  The region name

--tenant,       -tn,   *  The tenant name
```

Example:

```
    m3 start-instances --instance-id <instance_id> --tenant <tenant_name> --region
<region_name>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
    m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
    m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Associate static IP with instance:

```
    m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

4. Creates instances of the specified configuration:

```
    m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

5. Deactivate specified VLAN on specified region in tenant:

```
    m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

6. Describe available VLANs on specified region in tenant:

```
m3 describe-vlans -tn <tenant> -r <region>
```

7. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

8. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

9. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

10. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

11. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

12. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

13. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

14. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

15. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 manage-termination-protection

Description:

Manages termination protection for public cloud instances

Usage: m3 manage-termination-protection [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --
json)

--action,       -a,    *  Action type, allowed values: [ENABLE, DISABLE]

--instance-id,  -iid,  *  The ID of the instance

--region,       -r,    *  The region name

--tenant,       -tn,   *  The tenant name
```

Example:

```
m3 manage-termination-protection --tenant <tenant_name> --region <region_name> --
instance-id <instance_id> --action <action>
```

m3 delete-terraform-template

Description:

Deletes a Terraform template

Usage: m3 delete-terraform-template(deltpl) [parameters]

Parameters:

```
--help                  Shows the short help for the command

--full-help             Shows the detailed help for the command

--verbose               Controls the verbosity of command output

--json                  Returns the server response in the JSON format

--table                 Returns the server response in the table form (default)

--full                  Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                   Shows raw response from the server (can be used with --json)

--cloud,     -c,    *   The cloud.

                        Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--template,  -tpl,  *   The name of the template to be deleted

--tenant,    -tn,   *   The tenant name
```

Example:

```
m3 delete-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name>
```

Related commands:

1. Applies a Terraform template:

```
m3 apply-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

2. Describes Terraform template:

```
m3 describe-terraform-templates -c <cloud> -tn <tenant>
```

3. Describes a Terraform stack:

```
m3 describe-terraform-stacks -c <cloud> -tn <tenant>
```

4. Destroys resources related to a Terraform template or stack:

```
m3 destroy-terraform-stack -c <cloud> -tn <tenant> -tpl <template>
```

5. Exports a Terraform template as a signed URL:

```
m3 export-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

6. Lock a Terraform template to prevent any actions from other users:

```
 m3 lock-terraform-template -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

7. Plans the selected Terraform template:

```
 m3 plan-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

8. Prolong a Terraform template lock to prevent any actions from other users:

```
 m3 prolong-terraform-template-lock -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

9. Unlock a Terraform template to allow actions from other users:

```
 m3 unlock-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

10. Uploads a Terraform template from Git:

```
m3 upload-terraform-template-from-git -c <cloud> -tn <tenant> -tpl <template> -
url <git_url> -tkn <token> -b <branch> -wh <webhook> -ptype <provider_type> -terv
<terraform_version>
```

11. Uploads a Terraform template:

```
m3 upload-terraform-template -fpath <file_path> -terv <terraform_version> -c
<cloud> -tn <tenant> -tpl <template>
```

m3 plan-terraform-template

Description:

Plans the selected Terraform template

Usage: m3 plan-terraform-template(plantpl) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form
(default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with -
-json)

--cloud,           -c,      *   The cloud.

                                Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--template,        -tpl,    *   The name of the template to be planned

--tenant,          -tn,     *   The tenant name

--variables,       -var,        Provide the variables along with their values. The
format should be:

                                "key1:value1" for strings,
"key2:\"value2_1,value2_2\"" for lists and "key3:\"key3_1=value3_1,key3_2=value3_2\""
for objects.

                                Simultaneous use is possible:
"key1:value1,key2:\"value2_1,value2_2\",key3:\"key3_1=value3_1,key3_2=value3_2\""

                                Note: the example uses cmd syntax. If you use bash or
powershell, update the parameter value specification accordingly

--variables-file,  -vfile,      Specify the path to the JSON file that contains the
variables. Supported types: STRING, MAP, LIST, BOOL, NUMBER
```

Examples:

1. Plans a Terraform template:

```
m3 plan-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name>
```

2. Plans a Terraform template with a specific value for a string:

```
m3 plan-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name> --variable <key:value>
```

3. Plans a Terraform template with a specific value for a list:

```
m3 plan-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name> --variable <key:"value1,valueN">
```

4. Plans a Terraform template with a specific value for an object:

```
m3 plan-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name> --variable <key1:"key2=value2">
```

5. Plans a Terraform template with multiple values, which can be a combination of strings, lists, and objects:

```
m3 plan-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name> --variables
"key1:\"value1_1,value1_2\",key2:value2,key3:\"key3_1=value3_1\""
```

6. Plans a Terraform template with specific values in a JSON file. Supported types: STRING, LIST, MAP, NUMBER, BOOL:

```
m3 plan-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name> --variables-file <path_to_file>
```

Related commands:

1. Applies a Terraform template:

```
m3 apply-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

2. Deletes a Terraform template:

```
m3 delete-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

3. Describes Terraform template:

```
m3 describe-terraform-templates -c <cloud> -tn <tenant>
```

4. Describes a Terraform stack:

```
m3 describe-terraform-stacks -c <cloud> -tn <tenant>
```

5. Destroys resources related to a Terraform template or stack:

```
m3 destroy-terraform-stack -c <cloud> -tn <tenant> -tpl <template>
```

6. Exports a Terraform template as a signed URL:

```
m3 export-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

7. Lock a Terraform template to prevent any actions from other users:

```
m3 lock-terraform-template -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

8. Prolong a Terraform template lock to prevent any actions from other users:

```
m3 prolong-terraform-template-lock -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

9. Unlock a Terraform template to allow actions from other users:

```
m3 unlock-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

10. Uploads a Terraform template from Git:

```
m3 upload-terraform-template-from-git -c <cloud> -tn <tenant> -tpl <template> -
url <git_url> -tkn <token> -b <branch> -wh <webhook> -ptype <provider_type> -terv
<terraform_version>
```

11. Uploads a Terraform template:

```
m3 upload-terraform-template -fpath <file_path> -terv <terraform_version> -c
<cloud> -tn <tenant> -tpl <template>
```

m3 apply-terraform-template

Description:

Applies a Terraform template

Usage: m3 apply-terraform-template(applytpl) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form
(default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with -
-json)

--cloud,           -c,      *   The cloud.

                                Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--template,        -tpl,    *   The name of the template to be applied

--tenant,          -tn,     *   The tenant name

--variables,       -var,        Provide the variables along with their values. The
format should be:

                                "key1:value1" for strings,
"key2:\"value2_1,value2_2\"" for lists and "key3:\"key3_1=value3_1,key3_2=value3_2\""
for objects.

                                Simultaneous use is possible:
"key1:value1,key2:\"value2_1,value2_2\",key3:\"key3_1=value3_1,key3_2=value3_2\""

                                Note: the example uses cmd syntax. If you use bash or
powershell, update the parameter value specification accordingly

--variables-file,  -vfile,      Specify the path to the JSON file that contains the
variables. Supported types: STRING, MAP, LIST, BOOL, NUMBER
```

Examples:

1. Applies a Terraform template:

```
m3 apply-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name>
```

2. Applies a Terraform template with specific parameters for a string:

```
m3 apply-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name> --variable <key:value>
```

3. Applies a Terraform template with specific parameters for a list:

```
m3 apply-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name> --variable <key:"value1, valueN">
```

4. Applies a Terraform template with specific parameters for an object:

```
m3 apply-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name> --variable <key1:"key2=value2">
```

5. Applies a Terraform template with multiple values, which can be a combination of strings, lists, and objects:

```
m3 apply-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name> --variables
"key1:\"value1_1,value1_2\",key2:value2,key3:\"key3_1=value3_1\""
```

6. Applies a Terraform template with specific values in a JSON file. Supported types: STRING, LIST, MAP, NUMBER, BOOL:

```
m3 apply-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name> --variables-file <path_to_file>
```

Related commands:

1. Deletes a Terraform template:

```
m3 delete-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

2. Describes Terraform template:

```
m3 describe-terraform-templates -c <cloud> -tn <tenant>
```

3. Describes a Terraform stack:

```
m3 describe-terraform-stacks -c <cloud> -tn <tenant>
```

4. Destroys resources related to a Terraform template or stack:

```
m3 destroy-terraform-stack -c <cloud> -tn <tenant> -tpl <template>
```

5. Exports a Terraform template as a signed URL:

```
m3 export-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

6. Lock a Terraform template to prevent any actions from other users:

```
m3 lock-terraform-template -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

7. Plans the selected Terraform template:

```
m3 plan-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

8. Prolong a Terraform template lock to prevent any actions from other users:

```
m3 prolong-terraform-template-lock -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

9. Unlock a Terraform template to allow actions from other users:

```
m3 unlock-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

10. Uploads a Terraform template from Git:

```
m3 upload-terraform-template-from-git -c <cloud> -tn <tenant> -tpl <template> -
url <git_url> -tkn <token> -b <branch> -wh <webhook> -ptype <provider_type> -terv
<terraform_version>
```

11. Uploads a Terraform template:

```
m3 upload-terraform-template -fpath <file_path> -terv <terraform_version> -c
<cloud> -tn <tenant> -tpl <template>
```

m3 lock-terraform-template

Description:

Lock a Terraform template to prevent any actions from other users

Usage: m3 lock-terraform-template(locktpl) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --json)

--cloud,       -c,    *   The cloud.

                          Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--expiration,  -exp,  *   Expiration parameter which specifies time in hours. You can
specify the lock time within the range of 1-168 hours

--template,    -tpl,  *   The name of the Terraform template that is to be locked

--tenant,      -tn,   *   The tenant name
```

Example:

```
m3 lock-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name> --expiration <hours>
```

Related commands:

1. Applies a Terraform template:

```
m3 apply-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

2. Deletes a Terraform template:

```
m3 delete-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

3. Describes Terraform template:

```
m3 describe-terraform-templates -c <cloud> -tn <tenant>
```

4. Describes a Terraform stack:

```
m3 describe-terraform-stacks -c <cloud> -tn <tenant>
```

5. Destroys resources related to a Terraform template or stack:

```
m3 destroy-terraform-stack -c <cloud> -tn <tenant> -tpl <template>
```

6. Exports a Terraform template as a signed URL:

```
m3 export-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

7. Plans the selected Terraform template:

```
m3 plan-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

8. Prolong a Terraform template lock to prevent any actions from other users:

```
m3 prolong-terraform-template-lock -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

9. Unlock a Terraform template to allow actions from other users:

```
m3 unlock-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

10. Uploads a Terraform template from Git:

```
m3 upload-terraform-template-from-git -c <cloud> -tn <tenant> -tpl <template> -
url <git_url> -tkn <token> -b <branch> -wh <webhook> -ptype <provider_type> -terv
<terraform_version>
```

11. Uploads a Terraform template:

```
m3 upload-terraform-template -fpath <file_path> -terv <terraform_version> -c
<cloud> -tn <tenant> -tpl <template>
```

m3 prolong-terraform-template-lock

Description:

Prolong a Terraform template lock to prevent any actions from other users

Usage: m3 prolong-terraform-template-lock(ptplock) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --json)

--cloud,       -c,    *   The cloud.

                          Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--expiration,  -exp,  *   Expiration parameter which specifies time in hours. You can
prolong the locking time in the range of 1-168 hours

--template,    -tpl,  *   The name of the Terraform template for which the lock is to
be prolonged

--tenant,      -tn,   *   The tenant name
```

Example:

```
m3 prolong-terraform-template-lock --cloud <cloud_name> --template <name> --tenant
<tenant_name> --expiration <hours>
```

Related commands:

1. Applies a Terraform template:

```
m3 apply-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

2. Deletes a Terraform template:

```
m3 delete-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

3. Describes Terraform template:

```
m3 describe-terraform-templates -c <cloud> -tn <tenant>
```

4. Describes a Terraform stack:

```
m3 describe-terraform-stacks -c <cloud> -tn <tenant>
```

5. Destroys resources related to a Terraform template or stack:

```
m3 destroy-terraform-stack -c <cloud> -tn <tenant> -tpl <template>
```

6. Exports a Terraform template as a signed URL:

```
m3 export-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

7. Lock a Terraform template to prevent any actions from other users:

```
m3 lock-terraform-template -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

8. Plans the selected Terraform template:

```
m3 plan-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

9. Unlock a Terraform template to allow actions from other users:

```
m3 unlock-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

10. Uploads a Terraform template from Git:

```
m3 upload-terraform-template-from-git -c <cloud> -tn <tenant> -tpl <template> -
url <git_url> -tkn <token> -b <branch> -wh <webhook> -ptype <provider_type> -terv
<terraform_version>
```

11. Uploads a Terraform template:

```
m3 upload-terraform-template -fpath <file_path> -terv <terraform_version> -c
<cloud> -tn <tenant> -tpl <template>
```

m3 unlock-terraform-template

Description:

Unlock a Terraform template to allow actions from other users

Usage: m3 unlock-terraform-template(unlocktpl) [parameters]

Parameters:

```
--help                  Shows the short help for the command

--full-help             Shows the detailed help for the command

--verbose               Controls the verbosity of command output

--json                  Returns the server response in the JSON format

--table                 Returns the server response in the table form (default)

--full                  Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                   Shows raw response from the server (can be used with --json)

--cloud,     -c,    *   The cloud.

                        Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--template,  -tpl,  *   The name of the Terraform template that needs to be unlocked

--tenant,    -tn,   *   The tenant name
```

Example:

```
m3 unlock-terraform-template --cloud <cloud_name> --template <name> --tenant
<tenant_name> --expiration <hours>
```

Related commands:

1. Applies a Terraform template:

```
m3 apply-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

2. Deletes a Terraform template:

```
m3 delete-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

3. Describes Terraform template:

```
m3 describe-terraform-templates -c <cloud> -tn <tenant>
```

4. Describes a Terraform stack:

```
m3 describe-terraform-stacks -c <cloud> -tn <tenant>
```

5. Destroys resources related to a Terraform template or stack:

```
m3 destroy-terraform-stack -c <cloud> -tn <tenant> -tpl <template>
```

6. Exports a Terraform template as a signed URL:

```
m3 export-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

7. Lock a Terraform template to prevent any actions from other users:

```
m3 lock-terraform-template -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

8. Plans the selected Terraform template:

```
m3 plan-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

9. Prolong a Terraform template lock to prevent any actions from other users:

```
m3 prolong-terraform-template-lock -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

10. Uploads a Terraform template from Git:

```
m3 upload-terraform-template-from-git -c <cloud> -tn <tenant> -tpl <template> -
url <git_url> -tkn <token> -b <branch> -wh <webhook> -ptype <provider_type> -terv
<terraform_version>
```

11. Uploads a Terraform template:

```
m3 upload-terraform-template -fpath <file_path> -terv <terraform_version> -c
<cloud> -tn <tenant> -tpl <template>
```

m3 destroy-terraform-stack

Description:

Destroys resources related to a Terraform template or stack

Usage: m3 destroy-terraform-stack(dtrterstack) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --json)

--cloud,     -c,     *    The cloud.

                          Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--template,  -tpl,   *    The name of the template to be destroyed

--tenant,    -tn,    *    The tenant name

--stack-id,  -stid,       The ID of the stack which resources will be destroyed
```

Example:

```
    m3 destroy-terraform-stack --cloud <cloud_name> --template <name> --tenant
<tenant_name> --template <name>
```

Related commands:

1. Applies a Terraform template:

```
    m3 apply-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

2. Deletes a Terraform template:

```
    m3 delete-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

3. Describes Terraform template:

```
    m3 describe-terraform-templates -c <cloud> -tn <tenant>
```

4. Describes a Terraform stack:

```
    m3 describe-terraform-stacks -c <cloud> -tn <tenant>
```

5. Exports a Terraform template as a signed URL:

```
m3 export-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

6. Lock a Terraform template to prevent any actions from other users:

```
m3 lock-terraform-template -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

7. Plans the selected Terraform template:

```
m3 plan-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

8. Prolong a Terraform template lock to prevent any actions from other users:

```
m3 prolong-terraform-template-lock -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

9. Unlock a Terraform template to allow actions from other users:

```
m3 unlock-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

10. Uploads a Terraform template from Git:

```
m3 upload-terraform-template-from-git -c <cloud> -tn <tenant> -tpl <template> -
url <git_url> -tkn <token> -b <branch> -wh <webhook> -ptype <provider_type> -terv
<terraform_version>
```

11. Uploads a Terraform template:

```
m3 upload-terraform-template -fpath <file_path> -terv <terraform_version> -c
<cloud> -tn <tenant> -tpl <template>
```

m3 create-instance-quota

Description:

Sets up a number of instances allowed for creation on a specific tenant within a specific interval

Usage: m3 create-instance-quota(cinquota) [parameters]

Parameters:

```
--help                                      Shows the short help for the command

--full-help                                 Shows the detailed help for the command

--verbose                                   Controls the verbosity of command output

--json                                      Returns the server response in the JSON
format

--table                                     Returns the server response in the table
form (default)

--full                                      Shows the full response from the server
without any specific formatting (can be used with --json)

--raw                                       Shows raw response from the server (can be
used with --json)

--creation-interval-hours,  -h,       *  The period in hours during which the
specified amount of instances can be created

--instance-amount,          -amount,  *  The number of instances one can create
during creation interval

--region,                   -r,       *  The region name

--tenant,                   -tn,      *  The tenant name
```

Example:

```
    m3 create-instance-quota --tenant <tenant_name> --region <region_name> --
instance-amount <instances_number> --creation-interval-hours <hours>
```

Related commands:

1. Deletes the limitation for the number of instances allowed for creation on a specific tenant within a specific interval:

```
    m3 delete-instance-quota -tn <tenant> -r <region>
```

2. Describes the limitation for the number of instances allowed for creation on a specific tenant within a specific interval:

```
    m3 describe-instance-quota -tn <tenant> -r <region>
```

3. Sets up an amount and size of storages allowed for creation on a specific tenant within a specific interval:

```
m3 create-storage-quota -tn <tenant> -r <region> -storsize <storage_max_size> -h
<creation_interval_hours> -amount <storage_amount>
```

m3 describe-instance-quota

Description:

Describes the limitation for the number of instances allowed for creation on a specific tenant within a specific interval

Usage: m3 describe-instance-quota(dinquota) [parameters]

Parameters:

```
--help                Shows the short help for the command

--full-help           Shows the detailed help for the command

--verbose             Controls the verbosity of command output

--json                Returns the server response in the JSON format

--table               Returns the server response in the table form (default)

--full                Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                 Shows raw response from the server (can be used with --json)

--region,    -r,   *  The region name

--tenant,    -tn,  *  The tenant name
```

Example:

```
    m3 describe-instance-quota --region <region_name> --tenant <name>
```

Related commands:

1. Deletes the limitation for the number of instances allowed for creation on a specific tenant within a specific interval:

```
    m3 delete-instance-quota -tn <tenant> -r <region>
```

2. Describes the limitation for the number and size of storages allowed for creation on a specific tenant within a specific interval:

```
    m3 describe-storage-quota -tn <tenant> -r <region>
```

3. Sets up a number of instances allowed for creation on a specific tenant within a specific interval:

```
    m3 create-instance-quota -tn <tenant> -r <region> -h <creation_interval_hours> -
    amount <instance_amount>
```

m3 delete-instance-quota

Description:

Deletes the limitation for the number of instances allowed for creation on a specific tenant within a specific interval

Usage: m3 delete-instance-quota(delinquota) [parameters]

Parameters:

```
--help                Shows the short help for the command

--full-help           Shows the detailed help for the command

--verbose             Controls the verbosity of command output

--json                Returns the server response in the JSON format

--table               Returns the server response in the table form (default)

--full                Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                 Shows raw response from the server (can be used with --json)

--region,    -r,   *  The region name

--tenant,    -tn,  *  The tenant name
```

Example:

```
    m3 delete-instance-quota --tenant <tenant_name> --region <region_name>
```

Related commands:

1. Describes the limitation for the number of instances allowed for creation on a specific tenant within a specific interval:

```
    m3 describe-instance-quota -tn <tenant> -r <region>
```

2. Sets up a number of instances allowed for creation on a specific tenant within a specific interval:

```
    m3 create-instance-quota -tn <tenant> -r <region> -h <creation_interval_hours> -
amount <instance_amount>
```

m3 create-storage-quota

Description:

Sets up an amount and size of storages allowed for creation on a specific tenant within a specific interval

Usage: m3 create-storage-quota(cstorquota) [parameters]

Parameters:

```
--help                                      Shows the short help for the command

--full-help                                 Shows the detailed help for the command

--verbose                                   Controls the verbosity of command output

--json                                      Returns the server response in the JSON
format

--table                                     Returns the server response in the table
form (default)

--full                                      Shows the full response from the server
without any specific formatting (can be used with --json)

--raw                                       Shows raw response from the server (can be
used with --json)

--creation-interval-hours,  -h,         *   The period in hours during which the
specified amount of storages can be created

--region,                   -r,         *   The region name

--storage-amount,           -amount,    *   The number of storages one can create
during creation interval

--storage-max-size,         -storsize,  *   The maximum size of a storage at creation,
in GB

--tenant,                   -tn,        *   The tenant name
```

Example:

```
    m3 create-storage-quota --tenant <tenant_name> --region <region_name> --storage-
amount <storage_number> --creation-interval-hours <hours> --storage-max-size
<size_GB>
```

Related commands:

1. Deletes the limitations for an amount and size of storages allowed for creation on a specific tenant within a specific interval:

```
    m3 delete-storage-quota -tn <tenant> -r <region>
```

2. Describes the limitation for the number and size of storages allowed for creation on a specific tenant within a specific interval:

```
m3 describe-storage-quota -tn <tenant> -r <region>
```

3. Sets up a number of instances allowed for creation on a specific tenant within a specific interval:

```
m3 create-instance-quota -tn <tenant> -r <region> -h <creation_interval_hours> -
amount <instance_amount>
```

m3 describe-storage-quota

Description:

Describes the limitation for the number and size of storages allowed for creation on a specific tenant within a specific interval

Usage: m3 describe-storage-quota(dstorquota) [parameters]

Parameters:

```
--help                Shows the short help for the command

--full-help           Shows the detailed help for the command

--verbose             Controls the verbosity of command output

--json                Returns the server response in the JSON format

--table               Returns the server response in the table form (default)

--full                Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                 Shows raw response from the server (can be used with --json)

--region,    -r,   *  The region name

--tenant,    -tn,  *  The tenant name
```

Example:

```
    m3 describe-storage-quota --region <region_name> --tenant <name>
```

Related commands:

1. Deletes the limitations for an amount and size of storages allowed for creation on a specific tenant within a specific interval:

```
    m3 delete-storage-quota -tn <tenant> -r <region>
```

2. Describes the limitation for the number of instances allowed for creation on a specific tenant within a specific interval:

```
    m3 describe-instance-quota -tn <tenant> -r <region>
```

3. Sets up an amount and size of storages allowed for creation on a specific tenant within a specific interval:

```
    m3 create-storage-quota -tn <tenant> -r <region> -storsize <storage_max_size> -h
   <creation_interval_hours> -amount <storage_amount>
```

m3 delete-storage-quota

Description:

Deletes the limitations for an amount and size of storages allowed for creation on a specific tenant within a specific interval

Usage: m3 delete-storage-quota(delstorquota) [parameters]

Parameters:

```
--help                Shows the short help for the command

--full-help           Shows the detailed help for the command

--verbose             Controls the verbosity of command output

--json                Returns the server response in the JSON format

--table               Returns the server response in the table form (default)

--full                Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                 Shows raw response from the server (can be used with --json)

--region,    -r,   *  The region name

--tenant,    -tn,  *  The tenant name
```

Example:

```
    m3 delete-storage-quota  --tenant <tenant_name> --region <region_name>
```

Related commands:

1. Describes the limitation for the number and size of storages allowed for creation on a specific tenant within a specific interval:

```
    m3 describe-storage-quota -tn <tenant> -r <region>
```

2. Sets up an amount and size of storages allowed for creation on a specific tenant within a specific interval:

```
    m3 create-storage-quota -tn <tenant> -r <region> -storsize <storage_max_size> -h
   <creation_interval_hours> -amount <storage_amount>
```

m3 create-key

Description:

Creates a SSH key used to access instances without need to provide login credentials

Usage: m3 create-key(ckey) [parameters]

Parameters:

```
--help                          Shows the short help for the command

--full-help                     Shows the detailed help for the command

--verbose                       Controls the verbosity of command output

--json                          Returns the server response in the JSON format

--table                         Returns the server response in the table form (default)

--full                          Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                           Shows raw response from the server (can be used with --
json)

--key-name,      -kname,  *     The SSH key name of the new key.

                                SSH key names must be 6-32 characters long, and include
only these characters - '0-9', 'a-z', 'A-Z', '-_'

--all-tenants,   -AT,           A flag. If specified the key pair for all tenants will
be created

--cloud,         -c,            The cloud name where the key will be applied.

                                Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK]

--region,        -r,            The region name where the key will be applied

--save-to-path,  -path,         The path to the directory where the new SSH keys will be
saved

--tenant,        -tn,           The tenant name where the key will be applied
```

Example:

```
   m3 create-key --key-name <key_name> --cloud <cloud> --region <region> --tenant
<tenant_name>
```

Related commands:

1. Deletes a SSH key from your account:

```
    m3 delete-key -kname <key_name>
```

2. Describes your SSH keys existing for a specific tenant:

```
m3 describe-keys -tn <tenant>
```

3. Imports public part of SSH keys for a specific cloud, region and tenant to Maestro:

```
m3 import-key -kname <key_name> -fpath <file_path>
```

4. Manage your SSH keys. Adds or deletes an SSH key in a region:

```
m3 manage-key -kname <key_name> -tn <tenant> -a <action> -c <cloud>
```

m3 manage-key

Description:

Manage your SSH keys. Adds or deletes an SSH key in a region

Usage: m3 manage-key(mkey) [parameters]

Parameters:

```
--help                        Shows the short help for the command

--full-help                   Shows the detailed help for the command

--verbose                     Controls the verbosity of command output

--json                        Returns the server response in the JSON format

--table                       Returns the server response in the table form (default)

--full                        Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                         Shows raw response from the server (can be used with --
json)

--action,       -a,      *    An action to be done with a keypair. Allowed values:
[ADD, REMOVE]

--cloud,        -c,      *    The cloud. Allowed_values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK]

--key-name,     -kname,  *    The SSH key name

--tenant,       -tn,     *    The tenant name

--all-regions,  -R,           A flag. If specified, the key will be updated in all
regions of the cloud provider

--region,       -r,           The region name. Required if the all-region parameter is
not specified. For several regions, specify the regions one by one, separated by a
comma without space (e.g., value1,value2)
```

Example:

```
    m3 manage-key--cloud <cloud_name> --key-name <name> --region <region_name> --
action <action> --tenant <tenant_name>
```

Related commands:

1. Creates a SSH key used to access instances without need to provide login credentials:

```
    m3 create-key -kname <key_name>
```

2. Deletes a SSH key from your account:

```
    m3 delete-key -kname <key_name>
```

3. Describes your SSH keys existing for a specific tenant:

```
m3 describe-keys -tn <tenant>
```

4. Imports public part of SSH keys for a specific cloud, region and tenant to Maestro:

```
m3 import-key -kname <key_name> -fpath <file_path>
```

m3 describe-tenants

Description:

Describes the tenants available for the user

Usage: m3 describe-tenants(dtn) [parameters]

Parameters:

```
--help                Shows the short help for the command

--full-help           Shows the detailed help for the command

--verbose             Controls the verbosity of command output

--json                Returns the server response in the JSON format

--table               Returns the server response in the table form (default)

--full                Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                 Shows raw response from the server (can be used with --json)

--all,       -A,      A flag. If specified active and inactive tenants including
hidden regions will be displayed

--cloud,     -c,      The cloud.

                      Allowed values: [AWS, AZURE, ENTERPRISE, GOOGLE, HARDWARE,
NUTANIX, OPEN_STACK, VSPHERE, HYPERV, VMWARE, WORKSPACE]

--hidden,    -H,      A flag. If specified the hidden regions will be displayed

--inactive,  -N,      A flag. If specified only the inactive tenants will be displayed

--tenant,    -tn,     A list of tenants. Pass several values in the following format:
value1,value2,value3
```

Examples:

1. Outputs the list of all tenants in the cloud:

```
m3 describe-tenants --cloud <cloud_name>
```

2. Outputs the list of inactive tenants in the cloud:

```
m3 describe-tenants --cloud <cloud_name> --inactive
```

3. Outputs the description of particular tenants:

```
m3 describe-tenants --cloud <cloud_name> --tenant-list
<tenant_name1>,<tenant_nameN>
```

Related commands:

1. Describes images:

```
m3 describe-images -tn <tenant> -r <region>
```

2. Describes the regions available for a tenant in the specified cloud:

```
m3 describe-regions -tn <tenant> -c <cloud>
```

3. Describes the shapes available for your tenant:

```
m3 describe-shapes -tn <tenant> -c <cloud> -r <region>
```

m3 describe-regions

Description:

Describes the regions available for a tenant in the specified cloud

Usage: m3 describe-regions(dr) [parameters]

Parameters:

```
--help                        Shows the short help for the command

--full-help                   Shows the detailed help for the command

--verbose                     Controls the verbosity of command output

--json                        Returns the server response in the JSON format

--table                       Returns the server response in the table form (default)

--full                        Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                         Shows raw response from the server (can be used with --
json)

--cloud,            -c,   *   The cloud.

                              Allowed values: [AWS, AZURE, ENTERPRISE, GOOGLE,
HARDWARE, NUTANIX, OPEN_STACK, VSPHERE]

--tenant,           -tn,  *   The tenant name

--inactive,         -N,       A flag. If specified, the inactive regions are shown

--include-hidden,   -H,       A flag. If specified, the hidden regions are shown
```

Example:

```
    m3 describe-regions --instance-id <instance_id> --tenant <tenant_name> --region
<region_name>
```

Related commands:

1. Describes images:

```
    m3 describe-images -tn <tenant> -r <region>
```

2. Describes the shapes available for your tenant:

```
    m3 describe-shapes -tn <tenant> -c <cloud> -r <region>
```

3. Describes the tenants available for the user:

```
    m3 describe-tenants
```

m3 describe-shapes

Description:

Describes the shapes available for your tenant

Usage: m3 describe-shapes(dsh) [parameters]

Parameters:

```
--help                      Shows the short help for the command

--full-help                 Shows the detailed help for the command

--verbose                   Controls the verbosity of command output

--json                      Returns the server response in the JSON format

--table                     Returns the server response in the table form (default)

--full                      Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                       Shows raw response from the server (can be used with --
json)

--cloud,          -c,   *   The cloud.

                            Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--region,         -r,   *   The region name

--tenant,         -tn,  *   The tenant name

--native-shapes,  -ns,      Flag. If specified, shows cloud-native instance types
instead of Maestro3 standardized shapes
```

Example:

```
m3 describe-shapes --cloud <cloud> --tenant <tenant_name> --region <region>
```

Related commands:

1. Describes images:

```
m3 describe-images -tn <tenant> -r <region>
```

2. Describes the regions available for a tenant in the specified cloud:

```
m3 describe-regions -tn <tenant> -c <cloud>
```

3. Describes the tenants available for the user:

```
m3 describe-tenants
```

m3 add-schedule-instances

Description:

Adds an existing schedule to one or several instances

Usage: m3 add-schedule-instances(addschin) [parameters]

Parameters:

```
--help                      Shows the short help for the command

--full-help                 Shows the detailed help for the command

--verbose                   Controls the verbosity of command output

--json                      Returns the server response in the JSON format

--table                     Returns the server response in the table form (default)

--full                      Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                       Shows raw response from the server (can be used with --
json)

--cloud,         -c,    *   The cloud.

                            Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--instance-id,   -iid,  *   The IDs of the instances.

                            To set the schedule for several instances, specify the IDs
one by one, separated by a comma without space (e.g., vmo00000001,vmo00000002)

--name,          -n,    *   The name of the schedule

--region,        -r,    *   The region name

--tenant,        -tn,   *   The tenant name
```

Examples:

1. Adds a schedule for a single instance:

```
m3 add-schedule-instances --cloud <cloud> --region <region> --tenant
<tenant_name> --instance-id <instance_id>,<instance_idN> -dn <schedule_name>
```

2. Adds a schedule for multiple instances:

```
 m3 add-schedule-instances --cloud <cloud> --region <region> --tenant
<tenant_name> --instance-id <instance_id>,<instance_idN> -dn <schedule_name>
```

Related commands:

1. Creates a new schedule for automatic instance state management:

```
m3 create-schedule -r <region> -tn <tenant> -n <name> -cron <cron> -d
<description> -a <action> -schtype <schedule_type> -c <cloud>
```

2. Deletes a schedule from one or several instances:

```
m3 delete-schedule-instances -tn <tenant> -c <cloud> -r <region> -n <name> -iid
<instance_id1>,<instance_idN>
```

3. Deletes a schedule from your tenants schedule library:

```
m3 delete-schedule -r <region> -tn <tenant> -n <name>
```

4. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

5. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

6. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

7. Describes the schedules set to instances in your tenant:

```
m3 describe-schedules -tn <tenant> -c <cloud>
```

m3 delete-schedule-instances

Description:

Deletes a schedule from one or several instances

Usage: m3 delete-schedule-instances(delschin) [parameters]

Parameters:

```
--help                      Shows the short help for the command

--full-help                 Shows the detailed help for the command

--verbose                   Controls the verbosity of command output

--json                      Returns the server response in the JSON format

--table                     Returns the server response in the table form (default)

--full                      Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                       Shows raw response from the server (can be used with --
json)

--cloud,         -c,    *   The cloud.

                            Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--instance-id,   -iid,  *   The IDs of the instances.

                            To delete the schedule from several instances, specify the
IDs one by one, separated by a comma without space (e.g., vmo00000001,vmo00000002)

--name,          -n,    *   The name of the schedule

--region,        -r,    *   The region name

--tenant,        -tn,   *   The tenant name
```

Example:

```
    m3 delete-schedule-instances --cloud <cloud> --region<region> --instance-id
<instance_id1>,<instance_idN> -dn <schedule_name> --tenant <tenant_name>
```

Related commands:

1. Adds an existing schedule to one or several instances:

```
    m3 add-schedule-instances -tn <tenant> -c <cloud> -r <region> -n <name> -iid
   <instance_id1>,<instance_idN>
```

2. Creates a new schedule for automatic instance state management:

```
    m3 create-schedule -r <region> -tn <tenant> -n <name> -cron <cron> -d
   <description> -a <action> -schtype <schedule_type> -c <cloud>
```

3. Deletes a schedule from your tenants schedule library:

```
m3 delete-schedule -r <region> -tn <tenant> -n <name>
```

4. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

5. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

6. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

7. Describes the schedules set to instances in your tenant:

```
m3 describe-schedules -tn <tenant> -c <cloud>
```

m3 delete-tags

Description:

Deletes one or several tags from an instance in public or private cloud

Usage: m3 delete-tags(deltag) [parameters]

Parameters:

```
--help                              Shows the short help for the command

--full-help                         Shows the detailed help for the command

--verbose                           Controls the verbosity of command output

--json                              Returns the server response in the JSON format

--table                             Returns the server response in the table form
(default)

--full                              Shows the full response from the server without
any specific formatting (can be used with --json)

--raw                               Shows raw response from the server (can be used
with --json)

--cloud,              -c,       *   The cloud.

                                    Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--instance-id,        -iid,     *   The ID of the instance

--region,             -r,       *   The region name

--tag-key,            -key,     *   Tag-keys. Pass several keys of tags in the
following format: key1,key2,key3

--tenant,             -tn,      *   The tenant name

--availability-zone,  -az,          The availability zone name (for Google)

--resource-group,     -rgname,      The resource group name (for Azure)
```

Examples:

1. Updates instance tags:

```
m3 delete-tags --cloud <cloud_name> --instance-id <instance_id> --tenant
<tenant_name> --region <region_name> --tag <tag_names>
```

2. Updates instance tags in a public cloud (Google) in a specific availability zone:

```
m3 delete-tags --cloud <cloud_name> --instance-id <instance_id> --tenant
<tenant_name> --region <region_name> --tag <tag_names> --availability-zone
<zone_name>
```

3. Updates instance tags in a public cloud (Azure) in a specific resource group:

```
 m3 delete-tags --cloud <cloud_name> --instance-id <instance_id> --tenant
<tenant_name> --region <region_name> --tag <tag_names> --resource-group
<resource_group_name>
```

Related commands:

1. Describes instance tags. Applicable both for public and private clouds:

```
 m3 describe-tags -tn <tenant> -r <region> -c <cloud> -iid
<instance_id1>,<instance_idN>
```

2. Sets tag for the instance. Applicable both for public and private clouds:

```
 m3 set-tags -tn <tenant> -r <region> -c <cloud> -iid
<instance_id1>,<instance_idN> -tag <tag>
```

m3 describe-tags

Description:

Describes tags on an instance in public or private cloud

Usage: m3 describe-tags(dtag) [parameters]

Parameters:

```
--help                              Shows the short help for the command

--full-help                         Shows the detailed help for the command

--verbose                           Controls the verbosity of command output

--json                              Returns the server response in the JSON format

--table                             Returns the server response in the table form
(default)

--full                              Shows the full response from the server without
any specific formatting (can be used with --json)

--raw                               Shows raw response from the server (can be used
with --json)

--cloud,              -c,       *   The cloud.

                                    Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--instance-id,        -iid,     *   The ID of the instance

--region,             -r,       *   The region name

--tenant,             -tn,      *   The tenant name

--availability-zone,  -az,          The availability zone name (for Google)

--resource-group,     -rgname,      The resource group name (for Azure)
```

Examples:

1. Describes instance tags:

   m3 describe-tags –cloud –instance-id –tenant –region

2. Describes instance tags in a public cloud (Google) in a specific availability zone:

   m3 describe-tags –cloud –instance-id –tenant –region –availability-zone

3. Describes instance tags in a public cloud (Azure) in a specific resource group:

   m3 describe-tags –cloud –instance-id –tenant –region –resource-group

Related commands:

1. Deletes tags. Applicable both for public and private clouds:

```
m3 delete-tags -tn <tenant> -r <region> -c <cloud> -iid <instance_id> -key
<tag_key1>,<tag_keyN>
```

2. Sets tag for the instance. Applicable both for public and private clouds:

```
m3 set-tags -tn <tenant> -r <region> -c <cloud> -iid
<instance_id1>,<instance_idN> -tag <tag>
```

m3 set-tags

Description:

Updates instance tags. Applicable in public and private clouds

Usage: m3 set-tags(stag) [parameters]

Parameters:

```
--help                              Shows the short help for the command

--full-help                         Shows the detailed help for the command

--verbose                           Controls the verbosity of command output

--json                              Returns the server response in the JSON format

--table                             Returns the server response in the table form
(default)

--full                              Shows the full response from the server without
any specific formatting (can be used with --json)

--raw                               Shows raw response from the server (can be used
with --json)

--cloud,              -c,       *   The cloud.

                                    Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--instance-id,        -iid,     *   The ID of the instance

--region,             -r,       *   The region name

--tag,                -tag,     *   Tags. Pass several values in the following format:
key1:val1,key2:val2,key3:val3

--tenant,             -tn,      *   The tenant name

--availability-zone,  -az,          The availability zone name (for Google)

--overwrite,          -O,           Flag. If specified, the existing tags will be
replaced with the passed

--resource-group,     -rgname,      The resource group name (for Azure)

--storage-id,         -storid,      Storage IDs. Pass several values in the following
format: storage1,storage2,storage3
```

Examples:

1. Updates instance tags:

```
m3 set-tags --cloud <cloud_name> --instance-id <instance_id> --tenant
<tenant_name> --region <region_name> --tag <tag_names>
```

2. Updates instance tags in a public cloud (Google) in a specific availability zone:

```
m3 set-tags --cloud <cloud_name> --instance-id <instance_id> --tenant
<tenant_name> --region <region_name> --tag <tag_names> --availability-zone
<zone_name>
```

3. Updates instance tags in a public cloud (Azure) in a specific resource group:

```
m3 set-tags --cloud <cloud_name> --instance-id <instance_id> --tenant
<tenant_name> --region <region_name> --tag <tag_names> --resource-group
<resource_group_name>
```

4. Updates tag for the instance with a specified storage (only for private cloud):

```
m3 set-tags --cloud <cloud_name> --instance-id <instance_id> --tenant
<tenant_name> --region <region_name> --tag <tag_names> --storage-id
<storage_id1>,<storage_idN>
```

Related commands:

1. Deletes tags. Applicable both for public and private clouds:

```
m3 delete-tags -tn <tenant> -r <region> -c <cloud> -iid <instance_id> -key
<tag_key1>,<tag_keyN>
```

2. Describes instance tags. Applicable both for public and private clouds:

```
m3 describe-tags -tn <tenant> -r <region> -c <cloud> -iid
<instance_id1>,<instance_idN>
```

m3 upload-terraform-template

Description:

Uploads a Terraform template

Usage: m3 upload-terraform-template(upltpl) [parameters]

Parameters:

```
--help                                  Shows the short help for the command

--full-help                             Shows the detailed help for the command

--verbose                               Controls the verbosity of command output

--json                                  Returns the server response in the JSON format

--table                                 Returns the server response in the table form
(default)

--full                                  Shows the full response from the server without
any specific formatting (can be used with --json)

--raw                                   Shows raw response from the server (can be used
with --json)

--cloud,              -c,          *    The cloud.

                                        Allowed values: [AWS, AZURE, GOOGLE, NUTANIX,
OPEN_STACK, VSPHERE]

--file-path,          -fpath,      *    Path to the file that will be used as a source
of the template

--template,           -tpl,        *    The name of the template that will be uploaded

--tenant,             -tn,         *    The tenant name

--terraform-version,  -terv,       *    The version of Terraform to use. The version of
template should be indicated with the letter 'v'. For example v0.14.9

--approval-policy,    -aprpolicy,       The approval rule. Allowed values: [ALL, ONE].
If specified, template will be send to request the technical approval of your
Terraform template from other persons

                                        ALL: All approvals required

                                        ONE: At least one approval required

--approver,           -apr,             Template Approvers. For several template
approvers, please specify each approver's email individually, separated by a comma
without a space. For example: email1,email2

--description,        -d,               The description for the Terraform template.
```

```
Describe the purpose of your template or provide other relevant information

--multistack,          -M,             A flag. If specified the template can be used
to create multiple stacks

--variables,           -var,           Provide the variables along with their values.
The format should be:

                                       "key1:value1" for strings,
"key2:\"value2_1,value2_2\"" for lists and "key3:\"key3_1=value3_1,key3_2=value3_2\""
for objects.

                                       Simultaneous use is possible:
"key1:value1,key2:\"value2_1,value2_2\",key3:\"key3_1=value3_1,key3_2=value3_2\""

                                       Note: the example uses cmd syntax. If you use
bash or powershell, update the parameter value specification accordingly

--variables-file,      -vfile,         Specify the path to the JSON file that contains
the variables. Supported types: STRING, MAP, LIST, BOOL, NUMBER
```

Examples:

```
    m3 upload-terraform-template --source-path <path> --terraform-version <version> -
-cloud <cloud> --tenant <tenant_name> --template <name>

                                  --variables
"key1:\"value1_1,value1_2\",key2:value2,key3:\"key3_1=value3_1\"" OR --variables-file
<path_to_file>
```

Related commands:

1. Applies a Terraform template:

```
    m3 apply-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

2. Deletes a Terraform template:

```
    m3 delete-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

3. Describes Terraform template:

```
    m3 describe-terraform-templates -c <cloud> -tn <tenant>
```

4. Describes a Terraform stack:

```
    m3 describe-terraform-stacks -c <cloud> -tn <tenant>
```

5. Destroys resources related to a Terraform template or stack:

```
    m3 destroy-terraform-stack -c <cloud> -tn <tenant> -tpl <template>
```

6. Exports a Terraform template as a signed URL:

```
    m3 export-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

7. Lock a Terraform template to prevent any actions from other users:

```
    m3 lock-terraform-template -c <cloud> -tn <tenant> -tpl <template> -exp
   <expiration>
```

8. Plans the selected Terraform template:

```
m3 plan-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

9. Prolong a Terraform template lock to prevent any actions from other users:

```
m3 prolong-terraform-template-lock -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

10. Unlock a Terraform template to allow actions from other users:

```
m3 unlock-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

11. Uploads a Terraform template from Git:

```
m3 upload-terraform-template-from-git -c <cloud> -tn <tenant> -tpl <template> -
url <git_url> -tkn <token> -b <branch> -wh <webhook> -ptype <provider_type> -terv
<terraform_version>
```

m3 export-terraform-template

Description:

Exports a Terraform template as a signed URL

Usage: m3 export-terraform-template(exptpl) [parameters]

Parameters:

```
--help                  Shows the short help for the command

--full-help             Shows the detailed help for the command

--verbose               Controls the verbosity of command output

--json                  Returns the server response in the JSON format

--table                 Returns the server response in the table form (default)

--full                  Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                   Shows raw response from the server (can be used with --json)

--cloud,     -c,    *   The cloud.

                        Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--template,  -tpl,  *   The name of the template to be exported

--tenant,    -tn,   *   The tenant name
```

Example:

```
    m3 export-terraform-template --cloud <cloud> --tenant <tenant_name> --template
<name>
```

Related commands:

1. Applies a Terraform template:

```
    m3 apply-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

2. Deletes a Terraform template:

```
    m3 delete-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

3. Describes Terraform template:

```
    m3 describe-terraform-templates -c <cloud> -tn <tenant>
```

4. Describes a Terraform stack:

```
    m3 describe-terraform-stacks -c <cloud> -tn <tenant>
```

5. Destroys resources related to a Terraform template or stack:

```
    m3 destroy-terraform-stack -c <cloud> -tn <tenant> -tpl <template>
```

6. Lock a Terraform template to prevent any actions from other users:

```
 m3 lock-terraform-template -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

7. Plans the selected Terraform template:

```
 m3 plan-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

8. Prolong a Terraform template lock to prevent any actions from other users:

```
 m3 prolong-terraform-template-lock -c <cloud> -tn <tenant> -tpl <template> -exp
<expiration>
```

9. Unlock a Terraform template to allow actions from other users:

```
 m3 unlock-terraform-template -c <cloud> -tn <tenant> -tpl <template>
```

10. Uploads a Terraform template from Git:

```
m3 upload-terraform-template-from-git -c <cloud> -tn <tenant> -tpl <template> -
url <git_url> -tkn <token> -b <branch> -wh <webhook> -ptype <provider_type> -terv
<terraform_version>
```

11. Uploads a Terraform template:

```
m3 upload-terraform-template -fpath <file_path> -terv <terraform_version> -c
<cloud> -tn <tenant> -tpl <template>
```

m3 multitenant-report

Description:

Gets multitenant billing report

Usage: m3 multitenant-report(mreport) [parameters]

Parameters:

```
--help                                  Shows the short help for the command

--full-help                             Shows the detailed help for the command

--verbose                               Controls the verbosity of command output

--json                                  Returns the server response in the JSON format

--table                                 Returns the server response in the table form
(default)

--full                                  Shows the full response from the server
without any specific formatting (can be used with --json)

--raw                                   Shows raw response from the server (can be
used with --json)

--from,                    -from,    *  The start range date. Format "dd.mm.yyyy"

--report-type,             -rtype,   *  The type of the report. Allowed values:
[ACCOUNT, ACTIVE, ADJUSTMENT, ALL_PERSONAL, ANNUAL, CUSTOMERS, INACTIVE, NOT_PMC,
UNITS, UPSA_INACTIVE, NATIVE]

--to,                      -to,      *  The end range date. Format "dd.mm.yyyy"

--account-id,              -accid,      The account-id parameter may be specified only
in case ACCOUNT report-type is set. account-id is not applicable with other values of
report-type

--include-billing-source,  -ibs,        A flag. Include billing source for public
cloud providers

--region,                  -r,          The cloud providers or the region or the
report family. Allowed values: [HARDWARE, AWS, AWS_UNREACHABLE, AZURE, AZURE_NATIVE,
GOOGLE, MOBILE, ENTERPRISE, SWIFT_STACK, REPORT_PORTAL, WORKSPACES, AWS_WORKSPACES,
AZURE_WORKSPACES, AWS_PAAS, AWS_ATLAS, AZURE_PAAS, GOOGLE_PAAS, PRIVATE_PAAS,
PRIVATE]

--tag,                     -tag,        Collect only records with specified tag. Use
the following format: tag=value

--tenant-group,            -tg,         The tenant group
```

Example:

```
m3 multitenant-report --from <dd.mm.yyyy> --to <dd.mm.yyyy> --region <region_zone> --report-type <report_type> --include-billing-source
```

Related commands:

1. Cost and usage optimization report. Command sends the report only to email:

```
m3 cost-usage-report -date <dd.mm.yyyy> -tn <tenant> -r <region> -rt <resource_type>
```

2. Gets a budgets billing report for a tenant:

```
m3 budgets-report -tg <tenant_group> -y <year> -m <month>
```

3. Gets a total billing report for a tenant:

```
m3 total-report -tg <tenant_group>
```

4. Gets billing region types:

```
m3 billing-region-types
```

5. Gets cost object report for the specified tenant:

```
m3 cost-object-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

6. Gets hourly billing report for the specified tenant:

```
m3 hourly-report -tg <tenant_group>
```

7. Gets resource billing report for the specified tenant:

```
m3 resource-report -tg <tenant_group>
```

8. Gets subtotal billing report for the specified tenant:

```
m3 subtotal-report -tg <tenant_group>
```

9. Gets untagged resource billing report:

```
m3 untagged-resource-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

10. This command is a single point of entry for report-related commands: ‘total-report’, ‘subtotal-report’, ‘resource-report’, ‘budgets-report’ and ‘hourly-report’:

```
m3 report -tg <tenant_group> -y <year> -m <month>
```

m3 billing-region-types

Description:

Gets billing region types

Usage: m3 billing-region-types(brtypes) [parameters]

Parameters:

```
--help              Shows the short help for the command

--full-help         Shows the detailed help for the command

--verbose           Controls the verbosity of command output

--json              Returns the server response in the JSON format

--table             Returns the server response in the table form (default)

--full              Shows the full response from the server without any specific
formatting (can be used with --json)

--raw               Shows raw response from the server (can be used with --json)

--all,       -A,    A flag. Includes inactive regions
```

Example:

```
m3 billing-region-types --all
```

Related commands:

1. Cost and usage optimization report. Command sends the report only to email:

```
m3 cost-usage-report -date <dd.mm.yyyy> -tn <tenant> -r <region> -rt
<resource_type>
```

2. Gets a budgets billing report for a tenant:

```
m3 budgets-report -tg <tenant_group> -y <year> -m <month>
```

3. Gets a total billing report for a tenant:

```
m3 total-report -tg <tenant_group>
```

4. Gets cost object report for the specified tenant:

```
m3 cost-object-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

5. Gets hourly billing report for the specified tenant:

```
m3 hourly-report -tg <tenant_group>
```

6. Gets multitenant billing report:

```
m3 multitenant-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -rtype <report_type>
```

7. Gets resource billing report for the specified tenant:

```
m3 resource-report -tg <tenant_group>
```

8. Gets subtotal billing report for the specified tenant:

```
m3 subtotal-report -tg <tenant_group>
```

9. Gets untagged resource billing report:

```
m3 untagged-resource-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

10. This command is a single point of entry for report-related commands: ‘total-report’, ‘subtotal-report’, ‘resource-report’, ‘budgets-report’ and ‘hourly-report’:

```
m3 report -tg <tenant_group> -y <year> -m <month>
```

m3 describe-user-permissions

Description:

Describes the permission groups assigned to you in the specified tenant

Usage: m3 describe-user-permissions(duserperm) [parameters]

Parameters:

```
--help                        Shows the short help for the command

--full-help                   Shows the detailed help for the command

--verbose                     Controls the verbosity of command output

--json                        Returns the server response in the JSON format

--table                       Returns the server response in the table form (default)

--full                        Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                         Shows raw response from the server (can be used with --
json)

--cloud,        -c,      *    The cloud.

                              Allowed values: [AWS, AZURE, GOOGLE, NUTANIX, OPEN_STACK,
VSPHERE]

--environment,  -env,    *    The Maestro environment or the third-party application
for which to describe your permissions.

                              Allowed values: [M3_UI, M3_SDK, AWS_CONSOLE,
GOOGLE_CONSOLE, AZURE_CONSOLE]

--tenant,       -tn,     *    The tenant name

--group-name,   -gname,       The name of the permission group
```

Example:

```
m3 describe-user-permissions --cloud <cloud> --tenant <tenant_name> --environment
<environment>
```

Related commands:

1. Describes system status:

```
    m3 health-check
```

m3 allocate-ip

Description:

Allocate static ip in the specified region in tenant:

Usage: m3 allocate-ip(alip) [parameters]

Parameters:

```
--help                  Shows the short help for the command

--full-help             Shows the detailed help for the command

--verbose               Controls the verbosity of command output

--json                  Returns the server response in the JSON format

--table                 Returns the server response in the table form (default)

--full                  Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                   Shows raw response from the server (can be used with --json)

--network,   -net,  *   The id of the target network

--region,    -r,    *   The region name

--tenant,    -tn,   *   The tenant name
```

Example:

```
    m3 allocate-ip --tenant <tenant_name> --region <region_name>  --network
<network_id>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
    m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Associate static IP with instance:

```
    m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

3. Creates instances of the specified configuration:

```
    m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

4. Deactivate specified VLAN on specified region in tenant:

```
    m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

5. Describe available VLANs on specified region in tenant:

```
    m3 describe-vlans -tn <tenant> -r <region>
```

6. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

7. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

8. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

9. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

10. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

11. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

12. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

13. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

14. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

15. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 release-ip

Description:

Release static ip in the specified region in tenant:

Usage: m3 release-ip(rip) [parameters]

Parameters:

```
--help                  Shows the short help for the command

--full-help             Shows the detailed help for the command

--verbose               Controls the verbosity of command output

--json                  Returns the server response in the JSON format

--table                 Returns the server response in the table form (default)

--full                  Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                   Shows raw response from the server (can be used with --json)

--ip,         -ip,   *  The target static ip

--region,     -r,    *  The region name

--tenant,     -tn,   *  The tenant name
```

Example:

```
m3 release-ip --tenant <tenant_name> --region <region_name>  --ip <target_ip>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Associate static IP with instance:

```
m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

4. Creates instances of the specified configuration:

```
m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

5. Deactivate specified VLAN on specified region in tenant:

```
m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

6. Describe available VLANs on specified region in tenant:

```
m3 describe-vlans -tn <tenant> -r <region>
```

7. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

8. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

9. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

10. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

11. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

12. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

13. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

14. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

15. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 describe-ip

Description:

Describe static ips in the specified region in tenant:

Usage: m3 describe-ip(dip) [parameters]

Parameters:

```
--help                Shows the short help for the command

--full-help           Shows the detailed help for the command

--verbose             Controls the verbosity of command output

--json                Returns the server response in the JSON format

--table               Returns the server response in the table form (default)

--full                Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                 Shows raw response from the server (can be used with --json)

--region,    -r,   *  The region name

--tenant,    -tn,  *  The tenant name
```

Example:

```
m3 describe-ip --tenant <tenant_name> --region <region_name>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Associate static IP with instance:

```
m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

4. Creates instances of the specified configuration:

```
m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

5. Deactivate specified VLAN on specified region in tenant:

```
m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

6. Describe available VLANs on specified region in tenant:

```
m3 describe-vlans -tn <tenant> -r <region>
```

7. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

8. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

9. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

10. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

11. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

12. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

13. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

14. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

15. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 describe-vlans

Description:

Describe available VLANs in the specified region in tenant:

Usage: m3 describe-vlans(dvlans) [parameters]

Parameters:

```
--help                Shows the short help for the command

--full-help           Shows the detailed help for the command

--verbose             Controls the verbosity of command output

--json                Returns the server response in the JSON format

--table               Returns the server response in the table form (default)

--full                Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                 Shows raw response from the server (can be used with --json)

--region,    -r,   *  The region name

--tenant,    -tn,  *  The tenant name
```

Example:

```
    m3 describe-vlans --tenant <tenant_name> --region <region_name>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
    m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
    m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Associate static IP with instance:

```
    m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

4. Creates instances of the specified configuration:

```
    m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

5. Deactivate specified VLAN on specified region in tenant:

```
    m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

6. Describe static IPs on specified region in tenant:

```
    m3 describe-ip -tn <tenant> -r <region>
```

7. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

8. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

9. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

10. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

11. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

12. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

13. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

14. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

15. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 deactivate-vlan

Description:

Deactivate specified VLAN in the specified region in tenant:

Usage: m3 deactivate-vlan(dvlan) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --json)

--region,     -r,     *   The region name

--tenant,     -tn,    *   The tenant name

--vlan-name,  -vlan,  *   The target VLAN name
```

Example:

```
    m3 deactivate-vlan --tenant <tenant_name> --region <region_name> --vlan-name
<vlan_name>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
    m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
    m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Associate static IP with instance:

```
    m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

4. Creates instances of the specified configuration:

```
    m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

5. Describe available VLANs on specified region in tenant:

```
    m3 describe-vlans -tn <tenant> -r <region>
```

6. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

7. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

8. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

9. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

10. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

11. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

12. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

13. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

14. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

15. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 activate-vlan

Description:

Activate specified VLAN in the specified region in tenant:

Usage: m3 activate-vlan(avlan) [parameters]

Parameters:

```
--help                      Shows the short help for the command

--full-help                 Shows the detailed help for the command

--verbose                   Controls the verbosity of command output

--json                      Returns the server response in the JSON format

--table                     Returns the server response in the table form (default)

--full                      Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                       Shows raw response from the server (can be used with --
json)

--description,  -d,     *   The VLAN description

--region,       -r,     *   The region name

--tenant,       -tn,    *   The tenant name

--vlan-name,    -vlan,  *   The target VLAN name
```

Example:

```
    m3 activate-vlan --tenant <tenant_name> --region <region_name> --vlan-name
<vlan_name> --description <vlan_description>
```

Related commands:

1. Allocate static IP on specified region in tenant:

```
    m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

2. Associate static IP with instance:

```
    m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

3. Creates instances of the specified configuration:

```
    m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

4. Deactivate specified VLAN on specified region in tenant:

```
    m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

5. Describe available VLANs on specified region in tenant:

```
    m3 describe-vlans -tn <tenant> -r <region>
```

6. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

7. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

8. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

9. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

10. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

11. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

12. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

13. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

14. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

15. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 move-to-vlan

Description:

Move specific instance to another VLAN:

Usage: m3 move-to-vlan(mvlan) [parameters]

Parameters:

```
--help                      Shows the short help for the command

--full-help                 Shows the detailed help for the command

--verbose                   Controls the verbosity of command output

--json                      Returns the server response in the JSON format

--table                     Returns the server response in the table form (default)

--full                      Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                       Shows raw response from the server (can be used with --
json)

--instance-id,  -i,     *   Target instance id

--region,       -r,     *   The region name

--tenant,       -tn,    *   The tenant name

--vlan-name,    -vlan,  *   The target VLAN name
```

Example:

```
    m3 move-to-vlan --tenant <tenant_name> --region <region_name> --vlan-name
<vlan_name> --instance-id <instance_id>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
    m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
    m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Associate static IP with instance:

```
    m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

4. Creates instances of the specified configuration:

```
    m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

5. Deactivate specified VLAN on specified region in tenant:

```
    m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

6. Describe available VLANs on specified region in tenant:

```
m3 describe-vlans -tn <tenant> -r <region>
```

7. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

8. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

9. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

10. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

11. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

12. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

13. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

14. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

15. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 associate-ip

Description:

Associate specific static IP with instance:

Usage: m3 associate-ip(asip) [parameters]

Parameters:

```
--help                    Shows the short help for the command

--full-help               Shows the detailed help for the command

--verbose                 Controls the verbosity of command output

--json                    Returns the server response in the JSON format

--table                   Returns the server response in the table form (default)

--full                    Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                     Shows raw response from the server (can be used with --json)

--instance-id,  -i,   *   Target instance ID

--region,       -r,   *   The region name

--static-ip,    -ip,  *   The target static IP

--tenant,       -tn,  *   The tenant name
```

Example:

```
   m3 associate-ip --tenant <tenant_name> --region <region_name> --static-ip <ip> --
instance-id <instance_id>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
   m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
   m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Creates instances of the specified configuration:

```
   m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

4. Deactivate specified VLAN on specified region in tenant:

```
   m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

5. Describe available VLANs on specified region in tenant:

```
   m3 describe-vlans -tn <tenant> -r <region>
```

6. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

7. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

8. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

9. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

10. Disassociate static IP from the instance:

```
m3 disassociate-ip -tn <tenant> -r <region> -ip <static_ip>
```

11. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

12. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

13. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

14. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

15. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 disassociate-ip

Description:

Disassociate specific static IP from the instance:

Usage: m3 disassociate-ip(dsip) [parameters]

Parameters:

```
--help                  Shows the short help for the command

--full-help             Shows the detailed help for the command

--verbose               Controls the verbosity of command output

--json                  Returns the server response in the JSON format

--table                 Returns the server response in the table form (default)

--full                  Shows the full response from the server without any specific
formatting (can be used with --json)

--raw                   Shows raw response from the server (can be used with --json)

--region,     -r,   *   The region name

--static-ip,  -ip,  *   The target static IP

--tenant,     -tn,  *   The tenant name
```

Example:

```
m3 disassociate-ip --tenant <tenant_name> --region <region_name> --static-ip <ip>
```

Related commands:

1. Activate specified VLAN on specified region in tenant:

```
m3 activate-vlan -tn <tenant> -r <region> -vlan <vlan_name> -d <description>
```

2. Allocate static IP on specified region in tenant:

```
m3 allocate-ip -tn <tenant> -r <region> -net <network>
```

3. Associate static IP with instance:

```
m3 associate-ip -tn <tenant> -r <region> -ip <static_ip> -i <instance_id>
```

4. Creates instances of the specified configuration:

```
m3 run-instances -c <cloud> -tn <tenant> -r <region> -n <name> -imname <image>
```

5. Deactivate specified VLAN on specified region in tenant:

```
m3 deactivate-vlan -tn <tenant> -r <region> -vlan <vlan_name>
```

6. Describe available VLANs on specified region in tenant:

```
m3 describe-vlans -tn <tenant> -r <region>
```

7. Describe static IPs on specified region in tenant:

```
m3 describe-ip -tn <tenant> -r <region>
```

8. Describes insights for an instance in specific region for a specific tenant:

```
m3 describe-insights -c <cloud> -r <region> -tn <tenant> -iid <instance_id>
```

9. Describes instances existing in a specific region for a specific tenant:

```
m3 describe-instances -tn <tenant> -r <region>
```

10. Describes resources existing in a specific region for a specific tenant:

```
m3 describe-resources -r <region> -tn <tenant>
```

11. Move instance To another vlan:

```
m3 move-to-vlan -tn <tenant> -r <region> -vlan <vlan_name> -i <instance_id>
```

12. Reboots the specified instance:

```
m3 reboot-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

13. Release static IP on specified region in tenant:

```
m3 release-ip -tn <tenant> -r <region> -ip <ip>
```

14. Starts the specified instances:

```
m3 start-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

15. Stops an instance:

```
m3 stop-instances -tn <tenant> -r <region> -iid <instance_id1>,<instance_idN>
```

16. Terminates an instance:

```
m3 terminate-instances -tn <tenant> -r <region> -iid
<instance_id1>,<instance_idN>
```

m3 report

Description:

This command serves as a single point of entry for report-related commands:'total-report', 'subtotal-report', 'resource-report', and 'hourly-report'

Usage: m3 report(report) [parameters]

Parameters:

```
--help                      Shows the short help for the command

--full-help                 Shows the detailed help for the command

--verbose                   Controls the verbosity of command output

--json                      Returns the server response in the JSON format

--table                     Returns the server response in the table form (default)

--full                      Shows the full response from the server without any
specific formatting (can be used with --json)

--raw                       Shows raw response from the server (can be used with --
json)

--tenant-group,  -tg,   *   The tenant group

--year,          -y,    *   Year. Format (yyyy). Use with 'month' for a 1-month range,
or with 'month' and 'day' for a 1-day range

--month,         -m,    *   Month. Format (mm). Use with 'year' for a 1-month range,
or with 'day' for a 1-day range

--day,           -d,        Day. Format (dd). Use with 'year' and 'month' for a 1-day
range

--type,          -t,        Report type. Possible parameter values: [total, subtotal,
resource, hourly, budgets]. Default: total ('total-report' command)

--region,        -r,        The region name. Specify this parameter to filter report
records by region

--tag,           -tag,      Collects only records with a specified tag. Use the
following format: tag=value

--report,        -R,        A flag. If specified the report will be sent by email

--url,           -U,        A flag. If specified, the presigned URL will be generated
(used for the type: 'total', 'subtotal', 'resource' and 'hourly')

--instance-id,   -iid,      The ID of the instance (used for the type: 'resource',
'hourly')
```

```
--adjustment,    -A,       A flag. If specified, only adjustments will be shown (used
for the type: 'total', 'subtotal')
```

Examples:

Total, Subtotal, and Resource Reports:

```
1. For the current month (specify year and month):

   m3 report --type total|subtotal|resource --tenant-group <tenant_group_name> --year
<yyyy> --month <mm>

2. For a specific day (specify year, month, and day):

   m3 report --type total|subtotal|resource --tenant-group <tenant_group_name> --year
<yyyy> --month <mm> --day <dd>
```

Hourly Report:

```
m3 report --type hourly --tenant-group <tenant_group_name> --year <yyyy> --month <mm>
--day <dd>
```

Related commands:

1. Cost and usage optimization report. Command sends the report only to email:

```
   m3 cost-usage-report -date <dd.mm.yyyy> -tn <tenant> -r <region> -rt
  <resource_type>
```

2. Gets a budgets billing report for a tenant:

```
   m3 budgets-report -tg <tenant_group> -y <year> -m <month>
```

3. Gets a total billing report for a tenant:

```
   m3 total-report -tg <tenant_group>
```

4. Gets billing region types:

```
   m3 billing-region-types
```

5. Gets cost object report for the specified tenant:

```
   m3 cost-object-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

6. Gets hourly billing report for the specified tenant:

```
   m3 hourly-report -tg <tenant_group>
```

7. Gets multitenant billing report:

```
   m3 multitenant-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -rtype <report_type>
```

8. Gets resource billing report for the specified tenant:

```
   m3 resource-report -tg <tenant_group>
```

9. Gets subtotal billing report for the specified tenant:

```
   m3 subtotal-report -tg <tenant_group>
```

10. Gets untagged resource billing report:

```
  m3 untagged-resource-report -from <dd.mm.yyyy> -to <dd.mm.yyyy> -tn <tenant>
```

m3 create-recommendation-settings

Description:

Create recommendation settings for cost optimization recommendations

Usage: m3 create-recommendation-settings(crset) [parameters]

Parameters:

```
--help                                  Shows the short help for the command

--full-help                             Shows the detailed help for the command

--verbose                               Controls the verbosity of command output

--json                                  Returns the server response in the JSON format

--table                                 Returns the server response in the table form
(default)

--full                                  Shows the full response from the server without
any specific formatting (can be used with --json)

--raw                                   Shows raw response from the server (can be used
with --json)

--cloud,                  -c,     *     Cloud provider. Allowed values: AWS, AZURE,
GOOGLE

--disabled-until,         -du,    *     Date until which recommendations are disabled.
Format: dd.mm.yyyy

--tenant,                 -tn,    *     The tenant name

--category,               -cat,         Recommendation categories (required for -R
flag). Pass several values in the following format:
SCHEDULES,SHUT_DOWN,SCALING,SHAPE,SPLITTING

--native-resource-id,     -nrid,        Native resource identifier (ARN for AWS,
Resource ID for Azure, or Project ID for GCP. Required for -SRE with --type NRID)

--region,                 -r,           Region name (required for -R flag and -SRE with
--type RESOURCE)

--resource-id,            -rid,         Resource identifier (required for -R flag and -
SRE with --type RESOURCE)

--resource-type,          -rt,          Resource type (required for -R flag and -SRE
with --type RESOURCE). Allowed value: INSTANCE

--rightsizer,             -R,           Enable Rightsizer recommendations

--syndicate-rule-engine,  -SRE,         Enable Syndicate Rule Engine recommendations
```

```
--tag,                    -tag,      Tags (required for -SRE with --type TAG_FILTER).
Pass several values in the following format: key1:val1,key2:val2

--type,                   -t,        Recommendation filter type (required when using
-SRE flag). Pass several values in the following format: TAG_FILTER, RESOURCE, NRID
```

Examples:

```
1. Syndicate Rule Engine (SRE) recommendations:

    1.1 Using TAG_FILTER type:

        m3 create-recommendation-settings -SRE --type <type> --tenant <tenant_name> -
-cloud <cloud> --disabled-until <dd.mm.yyyy> --tag <key1:val1,key2:val2>

    1.2 Using RESOURCE type:

        m3 create-recommendation-settings -SRE --type <type> --tenant <tenant_name> -
-cloud <cloud> --disabled-until <dd.mm.yyyy> --region <region> --resource-type
<resource_type> --resource-id <resource_id>

    1.3 Using NRID type:

        m3 create-recommendation-settings -SRE --type <type> --tenant <tenant_name> -
-cloud <cloud> --disabled-until <dd.mm.yyyy> --native-resource-id <ARN>

    1.4 Combining multiple types (all at once):

        m3 create-recommendation-settings -SRE --type <type1,type2,type3> --tenant
<tenant_name> --cloud <cloud> --disabled-until <dd.mm.yyyy> --tag
<key1:val1,key2:val2> --region <region> --resource-type <resource_type> --resource-id
<resource_id> --native-resource-id <ARN>

2. Rightsizer (R) recommendations:

    m3 create-recommendation-settings -R --tenant <tenant_name> --cloud <cloud> --
disabled-until <dd.mm.yyyy> --region <region> --resource-type <resource_type> --
resource-id <resource_id> --category <category>

3. Combined SRE and Rightsizer settings:

    m3 create-recommendation-settings -SRE --type <type1,type2,type3> -R --tenant
<tenant_name> --cloud <cloud> --disabled-until <dd.mm.yyyy> --tag
<key1:val1,key2:val2> --native-resource-id <ARN> --region <region> --resource-type
<resource_type> --resource-id <resource_id> --category <category>
```

m3 update-recommendation-settings

Description:

Update recommendation settings for cost optimization recommendations

Usage: m3 update-recommendation-settings(urset) [parameters]

Parameters:

```
--help                                  Shows the short help for the command

--full-help                             Shows the detailed help for the command

--verbose                               Controls the verbosity of command output

--json                                  Returns the server response in the JSON format

--table                                 Returns the server response in the table form
(default)

--full                                  Shows the full response from the server without
any specific formatting (can be used with --json)

--raw                                   Shows raw response from the server (can be used
with --json)

--cloud,                  -c,     *     Cloud provider. Allowed values: AWS, AZURE,
GOOGLE

--disabled-until,         -du,    *     Date until which recommendations are disabled.
Format: dd.mm.yyyy

--tenant,                 -tn,    *     The tenant name

--category,               -cat,         Recommendation categories (required for -R
flag). Pass several values in the following format:
SCHEDULES,SHUT_DOWN,SCALING,SHAPE,SPLITTING

--native-resource-id,     -nrid,        Native resource identifier (ARN for AWS,
Resource ID for Azure, or Project ID for GCP. Required for -SRE flag with --type-to-
id NRID:<id>)

--region,                 -r,           Region name (required for -R flag and -SRE flag
with RESOURCE type)

--resource-id,            -rid,         Resource identifier (required for -R flag and -
SRE flag with RESOURCE type)

--resource-type,          -rt,          Resource type (required for -R flag and -SRE
flag with RESOURCE type). Allowed value: INSTANCE

--rightsizer,             -R,           Update Rightsizer recommendations

--syndicate-rule-engine,  -SRE,         Update Syndicate Rule Engine recommendations
```

```
--tag,                    -tag,      Tags (required for -SRE flag with TAG_FILTER
type). Pass several values in the following format: key1:val1,key2:val2

--type-to-id,             -tid,      Mapping of recommendation filter types to their
IDs (required when using -SRE flag). Pass several values in the following format:
TYPE1:ID1,TYPE2:ID2. Types: TAG_FILTER, RESOURCE, NRID
```

Examples:

```
1. Syndicate Rule Engine (SRE) recommendations:

    1.1 Using TAG_FILTER type:

        m3 update-recommendation-settings -SRE --type-to-id <type1>:<id1> --tenant
<tenant_name> --cloud <cloud> --disabled-until <dd.mm.yyyy> --tag
<key1:val1,key2:val2>

    1.2 Using RESOURCE type:

        m3 update-recommendation-settings -SRE --type-to-id <type1>:<id1> --tenant
<tenant_name> --cloud <cloud> --disabled-until <dd.mm.yyyy> --region <region> --
resource-type <resource_type> --resource-id <resource_id>

    1.3 Using NRID type:

        m3 update-recommendation-settings -SRE --type-to-id <type1>:<id1> --tenant
<tenant_name> --cloud <cloud> --disabled-until <dd.mm.yyyy> --arn <arn>

    1.4 Combining multiple types (each with its own ID):

        m3 update-recommendation-settings -SRE --type-to-id
<type1>:<id1>,<type2>:<id2>,<type3>:<id3> --tenant <tenant_name> --cloud <cloud> --
disabled-until <dd.mm.yyyy> --tag <key1:val1,key2:val2> --region <region> --resource-
type <resource_type> --resource-id <resource_id> --arn <arn>

2. Rightsizer (R) recommendations:

    m3 update-recommendation-settings -R --tenant <tenant_name> --cloud <cloud> --
disabled-until <dd.mm.yyyy> --region <region> --resource-type <resource_type> --
resource-id <resource_id> --category <category>

3. Combined SRE and Rightsizer settings:

    m3 update-recommendation-settings -SRE --type-to-id <type1>:<id1>,<type2>:<id2> -
R --tenant <tenant_name> --cloud <cloud> --disabled-until <dd.mm.yyyy> --tag
<key1:val1,key2:val2> --arn <arn> --region <region> --resource-type <resource_type> -
-resource-id <resource_id> --category <category>
```

m3 describe-recommendation-settings

Description:

Describe recommendation settings for cost optimization recommendations

Usage: m3 describe-recommendation-settings(drset) [parameters]

Parameters:

```
--help                                Shows the short help for the command

--full-help                           Shows the detailed help for the command

--verbose                             Controls the verbosity of command output

--json                                Returns the server response in the JSON format

--table                               Returns the server response in the table form
(default)

--full                                Shows the full response from the server without
any specific formatting (can be used with --json)

--raw                                 Shows raw response from the server (can be used
with --json)

--cloud,                  -c,    *    Cloud provider. Allowed values: AWS, AZURE,
GOOGLE

--tenant,                 -tn,   *    The tenant name

--category,               -cat,       Recommendation categories (required for -R flag).
Pass several values in the following format:
SCHEDULES,SHUT_DOWN,SCALING,SHAPE,SPLITTING

--region,                 -r,         Region name (required for -R flag and -SRE flag
with RESOURCE type)

--resource-id,            -rid,       Resource identifier (required for -R flag and -
SRE flag with RESOURCE type)

--resource-type,          -rt,        Resource type (required for -R flag and -SRE flag
with RESOURCE type). Allowed value: INSTANCE

--rightsizer,             -R,         Describe Rightsizer recommendations

--syndicate-rule-engine,  -SRE,       Describe Syndicate Rule Engine recommendations

--type,                   -t,         Recommendation filter type (required when using -
SRE flag). Pass several values in the following format: TAG_FILTER, RESOURCE, NRID
(NRID: ARN for AWS, Resource ID for Azure, or Project ID for GCP)
```

Examples:

```
1. Describe all Rightsizer settings:

    m3 describe-recommendation-settings -R --tenant <tenant_name> --cloud <cloud>

2. Describe Rightsizer settings with specific categories:

    m3 describe-recommendation-settings -R --tenant <tenant_name> --cloud <cloud> --
category <category>

3. Describe Rightsizer settings for specific resource:

    m3 describe-recommendation-settings -R --tenant <tenant_name> --cloud <cloud> --
region <region> --resource-type <resource_type> --resource-id <resource_id>

4. Describe all Syndicate Rule Engine settings:

    m3 describe-recommendation-settings -SRE --tenant <tenant_name> --cloud <cloud>

5. Describe Syndicate Rule Engine settings with specific types:

    m3 describe-recommendation-settings -SRE --tenant <tenant_name> --cloud <cloud> -
-type <type1,type2>

6. Describe Syndicate Rule Engine settings for specific resource:

    m3 describe-recommendation-settings -SRE --tenant <tenant_name> --cloud <cloud> -
-region <region> --resource-type <resource_type> --resource-id <resource_id> --type
<type1,type2>

7. Describe both Rightsizer and Syndicate Rule Engine settings:

    m3 describe-recommendation-settings -R -SRE --tenant <tenant_name> --cloud
<cloud>

8. Describe both with all filters:

    m3 describe-recommendation-settings -R -SRE --tenant <tenant_name> --cloud
<cloud> --region <region> --resource-type <resource_type> --resource-id <resource_id>
--category <category> --type <type1,type2,type3>
```

m3 remove-recommendation-settings

Description:

Remove recommendation settings for cost optimization recommendations

This command removes existing recommendation settings for either Rightsizer or

Syndicate Rule Engine (or both).

Usage: m3 remove-recommendation-settings(rrset) [parameters]

Parameters:

```
--help                                  Shows the short help for the command

--full-help                             Shows the detailed help for the command

--verbose                               Controls the verbosity of command output

--json                                  Returns the server response in the JSON format

--table                                 Returns the server response in the table form
(default)

--full                                  Shows the full response from the server without
any specific formatting (can be used with --json)

--raw                                   Shows raw response from the server (can be used
with --json)

--cloud,                  -c,      *    Cloud provider. Allowed values: AWS, AZURE,
GOOGLE

--tenant,                 -tn,     *    The tenant name

--category,               -cat,         Recommendation categories (required for -R
flag). Pass several values in the following format:
SCHEDULES,SHUT_DOWN,SCALING,SHAPE,SPLITTING

--recommendation-id,      -recid,       Recommendation IDs. Pass several values in the
following format: ID1, ID2, ID3, ...

--region,                 -r,           Region name (required for -R flag and -SRE flag
with RESOURCE type)

--resource-id,            -rid,         Resource identifier (required for -R flag and -
SRE flag with RESOURCE type)

--resource-type,          -rt,          Resource type (required for -R flag and -SRE
flag with RESOURCE type). Allowed value: INSTANCE

--rightsizer,             -R,           Remove Rightsizer recommendations

--syndicate-rule-engine,  -SRE,         Remove Syndicate Rule Engine recommendations
```

Examples:

```
1. Remove Rightsizer recommendations:

    m3 remove-recommendation-settings -R --tenant <tenant_name> --cloud <cloud> --
region <region> --resource-type <resource_type> --resource-id <resource_id> --
category <category1,category2,category3,category4,category5>

2. Remove Syndicate Rule Engine recommendations:

    2.1 Remove TAG_FILTER, RESOURCE or ARN type:

        m3 remove-recommendation-settings -SRE --type-to-id <type>:<id> --tenant
<tenant_name> --cloud <cloud>

    2.2 Remove multiple types at once:

        m3 remove-recommendation-settings -SRE --type-to-id
<type1>:<id1>,<type2>:<id2>,<type3>:<id3> --tenant <tenant_name> --cloud <cloud>

3. Remove both Rightsizer and Syndicate Rule Engine settings:

    m3 remove-recommendation-settings -R -SRE --tenant <tenant_name> --cloud <cloud>
--region <region> --resource-type <resource_type> --resource-id <resource_id> --
category <category> --type-to-id <type1>:<id1>,<type2>:<id2>
```