Coherent UI for Unity3D 1.8.1

Contents

1	Intro	duction	1
	1.1	Brief overview of Coherent UI	1
	1.2	Differences between Desktop and Mobile version	1
2	Insta	allation	3
	2.1	Prerequisites	3
	2.2	Package contents and structure	3
	2.3	Usage of the package	4
	2.4	Switching between build targets	5
	2.5	Trial version registration	6
3	Sam	ples	7
	3.1	Hello, Coherent UI	7
	3.2	Facebook integration	9
	3.3	Menu And HUD	10
	3.4	Binding Demo	12
	3.5	Archive resource	16
	3.6	Mobile Input	17
	3.7	Oculus	19
	3.8	Mobile Surface	19
	3.9	Live Game Views	20
	3.10	IME Sample	20
4	Prog	grammer's API	23
	4.1	CoherentUISystem properties for Desktop	23
	4.2	CoherentUISystem properties for Mobile	23
	4.3	CoherentUIView properties for Desktop	24
	4.4	CoherentUIView properties for Mobile	25
	4.5	CoherentUILiveGameView properties for Desktop	25
5	Impo	ortant points	27
	5.1	Binding	27
	E 2	CohorontMothod attribute for NET agripts	27

iv CONTENTS

	5.3	Names	paces .		29
	5.4	Subcla	ssing Cohe	erentUIView and UnityViewListener	29
	5.5	Cohere	ent UI syste	em lifetime	30
	5.6	Custon	nizing initia	alization of the Coherent UI System	30
	5.7	Update	cycle .		31
	5.8	Input fo	rwarding -	Desktop	31
	5.9	Input fo	rwarding -	Mobile	31
	5.10	Mobile	Preview		32
	5.11	Custon	n file handl	ler	32
	5.12	UI Res	ources .		33
	5.13	Click-to	-focus Vie	ws - Desktop only	33
	5.14	View F	ilters - Des	sktop only	34
	5.15	Hit test	ing - Desk	top only	34
	5.16	Mobile	Surface V	iews	35
	5.17	Loggin	g		35
	5.18	Live Ga	ame Views		35
_	D				07
6	nequ	uiremen	its		37
7	Nam	espace	Documen	ntation	39
	7.1	Packag	je Coherer	nt	39
	7.2	Packag	je Coherer	nt.UI	39
		7.2.1	Enumera	tion Type Documentation	41
			7.2.1.1	CertificateStatus	41
			7.2.1.2	CursorTypes	41
			7.2.1.3	Direct3DInterfaceType	41
			7.2.1.4	DownloadErrorType	42
			7.2.1.5	FileSelectionMode	42
			7.2.1.6	JavaScriptMessageType	42
			7.2.1.7	MediaStreamType	42
			7.2.1.8	RenderingDeviceType	42
			7.2.1.9	ScriptCallErrorType	42
			7.2.1.10	SystemErrorType	42
			7.2.1.11	TextInputControlType	42
			7.2.1.12	UserAgentType	42
			7.2.1.13	ViewErrorType	43
			7.2.1.14	ViewType	43
	7.3	Packag	je Coherer	nt.UI.Binding	43
		7.3.1	Enumera	tion Type Documentation	44
			7.3.1.1	PropertyBindingFlags	44
			7.3.1.2	ValueType	44

CONTENTS

8	Clas	s Docu	mentation		45
	8.1	Cohere	ent.UI.Bour	ndEventHandle Struct Reference	45
		8.1.1	Detailed [Description	45
	8.2	Cohere	ent.UI.Bindi	ng.BoundObject Struct Reference	45
		8.2.1	Detailed [Description	45
		8.2.2	Member F	Function Documentation	45
			8.2.2.1	BindMethods	45
	8.3	Cohere	ent.UI.Brow	serView Class Reference	46
		8.3.1	Detailed [Description	46
		8.3.2	Member F	Function Documentation	46
			8.3.2.1	GetHistory	46
			8.3.2.2	GetViewType	46
			8.3.2.3	GoBack	46
			8.3.2.4	GoForward	46
	8.4	Cohere	ent.UI.Brow	serViewListener Class Reference	47
		8.4.1	Detailed [Description	49
		8.4.2	Member F	Function Documentation	49
			8.4.2.1	CreateSurface	49
			8.4.2.2	DestroySurface	50
			8.4.2.3	OnBindingsReleased	51
			8.4.2.4	OnCallback	51
			8.4.2.5	OnCaretRectChanged	51
			8.4.2.6	OnCertificateError	51
			8.4.2.7	OnCursorChanged	52
			8.4.2.8	OnDraw	52
			8.4.2.9	OnError	52
			8.4.2.10	OnFailLoad	52
			8.4.2.11	OnFileSelectRequest	52
			8.4.2.12	OnFinishLoad	53
			8.4.2.13	OnGetAuthCredentials	53
			8.4.2.14	OnIMEShouldCancelComposition	53
			8.4.2.15	OnJavaScriptMessage	53
			8.4.2.16	OnNavigateTo	54
			8.4.2.17	OnReadyForBindings	55
			8.4.2.18	OnRequestMediaStream	55
			8.4.2.19	OnScriptMessage	55
			8.4.2.20	OnStartLoading	55
			8.4.2.21	OnStopLoading	55
			8.4.2.22	OnTextInputTypeChanged	56
			8.4.2.23	OnURLRequest	57

vi CONTENTS

		8.4.2.24	OnViewCreated	57
		8.4.2.25	Release	57
	8.4.3	Event Do	cumentation	57
		8.4.3.1	BindingsReleased	57
		8.4.3.2	Callback	57
		8.4.3.3	CaretRectChanged	57
		8.4.3.4	CertificateError	57
		8.4.3.5	CursorChanged	58
		8.4.3.6	Draw	58
		8.4.3.7	Error	58
		8.4.3.8	FailLoad	58
		8.4.3.9	FileSelectRequest	58
		8.4.3.10	FinishLoad	58
		8.4.3.11	GetAuthCredentials	58
		8.4.3.12	IMEShouldCancelComposition	58
		8.4.3.13	JavaScriptMessage	58
		8.4.3.14	NavigateTo	58
		8.4.3.15	ReadyForBindings	58
		8.4.3.16	RequestMediaStream	58
		8.4.3.17	ScriptMessage	59
		8.4.3.18	StartLoading	59
		8.4.3.19	StopLoading	59
		8.4.3.20	TextInputTypeChanged	59
		8.4.3.21	URLRequest	59
		8.4.3.22	ViewCreated	59
8.5	Cohere	ent.UI.Brov	vserViewListenerBase Class Reference	59
	8.5.1	Detailed	Description	59
8.6	Cohere	ent.UI.Bind	ing.CallbackArguments Class Reference	59
	8.6.1	Detailed	Description	60
	8.6.2	Member	Data Documentation	60
		8.6.2.1	Arguments	60
8.7	Cohere	ent.UI.Cert	ificate Class Reference	60
	8.7.1	Detailed	Description	60
	8.7.2	Property	Documentation	60
		8.7.2.1	Fingerprint	60
		8.7.2.2	FingerprintCA	61
		8.7.2.3	Issuer	61
		8.7.2.4	SerialNumber	61
		8.7.2.5	Subject	61
		8.7.2.6	ValidEnd	61

CONTENTS vii

		8.7.2.7	ValidStart	61
8.8	Cohere	ent.UI.Certi	ificatePrincipal Class Reference	61
	8.8.1	Detailed [Description	62
	8.8.2	Property	Documentation	62
		8.8.2.1	CommonName	62
		8.8.2.2	CountryName	62
		8.8.2.3	DomainComponents	62
		8.8.2.4	LocalityName	62
		8.8.2.5	OrganizationNames	62
		8.8.2.6	OrganizationUnitNames	62
		8.8.2.7	StateOrProvinceName	62
		8.8.2.8	StreetAddresses	62
8.9	Cohere	ent.UI.Chilo	dViewInfo Class Reference	62
	8.9.1	Detailed [Description	63
	8.9.2	Property	Documentation	63
		8.9.2.1	Listener	63
		8.9.2.2	NewViewInfo	63
8.10	Cohere	ent.UI.Bindi	ing.CoherentProperty Class Reference	63
	8.10.1	Detailed [Description	63
	8.10.2	Construct	tor & Destructor Documentation	63
		8.10.2.1	CoherentProperty	63
		8.10.2.2	CoherentProperty	63
8.11	Cohere	ent.UI.Bindi	ing.CoherentType Class Reference	63
	8.11.1	Detailed [Description	64
8.12	Cohere	ent.UI.Dow	nload Class Reference	64
	8.12.1	Detailed [Description	64
	8.12.2	Member F	Function Documentation	64
		8.12.2.1	Cancel	64
		8.12.2.2	Destroy	65
		8.12.2.3	GetDownloadedBytesSoFar	65
		8.12.2.4	GetFilename	65
		8.12.2.5	GetId	65
		8.12.2.6	GetReferrer	65
		8.12.2.7	GetTotalBytes	65
		8.12.2.8	GetURL	65
		8.12.2.9	HasFailed	66
		8.12.2.10	IsCancelled	66
		8.12.2.11	IsComplete	66
8.13			ntListener Class Reference	66
	8.13.1	Detailed [Description	66

viii CONTENTS

	8.13.2	Member I	Function Documentation	66
		8.13.2.1	OnDownloadComplete	66
		8.13.2.2	OnDownloadFailed	67
		8.13.2.3	OnDownloadStarted	67
		8.13.2.4	OnError	67
		8.13.2.5	SystemReady	67
8.14	Cohere	nt.UI.Ever	ntModifiersState Class Reference	67
	8.14.1	Detailed I	Description	67
8.15	Cohere	nt.UI.Ever	ntMouseModifiersState Class Reference	67
	8.15.1	Detailed I	Description	67
8.16	Cohere	nt.UI.FileF	Handler Class Reference	67
	8.16.1	Detailed I	Description	68
	8.16.2	Member I	Function Documentation	68
		8.16.2.1	ReadFile	68
		8.16.2.2	WriteFile	68
8.17	Cohere	nt.UI.HTT	PHeader Class Reference	68
	8.17.1	Detailed I	Description	68
	8.17.2	Property	Documentation	68
		8.17.2.1	Content	68
		8.17.2.2	Field	69
8.18	Cohere	nt.UI.ILog	Handler Class Reference	69
	8.18.1	Detailed I	Description	69
	8.18.2	Member I	Function Documentation	69
		8.18.2.1	Assert	69
		8.18.2.2	WriteLog	69
8.19	Cohere	nt.UI.Imag	geData Class Reference	69
	8.19.1	Detailed I	Description	70
	8.19.2	Member I	Function Documentation	70
		8.19.2.1	Destroy	70
		8.19.2.2	Update	70
8.20	Cohere	nt.UI.Bind	ling.InvalidValueCastException Class Reference	70
	8.20.1	Detailed I	Description	70
8.21	Cohere	nt.UI.KeyE	EventData Class Reference	70
	8.21.1	Detailed I	Description	71
	8.21.2	Property	Documentation	71
		8.21.2.1	IsAutoRepeat	71
		8.21.2.2	IsNumPad	71
		8.21.2.3	KeyCode	71
		8.21.2.4	Modifiers	71
		8.21.2.5	Type	71

CONTENTS

8.22	Cohere	ent.UI.MediaStreamDevice Class Reference				
	8.22.1	Detailed Description	71			
	8.22.2	Property Documentation	72			
		8.22.2.1 DeviceId	72			
		8.22.2.2 Name	72			
		8.22.2.3 Type	72			
8.23	Cohere	nt.UI.MediaStreamRequest Class Reference	72			
	8.23.1	Detailed Description	72			
	8.23.2	Member Function Documentation	72			
		8.23.2.1 Respond	72			
	8.23.3	Property Documentation	72			
		8.23.3.1 Devices	72			
8.24	Cohere	nt.UI.MouseEventData Class Reference	73			
	8.24.1	Detailed Description	73			
	8.24.2	Property Documentation	73			
		8.24.2.1 Button	73			
		8.24.2.2 Modifiers	73			
		8.24.2.3 MouseModifiers	73			
		8.24.2.4 Type	73			
		8.24.2.5 WheelX	73			
		8.24.2.6 WheelY	74			
		8.24.2.7 X	74			
		8.24.2.8 Y	74			
8.25	Cohere	nt.UI.ResourceData Class Reference	74			
	8.25.1	Detailed Description	74			
	8.25.2	Member Function Documentation	74			
		8.25.2.1 GetBuffer	74			
		8.25.2.2 GetSize	74			
		8.25.2.3 SignalFailure	75			
		8.25.2.4 SignalSuccess	75			
8.26	Cohere	nt.UI.ResourceResponse Class Reference	75			
	8.26.1	Detailed Description	75			
	8.26.2	Member Function Documentation	75			
		8.26.2.1 GetBuffer	75			
		8.26.2.2 SignalFailure	75			
		8.26.2.3 SignalSuccess	76			
8.27	Cohere	nt.UI.SurfaceResponse Class Reference	76			
	8.27.1	Detailed Description	76			
	8.27.2	Member Function Documentation	76			
		8.27.2.1 Signal	76			

CONTENTS

8.28	Cohere	nt.UI.Syst	nt.UI.SystemError Class Reference				
	8.28.1	Detailed I	Description	76			
	8.28.2	Property	Documentation	77			
		8.28.2.1	Error	77			
		8.28.2.2	ErrorCode	77			
8.29	Cohere	nt.UI.Syst	emSettings Class Reference	77			
	8.29.1	Detailed I	Description	77			
	8.29.2	Property	Documentation	78			
		8.29.2.1	CachePath	78			
		8.29.2.2	CookiesResource	78			
		8.29.2.3	CustomUserAgentString	78			
		8.29.2.4	D3DObject	78			
		8.29.2.5	FocusWindow	78			
		8.29.2.6	HostDirectory	78			
		8.29.2.7	HTML5LocalStoragePath	78			
		8.29.2.8	MinidumpFolder	78			
8.30	Cohere	nt.UI.Syst	emSettingsBase Class Reference	78			
	8.30.1	Detailed I	Description	79			
	8.30.2	Property	Documentation	79			
		8.30.2.1	AllowCookies	79			
		8.30.2.2	CustomUserAgentString	79			
		8.30.2.3	D3DInterfaceType	79			
		8.30.2.4	DebuggerPort	79			
		8.30.2.5	DisableWebSecurity	80			
		8.30.2.6	EnableProxy	80			
		8.30.2.7	EnableSupportForProprietaryCodecs	80			
		8.30.2.8	ForceDisablePluginFullscreen	80			
		8.30.2.9	UserAgent	80			
		8.30.2.10	WriteMinidumps	80			
8.31	Cohere	nt.UI.Touc	hEventData Class Reference	80			
	8.31.1	Detailed I	Description	81			
	8.31.2	Property	Documentation	81			
		8.31.2.1	HasRadiusInformation	81			
		8.31.2.2	$Id \ldots \ldots \ldots \ldots \ldots \ldots$	81			
		8.31.2.3	RadiusX	81			
		8.31.2.4	RadiusY	81			
		8.31.2.5	Type	81			
		8.31.2.6	x	81			
		8.31.2.7	Y	81			
8.32	Cohere	nt.UI.UISy	vstem Class Reference	81			

CONTENTS xi

	8.32.1	Detailed Description	82
	8.32.2	Member Function Documentation	82
		8.32.2.1 CreateView	82
		8.32.2.2 CreateView	82
		8.32.2.3 FetchSurfaces	82
		8.32.2.4 Uninitialize	82
		8.32.2.5 Update	83
8.33	Cohere	nt.UI.Binding.UnsupportedPrimitiveTypeException Class Reference	83
	8.33.1	Detailed Description	83
8.34	Cohere	nt.UI.URLRequest Class Reference	83
	8.34.1	Detailed Description	84
	8.34.2	Member Function Documentation	84
		8.34.2.1 AppendExtraHeaderValue	84
		8.34.2.2 Deny	84
		8.34.2.3 GetExtraHeader	84
		8.34.2.4 GetExtraHeaders	84
		8.34.2.5 GetMethod	84
		8.34.2.6 GetReferrer	85
		8.34.2.7 GetURL	85
		8.34.2.8 RemoveExtraHeader	85
		8.34.2.9 SetExtraHeader	85
		8.34.2.10 SetExtraHeaders	85
		8.34.2.11 SetMethod	85
		8.34.2.12 SetReferrer	85
		8.34.2.13 SetURL	86
8.35	Cohere	nt.UI.Binding.Value Class Reference	86
	8.35.1	Detailed Description	87
	8.35.2	Constructor & Destructor Documentation	87
		8.35.2.1 Value	87
		8.35.2.2 Value	87
		8.35.2.3 Value	87
		8.35.2.4 Value	88
		8.35.2.5 Value	88
		8.35.2.6 Value	88
		8.35.2.7 Value	88
		8.35.2.8 Value	88
		8.35.2.9 Value	88
		8.35.2.10 Value	89
		8.35.2.11 Value	90
		8.35.2.12 Value	90

xii CONTENTS

	8.35.3	Member Function Documentation	90
		8.35.3.1 Equals	90
		8.35.3.2 GetHashCode	90
		8.35.3.3 operator bool	90
		8.35.3.4 operator byte	90
		8.35.3.5 operator Dictionary< string, Value >	91
		8.35.3.6 operator double	91
		8.35.3.7 operator float	91
		8.35.3.8 operator int	91
		8.35.3.9 operator sbyte	92
		8.35.3.10 operator string	93
		8.35.3.11 operator uint	93
		8.35.3.12 operator Value[]	93
		8.35.3.13 operator!=	93
		8.35.3.14 operator==	94
	8.35.4	Member Data Documentation	95
		8.35.4.1 Type	95
8.36	Cohere	nt.UI.Binding.ValueObject Class Reference	95
	8.36.1	Detailed Description	95
8.37	Cohere	nt.UI.View Class Reference	95
	8.37.1	Detailed Description	98
	8.37.2	Member Function Documentation	98
		8.37.2.1 AuthCredentialsResponse	98
		8.37.2.2 BindCall	98
		8.37.2.3 CreateImageData	98
		8.37.2.4 Destroy	98
		8.37.2.5 DownloadUrl	98
		8.37.2.6 DrawSurface	99
		8.37.2.7 ExecuteScript	99
		8.37.2.8 FetchMouseOnUIQuery	99
		8.37.2.9 FetchSurface	99
		8.37.2.10 GetClickThroughAlphaThreshold	99
		8.37.2.11 GetCurentViewPath	99
		8.37.2.12 GetHeight	99
		8.37.2.13 GetLastFailedPath	00
		8.37.2.14 GetLastLoadedPath	00
		8.37.2.15 GetLastRequestedPath	00
		8.37.2.16 GetTargetFramerate	00
		8.37.2.17 GetViewType	00
		8.37.2.18 GetWidth	00

CONTENTS xiii

		8.37.2.19	HasMouseQueryFinished	101
		8.37.2.20	MEActivate	101
		8.37.2.21	MECancelComposition	101
		8.37.2.22	IMEConfirmComposition	101
		8.37.2.23	IMEIsActive	101
		8.37.2.24	MESetComposition	101
		8.37.2.25	InterceptURLRequests	102
		8.37.2.26	sMouseOnView	102
		8.37.2.27	SOnDemand	102
		8.37.2.28	ssueMouseOnUIQuery	102
		8.37.2.29	sTransparent	103
		8.37.2.30	KeyEvent	103
		8.37.2.31	KillFocus	103
		8.37.2.32	Load	103
		8.37.2.33	MouseActivate	103
		8.37.2.34	MouseEvent	103
		8.37.2.35	PeekFrameReady	103
			Redraw	
			RegisterForEvent	
		8.37.2.38	Reload	105
			ReplyToJavaScriptMessage	
			RequestFrame	
			RequestFrame	
			Resize	
		8.37.2.43	SetClickThroughAlphaThreshold	106
		8.37.2.44	SetFocus	106
			·	106
				106
				106
				106
				107
				107
			•	107
				107
				107
8.38				107
			•	108
	8.38.2			108
				108
		8.38.2.2	ErrorCode	108

XIV

8.39	Cohere	ent.UI.View	Info Class Reference	. 108			
	8.39.1	Detailed [Description	. 109			
	8.39.2	2 Property Documentation					
		8.39.2.1	ClickThroughAlphaThreshold	. 109			
		8.39.2.2	ControlTimeOnDemand	. 109			
		8.39.2.3	ForceSoftwareRendering	. 109			
		8.39.2.4	Height	. 109			
		8.39.2.5	IsOnDemand	109			
		8.39.2.6	IsTransparent	109			
		8.39.2.7	SupportClickThrough	109			
		8.39.2.8	TargetFrameRate	. 109			
		8.39.2.9	UsesSharedMemory	. 109			
		8.39.2.10	Width	. 110			
8.40	Cohere	ent.UI.View	Listener Class Reference	. 110			
	8.40.1	Detailed [Description	. 112			
	8.40.2	Member F	Function Documentation	. 112			
		8.40.2.1	CreateSurface	. 112			
		8.40.2.2	DestroySurface	. 113			
		8.40.2.3	OnBindingsReleased	. 113			
		8.40.2.4	OnCallback	. 113			
		8.40.2.5	OnCaretRectChanged	. 113			
		8.40.2.6	OnCertificateError	. 113			
		8.40.2.7	OnCursorChanged	. 114			
		8.40.2.8	OnDraw	. 114			
		8.40.2.9	OnError	. 114			
		8.40.2.10	OnFailLoad	. 114			
		8.40.2.11	OnFileSelectRequest	. 115			
		8.40.2.12	OnFinishLoad	. 115			
		8.40.2.13	OnGetAuthCredentials	. 115			
		8.40.2.14	OnIMEShouldCancelComposition	. 115			
		8.40.2.15	OnJavaScriptMessage	. 115			
		8.40.2.16	OnNavigateTo	. 116			
		8.40.2.17	OnReadyForBindings	. 116			
		8.40.2.18	OnRequestMediaStream	. 116			
		8.40.2.19	OnScriptMessage	. 116			
		8.40.2.20	OnStartLoading	. 116			
		8.40.2.21	OnStopLoading	. 117			
		8.40.2.22	OnTextInputTypeChanged	. 117			
		8.40.2.23	OnURLRequest	. 117			
		8.40.2.24	OnViewCreated	. 117			

CONTENTS xv

	8.40.2.25 Release				
8.40.3	Event Documentation				
	8.40.3.1 BindingsReleased				
	8.40.3.2 Callback				
	8.40.3.3 CaretRectChanged				
	8.40.3.4 CertificateError				
	8.40.3.5 CursorChanged				
	8.40.3.6 Draw				
	8.40.3.7 Error				
	8.40.3.8 FailLoad				
	8.40.3.9 FileSelectRequest				
	8.40.3.10 FinishLoad				
	8.40.3.11 GetAuthCredentials				
	8.40.3.12 IMEShouldCancelComposition				
	8.40.3.13 JavaScriptMessage				
	8.40.3.14 NavigateTo				
	8.40.3.15 ReadyForBindings				
	8.40.3.16 RequestMediaStream				
	8.40.3.17 ScriptMessage				
	8.40.3.18 StartLoading				
	8.40.3.19 StopLoading				
	8.40.3.20 TextInputTypeChanged				
	8.40.3.21 URLRequest				
	8.40.3.22 ViewCreated				
8.41 Coher	ent.UI.ViewListenerBase Class Reference				
8.41.1	Detailed Description				
8.41.2	Member Enumeration Documentation				
	8.41.2.1 MessageLevel				

121

Index

Chapter 1

Introduction

This guide describes the features of the Coherent UI integration in Unity3D. A basic understanding of the Unity3D engine, as well as HTML/JavaScript is assumed. Having basic knowledge of the C++ API and design of Coherent UI may be advantageous. To familiarize yourself with Coherent UI, please read the main documentation file or visit Coherent UI website.

1.1 Brief overview of Coherent UI

Coherent UI is a modern user interface middleware solution that allows you to integrate HTML pages built with CSS and JavaScript in your game. The communication between your game and the HTML engine is done through the UI System component. Each HTML page is called a View. The View component allows you to perform operations on the page, such as resizing, navigating to a different URL, sending input events, executing custom JavaScript code and so on. You can create a view through the CreateView method of the UI System component. It requires you to supply some initialization parameters, such as width, height, initial URL, etc. It also requires an instance of a View Listener. Coherent UI is highly asynchronous by design, meaning that when you change the URL of a View, for example, the function will return immediately and you will receive a notification when the URL has actually changed. The ViewListener is the class that receives such notifications for a specific view - when the URL was changed, the page you're trying to open requires authentication details, etc.

1.2 Differences between Desktop and Mobile version

Coherent UI can be divided conceptually in two libraries - Coherent UI Desktop (for Windows & MacOSX) and Coherent UI Mobile (for iOS and Android). Due to platform limitations the two have a different subset of features. Namely the Mobile version has some limitations while the Desktop version is fully featured.

Warning

The current version of Coherent UI for Android has known issues when using the software keyboard alongside with Unity's one. Keyboards other than the default may not work as expected (e.g. Swype).

Mobile limitations on Coherent UI Mobile include:

- You are only able to create 2D views on-top of your game for HUDs or in-game browsers. Views splatted on 3D surfaces in the game world are not supported due to platform limitations on iOS and Android.
- Input management must be implemented through minor changes in the HTML & JS and is not pixel perfect but HTML element-based.
- · Bound objects are currently missing from the binding
- · No on-demand views and frame-rate control

2 Introduction

• When writing scripts, the IDE's autocompletion will use the API for the Desktop version. There are a few methods that are available only for Desktop and others only for Mobile, so you won't see the mobile ones in your code editor. The classes for the mobile version are named the same as the desktop version but they're in a different namespace, *Coherent.UI.Mobile*. You can inspect the objects in that namespace to check the availability of the method you're looking for. In MonoDevelop you can inspect an object by using the "Go to declaration (F12)" feature.

Other that that the API has been kept 100% compatible between the Desktop & Mobile versions. The Core binding, Resource management and View management are the same. *Coherent UI Mobile* supports both device builds and simulator ones.

Chapter 2

Installation

Coherent UI for Unity3D is distributed in a **unitypackage** file. You can import this package in your project by either double-clicking on it, or by importing it through Unity in the *Project* window.

Note

Versions 1.5.3 and prior: After importing the package, you have to **install** the assets provided. This is done by the $Assets \rightarrow Coherent UI \rightarrow Install Coherent UI$ menu entry.

Versions 1.5.4 and later: The install step required for previous versions was removed in Coherent UI 1.5.4. The new structure places the UI Resources inside the WebPlayerTemplates folder since it's the only one that Unity ignores when compiling scripts. The files placed there are not actual web player templates but a collection of HTML/CSS/JS files that are used by the samples. These files won't interfere with actual Web Player Templates as long as there is no file named *index.html*. The default UI Resources path is no longer set (the installation step in previous versions did that) and the default file handler will try to find the assets in the WebPlayerTemplates folder when ran in the **Editor**. For built games you **must** set the UI Resources path using the $Edit \rightarrow Project Settings \rightarrow Coherent UI \rightarrow Select UI Folder entry.$

2.1 Prerequisites

- Unity3D 3.5.7 or later is required
- · Only Pro version of Unity is supported
- Coherent UI Mobile supports iOS 5.1 and above.
- Coherent UI Mobile supports Android 3.0 and above (API level 11).
- Mobile versions of Coherent UI SDK for Unity3D work with the free version, but the Preview feature will not work.
- Java Development Kit (JDK) is required for exporting to Android. Referring to the folder you installed JD-K in as <JDK>, you need to have the <JDK>/bin folder in your PATH environment variable and set the JAVA_HOME environment variable to <JDK>.

Note

Coherent UI SDK has different requirements than the requirements for Unity3D. Unity supports older hardware via fallbacks, which may prevent Coherent UI SDK from running on older graphics cards. Please make sure that the requirements of Coherent UI SDK match your client requirements for the project.

2.2 Package contents and structure

The package has the following structure:

4 Installation

- CoherentUI contains the UI debugger, samples, and documentation.
- CoherentUI/Editor contains editor classes for displaying the properties of Coherent UI components plus a
 post-build step class. These classes provide utility functionality.
- · Plugins contains the Coherent UI libraries. These are automatically copied when building.
- Standard Assets/Scripts/CoherentUI contains the Coherent UI integration classes. You'll find a Detail folder inside which contains classes that are internal for the implementation and are used by the "public" classes. The interface you should be using is outside the Detail folder.
- StreamingAssets contains assets that need to be copied as-is in the build directory. These include the Coherent UI host process executable, the libraries it needs, locales and UI resources.

2.3 Usage of the package

After importing the *CoherentUI.unitypackage* in your project, the two main scripts you'll be using are *Standard Assets/Scripts/CoherentUI/CoherentUISystem* and *Standard Assets/Scripts/CoherentUI/CoherentUIView*. The easiest way to use Coherent UI is to drag the CoherentUIView component onto an object and hitting Play that's it! Everything will be up and running. Actually, you can do the same for most of the usage scenarios - just drag the component and then configure it in the inspector. Here's a bit more detail about the two scripts.

The first script, CoherentUISystem, defines initialization parameters of the Coherent UI System and should be placed no more than once in your project. The UI system is meant to be initialized in the first scene and live throughout the game's lifetime. You need to add this component to your scene only if you need custom initialization of the Coherent UI System. For the most cases, using only CoherentUIViews is enough - they will automatically create an instance of the Coherent UI System for you with reasonable default parameters. Check CoherentUISystem Lifetime for details.




Figure 2.1: CoherentUISystem properties

The second script, <code>CoherentUIView</code>, will represent a single HTML page. This is the component that renders your CSS and JavaScript animations and makes your game alive. This component can be placed on any object that is renderable and serves as its material. When placing it on an object all the needed components are automatically created, hidden from you, and the rendered output is bound to the mainTexture of a new material that is created at runtime. This material is set as the gameObject's renderer material so that you see the page rendered on your object.




Figure 2.2: CoherentUIView properties

You can also place views on cameras. When doing so, you get your page rendered on the whole viewport of the camera. This way you can easily add a heads-up display for your game. Don't forget to mark your HUD as transparent and make your HTML page transparent! There's even an option for drawing the HUD after the post-effects if you like (The option is available for non-HUDs, too, but it results in a no-op because it doesn't make sense).

2.4 Switching between build targets

Coherent UI Mobile has different properties and a restricted subset of features compared to the desktop versions. To switch between the desktop features and the mobile ones you must switch the current active target in Unity. This is done by clicking on File->Build Settings selecting the target platform and clicking "Switch Platform". After doing so the properties of the Views will change to reflect their capabilities specific to the selected platform. Even if the current target is iOS or Android and hence you'll build with Coherent UI Mobile you can still preview your game in the Editor. The preview will use the desktop version of Coherent UI. Keep in mind that in this case you might see some differences compared to the the mobile device after the build as the desktop version has more features. You should check often how your UI behaves and looks on the device itself (or the simulator).

6 Installation

2.5 Trial version registration

The trial version of Coherent UI for Unity3D requires a simple registration. The registration requires:

- the email you used for downloading Coherent UI
- · internet connection
- · outgoing connections to port 3000 to be allowed in your firewall

The registration is started automatically when you run the game. It shows a simple form that asks for your email.

You can register Coherent UI on multiple machines, provided that they run different operating systems.

Games exported with the trial version of Coherent UI also require registration. This means if you want to run your built game on a different computer, you'll have to register Coherent UI on that computer, too. When building a game using the trial version of Coherent UI the activator is packaged as well and ran when the game is started. For manual activation, copy the *CoherentUI/Activator* folder from your Unity3D project to the machine and run:

```
Activator.exe --unity3d --host \
"<FULL PATH TO GAME DATA FOLDER>/StreamingAssets/CoherentUI_Host/windows"
```

on Windows and:

```
Activator.app/Contents/MacOS/Activator --unity3d --host \
"<FULL PATH TO GAME APP>/Contents/Data/StreamingAssets/CoherentUI_Host/macosx"
```

on Mac OS X.

Chapter 3

Samples

Note

Some samples show Desktop-specific features while others focus on Mobile targets

The samples provide a starting point for you. They are located in Assets/CoherentUI/Samples and the required scripts are already configured.

The samples are based on a simple scene we've set up for you. The scene consists of a light, a floor, a cube, and a FPS controller so you can move around. There are a few key points in the base sample you should be aware of.

- The FPS controller's MouseLook script has been modified a bit you can toggle if it's active using the **Alt** key. This was done for convenience so you can navigate over the page, projected on the cube easily, without looking around. The CharacterMotor script has also been modified for the same reason.
- The cube's faces all have MeshCollider components. They are needed by Unity to produce texture coordinates in the raycast hit info. The texture coordinates, in turn, are needed to calculate the position of the hit point on the Coherent UI View.
- The scenes that have interactive Coherent UI surfaces placed on objects use the *Click-to-focus* feature of the Coherent UI View. It allows the user to forward input to the view when she clicks on it and stop forwarding it when she clicks outside.

Note

In the case where the mesh collider does not coincide with the actual geometry of the object, the raycast and coordinate calculation must take place in the user code. In the samples we're only using simple geometry that is the same as the mesh collider so no further work is needed.

3.1 Hello, Coherent UI

Just hit play - and you'll see a rotating cube and a sign, saying "Hello, Coherent UI". The sample demonstrates the easiest possible setup for Coherent UI for Unity3D. The scene is made of a cube in front of the camera with a script that rotates it, and a Coherent UI component attached to the main camera. The component's URL is set to a local resource using our special coui:// protocol and the "Transparent" checkbox is ticked. You can preview the page displayed in your browser to see what you can expect.

Note

The **coui** protocol uses the folder selected by the $Edit \rightarrow Project\ Settings \rightarrow Coherent\ UI \rightarrow Select\ UI\ folder$ menu item as a root for a virtual file system.

You can also add a *CoherentUIView* component to a 3D object if you like. To do so, locate the *CoherentUIView* script under **Standard Assets/Scripts/Coherent UI/CoherentUIView** in the *Project* window and then add it to the object of your choice. In Unity3D 4.x you can do that from the inspector windows by clicking "Add component".

Here's a sample where a Coherent UI View component is added to a cube. Make sure you tick the "Click to focus" checkbox for the view to get input forwarding easily.




Figure 3.1: CoherentUIView on a texture

You can also try pages that show dialog boxes, such as

- http://www.w3schools.com/js/tryit.asp?filename=tryjs_alert
- http://www.w3schools.com/js/tryit.asp?filename=tryjs_confirm
- http://www.w3schools.com/js/tryit.asp?filename=tryjs_prompt
- http://www.httpwatch.com/httpgallery/authentication/ (scroll down and click Display Image)

If you do not handle the Listener events for dialog boxes by yourself they will be handled automatically by Coherent UI.




Figure 3.2: CoherentUIView showing a prompt

3.2 Facebook integration

This sample uses a facebook application that shows some of your photos in a rotating circle. You'll see how to customize the View and ViewListener behaviour to suit your needs.

Note

If you're having trouble displaying the local resources, make sure you have selected the *UIResources* folder located in the root of the project using the $Edit \rightarrow Project\ Settings \rightarrow Coherent\ UI \rightarrow Select\ UI\ folder\ menu$ in the editor. This folder will be used for resources addressed with <code>coui://links</code>.




Figure 3.3: CoherentUIView Facebook integration sample

You will find a new script - FacebookSampleScript. We need to modify the default behaviour of Unity-ViewListener for this sample. The key points are:

- In its Start method the FacebookSampleScript obtains the CoherentUIView component in the game object.
- In the Start method the script also attaches to the CoherentUIView.OnViewCreated event to enable intercepting URL requests and to the UnityViewListener.URLRequest event to redirect the Facebook login URL to the local HTML page.

This is the easiest way to handle events provided by the <code>UnityViewListener</code>. Another option is to derive the <code>UnityViewListener</code> and <code>CoherentUIView</code> but that is unnecessary.

The FacebookSampleScript.OnURLRequestHandler checks if the requested URL is the one that was registered in the Facebook Application settings (this might be any made up URL). If that's the case, we redirect it to the local page that uses our Facebook application. You will find the page we're redirecting to in the sample project folder under FacebookSample/facebook.html.

Now that we've explained what the class does, the only thing left is to hit play. You can press **Alt** to stop moving/looking so you can browse in the Facebook application.

3.3 Menu And HUD

This sample shows a game menu and HUD built with Coherent UI.

3.3 Menu And HUD

Note

If you're having trouble displaying the local resources, make sure you have selected the *UIResources* folder located in the root of the project using the $Edit \rightarrow Project \ Settings \rightarrow Coherent \ UI \rightarrow Select \ UI \ folder \ menu$ in the editor. This folder will be used for resources addressed with coui:// links.

Double-click the *Menu* scene in the Project window (located in *Scenes*) to make it active, if it isn't already. In the *Menu* scene we have a MenuScript component attached to the camera. MenuScript does three things:

- sends the mouse position to the view every Update ()
- · registers the handlers for clicking on a menu button
- loads the game when the "New Game" button is clicked

Note

You have to add the game scene to the build settings of your project so Unity3D can load it.

In the game, we have another component for controlling the view - HUD, this time implemented in *UnityScript*. Each frame the component updates the compass orientation, based on its transformation.

In addition to updating the compass, the HUD component takes care of disabling the <code>CharacterMotor</code> component when the focus is on a <code>Click-to-focus</code> view. The HUD script attaches to <code>CoherentUISystem::On-ViewFocused</code> event and changes the <code>canControl</code> property of the selected <code>CharacterMotor</code> whenever a <code>Click-to-focus</code> view gains or loses focus. This allows typing in the focused view without moving the character. Here is the HUD component in code:

```
#pragma strict
#if UNITY_STANDALONE || UNITY_STANDALONE_WIN || UNITY_STANDALONE_OSX || UNITY_EDITOR
import Coherent.UI.Binding; // to use View.TriggerEvent with extra arguments
private var View : Coherent.UI.View;
private var CurrentDirection : float;
// CharacterMotor component to be disabled when a Click-To-Focus view has gained focus
public var characterMotor : CharacterMotor;
function Start () {
    var viewComponent = GetComponent(typeof(CoherentUIView)) as CoherentUIView;
    viewComponent.OnViewCreated += this.ViewCreated;
    viewComponent.OnViewDestroyed += this.ViewDestroyed;
    CurrentDirection = 0:
    var uiSystem = Component.FindObjectOfType(typeof(CoherentUISystem)) as CoherentUISystem;
    // get notified when a Click-to-focus view gains or loses focus
    uiSystem.OnViewFocused += this.ViewFocused;
function ViewCreated(view : Coherent.UI.View) {
    View = view;
    var viewComponent = GetComponent(typeof(CoherentUIView)) as CoherentUIView;
    Debug.LogWarning(String.Format("View {0} created", viewComponent.Page));
function ViewDestroyed() {
    View = null;
function ViewFocused(focused : boolean) {
    if (characterMotor)
        // enable or disable the character movements
        characterMotor.canControl = !focused;
function Update ()
    if (View != null)
        var direction = this.transform.rotation.eulerAngles.v;
        if (Mathf.Abs(direction - CurrentDirection) > 2)
```

In the game scene we have one more component - ObjectPicker, that takes care of directing the input to the correct CoherentUIView. First it checks whether the mouse is on a HUD element and if it is not, then raycasts and checks whether the mouse is over the browser window. Make sure the "Support Click Through" checkbox is ticked on the HUD CoherentUIView - this allows you to detect whether the mouse is over a transparent area in the View. If the property is left unchecked the input will never reach any objects in the world, because the system will think that the mouse is always over the HUD.




Figure 3.4: CoherentUIView HUD sample in action

3.4 Binding Demo

This sample will demonstrate communication between Unity3D and JavaScript used by the HTML page loaded in a Coherent UI View.

Note

If you're having trouble displaying the local resources, make sure you have selected the *UIResources* folder located in the root of the project using the $Edit \rightarrow Project$ Settings \rightarrow Coherent $UI \rightarrow$ Select UI folder menu in the editor. This folder will be used for resources addressed with coui: // links.

The sample shows a simple options dialog. The options are passed from JavaScript to Unity3D and back to exercise the binding. This walkthrough will give you a brief overview of the Coherent UI Binding fundamentals but be sure

3.4 Binding Demo 13

to check out the Binding section in this guide, as well as the **Binding for .NET** section in the general reference document.

Note

This sample guide is written for C# Unity3D scripts

First, when passing custom object types between Unity3D and JavaScript, you must first inform Coherent UI about the data in the type. You can do that using the CoherentType attribute:

```
using Coherent.UI.Binding;

// all properties / fields for Options will be visible to Coherent UI
[CoherentType(PropertyBindingFlags.All)]
public struct GameOptions
{
    public string Backend;
    public uint Width;
    public uint Height;

    public string Username
    {
        get {
            return System.Security.Principal.WindowsIdentity.GetCurrent().Name.ToString();
        }
    }

    // rename the NetPort property to NetworkPort
    [CoherentProperty("NetworkPort")]
    public uint NetPort { get; set; }
}
```

Now the <code>GameOptions</code> structure will correspond to a JavaScript object having the same properties. Note that you can rename a property using the <code>CoherentProperty</code> attribute. In this case, the "NetPort" property will correspond to "NetworkPork" in JavaScript.

After exposing the properties, we need to register some event handlers. This can be done in two ways. The first way to bind event handlers is to add a handler for the <code>ReadyForBindings</code> event of the <code>UnityViewListener</code> (manual binding). The second way (.NET only) is to add a <code>CoherentMethod</code> attribute to the method you want to bind (automatic binding). See the <code>CoherentMethod</code> section in this guide for more details.

Note

The sample provides two scripts for binding - ManualBinding.cs and AutomaticBinding.cs. Make sure that only one of those scripts is active when exploring the sample.

We'll explore the manual binding first. Start by registering a handler for ReadyForBindings:

```
m_View = GetComponent<CoherentUIView>();
m_View.Listener.ReadyForBindings += HandleReadyForBindings;
```

The handler would look like this:

Now, when JavaScript calls engine.call ("ApplyOptions", options), Unity3D will execute its handler - namely the (Action<GameOptions>) this.ApplyOptions method registered above.

The options structure passed as a parameter looks like this:

```
function onApplyButton() {
    var options = {};
    options.__Type = "GameOptions";
    options.Backend = $("#backend").text();
    options.Width = Number($("#gameWidth").val());
    options.Height = Number($("#gameHeight").val());
    options.Username = $("#user").text();
    options.NetworkPort = Number($("#netPort").val());

    // This will call the C++ engine code with the just created structure. It'll be correctly populated engine.call("ApplyOptions", options);
}
```

Note that there is one "internal" property - __Type. This property defines the mapped type and is essential for correct behavior of the binding provided by Coherent UI.

The "ApplyOptions" handler just bounces the options back to JavaScript:

```
public void ApplyOptions(GameOptions options)
{
    m_View.View.TriggerEvent("gameConsole:Trace", options);
}
```

gameConsole: Trace will dump the options object in the console.




Figure 3.5: Binding sample in action

The automatic binding saves us the first two steps - instead of registering a handler in the UnityViewListener callback you can decorate a method with the CoherentMethod attribute:

```
[Coherent.UI.CoherentMethod("ApplyOptions", false)]
public void ApplyOptions(GameOptions options)
{
    m_View.View.TriggerEvent("gameConsole:Trace", options);
```

3.4 Binding Demo 15

The first argument of the attribute is the JavaScript function that we're binding. The second defines whether the function is an *event* (opposed to a *call - calls* are single-cast only).

Returning a value to JavaScript

Calls can also return a value. Let's inspect the "GetLatency" binding:

```
// By default, the second argument of CoherentMethod is false
[Coherent.UI.CoherentMethod("GetLatency")]
public int GetNetworkLatency()
{
    // not actual latency :)
    return (int)UnityEngine.Random.Range(0, 1000);
}
```

Since the execution of JavaScript is **not** synchronous you will receive the result in a callback. Coherent UI provides a promise/future pattern for convenience. This is the "GetLatency" JavaScript call in all its glory:

```
function getLatency() {
   engine.call("GetLatency").then(function() {
        $("#latency").text(arguments[0]);
   });
}
```

As you can see from the script, the value returned by Unity3D will be passed to the callback as an argument.

Method Binding

This sample also shows how to use binding of .Net methods. For detailed explanation see "Exposing Methods" in the "Binding for .Net" chapter in the API documentation.

The sample exposes an instance of MyMath to JavaScript.

```
class MyMath
{
    public double Sum(double[] numbers)
    {
        return numbers.Sum();
    }
    public double Average(double[] numbers)
    {
        return numbers.Average();
    }
}
```

When the game is up and running, we request the MyMath instance, store it as a global object and register two console commands that use it.

```
engine.on('Ready', function () {
              //get the exposed MvMath object
              engine.call('GetMath').then(function (math) {
                              // store reference to the object
                            window.MyMath = math;
                              // register commands for the console
                            engine.trigger('gameConsole:AddCommand', 'sum', 'computes the sum of its arguments', function (line
                                            var numbers = line.split(/\s+/).map(Number);
                                            numbers.splice(0, 1);
                                            window.MyMath.Sum(numbers).then(function (sum) {
                                                          engine.trigger('gameConsole:Trace', 'The sum of', numbers, 'is', sum);
                                            });
                            });
                             engine.trigger('gameConsole:AddCommand', 'avg', 'computes the average of its arguments', function (its arguments') and the state of t
                      line) {
                                            var numbers = line.split(/\s+/).map(Number);
                                           numbers.splice(0, 1);
                                            window.MyMath.Average(numbers).then(function (avg) {
```

To try out the commands press \sim to open the game console and type sum 40 2.

Events

When you need multiple handlers for a JavaScript function you need to register an *event*. This can be done by the Coherent.UI.View.RegisterForEvent method for manual binding

```
m_View.View.RegisterForEvent("ViewReady", (Action)this.ViewReady);
```

and passing true as a second parameter of the CoherentMethod attribute for automatic binding.

```
[Coherent.UI.CoherentMethod("ViewReady", true)]
public void ViewReady()
{
    // show the options
    m_View.View.TriggerEvent("OpenOptions", m_GameOptions);
}
```

Bear in mind that events cannot return a value.

If you want to handle an event in JavaScript, you need to register a handler using the engine.on call.

```
engine.on('OpenOptions', function (options) {
    // Open an options dialog
});
```

An event can be triggered by JavaScript by using

```
engine.trigger("EventName", eventArgs);

or by Unity3D using

m_View.View.TriggerEvent("EventName", eventArgs);
```

This concludes the binding demo walkthrough.

where m_View is CoherentUIView.

3.5 Archive resource

This sample demonstrates reading resources from an archive through a custom file handler.

The scene is just a simple camera that has an attached <code>CoherentUIView</code> component and another one that forwards input to the view. The important component for this sample is <code>CustomFileHandlerScript</code>. It sets the <code>CoherentUISystem</code> factory function object in its <code>Awake</code> method so the system is initialized with the custom handler.

```
void Awake()
{
    CoherentUISystem.FileHandlerFactoryFunc = () => { return new CustomFileHandler("UIResources", "
    ArchiveResource.tar"); };
}
```

In fact, that's all the component has to do - set the <code>CoherentUISystem.FileHandlerFactoryFunc</code> prior to any <code>Start</code> method being called. The returned <code>CustomFileHandler</code> is the class that does the actual reading/writing. The methods the user needs to implement are:

3.6 Mobile Input

```
public override void ReadFile (string url, Coherent.UI.ResourceResponse response)
{
    ...
}
public override void WriteFile (string url, Coherent.UI.ResourceData resource)
{
    ...
}
```

They will be called for all coui://links and for the cookies (if enabled).

Note

When reading/writing cookies, you may receive a URL that has a file://scheme.

The input URL can be interpreted in any way you see fit for your handler. In the example we try to open the link *coui://UIResources/mainmenu/menu.html*. The *mainmenu/menu.html* is actually compressed in an archive. First we verify that the host part of the URL (*UIResources*) is what we expect for compressed resources and then proceed to search the archive for the resource.

Since Coherent UI supports asynchronous reading/writing of resources, when done with the I/O operations, you must use the ResourceResponse or ResourceData object to signal the outcome. You can do that by using the SignalSuccess and SignalFailure methods.

Note

At the moment the data you read/write must be converted to a native buffer before usage. This is done with the System.Runtime.InteropServices.Marshal class. Here's a short snippet that reads a file and then copies the managed buffer in an unmanaged buffer provided by the ResourceResponse object:

```
public override void ReadFile (string url, Coherent.UI.ResourceResponse response)
{
    byte[] bytes = File.ReadAllBytes(url);
    IntPtr buffer = response.GetBuffer((uint)bytes.Length);
    if (buffer == IntPtr.Zero)
    {
        response.SignalFailure();
        return;
    }
    Marshal.Copy(bytes, 0, buffer, bytes.Length);
    response.SignalSuccess();
}
```

Make sure you check out the code in CustomFileHandlerScript for a complete example.

3.6 Mobile Input

Warning

Unity3D 3.5 doesn't support native plugins for iOS simulator builds. There are a couple of articles explaining how to workaround this limitation, but the most helpful is http://tech.enekochan.-com/2012/05/28/using-the-xcode-simulator-with-a-unity-3-native-ios-plug-in/

We have added a script with a post-process step that tries to fix the project, so it can be used with the iOS simulator. The script is in Editor/iOSSimulatorProjectFixer.cs.

This sample demonstrates how you can control what part of the input is forwarded to Unity3D by using JavaScript. The sample starts with an overlay that has 3 buttons on the left side, area for testing input forwarding on the right, and a red box in the world. The buttons enable/disable the input forwarding for touches on the right side of the overlay and the third one bumps the box upwards. When you touch the box a little force is applied and it should move forward as if you pushed it. If you touch the box in the right area of the overlay the force is applied only if input forwarding is enabled.

There are also buttons for toggling the overlay and mouse look controller in the top left corner for convenience.

Warning

The HTML code for the sample is not designed for small displays so it may look out of proportion on a phone or a phone simulator. You can try lowering the font size in the accompanying *css* file.

Note

The Coherent UI View used has its input state set to "Transparent". If you set it to "Take all" input is consumed before reaching Unity3D and if you set it to "Take none" it is sent directly to Unity3D.

Warning

Unfortunately, at the moment you can't see the actual behavior of the sample in the Unity3D Editor. Input is handled differently for the standalone and mobile versions so it recommended that you test your project either on a mobile device or an emulator.

Code-wise speaking, when you make a touch on a "Transparent" Coherent UI View, the engine.checkClick—Through function is called. You can check its code in coherent.js. Basically it obtains the DOM element from the touch coordinates and begins a series of checks. First, if the element is the document body or has the coui-noinput class, input is directly sent to the client (Unity3D). Otherwise, the element is checked for having a coui-inputcallback class. If it does, the element's couiInputCallback is invoked which determines whether the input is forwarded or consumed; if it doesn't have such class, input is consumed.

The sample enables/disables the input forwarding on the right area by removing/adding the **coui-noinput** class to the corresponding DOM element. In this sample, only the DOM element for the right area has the class **coui-inputcallback** and its <code>couiInputCallback</code> function is set when the engine has signaled it's ready. The function itself doesn't do anything special, it just always <code>returns true</code>, meaning that the input is consumed in JavaScript and never sent to the client (Unity3D).

You can also bump the box upwards which is a demonstration for the binding for Coherent UI Mobile. It's very much the same as binding for .NET/Unity3D standalone so we'll not go in detail here.

Summing up:

- if you want the input forwarded to the client when touching an element, simply add the **coui-noinput** class to the element.
- if you want an element to consume input, ensure that it does **not** have the **coui-noinput**.
- if you want to have custom processing over an element, ensure that it does **not** have the **coui-noinput**, add a **coui-inputcallback**, and add a function <code>couiInputCallback</code> which ultimately returns true if you want to consume the input or false if you want to forward it to the client.

Note that for obtaining the element below the touch point we're currently using <code>document.elementFrom-Point</code>. In the sample, the right area is represented by a <code><div></code> and there's some text inside it as a child element. Only the <code><div></code> has the <code>coui-inputcallback</code> class. If you touch the text its element will be checked for the <code>coui-inputcallback</code> class and since it doesn't have one input will be consumed. Since we want to apply the logic for all touches inside the area this presents a problem. One solution is to add the <code>coui-inputcallback</code> class to all child elements and set their <code>couiInputCallback</code> functions to the same variable. Another solution is to use the <code>pointer-events CSS</code> property on the children elements, e.g.:

```
#menu-right > *
{
    pointer-events: none;
}
```

This is how the sample solves the problem. Note that this is an experimental CSS property and prevents elements from being the target of pointer events. This is fine in the sample but may have adverse effects in your code so use it with caution.

3.7 Oculus 19

3.7 Oculus

Note

It is not possible to create a sample scene for Oculus Rift for Unity3D 3.5 using the official Oculus SDK. So our Oculus Rift sample scene is created with Unity3D 4 and can not be packaged in our asset store packages. You can download a package with the scene from: https://s3.amazonaws.com/CoherentLabs/-Public/Coherent_UI_Oculus_Sample.unitypackage

This sample demonstrates how you can create UI elements in your games for the Oculus Rift, using the CoherentUI and OculusVR integrations in Unity. The focus of the sample is on creating a HUD element that can be used with the Oculus headset.

Note

You should include the Oculus integration package for Unity in order to use Oculus in Unity3D (you need a Unity Pro 4.01 or higher version). For more information about the Oculus SDK and its integration with Unity, please visit http://www.oculusvr.com/.

You can get Oculus ready for use in Unity by following these steps:

- go to the official website of Oculus Rift http://www.oculusvr.com/;
- · download OculusUnityIntegration.unitypackage from there;
- open an Unity3D instance and go to Assets -> Import Package -> Custom Package. When the dialog box
 for choosing packages opens, go to the place with the downloaded package and select it. A new dialog box
 with a list of the files for import will open. Choose 'Import All'. After completing this step you should be able
 to see a new menu 'Oculus'.

Now we are ready to proceed with the sample. As you can see, there is an OVRPlayerController in the *Scene* menu (it can be added from Oculus -> Prefabs -> OVRPlayerController). The controller is comprised of two things: a simple character controller and another OVR prefab - OVRCameraController. The latter is used as an interface between Unity and the two cameras. Double-click it to reveal its children objects. Double-clicking the OVRCamera-Controller will show the cameras and a plane object attached to the right camera. This plane is used as a surface for drawing the HUD. There is an CoherentUIView component attached to it, which uses coui://UIResources/Menu-AndHUD/hud/hud.html as a page. It is suggested that for drawing HUD elements you attach the surface to the right camera for optimal results.

Note

To render a view on top of everything, we put an check mark in 'IsIndependentOfZBuffer'.

Warning

Whenever using a plane as a surface for views, choose a material for the plane and use a 'Transparent/Diffuse' shader for it.

This is basically all you need to draw the HUD. Hit play to see the result

3.8 Mobile Surface

The Mobile Surfaces sample shows how to use Coherent UI views on surfaces for mobile platforms. The sample shows a texture with a Coherent UI view on it that is rotating. Every 100 frames the view is changed and the texture is updated by calling the 'UpdateView' method of the view.

Note

To achive transparency of the surface *both* - the *IsTransparent* property of the view should be checked **and** the shader of the material should be set to *Transparent/Diffuse*.

3.9 Live Game Views

Note

Live Game Views are a Desktop-only feature.

The sample shows a simple scene with a Live Game View. The scene consists of a "game world" with a plane as ground, four rotating colored cubes and a light.

On the main Camera a Coherent UI View is attached that serves as an in-game HUD(heads-up-display). The Live Game View is part of the HUD. A Coherent UI Live Game View component is also attached to this camera and hence to the UI - it is the "link" between the View and the provider of the 3D images.

A second camera is fixed on the cubes and provides the source data. Everything this camera renders is automaticcally sent to the UI View linked to it as a dynamic "ImageData" object in the UI JavaScript Code. The HUD.html page draw the Live View with the following code:

```
window.onload = function() {
   var c = document.getElementById("myCanvas");
   c.onEngineImageDataUpdated = function (name, image) {
     var c = document.getElementById("myCanvas");
     var ctx = c.getContext("2d");

     ctx.clearRect(0, 0, c.width, c.height);
     ctx.putImageData(image, 0, 0);
     ctx.fillStyle = "white";
     ctx.font = "16pt Arial";
     ctx.fillText("Live Game View!", 15, 25);
   }
}
```

Every time a new frame is drawn by the "live" camera the "onEngineImageDataUpdated" is called on all "canvas" elements that define it in the page. There you can use the data in whatever fashion you need. In this sample we draw the image into the canvas and write some text on it. When you "Play" the game you'll see the four rotating cubes drawn in the HUD in the lower left corner as the "live" camera sees them.

Note that now the images of the camera are part of the UI DOM, so you can achieve all UI effects with it. The canvas elements can be animated, 3D transformed int the UI, post-effects can be applied on them, they can be interactive etc.

Via Live Game Views in a real game you can trivially have 3D animated unit portraits, animated items in the UI, 3D mini-maps, security cameras etc.

3.10 IME Sample

This sample demonstrates the usage of Input Method Editor for languages that require more complex input such as Chinese. To have IME enabled for a particular view you should just put a check on the *Enable IME* property of the **CoherentUIView** and this is all you need to do so as to have support for IME in your view.

Open the IME Sample, change your input language to one that requires IME, for example Chinese and hit play. Try to write something in the dialog that appears and hit 'Enter' or just press the 'Say' button. What you just wrote will appear in the dialog window.

Enabling IME does a few things:

- It subscribes for the OnCaretRectChanged, IMEShouldCancelComposition and OnTextInputControl-TypeChanged events.
- OnTextInputControlTypeChanged event is fired when the type of text input control changes. The method that subscribes for it determines from the new type of control whether IME composition mode in Unity should be turned off or on.
- OnCaretRectChanged event is fired when the caret has changed its position. It has arguments x and y for the top left position of the caret rectangle and width and height for its width and height, all of them measured in pixels, relatively to the view. Since in Unity you have to set the position of the candidate list window, this method is used for helping set the candidate window position on the screen.

3.10 IME Sample

Note

If you want to set the candidate window on a specific screen position or make the calculations on your own, you can subscribe with a method for the **CalculateIMECandidateListPosition** handler, which has the same arguments as OnCaretRectChanged and should return the desired position of the candidate window in screen space. Please note that (0, 0) for the IME cursor position in Unity is in the upper left corner in spite of bottom left.

22 Samples

Chapter 4

Programmer's API

The Unity API is an extension of the normal .Net API, and it is contained in the main API Reference documentation.

4.1 CoherentUISystem properties for Desktop

- Main Camera The main camera in the scene. This property is used only for Click to focus Views.
- **Host Directory** Path to the directory where the Coherent UI executable resides. This path can be relative to the resource path of the game (i.e. the *Assets* folder of the Unity3D project or the <YourGameName>_Data folder of the built game). By default it is *StreamingAssets/CoherentUI*.
- **Proxy** Enables proxy support by autodetecting the system settings. This detection is usually very slow and this setting should be enabled only when the user is behind a proxy and you're accessing the Internet.
- · Cookies Enables support for cookies.
- · Cookies file A file that will be used for reading and writing cookies when they are enabled.
- Cache path Path for saving cached data. Leave null for in-memory caching only.
- Local storage path Path for saving HTML5 page local storage data. Leave null to forbid local storage.
- Disable fullscreen plugins Disables fullscreen mode for all plugins (e.g. Flash, Silverlight, etc.)
- Disable web security Disable same origin policy. Use with caution.
- **Debugger port** The port that will be opened for the debugger to connect and debug your interface. A value of -1 means disabled.
- Support for Alt Tab Enables support for Alt and Tab in fullscreen DirectX9 applications for Windows. Due to restrictions in Dx9, it is necessary to reset Unity's graphics device in windowed mode before initializing UI System and after the system has been initialized and is ready, set reset it to fullscreen mode. If you uncheck this, the resets won't happen in fullscreen mode, but Alt+Tab functionality will not be supported.

The CoherentUISystem component also provides a static factory function object (FileHandlerFactory-Func) that the user can customize in order to make use of her own FileHandler. See the Custom file handler section for a detailed explanation.

4.2 CoherentUISystem properties for Mobile

- URL cache Decides if the device URL cache will be used.
- Memory cache size The maximum size of the in-memory cache.
- Disk cache size The maximum size of the disk cache.

24 Programmer's API

4.3 CoherentUIView properties for Desktop

- URL Indicates the URL that will be initially loaded.
- · Width The width of the Coherent UI View.
- · Height The height of the Coherent UI View.
- **Transparent** Defines if the View supports transparency.
- · Pre-load script The script will be executed before any other code in the UI View
- Smart input Available for transparent Views. Enables support for queries whether the cursor is over a transparent pixel. A transparent pixel is considered one that has an alpha value below or equal to the click-through alpha threshold.
- Smart input alpha A value in the range [0-1] inclusive that determines whether a pixel is transparent; A pixel is transparent if its alpha value is below or equal to the threshold.
- Lockable focus When enabled, the View takes the input focus when clicked and releases it when you click outside the View. See Click to focus Views
- Enable IME When enabled, this view will have Input Method Editor enabled for languages that have more complex input like Chinese.
- On Demand (Coherent UI Pro only) Provides perfect synchronization of the game frames and Coherent UI frames. Use this when you need to synchronize the game and the interface, e.g. when displaying name tags over the players. Using standard views may introduce a delay of a few frames.
- Timer override The UI uses the in-game timer (requires On-demand)
- Max. frame-rate (Coherent UI Pro only) Sets the maximum framerate for the View. The view will never exceed this framerate.
- **Draw order** Defines whether the View is drawn before or after the post-effects. Available for Views attached to cameras.
- Flip Y Flips the drawn image vertically.
- Auto UI messages When enabled, any event triggered in *JavaScript* on the engine object is forwarded to the game object containing the View.
- Enable [CoherentMethodAttribute] Enables the usage of the Coherent Method attribute
- Compensate gamma The View will have gamma corrected when linear color space is used. Whether you should use this property or not depends on the scene you are making are there any additional cameras, what kind of rendering path they use, etc. Generally, this property comes handy when you use linear color space and the view is attached to a camera with deferred lighting or if your main camera uses deferred lighting and the camera with the view does not.
- Always on top Indicates whether this value is z-buffer independent. If it is set to true, the view is rendered on top of everything.
- Show JS dialogs Automatically handle JavaScript messages and authentication requests. If enabled, a
 visual dialog will be shown; otherwise it's up to the programmer to make the appropriate response. If you do
 not respond to the message, the page will block until you do. Examine ViewListener.cs and CoherentDialog.cs
 for a sample reply logic.
- Software only rendering The View will be rendered without hardware acceleration.
- · Match camera size The View will be automatically resized to always match the size of the camera
- **Texture Filtering** The filtering mode used for rendering the views. The two available modes are Point Filtering and Linear Filtering. (View Filters Desktop only)

4.4 CoherentUIView properties for Mobile

- URL Indicates the URL that will be initially loaded.
- · Width The width of the Coherent UI View in pixels.
- Height The height of the Coherent UI View in pixels.
- X Position The X of the Coherent UI View position relative to the upper-left corner of the device screen.
- Y Position The Y of the Coherent UI View position relative to the upper-left corner of the device screen.
- Retina rescale If set the content will be scaled to fit the View.
- Enable WebGL Support This property is ignored due to vendor API limitations
- **Software only rendering Android only** The View will be rendered without hardware acceleration. Some devices might render pages incorrectly because of hardware capabilities in which case software rendering helps. Note that advanced transformations and effects are not available with software rendering.
- **Input behavior** Controls how the view handles user input (touches and gestures). The behavior only influences events that happen in the bounds of the View. If the user touches outside a view the event goes normally to the game.
 - Transparent the user controls which input events to be taken by the UI and which to pass to the game.
 This is explained in the Mobile input management section (Input forwarding Mobile)
 - Take all the View takes all the input nothing is passed to the game
 - Take none the View takes no input everything goes to the game
- Transparent Defines if the View supports transparency.
- Smart input Available for transparent Views. Enables transparent input.
- Auto UI messages When enabled, any event triggered in *JavaScript* on the engine object is forwarded to the game object containing the View.
- Enable [CoherentMethodAttribute] Enables the usage of the Coherent Method attribute

4.5 CoherentUILiveGameView properties for Desktop

Note

Live Game Views are a Desktop-only feature.

- Name This is the string used as an identifier for the Live Game View. In the UI JavaScript code this string can be used to apply specific logic to only certain live views.
- Width The Width of the Live Game View. The ImageData object created in the UI JavaScript DOM will have this width.
- Height The Height of the Live Game View. The ImageData object created in the UI JavaScript DOM will have this height.
- Source Camera The camera that will provide the images for the Live Game View. Everything rendered by this camera will be sent in the UI JavaScript universe and automatically updated every frame. If you omit a Source Camera than the source texture will be used.
- Source Texture A texture to be used as source for the Live Game View images. If both a camera and a texture are specified than the first frame in the live view will use the texture but all others will be provided by the Camera. If you omit specifing a Source Camera than only the texture will be used. If you change the content of the source texture and want to update the Live View linked to it you can do it by calling the "UpdateFromCurrentTexture" method of the Live Game View component.
- Read alpha Specifies if to read the alpha value drawn by the Source Camera.

26 Programmer's API

Chapter 5

Important points

5.1 Binding

Binding *C#*, *UnityScript* and *Boo* handlers to JavaScript callbacks is the same as binding for the .Net platform. You have to register handlers when the <code>UnityViewListener</code>'s <code>ReadyForBindings</code> event is fired. You can do that by using either <code>Coherent.UI.View.BindCall</code> (for single-cast delegates) and <code>Coherent.U-I.View.RegisterForEvent</code> (when you have multiple subscribers for the event). For more details see the general reference documentation, chapter <code>Binding</code> for <code>.Net</code>.

```
private void RegisterBindings(int frame, string url, bool isMain)
{
    if (isMain)
    {
        var view = ViewComponent.View;
        if (view != null)
        {
            // When engine.call('NewGame') is executed in JavaScript,
            // the this.NewGame method will be called as well
            view.BindCall("NewGame", (System.Action)this.NewGame);
        }
    }
}
```

The Coherent.UI.View can be obtained using the View property of the CoherentUIView component.

To take advantage of the *Unity3D* component and message system each CoherentUIView has the Intercept—AllEvents property. If intercepting of all events is enabled, any event triggered in *JavaScript* on the engine object is forwarded to the game object containing the view. This is done by using SendMessage with Coherent.—UI.Binding.Value[] containing all the event arguments.

```
engine.trigger('Event', 42);
// will execute SendMessage('Event', [42])
```

Note

Using this method of handling triggered events has some additional overhead over the direct .Net Coherent.UI.View.RegisterForEvent method.

5.2 CoherentMethod attribute for .NET scripts

Instead of handling the ReadyForBindings event and doing BindCall or RegisterForEvent by yourself, you can use the CoherentMethod attribute to decorate methods in components.

28 Important points

Warning

This attribute only works if the CoherentUIView's Enable Binding Attribute is set to true. By default it is false.

The decorated methods will be automatically bound to the <code>View</code> owned by the <code>CoherentUIView</code> component in the Game Object. If the Game Object has no <code>CoherentUIView</code> component, the attribute has no effect. The <code>CoherentMethod</code> attribute has a string property for the JavaScript event name, and an optional boolean parameter that specifies whether the method is a <code>call</code> or <code>event</code> handler (<code>calls</code> can have only a single handler, while <code>events</code> may have many). Here's an example component using the attribute:

```
public class BindingComponent : MonoBehaviour {
    [Coherent.UI.CoherentMethod("NewGame")]
    void MyCallHandler()
    {
        Debug.Log("MyCallHandler called in response to engine.call('NewGame')");
    }
    [Coherent.UI.CoherentMethod("EnemySpotted", true)]
    void MyEventHandler()
    {
        Debug.Log("MyEventHandler called in response to engine.trigger('EnemySpotted')");
    }
}
```

See the Binding Sample for a complete example.

Warning

- * Binding methods using the <code>CoherentMethod</code> attribute is easier than doing it manually in <code>ReadyForBindings</code>, but presents possible performance penalties during game startup. When the <code>CoherentU-IView</code> component is created, it searches all the other components in the host Game Object for methods marked with <code>CoherentMethod</code> using reflection. This can be a costly operation and to prevent undesirable slowdowns during startup the <code>Enable Binding Attribute</code> property for each <code>CoherentUIView</code> is set to false by default.
- * The <code>CoherentMethod</code> attribute currently does **NOT** support dynamically added components. Methods decorated with the attribute are only bound when the <code>CoherentUIView</code> component is created, which is usually when the <code>Game Object</code> it is part of is created.

JavaScript and Unity3D

Consult the *Binding for .NET* chapter in the general reference document. Check the *Binding Sample* and its walk-through in this guide for an example.

Briefly, Unity3D can call JavaScript using events; JavaScript can call Unity3D using events or calls.

Events

Events can be called by JavaScript

```
engine.trigger("MyEvent", args);

or Unity3D

coherentUIView.View.TriggerEvent("MyEvent", args);
```

The "MyEvent" will be handled by any registered method in JavaScript

```
engine.on("MyEvent", function() {...});
```

or Unity3D

5.3 Namespaces 29

```
coherentUIView.View.RegisterForEvent("MyEvent", handlerMethod);
```

Calls

Calls, unlike events, can have only one handler. The can also return values. To execute a call from JavaScript use

```
engine.call("MyCall", args);
```

It will be handled by a method registered using

```
coherentUIView.View.BindCall("MyCall", handlerMethod);
```

5.3 Namespaces

Coherent UI classes are placed in the Coherent.UI namespace for Desktop and Coherent.UI.Mobile for the Mobile version. You can check the Coherent UI files - for instance CoherentUIView and take a look at the beginning of the file at how the namespaces are imported depending on the Unity platform targeted. Exceptions to that rule are classes that cannot be in a namespace because Unity doesn't allow it, such as components that derive from MonoBehaviour.

5.4 Subclassing CoherentUIView and UnityViewListener

The default CoherentUIView component and the UnityViewListener provide the most common functionality and are usually enough for normal usage of *Coherent UI*. If you need custom behavior, you need to subclass them.

The class you derive from UnityViewListener would usually subscribe to various events that aren't handled by default. It is recommended not to override the OnViewCreated callbacks since the UnityViewListener class contains important logic that you would have to implement yourself otherwise.

The class you derive from CoherentUIView would only need to create an instance of your custom View Listener. This can be done by copying the Update method of CoherentUIView and editing it appropriately.

Note that when subclassing CoherentUIView you will no longer be able to view or edit the properties in the Inspector. That's because we're using C# properties in our component instead of fields and they are not automatically shown. To show the properties of a given C# script we need to make a new Editor script (inside the Editor folder of your Assets) that shows the properties for a specific type. We've already done that for CoherentUIView, but you'll have to do it yourself for derived classes. The script contents should be the following:

```
using UnityEngine;
using System.Collections;
using UnityEditor;

[CustomEditor(typeof(<YourType>))]
public class <YourType>ViewEditor : Editor {
    private <YourType> m_Target;
    private CoherentPropertyField[] m_Fields;

    public void OnEnable() {
        m_Target = target as <YourType>;
        m_Fields = CoherentExposeProperties.GetProperties(m_Target);
    }

    public override void OnInspectorGUI() {
        if(m_Target == null)
            return;
        this.DrawDefaultInspector();
        CoherentExposeProperties.Expose(m_Fields);
    }
}
```

Just replace < YourType> with the actual name of your class.

30 Important points

Note

In most cases, subclassing is unnecessary. See Facebook Sample for an example how to subscribe for UnityViewListener events.

5.5 Coherent UI system lifetime

Since initialization of the CoherentUISystem component is a costly operation, it is designed to be done once in the first scene of your game. The component itself has the same lifetime as the application. Since Unity tears down the state of the game when you load a new scene, the component is marked not be destroyed using the DontDestroyOn-Load() function. This makes it persist through scenes and is available using the Object.FindObjectOfType function. Getting the system can be done with the following line of code:

var uiSystem = Object.FindObjectOfType(typeof(CoherentUISystem)) as CoherentUISystem;

5.6 Customizing initialization of the Coherent UI System

When using only <code>CoherentUIView</code> components, the Coherent UI System will be automatically initialized using the default parameters. These parameters define global system settings such as whether cookies are enabled, local storage and cache paths, debugger port and others. Check the <code>CoherentUISystem</code> component for a full list.

The Coherent UI System can be initialized with parameters other than the defaults in the following ways. Either drag the CoherentUISystem component to any object and edit the properties in the Inspector window, or edit the CoherentUISystem.cs script located in Standard Assets/Scripts/CoherentUI to fit your needs.




Figure 5.1: Custom CoherentUISystem component

The CoherentUISystem component is designed to be only one in the whole game. Adding more than one CoherentUISystems to your level will result in undefined behavior.

5.7 Update cycle 31

5.7 Update cycle

In a standard C++ or .NET application you need to poll Coherent UI for surfaces each frame using the Update and FetchSurfaces API calls. In our Unity integration, this is all hidden from you and you don't have to worry about it. The CoherentUIViewRenderer component issues rendering events which are handled by our library. All that's left for you is to drag a CoherentUIView component on an object!

5.8 Input forwarding - Desktop

A CoherentUIView requires focus to receive user input. Usually you'd want to forward input to a single view, but for flexibility **Coherent UI** supports multiple focused views. A CoherentUIView's focus is controlled by the ReceivesInput property. To avoid confusion with multiple views, the property is set to **false** by default, meaning no input will be forwarded to **Coherent UI** unless you explicitly set it in your Game Object. It is **NOT** exposed in the Inspector, as it designed to be modified in code only.

Note

The forwarding happens in the CoherentUISystem's LateUpdate method, allowing you to do all your logic for input focus management in the Update methods of your components.

5.9 Input forwarding - Mobile

Due to differences in the input management for iOS/Android, Coherent UI provides a helper class for getting the list of touches for the current frame. The Coherent touch structure is InputManager.CoherentTouch - very much the same as Unity3D's Touch structure. The equivalent methods for Input.touchCount and Input. - GetTouch(index) are InputManager.TouchesCount and InputManager.GetTouch(index), respectively.

For **iOS** there's practically no difference between the Coherent and Unity3D touches. For **Android**, however, Coherent touches contain only touches that reached the game (i.e. the touch wasn't filtered using the techniques described in the next paragraph). The Unity3D supplied touches on Android aren't filtered and you get all of them when using the Input.touches array, regardless of whether they are on the UI or not. When using Coherent UI for mobile, it is recommended to use Coherent touches instead of Unity3D touches to avoid platform differences between iOS and Android.

On iOS/Android all *Coherent UI* Views are composited in 2D on-top of your Unity3D application content. When the user start a touch event or performs a gesture there is a mechanism that decides if that event should be handled by the UI or the application. It works like this: in the properties of the View the user can select one of three input modes for a every View - "Take AII", "Take None", "Transparent". Keep in mind that all those modifiers are in effect only for events that happend are in the bounds of the View. If the user touches outside a particular View the event is always handled by the game.

- "Take All" specifies that all events are handled by the View and nothing goes to the game. It is usable if you want to have for instance an in-game browser. All touches on it should be handled by itself and not influence the game.
- "Take None" specifies that the View passes all input to the game. This is usable if you need to just show some non-interactive views or disable their input completely in some situation.
- "Transparent" specifies that the input is either handled by the View or the game usable for HUDs, Menus etc. For Views with "Transparent" input mode the user is the one in charge of deciding if an element on the page is interactive hence should receive input or is 'input transparent'.

32 Important points

Note

iOS: Input "Transparent" views work correctly **ONLY** if you have included *coherent.js* in your HTML page.

Android: Input on any view works correctly ONLY if you have included coherent.js in your HTML page.

Upon touch within a View, Coherent UI Mobile inspects the touched element:

- if the element has the CSS class *coui-noinput* it passes input to the game. The element does not accept input.
- if the element has the CSS class *coui-inputcallback*, a method called *couiInputCallback*(x, y) is called on the element with the coordinates of the event. It should return "true" if the user wants the element to handle the input and "false" if the game should handle it. This allows for custom fine-grained control in JavaScript on which elements are interactive.
- if the class *coui-noinput* and *coui-inputcallback* are missing from the element, it is assumed that it is interactable and takes the input.

To summarize: If a View has an Input State set to "Transparent" all elements are by default interactive and take input. You can mark elements with the CSS class *coui-noinput* to make them transparent to input. If you need more advanced logic when deciding if an element is interactive or not you can decorate it with *coui-inputcallback* and implement a method *couiInputCallback(x, y)* on it.

5.10 Mobile Preview

The preview for the mobile versions of Coherent UI allows you to easily see how your page behaves without testing it on a device or simulator. There are a few notable differences, however. First, the input redirection is based on the Android version, meaning you need to import *coherent.js* in your HTML files for it to work. All other notes for the input regarding Android apply for the preview as well. Another difference is that on the devices the CoherentUIView is always shown on top. Due to the specifics of Unity this is not easy to simulate automatically without interfering with some client functionality. That's why it's up to the user to simulate this behaviour in the preview. You should ensure that the camera you have your view on is always drawn last so the views are displayed the same, both in Editor preview and on the device.

5.11 Custom file handler

The CoherentUISystem component makes use of a static factory function object (FileHandlerFactory-Func) to create the FileHandler object that is used reading URLs with the *coui* scheme. The default function returns a handler that reads resources from the path set by $Edit \rightarrow Project \ Settings \rightarrow Coherent \ UI \rightarrow Select \ UI$ folder for the Editor and in the Data folder for built games.

The factory function object is public and can be customized. The FileHandler it returns is passed to the UI initialization routine in the Start method of the CoherentUISystem component. That means the user should set the factory function prior to the invocation of the Start method of the components - e.g. in the Awake method.

Note

You can check the execution order of event function in Unity3D on this page

This is an example usage of a custom file handler:

```
public class CustomFileHandlerScript : MonoBehaviour {
    class CustomFileHandler : Coherent.UI.FileHandler
    {
        public override void ReadFile (string url, Coherent.UI.ResourceResponse response)
        {
            // Implementation here
        }
}
```

5.12 UI Resources 33

See Archive resource demo for an example.

5.12 UI Resources

Files for Coherent UI are by default selected from the folder set by $Edit \rightarrow Project \ Settings \rightarrow Coherent \ UI \rightarrow Select \ UI folder$. Resources found there will be used by the editor and will automatically be copied in your game upon build.

The selected UI resources folder is per-user so that different developers working on the game can have their UI folders wherever they want on their machine. You can also set a per-project folder for the UI resources. This is done by extending the CoherentPostProcessor class by setting a static const setting named ProjectUIResources:

```
public partial class CoherentPostProcessor {
    public static string ProjectUIResources = "relative/path/to/ui/resources";
}
```

The per-project path must be relative to the folder of the project and the extension class should live under the 'Editor' folder in Unity. This feature is very handy also if you build your game on machines that can't start Unity and you use the command line. The per-user setting overrides the per-project one so that developers can still put their resources wherever they want.

Warning

When using the "Build & run" option for Android, the required resources will **NOT** be packaged because this is done as a post-build step. Unity3D pushes the non-repacked APK first, and then executes the post-build step which results in an APK without UI resources and including unneeded files. To work around that, you should either use the "Build" option, which produces an APK on your computer that can be installed on a device using the ADB tool in the Android SDK, or generate an Eclipse project and run it from the IDE.

5.13 Click-to-focus Views - Desktop only

When the ClickToFocus property is enabled on a View, it will automatically take **all** the input focus when you click on it and lose it when you click somewhere else. When focused, all mouse and keyboard input will be forwarded to the View. "Click-to-focus" views have their ReceivesInput property managed by the CoherentUISystem and you should **NOT** set it manually. If you do so, you'll receive a warning message in Unity3D and the input forwarding behavior will be unexpected.

Warning

There is no way to prevent the standard Unity character controller scripts from moving the character, even when the input event is *used*. You have to manually disable your character controller when you want the user to type in in a view and stands still. For an explanation see the Menu And HUD sample.

34 Important points

Note

"Click-to-focus" views perform raycasts to obtain the object in the 3D world below the cursor. For a raycast to report the correct texture coordinates of the hitpoint, you need to set up a *Mesh Collider* on the objects with Coherent UI Views placed.

"Click-to-focus" Views are useful in cases when you want keyboard input forwarded to a View regardless of the mouse position, e.g. input fields.

Note

To function properly, "Click-to-focus" views need to know which camera is the main camera in the scene. For simple scenes, this can be obtained from the Camera.main property in Unity3D. This is what Coherent UI assumes is the main camera, and obtains it in the MonoBehaviour.OnEnable callback, which is executed when a scene is loaded. This is done only if there is no currently set camera for the m_Main-Camera field so it does not interfere with custom user code. For complex scenes with multiple cameras, however, it is up to you to set the public m_MainCamera field to the appropriate camera (also visible in the Inspector window).

Which <code>CoherentUIViews</code> receive input is up to your gameplay needs. Here we'll walk you through a simple script that you'll see used in the samples - it forwards input to the closest view under the cursor. First, it sets the <code>ReceivesInput</code> property to all views to false. Then it queries the <code>CoherentUIView</code> attached to the main camera (if any) whether the mouse is over a solid or transparent pixel (make sure to set the <code>SupportClick-Through</code> property of the HUD view to <code>true</code> to support this operation). If the mouse is over a solid pixel, then the HUD is focused and receives input. Otherwise, a raycast is generated that finds the object under the cursor. If that object has a <code>CoherentUIView</code> component, that's what gets the focus.

Here's the script itself:

To summarize, you can apply any logic you like for input forwarding - e.g. forward input to objects in the view frustum, HUD only, etc. Coherent UI supports multiple focused views. View focus can be modified using the Receives-Input property of CoherentUIView which is controlled only by the script code.

You can also mark views as "Click to focus" which makes them take all the focus when clicking them (and lose focus when clicking somewhere else). You should take care not to set the <code>ReceivesInput</code> property on "Click to focus"-enabled Views as it is automatically managed. Setting the <code>ReceivesInput</code> property on such views manually will result in unexpected behavior and will produce a warning message.

5.14 View Filters - Desktop only

Coherent UI provides three types of filtering:

- · Point Filtering applies point filtering to the view texture.
- Linear Filtering applies linear filtering to the view texture.

5.15 Hit testing - Desktop only

Note

For and explanation about input forwarding for Mobile check Input Forwarding Mobile

Forwarding input to Views attached to the camera is straight-forward - you only have to mark your view as an input receiver using the ReceivesInput property of CoherentUIView. The mouse position will be obtained from the Input.mousePosition property.

5.16 Mobile Surface Views 35

If you want to forward an input event to a View that's attached on an object in the 3D world, you'll have to do a bit more work. You'll have to use a raycast to find the object below the cursor and then transform the texture coordinates of the hit point into the space of the Coherent UI View. Note that Unity provides texture coordinates only when the object has a Mesh Collider component attached. The coordinates must be transformed from [0, 1] to [view.Width, view.Height]. This can usually be done simply by multiplying the coordinates by the dimensions of the View (which are available as properties). Then, you have to set the resulting coordinates to the CoherentUIView component using the SetMousePosition method. Check Input Forwarding for an example script that forwards input to the view on the object that is currently below the cursor. Note that in the samples the MeshCollider component has the same geometry as the renderable mesh. This may not always be true and in such cases you would have to make a transformation of the coordinates that works for you.

For a sample how hit testing works see the Menu and HUD sample.

5.16 Mobile Surface Views

Displaying CoherentUI view on a surface is straightforward for Desktop platforms. Unfortunately the performance and API restrictions of the current platforms do not allow us to fully support views on surfaces for mobile. *Mobile Surface Views* allow displaying of HTML5 content on a surface in mobile games with the following limitations:

- the view must be explicitly updated using the MobileSurfaceView. UpdateView method.
- · there is no input for the view. Input could be simulated using JavaScript.

To create a *Mobile Surface View*, simply add the component to a object with a renderer component. The Mobile-SurfaceView component will create a new texture for the renderer and replace the main texture of the material with the view.

See also the Mobile Surface Sample.

5.17 Logging

Coherent UI logs are automatically redirected to the Unity console (or game log for built games) using the Debug.Log method. You can control the minimum severity of the Coherent UI logs when initializing the Coherent UI System.

5.18 Live Game Views

Note

Live Game Views are a Desktop-only feature.

Live Game Views are one of the most powerful yet easy to use fetures in Coherent UI for Unity 3D. They allow you to have 3D rendered images (by a Unity3D Camera) as part of the UI itself. The images are automatically updated in a high-performance way and made available to the UI JavaScript code.

Via Live Game Views in a real game you can trivially have 3D animated unit portraits, animated items in the UI, 3D mini-maps, security cameras etc..

The steps to get a Live Game View are trivial:

- 1. Add the Coherent UI "Live Game View" Component to a GameObject that already has a Coherent UI View.
- 2. Give the link a Name
- 3. Set the size
- 4. Drag a Camera that will send the data

36 Important points

5. (Optional) You can select a texture too in the Component. If you don't select a Camera - this texture will be rendered instead. In this way you can send just textures in the UI.

The "Live Game View" Component represents a link between the View and a Unity Camera or a texture. When you attach it - it will automatically start sending the updated image drawn by the linked Camera to the JavaScript code of the page currently displayed by the View.

Every such link has a Name that is used to identify it inside the page's JS code. You can have as many Live Game Views attached to the same Coherent UI View as you want.

After you press "Play", the Live Game View will be operational and everything the Camera "sees" will be available in the UI as an ImageData object.

To use it - add a "canvas" element in the page and a "onEngineImageDataUpdated" function to it. This function will be called every time the image is updated and the name will be passed so that you can identify just the one you need.

In the "onEngineImageDataUpdated" function you can do whatever you need with the image - draw it in the canvas, apply filters, write text etc..

This snippet shows a sample UI JavaScript function that draws the image in a "canvas" element and writes text on it:

```
window.onload = function() {
  var c = document.getElementById("myCanvas");
  c.onEngineImageDataUpdated = function (name, image) {
    var c = document.getElementById("myCanvas");
    var ctx = c.getContext("2d");

    ctx.clearRect(0, 0, c.width, c.height);
    ctx.putImageData(image, 0, 0);
    ctx.fillStyle = "white";
    ctx.font = "16pt Arial";
    ctx.fillText("Live Game View!", 15, 25);
  }
}
```

As you can see we just listen for when a new image has arrived and re-draw the content of the canvas named "my-Canvas". The "name" parameter received is the "Name" of the Live Game View as specified in the Unity Inspector and allows us to identify the different links.

Note

For a sample scene with Live Game Views check the "Sample_LiveGameViews" scene available in the Coherent UI package.

Chapter 6

Requirements

To use Coherent UI SDK in your project, please make sure that the following minimum system requirements are met by your development environment and are compatible with your project requirements for the end-users.

Software Requirements

Windows

- Windows XP (required Service Pack 3)
- · Windows Vista (required Service Pack 2)
- Windows 7 (required Service Pack 1)
- Windows 8
- · Windows 8.1

Visual Studio 2010, 2012, 2013 is required to build Coherent UI SDK. DirectX SDK is required for older versions of Visual Studio to build some of the samples.

Note

- All Windows systems must have the latest Service Pack provided by Microsoft installed.
- DirectX shared textures require Windows Vista or later.
- Latest drivers provided by the hardware vendor are required.
- For Windows 8 and 8.1 only desktop mode applications are supported
- · WinRT is not supported
- The Coherent UI Samples require the Microsoft DirectX End-User Runtime (June 2010) to work compile (or at least d3dx9_43.dll and D3DCompiler_43.dll should be added to the output folder).

Linux

Generally any distribution similar to Ubuntu 12.04 LTS.

- · glibc 2.14 or later
- · libstdc++6 or later
- GTK 2.24.10 or later
- · GCC 4.6.3 or later

38 Requirements

Note

Only the latest video card drivers are supported. OpenGL 3.0 support is required.

Mac OS X

- 10.7 or later
- · XCode 4.4 or later

Note

Limited support for Mac OS 10.6.8 is available, but extensive testing should be performed, and some features might not work.

Hardware Requirements

- · Intel or AMD CPU architectures are supported (no ARM support)
- · Dual-core CPU is recommended
- 512 MB RAM
- · 350 MB HDD space for development
- 40-80 MB HDD space for runtime libraries

Video adapter:

- · Support for shader model 3.0 is required
- · DirectX 9.0c or later support
- OpenGL 3.0* or later support
- · Full non-power-of-two textures support
- · Dedicated video card recommended
- Certain features of Coherent UI may be available on earlier versions of OpenGL but we don't test that configuration and results may be unpredictable.
- On configurations with multiple video cards SLI, Optimus, etc., the faster card should be enabled, and your users should make sure that the same adapter runs both your application and the Coherent UI rendering processes.

Chapter 7

Namespace Documentation

7.1 Package Coherent

Namespaces

• package UI

7.2 Package Coherent.UI

Namespaces

· package Binding

Classes

· class HTTPHeader

Encapsulates a HTTP header field with it's content.

class BrowserView

Class that encapsulates a browser Coherent::UI::View

· class BrowserViewListener

Interface that allows clients to listen to Coherent::UI::ViewListener

• class BrowserViewListenerBase

Interface all browser view listeners inherit. For an easier to use interface inherit instead -. Coherent::UI::Browser-ViewListener

· class Certificate

Represents an SSL certificate.

· class CertificatePrincipal

Represents certificate principal.

· class ChildViewInfo

Helper structure for creating child views.

class Download

Encapsulates a download task.

· class EventListener

Abstract interface to listen to System-related events.

· class EventModifiersState

The state of the key modifiers when an event happens.

• class EventMouseModifiersState

The state of the mouse modifiers when an event happens.

· class FileHandler

Abstract interface that allows clients to provide their own file-handling functionality.

· class ILogHandler

Interface to allow custom logging.

class ImageData

This class represents a link to a

class KeyEventData

A keyboard event.

• class MediaStreamDevice

Represents a media stream device.

· class MediaStreamRequest

Represents a request for media stream.

class MouseEventData

A mouse event.

· class ResourceData

Abstract interface providing data for storing resources.

class ResourceResponse

Abstract interface for responding to read resource requests.

• class SurfaceResponse

Interface that signals for creation of rendering surfaces.

class SystemError

Encapsulates a system-related error.

· class SystemSettings

Encapsulates the settings of the

class SystemSettingsBase

Encapsulates the settings of the

· class TouchEventData

A touch event.

class UISystem

Encapsulates basic UI system functionality.

class URLRequest

represents a single URL request Allows monitoring and modifications of URL requests

· class View

Class that encapsulates a UI

class ViewError

Encapsulates a view-related error.

class ViewInfo

Encapsulates the options of a

· class ViewListener

Interface that allows clients to listen to

· class ViewListenerBase

Interface all view listeners inherit. For an easier to use interface inherit instead -. Coherent::UI::ViewListener

• struct BoundEventHandle

Handle for registered delegates

Enumerations

· enum CertificateStatus

Enum containing the possible certificate validation errors.

enum CursorTypes

Enum containing all the cursor types that a view can signal.

• enum Direct3DInterfaceType

Types of interface used for DirectX.

- enum DownloadErrorType { DownloadErrorType.DET_Success, DownloadErrorType.DET_Download-OperationFailed }
- enum FileSelectionMode

Enumeration for file selection modes.

enum JavaScriptMessageType

Enum containing the possible types of a javascript message.

enum MediaStreamType

Enumeration of media stream types.

• enum RenderingDeviceType

Types of rendering backend.

- enum ScriptCallErrorType { ScriptCallErrorType.SCE_Success, ScriptCallErrorType.SCE_ArgumentType, ScriptCallErrorType.SCE_NoSuchMethod, ScriptCallErrorType.SCE_NoResult }
- enum SystemErrorType { SystemErrorType.SE_Success, SystemErrorType.SE_InternalError, SystemErrorType.SE_InvalidKey, SystemErrorType.SE_MissingComponent }

System-related error-codes.

enum TextInputControlType

Enum containing the text input types reported for IME.

enum UserAgentType

Predefined values for the used User Agent. If you select "Custom" you also have to set the CustomUserAgentString.

enum ViewErrorType {

ViewErrorType.VE_Success, ViewErrorType.VE_FailedCreation, ViewErrorType.VE_FailedRendering-Creation, ViewErrorType.VE_ClickThroughFailed,

 $\label{thm:linear_view} ViewErrorType. VE_InvalidPath, \ ViewErrorType. VE_ChildCompositionFailed, \ ViewErrorType. VE_InvalidCall, \ ViewErrorType. VE_FrameAlreadyInFlight, \ ViewErrorType. \ ViewErrorTyp$

ViewErrorType.VE_FrameNotReady, ViewErrorType.VE_FrameNotRequeted, ViewErrorType.VE_Abnormal-Termination, ViewErrorType.VE_QueryNotReady }

View-related error codes.

enum ViewType

Enum containing the possible view types.

7.2.1 Enumeration Type Documentation

7.2.1.1 enum Coherent.UI.CertificateStatus

Enum containing the possible certificate validation errors.

7.2.1.2 enum Coherent.UI.CursorTypes

Enum containing all the cursor types that a view can signal.

7.2.1.3 enum Coherent.UI.Direct3DInterfaceType

Types of interface used for DirectX.

7.2.1.4 enum Coherent.UI.DownloadErrorType

Enumerator

DET_Success Indicates everything went fine.

DET_DownloadOperationFailed Indicates the download operation failed.

7.2.1.5 enum Coherent.UI.FileSelectionMode

Enumeration for file selection modes.

7.2.1.6 enum Coherent.UI.JavaScriptMessageType

Enum containing the possible types of a javascript message.

7.2.1.7 enum Coherent.UI.MediaStreamType

Enumeration of media stream types.

7.2.1.8 enum Coherent.UI.RenderingDeviceType

Types of rendering backend.

7.2.1.9 enum Coherent.UI.ScriptCallErrorType

Enumerator

SCE_Success Indicates that the call was successful.

SCE_ArgumentType Indicates that a script provided argument has different type than the one expected.

SCE_NoSuchMethod Indicates that there is no such method.

SCE_NoResult Indicates that there is no result for this call.

7.2.1.10 enum Coherent.UI.SystemErrorType

System-related error-codes.

Enumerator

SE_Success Indicates no error.

SE_InternalError Indicates a serious system internal error.

SE_InvalidKey Indicates that the user supplied an invalid activation key for this version of the product.

SE_MissingComponent Indicates that a component required by Coherent UI is missing.

7.2.1.11 enum Coherent.UI.TextInputControlType

Enum containing the text input types reported for IME.

7.2.1.12 enum Coherent.UI.UserAgentType

Predefined values for the used User Agent. If you select "Custom" you also have to set the CustomUserAgentString.

7.2.1.13 enum Coherent.UI.ViewErrorType

View-related error codes.

Enumerator

VE_Success Indicates no error.

VE_FailedCreation Indicates failure to create a view.

VE_FailedRenderingCreation Indicates failure to create the rendering resources associated with a view.

VE_ClickThroughFailed Indicates an error during click-through a query.

VE_InvalidPath Indicates that the view was redirected to an invalid path.

VE_ChildCompositionFailed Indicates that the composition of a child widget failed.

VE_InvalidCall Indicates a call on a type of view that is not called.

VE_FrameAlreadyInFlight Indicates that a frame is already in-flight.

VE_FrameNotReady Indicates that a frame is still being rendered.

VE_FrameNotRequeted Indicates that a new frame was not requested.

VE_AbnormalTermination Indicates an abnormal termination of the view.

VE_QueryNotReady Indicates that the mouse query hasn't finished yet.

7.2.1.14 enum Coherent.UI.ViewType

Enum containing the possible view types.

7.3 Package Coherent.UI.Binding

Classes

class CallbackArguments

Holds the arguments for the generic callback not handled by a registered delegate

struct BoundObject

Wrapper class for .Net objects exposed to Coherent UI

class CoherentProperty

Specify a property / field or method visible to Coherent UI

class CoherentType

Specify which properties and fields of a type are visible to Coherent UI

• class UnsupportedPrimitiveTypeException

Thrown when trying to bind a value of unsupported primitive type such as long

class InvalidValueCastException

Thrown when casting a Value to an incompatible type

· class Value

Type for representing generic JavaScript values

class ValueObject

Class for compound JavaScript objects, behaves like a Dictionary<string, Value>

Enumerations

 enum PropertyBindingFlags { PropertyBindingFlags.Explicit = 0, PropertyBindingFlags.Instance = 1, PropertyBindingFlags.Static = 2, PropertyBindingFlags.All = 3 }

Determines the set of the bound properties for this type

enum ValueType {

ValueType.Null, ValueType.Boolean, ValueType.Integer, ValueType.UInteger, ValueType.Number, ValueType.String, ValueType.Array, ValueType.Object, ValueType.SByte = 10, ValueType.Byte }

Specifies the type of Coherent.UI.Binding.Value

7.3.1 Enumeration Type Documentation

7.3.1.1 enum Coherent.UI.Binding.PropertyBindingFlags

Determines the set of the bound properties for this type

Enumerator

Explicit Bind only properties and fields with CoherentProperty attribute

Instance Bind only instance properties and fields

Static Bind only static properties and fields

All Bind all instance and static properties and fields

7.3.1.2 enum Coherent.UI.Binding.ValueType

Specifies the type of Coherent.UI.Binding.Value

Enumerator

Null empty value

Boolean boolean value **Integer** integer value

UInteger unsigned integer value

Numberdouble valueStringstring valueArrayarray valueObjectobject valueSBytesigned byte value

Byte unsigned byte value

Chapter 8

Class Documentation

8.1 Coherent.UI.BoundEventHandle Struct Reference

Handle for registered delegates

8.1.1 Detailed Description

Handle for registered delegates

8.2 Coherent.UI.Binding.BoundObject Struct Reference

Wrapper class for .Net objects exposed to Coherent UI

Static Public Member Functions

static BoundObject BindMethods (object target)
 expose object's methods to Coherent UI

8.2.1 Detailed Description

Wrapper class for .Net objects exposed to Coherent UI

8.2.2 Member Function Documentation

8.2.2.1 static BoundObject Coherent.UI.Binding.BoundObject.BindMethods (object target) [inline], [static]

expose object's methods to Coherent UI

Parameters

target	instance


Returns

46 Class Documentation

8.3 Coherent.UI.BrowserView Class Reference

Class that encapsulates a browser Coherent::UI::View

Inheritance diagram for Coherent.UI.BrowserView:



Public Member Functions

• override ViewType GetViewType ()

Get The type of this view.

• virtual void GoBack ()

Navigates back to the previous URL, if any.

virtual void GoForward ()

Navigates to the next URL, if any (i.e. available after navigating back)

• virtual void GetHistory ()

Issues a request for obtaining the navigation history for the view. BrowserViewListener::OnHistoryObtained

8.3.1 Detailed Description

Class that encapsulates a browser Coherent::UI::View

8.3.2 Member Function Documentation

```
8.3.2.1 virtual void Coherent.UI.BrowserView.GetHistory() [inline], [virtual]
```

Issues a request for obtaining the navigation history for the view. BrowserViewListener::OnHistoryObtained

8.3.2.2 override ViewType Coherent.UI.BrowserView.GetViewType() [inline], [virtual]

Get The type of this view.

Returns

the type of the view

Reimplemented from Coherent.UI.View.

8.3.2.3 virtual void Coherent.UI.BrowserView.GoBack() [inline], [virtual]

Navigates back to the previous URL, if any.


8.3.2.4 virtual void Coherent.UI.BrowserView.GoForward() [inline], [virtual]

Navigates to the next URL, if any (i.e. available after navigating back)

8.4 Coherent.UI.BrowserViewListener Class Reference

Interface that allows clients to listen to Coherent::UI::ViewListener

Inheritance diagram for Coherent.UI.BrowserViewListener:



Public Member Functions

• override void Release ()

Called when the listener is no longer needed by the UI system.

override void OnViewCreated (View view)

Called when the requested

• override void OnDraw (CoherentHandle handle, bool usesSharedMemory, int width, int height)

Called when a new surface has been drawn and is ready to use by the client.

• override void OnFinishLoad (int frameld, string validatedPath, bool isMainFrame, int statusCode, HTTP-Header[] headers)

Called when a frame has been successfully loaded.

override void OnFailLoad (int frameld, string validatedPath, bool isMainFrame, string error)

Called when a frame has been failed loading.

• override void OnURLRequest (string url, URLResponse response)

Called before an URL request is made. The default implementation allows all requests.

override void OnReadyForBindings (int frameld, string path, bool isMainFrame)

Called when a frame is ready for bindings.

override void OnBindingsReleased (int frameld, string path, bool isMainFrame)

Called when the bindings for frame are released.

override void OnStartLoading ()

Called when a new path has started loading.

override void OnStopLoading ()

Called when all load operations have completed.

override void OnNavigateTo (string path)

Called when the view starts navigation to a new path.

override void OnError (ViewError error)

Called when an error occurs for this specific

 override void OnScriptMessage (ViewListenerBase.MessageLevel level, string message, string sourceld, int line)

Called when a message is sent from a script running in this specific

override void OnCursorChanged (CursorTypes cursor)

Called when the cursor has changed internally in the

• override void OnCallback (string eventName, Binding.CallbackArguments arguments)

Called by the UI when there is no registered handler for this event.

override void OnJavaScriptMessage (string message, string defaultPrompt, string frameUrl, int messageType)

Called when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

• override void OnGetAuthCredentials (bool isProxy, string host, uint port, string realm, string scheme)

48 Class Documentation

Called when a view requires authentication credentials.

override void CreateSurface (bool sharedMemory, uint width, uint height, SurfaceResponse response)

Called when the The format for DirectX9 must be D3DFMT_A8R8G8B8 The format for DirectX10 and DirectX11 must be B8G8R8A8_UNORM

override void DestroySurface (CoherentHandle surface, bool usesSharedMemory)

Called when a surface is unneeded anymore and should be destroyed This function can be called from a thread different than the main UI system thread in order to support client applications with multi-threaded rendering.

override void OnCertificateError (string url, CertificateStatus status, Certificate certificate, CertificateError-Response response)

Called when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

override void OnRequestMediaStream (MediaStreamRequest request)

Called when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

override void OnTextInputTypeChanged (TextInputControlType type, bool canComposeInline)

Called when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View. View::IMEActivate

override void OnCaretRectChanged (uint x, uint y, uint width, uint height)

Called when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

override void OnIMEShouldCancelComposition ()

Called when the user must cancel the IME composition due to an event in the

override void OnFileSelectRequest (FileSelectRequest request)

Called when the view requests file selection. It could be either single file, directory or multiple files.

Events

CoherentUI OnViewCreated ViewCreated

Fired when the requested

CoherentUI_OnDraw Draw

Fired when a new surface has been drawn and is ready to use by the client.

CoherentUI OnFinishLoad FinishLoad

Fired when a frame has been successfully loaded.

· CoherentUI OnFailLoad FailLoad

Fired when a frame has been failed loading.

CoherentUI OnURLRequest URLRequest

Fired before an URL request is made. The default implementation allows all requests.

CoherentUI_OnReadyForBindings ReadyForBindings

Fired when a frame is ready for bindings.

CoherentUI_OnBindingsReleased BindingsReleased

Fired when the bindings for frame are released.

· CoherentUI OnStartLoading StartLoading

Fired when a new path has started loading.

CoherentUI_OnStopLoading StopLoading

Fired when all load operations have completed.

CoherentUI_OnNavigateTo NavigateTo

Fired when the view starts navigation to a new path.

CoherentUI_OnError Error

Fired when an error occurs for this specific

CoherentUI OnScriptMessage ScriptMessage

Fired when a message is sent from a script running in this specific

CoherentUI_OnCursorChanged CursorChanged

Fired when the cursor has changed internally in the

CoherentUI_OnCallback Callback

Fired by the UI when there is no registered handler for this event.

CoherentUI OnJavaScriptMessage JavaScriptMessage

Fired when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

• CoherentUI_OnGetAuthCredentials GetAuthCredentials

Fired when a view requires authentication credentials.

CoherentUI OnCertificateError CertificateError

Fired when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

• CoherentUI OnRequestMediaStream RequestMediaStream

Fired when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

CoherentUI_OnTextInputTypeChanged TextInputTypeChanged

Fired when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View. View::IMEActivate

CoherentUI_OnCaretRectChanged CaretRectChanged

Fired when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

• CoherentUI_OnIMEShouldCancelComposition IMEShouldCancelComposition

Fired when the user must cancel the IME composition due to an event in the

CoherentUI_OnFileSelectRequest FileSelectRequest

Fired when the view requests file selection. It could be either single file, directory or multiple files.

Additional Inherited Members

8.4.1 Detailed Description

Interface that allows clients to listen to Coherent::UI::ViewListener

8.4.2 Member Function Documentation

8.4.2.1 override void Coherent.UI.BrowserViewListener.CreateSurface (bool sharedMemory, uint width, uint height, SurfaceResponse response) [inline], [virtual]

Called when the The format for DirectX9 must be D3DFMT_A8R8G8B8 The format for DirectX10 and DirectX11 must be B8G8R8A8 UNORM

Parameters

sharedMemory	true if the surface should be created in shared memory (4 * width * height bytes); false if a
	shared texture must be created.
width	the width of the surface in pixels
height	the height of the surface in pixels
response	
	object to hold the response when the surface is created or fails it's creation - must be signaled

Returns

a handle to the created surface

Reimplemented from Coherent.UI.ViewListenerBase.

50 Class Documentation

8.4.2.2 override void Coherent.UI.BrowserViewListener.DestroySurface (CoherentHandle *surface*, bool *usesSharedMemory*) [inline], [virtual]

Called when a surface is unneeded anymore and should be destroyed This function can be called from a thread different than the main UI system thread in order to support client applications with multi-threaded rendering.

Parameters

surface	handle to the surface
usesShared-	determines whether the surface parameter is a handle to shared memory or shared texture
Memory	

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.3 override void Coherent.UI.BrowserViewListener.OnBindingsReleased (int *frameld*, string *path*, bool *isMainFrame*)
[inline], [virtual]

Called when the bindings for frame are released.

Parameters

	frameld	the id of the frame
ſ	path	the path in the frame
ſ	isMainFrame	true if this is the main frame of the view

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.4 override void Coherent.Ul.BrowserViewListener.OnCallback (string *eventName*, Binding.CallbackArguments *arguments*) [inline], [virtual]

Called by the UI when there is no registered handler for this event.

Parameters

eventName	name of the event
arguments	arguments of the event invocation

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.5 override void Coherent.UI.BrowserViewListener.OnCaretRectChanged (uint x, uint y, uint width, uint height) [inline], [virtual]

Called when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

Parameters

the	x position of the selection caret
the	y position of the selection caret
the	width of the selection caret
the	height of the selection caret

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.6 override void Coherent.UI.BrowserViewListener.OnCertificateError (string url, CertificateStatus status, Certificate certificate, CertificateErrorResponse response) [inline], [virtual]

Called when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

Parameters

52 Class Documentation

url	the url of the request
status	the error status of the certificate
certificate	the certificate details. This pointer will be valid only for this call
response	object to signal whether to continue loading the URL. This pointer will be valid only for this
	call

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.7 override void Coherent.UI.BrowserViewListener.OnCursorChanged (CursorTypes *cursor*) [inline], [virtual]

Called when the cursor has changed internally in the

Parameters 4 8 1

cursor	the new cursor
--------	----------------

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.8 override void Coherent.UI.BrowserViewListener.OnDraw (CoherentHandle handle, bool usesSharedMemory, int width, int height) [inline], [virtual]

Called when a new surface has been drawn and is ready to use by the client.

Parameters

handle	a handle to one of the buffers created by CreateSurface. May be a shared memory buffer or a shared texture depending on the way the View was created. The handle is valid only during this call
usesShared-	determines whether the handle parameter is a handle to shared memory or shared texture
Memory	
width	the width of the surface
height	the height of the surface

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.9 override void Coherent.UI.BrowserViewListener.OnError (ViewError error) [inline], [virtual]

Called when an error occurs for this specific

Parameters

error	error description

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.10 override void Coherent.UI.BrowserViewListener.OnFailLoad (int *frameld*, string *validatedPath*, bool *isMainFrame*, string *error*) [inline], [virtual]

Called when a frame has been failed loading.

Parameters

frameld	the id of the frame
validatedPath	the path in the frame
isMainFrame	true if this is the main frame of the View
error	error message for the failure

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.11 override void Coherent.UI.BrowserViewListener.OnFileSelectRequest (FileSelectRequest request) [inline], [virtual]

Called when the view requests file selection. It could be either single file, directory or multiple files.

Parameters

request	contains the file selection params for the request

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.12 override void Coherent.UI.BrowserViewListener.OnFinishLoad (int *frameld*, string *validatedPath*, bool *isMainFrame*, int *statusCode*, HTTPHeader[] *headers*) [inline], [virtual]

Called when a frame has been successfully loaded.

Parameters

frameld	the id of the loaded frame
validatedPath	the path loaded in the frame
isMainFrame	true if this is the main frame of the View
statusCode	the status code of the response
headers	an array of header fields
headersCount	the count of items in the headers array

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.13 override void Coherent.UI.BrowserViewListener.OnGetAuthCredentials (bool *isProxy*, string *host*, uint *port*, string *realm*, string *scheme*) [inline], [virtual]

Called when a view requires authentication credentials.

Parameters

isProxy	whether the request came from a server or a proxy
host	the host which triggered the request
port	the port at which the request was triggered
realm	realm of the authentication challenge. Encoded in UTF-8
scheme	the authentication scheme used, e.g. "basic" or "digest". Encoded in ASCII

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.14 override void Coherent.UI.BrowserViewListener.OnIMEShouldCancelComposition() [inline], [virtual]

Called when the user must cancel the IME composition due to an event in the

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.15 override void Coherent.UI.BrowserViewListener.OnJavaScriptMessage (string *message*, string *defaultPrompt*, string *frameUrl*, int *messageType*) [inline], [virtual]

Called when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

Parameters

message	the JavaScript message
defaultPrompt	the default value of the prompt text box, in case the message type is prompt
frameUrl	the URL which created the message
messageType	the type of the message (alert/confirm/prompt)

54 Class Documentation

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.16 override void Coherent.UI.BrowserViewListener.OnNavigateTo (string path) [inline], [virtual]

Called when the view starts navigation to a new path.

Parameters

path	URL that the view is navigating to

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.17 override void Coherent.UI.BrowserViewListener.OnReadyForBindings (int *frameld*, string *path*, bool *isMainFrame*) [inline], [virtual]

Called when a frame is ready for bindings.

Parameters

frameld	the id of the frame
path	the path in the frame
isMainFrame	true if this is the main frame of the view

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.18 override void Coherent.UI.BrowserViewListener.OnRequestMediaStream (MediaStreamRequest request) [inline], [virtual]

Called when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

Parameters

request	contains the available media streams for the request

 $\label{lem:lemented_control_control} Reimplemented from \ \ Coherent. UI. View Listener Base.$

8.4.2.19 override void Coherent.UI.BrowserViewListener.OnScriptMessage (ViewListenerBase.MessageLevel level, string message, string sourceld, int line) [inline], [virtual]

Called when a message is sent from a script running in this specific

Parameters

level	message level
message	the text of the message
sourceld	id of the script (usually file name)
line	the number of the line in which the message was sent

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.20 override void Coherent.UI.BrowserViewListener.OnStartLoading() [inline], [virtual]

Called when a new path has started loading.

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.21 override void Coherent.UI.BrowserViewListener.OnStopLoading() [inline], [virtual]

Called when all load operations have completed.

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.22 override void Coherent.Ul.BrowserViewListener.OnTextInputTypeChanged (TextInputControlType type, bool canComposeInline) [inline], [virtual]

Called when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View.:IMEActivate

Parameters

type	the type of the currently focused text input control by the user
canCompose-	if the IME composition could be performed in-line in the control
Inline	

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.23 override void Coherent.UI.BrowserViewListener.OnURLRequest (string *url*, URLResponse *response*) [inline], [virtual]

Called before an URL request is made. The default implementation allows all requests.

Parameters

url	the request URL
response	response whether to allow the request and may be redirect it. This pointer will be valid only
	for this call

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.24 override void Coherent.UI.BrowserViewListener.OnViewCreated (View view) [inline], [virtual]

Called when the requested

Parameters

view	the instance of the view containing all manipulation methods

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.2.25 override void Coherent.UI.BrowserViewListener.Release () [inline], [virtual]

Called when the listener is no longer needed by the UI system.

Reimplemented from Coherent.UI.ViewListenerBase.

8.4.3 Event Documentation

8.4.3.1 CoherentUI_OnBindingsReleased Coherent.UI.BrowserViewListener.BindingsReleased

Fired when the bindings for frame are released.

8.4.3.2 CoherentUI_OnCallback Coherent.UI.BrowserViewListener.Callback

Fired by the UI when there is no registered handler for this event.

56 Class Documentation

8.4.3.3 CoherentUI_OnCaretRectChanged Coherent.UI.BrowserViewListener.CaretRectChanged

Fired when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

8.4.3.4 CoherentUI_OnCertificateError Coherent.UI.BrowserViewListener.CertificateError

Fired when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

8.4.3.5 CoherentUI_OnCursorChanged Coherent.UI.BrowserViewListener.CursorChanged

Fired when the cursor has changed internally in the

8.4.3.6 CoherentUI_OnDraw Coherent.UI.BrowserViewListener.Draw

Fired when a new surface has been drawn and is ready to use by the client.

8.4.3.7 CoherentUI_OnError Coherent.UI.BrowserViewListener.Error

Fired when an error occurs for this specific

8.4.3.8 CoherentUI OnFailLoad Coherent.UI.BrowserViewListener.FailLoad

Fired when a frame has been failed loading.

8.4.3.9 CoherentUI_OnFileSelectRequest Coherent.UI.BrowserViewListener.FileSelectRequest

Fired when the view requests file selection. It could be either single file, directory or multiple files.

8.4.3.10 CoherentUI_OnFinishLoad Coherent.UI.BrowserViewListener.FinishLoad

Fired when a frame has been successfully loaded.

8.4.3.11 CoherentUI_OnGetAuthCredentials Coherent.UI.BrowserViewListener.GetAuthCredentials

Fired when a view requires authentication credentials.

 $8.4.3.12 \quad Coherent UI_On IMES hould Cancel Composition \ Coherent. UI. Browser View Listener. IMES hould Cancel Composition \ Coherent. UI. Browser View Listener. IMES hould Cancel Composition \ Coherent. UI. Browser View Listener. UI$

Fired when the user must cancel the IME composition due to an event in the

8.4.3.13 CoherentUI OnJavaScriptMessage Coherent.UI.BrowserViewListener.JavaScriptMessage

Fired when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

8.4.3.14 CoherentUI_OnNavigateTo Coherent.UI.BrowserViewListener.NavigateTo

Fired when the view starts navigation to a new path.

8.4.3.15 CoherentUI_OnReadyForBindings Coherent.UI.BrowserViewListener.ReadyForBindings

Fired when a frame is ready for bindings.

8.4.3.16 CoherentUI_OnRequestMediaStream Coherent.UI.BrowserViewListener.RequestMediaStream

Fired when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

8.4.3.17 CoherentUI_OnScriptMessage Coherent.UI.BrowserViewListener.ScriptMessage

Fired when a message is sent from a script running in this specific

8.4.3.18 CoherentUI_OnStartLoading Coherent.UI.BrowserViewListener.StartLoading

Fired when a new path has started loading.

8.4.3.19 CoherentUI_OnStopLoading Coherent.UI.BrowserViewListener.StopLoading

Fired when all load operations have completed.

8.4.3.20 CoherentUI_OnTextInputTypeChanged Coherent.UI.BrowserViewListener.TextInputTypeChanged

Fired when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View. View::IMEActivate

8.4.3.21 CoherentUI_OnURLRequest Coherent.UI.BrowserViewListener.URLRequest

Fired before an URL request is made. The default implementation allows all requests.


8.4.3.22 CoherentUI_OnViewCreated Coherent.UI.BrowserViewListener.ViewCreated

Fired when the requested

8.5 Coherent, UI. Browser View Listener Base Class Reference

Interface all browser view listeners inherit. For an easier to use interface inherit instead -. Coherent::UI::Browser-ViewListener

Inheritance diagram for Coherent.UI.BrowserViewListenerBase:



Additional Inherited Members

8.5.1 Detailed Description

Interface all browser view listeners inherit. For an easier to use interface inherit instead -. Coherent::UI::Browser-ViewListener

8.6 Coherent.UI.Binding.CallbackArguments Class Reference

Holds the arguments for the generic callback not handled by a registered delegate

Public Attributes

• Value[] Arguments

Arguments provided by JavaScript

8.6.1 Detailed Description

Holds the arguments for the generic callback not handled by a registered delegate

8.6.2 Member Data Documentation

8.6.2.1 Value [] Coherent.UI.Binding.CallbackArguments.Arguments

Arguments provided by JavaScript

8.7 Coherent.UI.Certificate Class Reference

Represents an SSL certificate.

Inherits IDisposable.

Properties

```
• byte[] SerialNumber [get]
```

Serial number of the certificate in DER encoding.

• byte[] Fingerprint [get]

the fingerprint of the certificate

• byte[] FingerprintCA [get]

the fingerprint of the certificate authority

CertificatePrincipal Subject [get]

Subject of the certificate.

• CertificatePrincipal Issuer [get]

Issuer of the certificate.

• uint ValidStart [get]

The starting date from which the certificate becomes valid in seconds since the UNIX epoch 01.01.1970.

• uint ValidEnd [get]

The date after which the certificate is no longer valid in seconds since the UNIX epoch 01.01.1970.

8.7.1 Detailed Description

Represents an SSL certificate.

8.7.2 Property Documentation

8.7.2.1 byte [] Coherent.UI.Certificate.Fingerprint [get]

the fingerprint of the certificate

the fingerprint in binary as 20 bytes

8.7.2.2 byte [] Coherent.UI.Certificate.FingerprintCA [get]

the fingerprint of the certificate authority

the fingerprint in binary as 20 bytes

8.7.2.3 CertificatePrincipal Coherent.UI.Certificate.Issuer [get]

Issuer of the certificate.

8.7.2.4 byte [] Coherent.UI.Certificate.SerialNumber [get]

Serial number of the certificate in DER encoding.

8.7.2.5 CertificatePrincipal Coherent.UI.Certificate.Subject [get]

Subject of the certificate.

8.7.2.6 uint Coherent.UI.Certificate.ValidEnd [get]

The date after which the certificate is no longer valid in seconds since the UNIX epoch 01.01.1970.

8.7.2.7 uint Coherent.UI.Certificate.ValidStart [get]

The starting date from which the certificate becomes valid in seconds since the UNIX epoch 01.01.1970.

8.8 Coherent.UI.CertificatePrincipal Class Reference

Represents certificate principal.

Inherits IDisposable.

Properties

• string[] StreetAddresses [get]

The list of street addresses of the principal

string[] OrganizationNames [get]

The list of organization names of the principal

• string[] OrganizationUnitNames [get]

The list of organization unit names of the principal

• string[] DomainComponents [get]

The list of domain components storage of the principal

• string CommonName [get]

Null terminated string with the common name of the subject.

• string LocalityName [get]

Null terminated string with the locality name of the subject.

• string StateOrProvinceName [get]

Null terminated string with the state or province name of the subject.

• string CountryName [get]

Null terminated string with the country name of the subject.

8.8.1 Detailed Description

Represents certificate principal.

8.8.2 Property Documentation

8.8.2.1 string Coherent.UI.CertificatePrincipal.CommonName [get]

Null terminated string with the common name of the subject.

8.8.2.2 string Coherent.UI.CertificatePrincipal.CountryName [get]

Null terminated string with the country name of the subject.

8.8.2.3 string [] Coherent.UI.CertificatePrincipal.DomainComponents [get]

The list of domain components storage of the principal

8.8.2.4 string Coherent.UI.CertificatePrincipal.LocalityName [get]

Null terminated string with the locality name of the subject.

8.8.2.5 string [] Coherent.UI.CertificatePrincipal.OrganizationNames [get]

The list of organization names of the principal

8.8.2.6 string [] Coherent.UI.CertificatePrincipal.OrganizationUnitNames [get]

The list of organization unit names of the principal

8.8.2.7 string Coherent.UI.CertificatePrincipal.StateOrProvinceName [get]

Null terminated string with the state or province name of the subject.

8.8.2.8 string [] Coherent.UI.CertificatePrincipal.StreetAddresses [get]

The list of street addresses of the principal

8.9 Coherent.UI.ChildViewInfo Class Reference

Helper structure for creating child views.

Inherits IDisposable.

Properties

```
• ViewInfo NewViewInfo [get, set]
```

An existing

• ViewListenerBase Listener [get, set]

View

8.9.1 Detailed Description

Helper structure for creating child views.

8.9.2 Property Documentation

```
8.9.2.1 ViewListenerBase Coherent.UI.ChildViewInfo.Listener [get], [set]
```

View

8.9.2.2 ViewInfo Coherent.UI.ChildViewInfo.NewViewInfo [get], [set]

An existing

8.10 Coherent.UI.Binding.CoherentProperty Class Reference

Specify a property / field or method visible to Coherent UI Inherits Attribute.

Public Member Functions

• CoherentProperty ()

Make a property / field or method visible to Coherent UI

• CoherentProperty (string name)

Make a property / field or method visible to Coherent UI

8.10.1 Detailed Description

Specify a property / field or method visible to Coherent UI

8.10.2 Constructor & Destructor Documentation

8.10.2.1 Coherent.UI.Binding.CoherentProperty.CoherentProperty() [inline]

Make a property / field or method visible to Coherent UI

8.10.2.2 Coherent.UI.Binding.CoherentProperty.CoherentProperty (string *name*) [inline]

Make a property / field or method visible to Coherent UI

Parameters

name | name of the property / field / method

8.11 Coherent.UI.Binding.CoherentType Class Reference

Specify which properties and fields of a type are visible to Coherent UI Inherits Attribute.

8.11.1 Detailed Description

Specify which properties and fields of a type are visible to Coherent UI

8.12 Coherent.UI.Download Class Reference

Encapsulates a download task.

Inherits IDisposable.

Public Member Functions

virtual void Destroy ()

Must be called when the client is ready with the download to free the resources associated with it If the download is not yet complete this implies a Cancel operation Calling any method after Finish is undefined.

virtual uint GetId ()

An opaque id of the download. Ids are unique per-system per-session and can be used to distinguish downloads poiniting to the same resource.

virtual bool Cancel ()

Cancels a download task.

• virtual string GetURL ()

The download url.

• virtual string GetFilename ()

The name of the downloaded file.

virtual string GetReferrer ()

The referrer of the download.

virtual uint GetTotalBytes ()

The estimated size of the download.

virtual uint GetDownloadedBytesSoFar ()

The bytes downloaded so far. NB. Downloads are completed asynchronously, this is an estimation and might not be up-to-date.

• virtual bool IsComplete ()

Tells if the download is complete.

virtual bool IsCancelled ()

Tells if the download has been cancelled.

• virtual bool HasFailed ()

Tells if the download has failed.

8.12.1 Detailed Description

Encapsulates a download task.

```
8.12.2 Member Function Documentation
```

```
8.12.2.1 virtual bool Coherent.UI.Download.Cancel() [inline], [virtual]
```

Cancels a download task.

Returns

true if the task has been cancelled. Calling Cancel on an already finished or stopped task will return false

```
8.12.2.2 virtual void Coherent.UI.Download.Destroy() [inline], [virtual]
```

Must be called when the client is ready with the download to free the resources associated with it If the download is not yet complete this implies a Cancel operation Calling any method after Finish is undefined.

```
8.12.2.3 virtual uint Coherent.UI.Download.GetDownloadedBytesSoFar() [inline], [virtual]
```

The bytes downloaded so far. NB. Downloads are completed asynchronously, this is an estimation and might not be up-to-date.

Returns

the bytes downloaded so far

```
8.12.2.4 virtual string Coherent.UI.Download.GetFilename() [inline], [virtual]
```

The name of the downloaded file.

Returns

the name of the file being doenloaded

```
8.12.2.5 virtual uint Coherent.UI.Download.Getld() [inline], [virtual]
```

An opaque id of the download. Ids are unique per-system per-session and can be used to distinguish downloads pointing to the same resource.

Returns

a unique id of the download

```
8.12.2.6 virtual string Coherent.UI.Download.GetReferrer() [inline], [virtual]
```

The referrer of the download.

Returns

the referrer

```
8.12.2.7 virtual uint Coherent.UI.Download.GetTotalBytes ( ) [inline], [virtual]
```

The estimated size of the download.

Returns

the estimated size in bytes

```
8.12.2.8 virtual string Coherent.UI.Download.GetURL() [inline], [virtual]
The download url.
Returns
     the url to download
8.12.2.9 virtual bool Coherent.UI.Download.HasFailed ( ) [inline], [virtual]
Tells if the download has failed.
Returns
     if the download has failed
8.12.2.10 virtual bool Coherent.UI.Download.lsCancelled() [inline], [virtual]
Tells if the download has been cancelled.
Returns
     if the download has been cancelled
8.12.2.11 virtual bool Coherent.UI.Download.IsComplete ( ) [inline], [virtual]
Tells if the download is complete.
Returns
     if the download is complete
```

8.13 Coherent.UI.EventListener Class Reference

Abstract interface to listen to System-related events.

Inherits IDisposable.

Public Member Functions

• virtual void SystemReady ()

Called when the system is fully initialized. Creating Views is now permitted.

• virtual void OnError (SystemError arg0)

Called when an error in the system occurs.

virtual bool OnDownloadStarted (Download downloadItem)

Called when the system tries to start a new download. Return true to allow for the download to begin or false to cancel it.

virtual void OnDownloadComplete (Download downloadItem, System.IntPtr data, uint size)

Called when a download is complete.

• virtual void OnDownloadFailed (Download downloadItem, DownloadErrorType error)

Called when a download has failed.

8.13.1 Detailed Description

Abstract interface to listen to System-related events.

8.13.2 Member Function Documentation

8.13.2.1 virtual void Coherent.UI.EventListener.OnDownloadComplete (Download downloadItem, System.IntPtr data, uint size) [inline], [virtual]

Called when a download is complete.

8.13.2.2 virtual void Coherent.UI.EventListener.OnDownloadFailed (Download downloadItem, DownloadErrorType error) [inline], [virtual]

Called when a download has failed.

8.13.2.3 virtual bool Coherent.UI.EventListener.OnDownloadStarted (Download downloadItem) [inline], [virtual]

Called when the system tries to start a new download. Return true to allow for the download to begin or false to cancel it.

8.13.2.4 virtual void Coherent.UI.EventListener.OnError (SystemError arg0) [inline], [virtual]

Called when an error in the system occurs.

8.13.2.5 virtual void Coherent.UI.EventListener.SystemReady() [inline], [virtual]

Called when the system is fully initialized. Creating Views is now permitted.

8.14 Coherent.UI.EventModifiersState Class Reference

The state of the key modifiers when an event happens.

Inherits IDisposable.

8.14.1 Detailed Description

The state of the key modifiers when an event happens.

8.15 Coherent.UI.EventMouseModifiersState Class Reference

The state of the mouse modifiers when an event happens.

Inherits IDisposable.

8.15.1 Detailed Description

The state of the mouse modifiers when an event happens.

8.16 Coherent. UI. File Handler Class Reference

Abstract interface that allows clients to provide their own file-handling functionality. Inherits IDisposable.

Public Member Functions

· virtual void ReadFile (string url, ResourceResponse response)

Requests to read a resource.

virtual void WriteFile (string url, ResourceData resource)

Request to write to a resource.

8.16.1 Detailed Description

Abstract interface that allows clients to provide their own file-handling functionality.

8.16.2 Member Function Documentation

8.16.2.1 virtual void Coherent.UI.FileHandler.ReadFile (string *url*, ResourceResponse *response*) [inline], [virtual]

Requests to read a resource.

Parameters

url	the coui url of the resource.
response	the response to be filled with the resource data or notified for failure

8.16.2.2 virtual void Coherent.UI.FileHandler.WriteFile (string url, ResourceData resource) [inline], [virtual]

Request to write to a resource.

Parameters

url	the coui url of the resource.
resource	the resource data that has to be written

8.17 Coherent.UI.HTTPHeader Class Reference

Encapsulates a HTTP header field with it's content.

Inherits IDisposable.

Properties

• string Field [get, set]

The name (key) of the HTTP header field.

• string Content [get, set]

The value of the HTTP header field.

8.17.1 Detailed Description

Encapsulates a HTTP header field with it's content.

8.17.2 Property Documentation

8.17.2.1 string Coherent.UI.HTTPHeader.Content [get], [set]

The value of the HTTP header field.

8.17.2.2 string Coherent.UI.HTTPHeader.Field [get], [set]

The name (key) of the HTTP header field.

8.18 Coherent.UI.ILogHandler Class Reference

Interface to allow custom logging.

Inherits IDisposable.

Public Member Functions

- virtual void WriteLog (Severity severity, string message, uint length)
 - Called when a log message has to be written.
- virtual void Assert (string message)

Called when an assert is triggered.

8.18.1 Detailed Description

Interface to allow custom logging.

8.18.2 Member Function Documentation

8.18.2.1 virtual void Coherent.UI.ILogHandler.Assert (string message) [inline], [virtual]

Called when an assert is triggered.

Parameters

message	a message that describes the reason for the assertion

8.18.2.2 virtual void Coherent.UI.ILogHandler.WriteLog (Severity, string *message*, uint *length*) [inline], [virtual]

Called when a log message has to be written.

Parameters

severity	the severity of the message
message	the log message itself
length	the length of the message

8.19 Coherent.UI.ImageData Class Reference

This class represents a link to a Inherits IDisposable.

Public Member Functions

• virtual void Update (IntPtr data, bool flipY)

Updates the content of the

• virtual void Destroy ()

Destroys the

8.19.1 Detailed Description

This class represents a link to a

8.19.2 Member Function Documentation

8.19.2.1 virtual void Coherent.UI.ImageData.Destroy() [inline], [virtual]

Destroys the

8.19.2.2 virtual void Coherent.UI.ImageData.Update (IntPtr data, bool flipY) [inline], [virtual]

Updates the content of the

Parameters

data	a pointer to the new data to copy in the object the size of the data must equal to the total size
	of the ImageData
flipY	tells if to flip vertically when copying

8.20 Coherent.UI.Binding.InvalidValueCastException Class Reference

Thrown when casting a Value to an incompatible type Inherits InvalidCastException.

8.20.1 Detailed Description

Thrown when casting a Value to an incompatible type

8.21 Coherent.UI.KeyEventData Class Reference

A keyboard event.

Inherits IDisposable.

Properties

```
• int KeyCode [get, set]
```

The key code.

• KeyEventData.EventType Type [get, set]

The type of the event.

• EventModifiersState Modifiers [get, set]

The current key modifiers.

• bool IsAutoRepeat [get, set]

Is it an auto-repeat event (the user is holding the key down). This value isn't crucial and you can set it to false if you don't have the information, however you might experience incorrect repeat behavior in such case.

• bool IsNumPad [get, set]

Is it a key from the num-pad.

8.21.1 Detailed Description

A keyboard event.

8.21.2 Property Documentation

```
8.21.2.1 bool Coherent.UI.KeyEventData.IsAutoRepeat [get], [set]
```

Is it an auto-repeat event (the user is holding the key down). This value isn't crucial and you can set it to false if you don't have the information, however you might experience incorrect repeat behavior in such case.

```
8.21.2.2 bool Coherent.UI.KeyEventData.IsNumPad [get], [set]
```

Is it a key from the num-pad.

```
8.21.2.3 int Coherent.UI.KeyEventData.KeyCode [get], [set]
```

The key code.

8.21.2.4 EventModifiersState Coherent.Ul.KeyEventData.Modifiers [get], [set]

The current key modifiers.

```
8.21.2.5 KeyEventData.EventType Coherent.UI.KeyEventData.Type [get], [set]
```

The type of the event.

8.22 Coherent.UI.MediaStreamDevice Class Reference

Represents a media stream device.

Inherits IDisposable.

Properties

• MediaStreamType Type [get]

type of the device

• string DeviceId [get]

Null terminated string with the unique id of the device.

• string Name [get]

Null terminated string with the device name. It may not be unique.

8.22.1 Detailed Description

Represents a media stream device.

8.22.2 Property Documentation

8.22.2.1 string Coherent.UI.MediaStreamDevice.DeviceId [get]

Null terminated string with the unique id of the device.

8.22.2.2 string Coherent.UI.MediaStreamDevice.Name [get]

Null terminated string with the device name. It may not be unique.

8.22.2.3 MediaStreamType Coherent.UI.MediaStreamDevice.Type [get]

type of the device

8.23 Coherent.UI.MediaStreamRequest Class Reference

Represents a request for media stream.

Inherits IDisposable.

Public Member Functions

void Respond (uint[] devices)

Respond to the media stream request.

Properties

• MediaStreamDevice[] Devices [get]

Get the list of available devices for the request. The list contains only devices of the requested types.

8.23.1 Detailed Description

Represents a request for media stream.

8.23.2 Member Function Documentation

8.23.2.1 void Coherent.UI.MediaStreamRequest.Respond (uint[] devices) [inline]

Respond to the media stream request.

Parameters

devices	array of indices of the media stream devices to use for the request	

Only a single device per stream type must be allowed. After a call to Respond calling any method on the instance results in undefined behavior. Must be called on the thread that owns the Coherent::UI::UISystem instance.

8.23.3 Property Documentation

```
8.23.3.1 MediaStreamDevice [] Coherent.UI.MediaStreamRequest.Devices [get]
```

Get the list of available devices for the request. The list contains only devices of the requested types.

8.24 Coherent.UI.MouseEventData Class Reference

A mouse event.

Inherits IDisposable.

Properties

```
    MouseEventData.EventType Type [get, set]
```

The type of the event.

• MouseEventData.MouseButton Button [get, set]

The mouse button that triggered the event.

• int X [get, set]

The X position of the mouse in pixels in the space of the view.

int Y [get, set]

The Y position of the mouse in pixels in the space of the view.

• float WheelX [get, set]

Scroll Delta X in wheel ticks. Positive numbers mean scrolling left.

• float WheelY [get, set]

Scroll Delta Y in wheel ticks. Positive numbers mean scrolling up.

• EventModifiersState Modifiers [get, set]

Key modifiers.

• EventMouseModifiersState MouseModifiers [get, set]

Mouse modifiers.

8.24.1 Detailed Description

A mouse event.

8.24.2 Property Documentation

 $\textbf{8.24.2.1} \quad \textbf{MouseEventData.MouseButton Coherent.UI.MouseEventData.Button} \quad \texttt{[get], [set]}$

The mouse button that triggered the event.

8.24.2.2 EventModifiersState Coherent.UI.MouseEventData.Modifiers [get], [set]

Key modifiers.

8.24.2.3 EventMouseModifiersState Coherent.UI.MouseEventData.MouseModifiers [get], [set]

Mouse modifiers.

8.24.2.4 MouseEventData.EventType Coherent.UI.MouseEventData.Type [qet], [set]

The type of the event.

8.24.2.5 float Coherent.UI.MouseEventData.WheelX [get], [set]

Scroll Delta X in wheel ticks. Positive numbers mean scrolling left.

8.24.2.6 float Coherent.UI.MouseEventData.WheelY [get], [set]

Scroll Delta Y in wheel ticks. Positive numbers mean scrolling up.

8.24.2.7 int Coherent.UI.MouseEventData.X [get], [set]

The X position of the mouse in pixels in the space of the view.

8.24.2.8 int Coherent.UI.MouseEventData.Y [get], [set]

The Y position of the mouse in pixels in the space of the view.

8.25 Coherent.UI.ResourceData Class Reference

Abstract interface providing data for storing resources.

Inherits IDisposable.

Public Member Functions

• virtual IntPtr GetBuffer ()

Get the buffer with the resource data.

virtual uint GetSize ()

Get the size of the data.

• virtual void SignalSuccess ()

Report that writing to resource was successful. This should be executed in the thread that all Coherent UI methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

• virtual void SignalFailure ()

Report that resource writing has failed. This should be executed in the thread that all Coherent UI methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

8.25.1 Detailed Description

Abstract interface providing data for storing resources.

8.25.2 Member Function Documentation

8.25.2.1 virtual IntPtr Coherent.UI.ResourceData.GetBuffer() [inline], [virtual]

Get the buffer with the resource data.

Returns

pointer to the beginning of the data. May return nullptr when acquiring the buffer has failed

8.25.2.2 virtual uint Coherent.UI.ResourceData.GetSize() [inline], [virtual]

Get the size of the data.

Returns

the size of the data

8.25.2.3 virtual void Coherent.UI.ResourceData.SignalFailure() [inline], [virtual]

Report that resource writing has failed. This should be executed in the thread that all Coherent UI methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

8.25.2.4 virtual void Coherent.UI.ResourceData.SignalSuccess() [inline], [virtual]

Report that writing to resource was successful. This should be executed in the thread that all Coherent UI methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

8.26 Coherent.UI.ResourceResponse Class Reference

Abstract interface for responding to read resource requests.

Inherits IDisposable.

Public Member Functions

virtual IntPtr GetBuffer (uint size)

Request buffer for resource data. GetBuffer must be called only once. GetBuffer may be called in any thread.

· virtual void SignalSuccess ()

Report that the resource is read successfully. This should be executed in the thread that all Coherent UI methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

• virtual void SignalFailure ()

Report that resource reading has failed. This should be executed in the thread that all Coherent UI methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

8.26.1 Detailed Description

Abstract interface for responding to read resource requests.

8.26.2 Member Function Documentation

8.26.2.1 virtual IntPtr Coherent.UI.ResourceResponse.GetBuffer (uint size) [inline], [virtual]

Request buffer for resource data. GetBuffer must be called only once. GetBuffer may be called in any thread.

Parameters

size	the size of the resource
------	--------------------------

Returns

pointer to the beginning of the buffer. It may return nullptr when allocating the buffer has failed

```
8.26.2.2 virtual void Coherent.UI.ResourceResponse.SignalFailure() [inline], [virtual]
```

Report that resource reading has failed. This should be executed in the thread that all Coherent UI methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

```
8.26.2.3 virtual void Coherent.UI.ResourceResponse.SignalSuccess() [inline], [virtual]
```

Report that the resource is read successfully. This should be executed in the thread that all Coherent UI methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

8.27 Coherent.UI.SurfaceResponse Class Reference

Interface that signals for creation of rendering surfaces.

Inherits IDisposable.

Public Member Functions

virtual void Signal (CoherentHandle handle)

Signals that the operation was completed. You should call this function in the same thread that updates the UI system.

8.27.1 Detailed Description

Interface that signals for creation of rendering surfaces.

8.27.2 Member Function Documentation

```
8.27.2.1 virtual void Coherent.UI.SurfaceResponse.Signal ( CoherentHandle handle ) [inline], [virtual]
```

Signals that the operation was completed. You should call this function in the same thread that updates the UI system.

Parameters

handle the created surface handle or a NULL handle if the operation fails

8.28 Coherent.UI.SystemError Class Reference

Encapsulates a system-related error.

Inherits IDisposable.

Properties

• SystemErrorType ErrorCode [get, set]

Indicates an error code.

• string Error [get, set]

Error description.

8.28.1 Detailed Description

Encapsulates a system-related error.

8.28.2 Property Documentation

8.28.2.1 string Coherent.UI.SystemError.Error [get], [set]

Error description.


8.28.2.2 SystemErrorType Coherent.UI.SystemError.ErrorCode [get], [set]

Indicates an error code.

8.29 Coherent.UI.SystemSettings Class Reference

Encapsulates the settings of the

Inheritance diagram for Coherent.UI.SystemSettings:



Properties

• new string HostDirectory [get, set]

Points to the folder where the host application and it's libraries reside (relative to the application's directory)

• new string CookiesResource [get, set]

Resource name to be used for storing and loading cookies. Leave nullptr to disable persistence of cookies.

• new string CachePath [get, set]

Path (relative to the host executable) where to save cached data. Leave nullptr for in-memory only caching.

new string HTML5LocalStoragePath [get, set]

Path (relative to the host executable) where to allow pages to save their HTML5 local data. Leave nullptr to forbid local storage.

• new string MinidumpFolder [get, set]

The folder where eventual minidumps will be saved (Windows only)

• new string CustomUserAgentString [get, set]

The user agent string that will be used if you select "UAT_Custom" for UserAgent.

• System.IntPtr FocusWindow [set]

The focus window that the client has passed when creating her device. This, along with D3DInterfaceType and D3D-Object, is needed for fullscreen apps that use DirectX9 or DirectX9Ex so as to support Alt+Tab functionality. Otherwise might be omitted. (Windows only)

• System.IntPtr D3DObject [set]

The D3DObject used by client to create her device. This, along with D3DInterfaceType and FocusWindow, is needed for fullscreen apps that use DirectX9 or DirectX9Ex so as to support Alt+Tab functionality. Otherwise might be omitted. (Windows only)

8.29.1 Detailed Description

Encapsulates the settings of the

8.29.2 Property Documentation

```
8.29.2.1 new string Coherent.UI.SystemSettings.CachePath [get], [set]
```

Path (relative to the host executable) where to save cached data. Leave nullptr for in-memory only caching.

```
8.29.2.2 new string Coherent.UI.SystemSettings.CookiesResource [get], [set]
```

Resource name to be used for storing and loading cookies. Leave nullptr to disable persistence of cookies.

```
8.29.2.3 new string Coherent.UI.SystemSettings.CustomUserAgentString [qet], [set]
```

The user agent string that will be used if you select "UAT_Custom" for UserAgent.

```
8.29.2.4 System.IntPtr Coherent.UI.SystemSettings.D3DObject [set]
```

The D3DObject used by client to create her device. This, along with D3DInterfaceType and FocusWindow, is needed for fullscreen apps that use DirectX9 or DirectX9Ex so as to support Alt+Tab functionality. Otherwise might be omitted. (Windows only)

```
8.29.2.5 System.IntPtr Coherent.UI.SystemSettings.FocusWindow [set]
```

The focus window that the client has passed when creating her device. This, along with D3DInterfaceType and D3DObject, is needed for fullscreen apps that use DirectX9 or DirectX9Ex so as to support Alt+Tab functionality. Otherwise might be omitted. (Windows only)

```
8.29.2.6 new string Coherent.UI.SystemSettings.HostDirectory [get], [set]
```

Points to the folder where the host application and it's libraries reside (relative to the application's directory)

```
8.29.2.7 new string Coherent.UI.SystemSettings.HTML5LocalStoragePath [get], [set]
```

Path (relative to the host executable) where to allow pages to save their HTML5 local data. Leave nullptr to forbid local storage.


```
8.29.2.8 new string Coherent.UI.SystemSettings.MinidumpFolder [get], [set]
```

The folder where eventual minidumps will be saved (Windows only)

8.30 Coherent.UI.SystemSettingsBase Class Reference

Encapsulates the settings of the

Inheritance diagram for Coherent.UI.SystemSettingsBase:



Properties

• bool EnableProxy [get, set]

Enables/disables proxy support. Proxy settings are auto-detected when proxy support is enabled. Enable proxy support only when the user really has a proxy, because otherwise the auto-detection is very slow.

• bool AllowCookies [get, set]

Enables/disables cookies when accessing the web.

bool ForceDisablePluginFullscreen [get, set]

Disables 'Fullscreen mode' on all Plugins(Flash etc.)

bool DisableWebSecurity [get, set]

Disable Same-Origin Policy. Use with caution.

• int DebuggerPort [get, set]

Port to use for remote debugging. Use -1 to disable debugging.

• bool WriteMinidumps [get, set]

If a

• bool EnableSupportForProprietaryCodecs [get, set]

Enable support for proprietary codecs. Playing proprietary codecs requires ffmpegsumo library that is capable of playing them as well. Note that distributing such ffmpegsumo library requires license from the repspective rights holder.

• Direct3DInterfaceType D3DInterfaceType [get, set]

The type of D3DObject supplied. This, along with D3DObject and FocusWindow, is needed for fullscreen apps that use DirectX9 or DirectX9Ex so as to support Alt+Tab functionality. Otherwise might be omitted. (Windows only)

• UserAgentType UserAgent [get, set]

The type of the user agent. If you select "UAT_Custom", you MUST also specify the user agent string - defaults to Chrome.

• string CustomUserAgentString [get, set]

The user agent string that will be used if you select "UAT_Custom" for UserAgent.

8.30.1 Detailed Description

Encapsulates the settings of the

8.30.2 Property Documentation

8.30.2.1 bool Coherent.UI.SystemSettingsBase.AllowCookies [get], [set]

Enables/disables cookies when accessing the web.

8.30.2.2 string Coherent.UI.SystemSettingsBase.CustomUserAgentString [get], [set]

The user agent string that will be used if you select "UAT_Custom" for UserAgent.

8.30.2.3 Direct3DInterfaceType Coherent.UI.SystemSettingsBase.D3DInterfaceType [get], [set]

The type of D3DObject supplied. This, along with D3DObject and FocusWindow, is needed for fullscreen apps that use DirectX9 or DirectX9Ex so as to support Alt+Tab functionality. Otherwise might be omitted. (Windows only)

8.30.2.4 int Coherent.UI.SystemSettingsBase.DebuggerPort [get], [set]

Port to use for remote debugging. Use -1 to disable debugging.

8.30.2.5 bool Coherent.UI.SystemSettingsBase.DisableWebSecurity [get], [set]

Disable Same-Origin Policy. Use with caution.

8.30.2.6 bool Coherent.UI.SystemSettingsBase.EnableProxy [get], [set]

Enables/disables proxy support. Proxy settings are auto-detected when proxy support is enabled. Enable proxy support only when the user really has a proxy, because otherwise the auto-detection is very slow.

8.30.2.7 bool Coherent.UI.SystemSettingsBase.EnableSupportForProprietaryCodecs [qet], [set]

Enable support for proprietary codecs. Playing proprietary codecs requires ffmpegsumo library that is capable of playing them as well. Note that distributing such ffmpegsumo library requires license from the repspective rights holder.

8.30.2.8 bool Coherent.UI.SystemSettingsBase.ForceDisablePluginFullscreen [get], [set]

Disables 'Fullscreen mode' on all Plugins(Flash etc.)

8.30.2.9 UserAgentType Coherent.Ul.SystemSettingsBase.UserAgent [get], [set]

The type of the user agent. If you select "UAT_Custom", you MUST also specify the user agent string - defaults to Chrome.

8.30.2.10 bool Coherent.UI.SystemSettingsBase.WriteMinidumps [get], [set]

If a

8.31 Coherent.UI.TouchEventData Class Reference

A touch event.

Inherits IDisposable.

Properties

```
int X [get, set]
```

The X position where the touch happened in pixels in the space of the view.

int Y [get, set]

The Y position where the touch happened in pixels in the space of the view.

uint ld [get, set]

Identifies a particular touch input. This value must stay consistent in a touch contact sequence.

• TouchEventData.EventType Type [get, set]

The type of the touch event.

• bool HasRadiusInformation [get, set]

Flags if there is contact radius information for this event.

• uint RadiusX [get, set]

The X radius of the contact (must be set only if HasRadiusInformation == true)

• uint RadiusY [get, set]

The Y radius of the contact (must be set only if HasRadiusInformation == true)

8.31.1 Detailed Description

A touch event.

8.31.2 Property Documentation

8.31.2.1 bool Coherent.UI.TouchEventData.HasRadiusInformation [get], [set]

Flags if there is contact radius information for this event.

```
8.31.2.2 uint Coherent.UI.TouchEventData.ld [get], [set]
```

Identifies a particular touch input. This value must stay consistent in a touch contact sequence.

```
8.31.2.3 uint Coherent.UI.TouchEventData.RadiusX [get], [set]
```

The X radius of the contact (must be set only if HasRadiusInformation == true)

```
8.31.2.4 uint Coherent.UI.TouchEventData.RadiusY [get], [set]
```

The Y radius of the contact (must be set only if HasRadiusInformation == true)

8.31.2.5 TouchEventData.EventType Coherent.UI.TouchEventData.Type [get], [set]

The type of the touch event.

```
8.31.2.6 int Coherent.UI.TouchEventData.X [get], [set]
```

The X position where the touch happened in pixels in the space of the view.

```
8.31.2.7 int Coherent.UI.TouchEventData.Y [get], [set]
```

The Y position where the touch happened in pixels in the space of the view.

8.32 Coherent.UI.UISystem Class Reference

Encapsulates basic UI system functionality.

Inherits IDisposable.

Public Member Functions

• virtual bool Uninitialize ()

Frees all resources used by the event system. the UISystem object is unusable after this call

virtual void Update ()

Communicates with the UI system process and performs all updates. Must be called in the thread that owns the system. All registered callbacks will be called in here

virtual void FetchSurfaces ()

Check if new surfaces have been drawn and are available. This function can be called from a thread different than the main UI system thread in order to support client applications with multi-threaded rendering. Fetches only the surfaces of buffered views; on-demand views must be fetched manually per-view

virtual void CreateView (ViewInfo info, string path, ViewListenerBase listener)

Creates a new UI Must be called after the system has signaled that it is ready via Coherent::UI::EventListener::-SystemReady

• virtual void CreateView (ViewInfo info, string path, ViewListenerBase listener, string scriptToExecute)

Creates a new UI Must be called after the system has signaled that it is ready via Coherent::UI::EventListener::-SystemReady

8.32.1 Detailed Description

Encapsulates basic UI system functionality.

8.32.2 Member Function Documentation

8.32.2.1 virtual void Coherent.UI.UISystem.CreateView (ViewInfo info, string path, ViewListenerBase listener) [inline], [virtual]

Creates a new UI Must be called after the system has signaled that it is ready via Coherent::UI::EventListener::-SystemReady

Parameters

info	an instance of the ViewInfo struct that describes all the parameters of the view
path	the page to load when the view is created
listener	an instance of the ViewListenerBase interface to allow listening to all the events raised for
	this view

8.32.2.2 virtual void Coherent.UI.UISystem.CreateView (ViewInfo info, string path, ViewListenerBase listener, string scriptToExecute) [inline], [virtual]

Creates a new UI Must be called after the system has signaled that it is ready via Coherent::UI::EventListener::-SystemReady

Parameters

info	an instance of the ViewInfo struct that describes all the parameters of the view
path	the page to load when the view is created
listener	an instance of the ViewListenerBase interface to allow listening to all the events raised for
	this view

```
8.32.2.3 virtual void Coherent.UI.UISystem.FetchSurfaces() [inline], [virtual]
```

Check if new surfaces have been drawn and are available. This function can be called from a thread different than the main UI system thread in order to support client applications with multi-threaded rendering. Fetches only the surfaces of buffered views; on-demand views must be fetched manually per-view

```
8.32.2.4 virtual bool Coherent.UI.UISystem.Uninitialize() [inline], [virtual]
```

Frees all resources used by the event system. the UISystem object is unusable after this call

Returns

true if the system has been properly uninitialized

```
8.32.2.5 virtual void Coherent.UI.UISystem.Update() [inline], [virtual]
```

Communicates with the UI system process and performs all updates. Must be called in the thread that owns the system. All registered callbacks will be called in here

8.33 Coherent.UI.Binding.UnsupportedPrimitiveTypeException Class Reference

Thrown when trying to bind a value of unsupported primitive type such as long Inherits Exception.

8.33.1 Detailed Description

Thrown when trying to bind a value of unsupported primitive type such as long

8.34 Coherent.UI.URLRequest Class Reference

represents a single URL request Allows monitoring and modifications of URL requests Inherits IDisposable.

Public Member Functions

HTTPHeader[] GetExtraHeaders ()

Get extra request headers

void SetExtraHeaders (HTTPHeader[] headers)

Set the extra headers.

• virtual string GetURL ()

Get the URL of the request.

virtual void SetURL (string url)

Replace the URL of the request.

virtual string GetMethod ()

Get the method of the request.

virtual void SetMethod (string method)

Set the method of the request.

virtual string GetReferrer ()

Get the referrer of the request.

• virtual void SetReferrer (string referrer)

Set the referrer of the request.

• virtual void SetExtraHeader (string field, string content)

Set extra header for the request. If there is already a header with that field name its content will be replaced.

virtual void AppendExtraHeaderValue (string field, string content)

Append extra header for the request. If there is already a header with that field name the content will be appended to the header current content with a comma as a separator between the values. If there is not such header it will be added.

virtual void RemoveExtraHeader (string field)

Remove extra header from the request.

virtual string GetExtraHeader (string field)

Get extra header value.

virtual void Deny ()

Deny the request.

8.34.1 Detailed Description

represents a single URL request Allows monitoring and modifications of URL requests

8.34.2 Member Function Documentation

```
8.34.2.1 virtual void Coherent.UI.URLRequest.AppendExtraHeaderValue ( string field, string content ) [inline], [virtual]
```

Append extra header for the request. If there is already a header with that field name the content will be appended to the header current content with a comma as a separator between the values. If there is not such header it will be added.

Parameters

field	name of the header
content	content of the header

8.34.2.2 virtual void Coherent.UI.URLRequest.Deny() [inline], [virtual]

Deny the request.

8.34.2.3 virtual string Coherent.UI.URLRequest.GetExtraHeader (string field) [inline], [virtual]

Get extra header value.

Parameters

field	field of the header

Returns

the value of the header or nullptr if there is such header in the request

```
8.34.2.4 HTTPHeader[] Coherent.UI.URLRequest.GetExtraHeaders() [inline]
Get extra request headers
Returns
     array of the extra request headers
8.34.2.5 virtual string Coherent.UI.URLRequest.GetMethod() [inline], [virtual]
Get the method of the request.
Returns
     the method as a string
8.34.2.6 virtual string Coherent.UI.URLRequest.GetReferrer() [inline], [virtual]
Get the referrer of the request.
Returns
     the referrer of the request
8.34.2.7 virtual string Coherent.UI.URLRequest.GetURL() [inline], [virtual]
Get the URL of the request.
Returns
     the URL of the request
8.34.2.8 virtual void Coherent.UI.URLRequest.RemoveExtraHeader( string field ) [inline], [virtual]
Remove extra header from the request.
Parameters
              field
                     field of the header to be removed
8.34.2.9 virtual void Coherent.UI.URLRequest.SetExtraHeader ( string field, string content ) [inline], [virtual]
Set extra header for the request. If there is already a header with that field name its content will be replaced.
```

Set extra neader for the request. If there is already a header with that field name its content will be replaced.

Parameters

field	name of the header
content	new content of the header

8.34.2.10 void Coherent.UI.URLRequest.SetExtraHeaders (HTTPHeader[] headers) [inline]

Set the extra headers.

Parameters

headers the array of new headers

8.34.2.11 virtual void Coherent.UI.URLRequest.SetMethod (string method) [inline],[virtual]

Set the method of the request.

Parameters

method the new method as string. method must be a valid HTTP method name

8.34.2.12 virtual void Coherent.UI.URLRequest.SetReferrer (string referrer) [inline], [virtual]

Set the referrer of the request.

Parameters

referrer the new referrer URL for the request

8.34.2.13 virtual void Coherent.UI.URLRequest.SetURL (string url) [inline], [virtual]

Replace the URL of the request.

8.35 Coherent.UI.Binding.Value Class Reference

Type for representing generic JavaScript values

Public Member Functions

• Value ()

Create a null value

• Value (bool value)

Create a boolean value

• Value (int value)

Create an integer value

• Value (uint value)

Create an unsigned integer value

• Value (sbyte value)

Create a signed byte value

• Value (byte value)

Create a byte value

• Value (float value)

Create a float value

• Value (double value)

Create a double value

• Value (string value)

Create a string value

• Value (Value[] value)

Create an array value

Value (Dictionary < string, Value > value)

Create an object value

• Value (ValueObject value)

Create an object value

override bool Equals (object obj)

Compare to another object

· override int GetHashCode ()

Hash code for Value

Static Public Member Functions

static implicit operator bool (Value value)

cast a value to a boolean

static implicit operator int (Value value)

cast a value to an int

• static implicit operator uint (Value value)

cast a value to an uint

static implicit operator sbyte (Value value)

cast a value to a signed byte

• static implicit operator byte (Value value)

cast a value to a byte

• static implicit operator float (Value value)

cast a value to a float

• static implicit operator double (Value value)

cast a value to a double

• static implicit operator string (Value value)

cast a value to a string

• static implicit operator Value[] (Value value)

cast a value to an array

static implicit operator Dictionary< string, Value > (Value value)

cast a value to a dictionary of properties

static bool operator== (Value lhs, Value rhs)

Compares two Value objects

• static bool operator!= (Value lhs, Value rhs)

Compares two Value objects

Public Attributes

ValueType Type

The type of the data stored in this Value instance

8.35.1 Detailed Description

Type for representing generic JavaScript values

8.35.2 Constructor & Destructor Documentation

8.35.2.1 Coherent.UI.Binding.Value.Value() [inline]

Create a null value

 $\textbf{8.35.2.2} \quad \textbf{Coherent.UI.Binding.Value.Value (bool \textit{value})} \quad \texttt{[inline]}$

Create a boolean value

Parameters

value the integer value of the Value object

8.35.2.3 Coherent.UI.Binding.Value.Value(int value) [inline]

Create an integer value

Parameters

value the integer value of the Value object

8.35.2.4 Coherent.UI.Binding.Value.Value (uint value) [inline]

Create an unsigned integer value

Parameters

value the unsigned integer value of the Value object

8.35.2.5 Coherent.UI.Binding.Value.Value (sbyte value) [inline]

Create a signed byte value

Parameters

value the signed byte value of the Value object

 $\textbf{8.35.2.6} \quad \textbf{Coherent.UI.Binding.Value.Value (\ byte \textit{value} \)} \quad \texttt{[inline]}$

Create a byte value

Parameters

value the byte value of the Value object

8.35.2.7 Coherent.UI.Binding.Value.Value (float value) [inline]

Create a float value

Parameters

value the float value of the Value object

8.35.2.8 Coherent.UI.Binding.Value.Value (double value) [inline]

Create a double value

Parameters

value the double value of the Value object

 $\textbf{8.35.2.9} \quad \textbf{Coherent.UI.Binding.Value.Value (string \textit{value})} \quad \texttt{[inline]}$

Create a string value

Parameters

value the string value of the Value object

8.35.2.10 Coherent.UI.Binding.Value(Value[] value) [inline]

Create an array value

Parameters

value the array value of the Value object

8.35.2.11 Coherent.UI.Binding.Value.Value (Dictionary < string, Value > value) [inline]

Create an object value

Parameters

value | dictionary of properties of the Value object

8.35.2.12 Coherent.UI.Binding.Value.Value (ValueObject *value*) [inline]

Create an object value

Parameters

value dictionary of properties of the Value object

8.35.3 Member Function Documentation

8.35.3.1 override bool Coherent.UI.Binding.Value.Equals (object obj) [inline]

Compare to another object

Parameters

obj

Returns

true if obj is a Value instance equal to this one

8.35.3.2 override int Coherent.UI.Binding.Value.GetHashCode () [inline]

Hash code for Value

Returns

hash code for the current instance

8.35.3.3 static implicit Coherent.UI.Binding.Value.operator bool (Value value) [inline], [static]

cast a value to a boolean

Parameters

value value to be casted

Returns

the boolean stored in the value

8.35.3.4 static implicit Coherent.UI.Binding.Value.operator byte (Value value) [inline], [static]

cast a value to a byte

Parameters

value value to be cast

Returns

the byte stored in the value

8.35.3.5 static implicit Coherent.UI.Binding.Value.operator Dictionary < string, Value > (Value value) [inline], [static]

cast a value to a dictionary of properties

Parameters

value | value to be casted

Returns

the dictionary of properties of the value

8.35.3.6 static implicit Coherent.UI.Binding.Value.operator double (Value value) [inline], [static]

cast a value to a double

Parameters

value value to be casted

Returns

the double stored in the value

8.35.3.7 static implicit Coherent.UI.Binding.Value.operator float (Value value) [inline], [static]

cast a value to a float

Parameters

value value to be casted

Returns

the float stored in the value

8.35.3.8 static implicit Coherent.UI.Binding.Value.operator int (Value value) [inline], [static] cast a value to an int

Parameters

value value to be casted

Returns

the int stored in the value

8.35.3.9 static implicit Coherent.UI.Binding.Value.operator sbyte (Value value) [inline], [static]

cast a value to a signed byte

Parameters

value value to be cast

Returns

the signed byte stored in the value

8.35.3.10 static implicit Coherent.UI.Binding.Value.operator string (Value value) [inline], [static]

cast a value to a string

Parameters

value value to be casted

Returns

the string stored in the value

8.35.3.11 static implicit Coherent.UI.Binding.Value.operator uint (Value value) [inline], [static]

cast a value to an uint

Parameters

value value to be casted

Returns

the unsigned int stored in the value

8.35.3.12 static implicit Coherent.UI.Binding.Value.operator Value[](Value value) [inline], [static]

cast a value to an array

Parameters

value value to be casted

Returns

the array of Value objects stored in the value

8.35.3.13 static bool Coherent.UI.Binding.Value.operator!=(Value Ihs, Value rhs) [inline], [static]

Compares two Value objects

Parameters

lhs	object to be compared
rhs	object to be compared

Returns

false if the objects are from the same type and have the same values

8.35.3.14 static bool Coherent.UI.Binding.Value.operator==(Value Ihs, Value rhs) [inline], [static]

Compares two Value objects

Parameters

lhs	object to be compared
rhs	object to be compared

Returns

true if the objects are from the same type and have the same values

8.35.4 Member Data Documentation

8.35.4.1 ValueType Coherent.UI.Binding.Value.Type

The type of the data stored in this Value instance

8.36 Coherent.UI.Binding.ValueObject Class Reference

Class for compound JavaScript objects, behaves like a Dictionary<string, Value> Inherits IDictionary< string, Value>, and IDictionary.


8.36.1 Detailed Description

Class for compound JavaScript objects, behaves like a Dictionary<string, Value>

8.37 Coherent.UI.View Class Reference

Class that encapsulates a UI

Inheritance diagram for Coherent.UI.View:



Public Member Functions

BoundEventHandle BindCall (string name, System.Delegate handler)

Expose C++ handler to be called from UI.

BoundEventHandle RegisterForEvent (string name, System.Delegate handler)

Expose C++ handler to be called when a specific event occurs.

void UnregisterFromEvent (BoundEventHandle handle)

Remove a registered C++ handler.

void UnbindCall (BoundEventHandle handle)

Remove a bound C++ handler.

void UnbindObject (object target)

Remove all handlers bound to a specific object.

virtual ViewType GetViewType ()

Get the type of the view.

virtual void Destroy ()

Destroys this view. After a call to Destroy calling any other method except the destructor results in undefined behavior

virtual void SetFocus ()

Sets this view on focus.

• virtual void KillFocus ()

Removes the focus from this view.

virtual void MouseEvent (MouseEventData arg0)

Sends a mouse event to the UI renderer.

virtual void KeyEvent (KeyEventData arg0)

Sends a key event to the UI renderer.

virtual void TouchEvent (TouchEventData events, uint count)

Sends a touch event to the UI renderer.

virtual void MouseActivate ()

Sends a mouse event to the UI renderer.

virtual int GetWidth ()

Gets the width of the

virtual int GetHeight ()

Gets the height of the

virtual void Resize (uint width, uint height)

Send a resize event to the UI renderer. Resize will result in multiple calls to CreateBuffers and DestroyBuffers in the listener

virtual void IssueMouseOnUIQuery (float normX, float normY)

Issues a query on the Calling IsMouseOnView while a query is in-flight is an error and will be logged - the result returned by IsMouseOnView in that case is undefined.

• virtual ViewErrorType HasMouseQueryFinished ()

Returns the status of the mouse query.

• virtual void FetchMouseOnUlQuery ()

Ends a mouse-on-UI query. Waits for the result. Should be called as far apart from IssueMouseOnUIQuery in order to maximize the chances that the query has finished at the time of this call and no waiting will be performed

• virtual bool IsMouseOnView ()

Checks if the mouse is currently on the logical view (a part of the view that has elements on it) or not (click-through). Uses the coordinates last set in IssueMouseOnUIQuery. Calling the method while a query is in-flight (between a call to IssueMouseOnUIQuery and FetchMouseOnUIQuery) results in a warning and the return result is undefined

virtual void SetClickThroughAlphaThreshold (float threshold)

The alpha value of the pixels is used to determine if the mouse is on an element or on the background (click-through). All pixels below or equal to the alpha threshold (default = 0) are marked as not-belonging to the

virtual float GetClickThroughAlphaThreshold ()

Get the currently set alpha threshold for click-through queries.

virtual void SetTargetFramerate (int target)

Sets the target frame-rate for the

virtual int GetTargetFramerate ()

Get the currently set target frame-rate for the

virtual bool IsOnDemand ()

Tells if this is an on-demand view. Frames must be explicitly requested for on-demand views (available only in Full versions of 'Coherent::Ul::View::RequestFrame'

virtual ViewErrorType RequestFrame ()

Requests a new frame for rendering. All triggered events before this call will be accounted for in the rendered view. Only one frame per-view could be requested simultaneously (available only in Full versions of

virtual ViewErrorType RequestFrame (double timeSinceArbitraryMoment)

Requests a new frame for rendering. All triggered events before this call will be accounted for in the rendered view. Only one frame per-view could be requested simultaneously (available only in Full versions of

virtual ViewErrorType PeekFrameReady ()

Tells if the last requested frame is ready or not. Does not block. This call must always be made between calls to RequestFrame and FetchSurface. (available only in Full versions of 'Coherent::UI::View::RequestFrame' 'Coherent::-UI::View::FetchSurface'

virtual ViewErrorType FetchSurface ()

Returns the requested surface. Works only for on-demand views. All buffered view should use the system's Fetch-Surfaces method. This call will block until the surface is ready. (available only in Full versions of

virtual ViewErrorType DrawSurface ()

[EXPERIMENTAL - DO NOT USE]

virtual bool UsesSharedMemory ()

Tells if this view uses shared memory for image transport.

virtual bool IsTransparent ()

Tells if this view is transparent or not.

virtual bool SupportsClickThrough ()

Tells if this view supports click-through queries or not.

• virtual void Redraw ()

Request a redraw of the current view.

virtual void DownloadUrl (string path)

Initiates a download request on the specified path.

virtual void Load (string path)

Loads a new path in the

virtual void Reload (bool ignoreCache)

Reloads the last requested or navigated-to path.

virtual string GetCurentViewPath ()

Get the last requested or navigated-to path.

virtual string GetLastRequestedPath ()

Get the last requested path to load for the

virtual string GetLastLoadedPath ()

Get the last successfully loaded path for the

virtual string GetLastFailedPath ()

Get the last failed path for the

• virtual void ExecuteScript (string script)

Execute arbitrary JavaScript code.

virtual void TriggerEvent (string eventName)

Triggers a UI event.

virtual void ReplyToJavaScriptMessage (bool success, string userInput)

Sends a reply to a javascript message triggered for the view.

• virtual void AuthCredentialsResponse (string username, string password, bool success)

Sends credentials for a pending authentication request for the view.

virtual void SetScriptError (ScriptCallErrorType error, string message)

Sets an error for the currently executing handler.

virtual void InterceptURLRequests (bool intercept)

Controls intercepting URL requests. For each request

virtual void IMEActivate (bool active)

Sets if the

• virtual bool IMEIsActive ()

Tells if IME events are currently active for this view.

• virtual bool IMESetComposition (string composition, uint cursorPos, uint targetStart, uint targetEnd)

Updates the internal state of the IME composition in the

virtual bool IMEConfirmComposition (string composition)

Confirms the current IME composition.

• virtual bool IMECancelComposition ()

Cancels the current IME composition.

• virtual ImageData CreateImageData (string name, int width, int height, IntPtr data, bool flipY)

Create an

8.37.1 Detailed Description

Class that encapsulates a UI

8.37.2 Member Function Documentation

8.37.2.1 virtual void Coherent.UI.View.AuthCredentialsResponse (string *username*, string *password*, bool *success*) [inline], [virtual]

Sends credentials for a pending authentication request for the view.

Parameters

username	the username
password	the password
success	defines whether the response is valid, i.e. if the request should be answered or canceled

8.37.2.2 BoundEventHandle Coherent.UI.View.BindCall (string name, System.Delegate handler) [inline]

Expose C++ handler to be called from UI.

Parameters

name	name for the handler in the UI
handler	handler to be executed

Returns

bound handle so the handler can be unbound later

8.37.2.3 virtual ImageData Coherent.UI.View.CreateImageData (string *name*, int *width*, int *height*, IntPtr *data*, bool *flipY*) [inline], [virtual]

Create an

Parameters

name	the name of the image data object
width	the width of the image
height	the height of the image
data	initial data to fill the image data with
flipY	flips vertically the content of the source image

Returns

the image data object created in the DOM of this View

```
8.37.2.4 virtual void Coherent.UI.View.Destroy() [inline], [virtual]
```

Destroys this view. After a call to Destroy calling any other method except the destructor results in undefined behavior

```
8.37.2.5 virtual void Coherent.UI.View.DownloadUrl (string path) [inline], [virtual]
```

Initiates a download request on the specified path.

```
8.37.2.6 virtual ViewErrorType Coherent.UI.View.DrawSurface() [inline], [virtual]
```

[EXPERIMENTAL - DO NOT USE]

8.37.2.7 virtual void Coherent.UI.View.ExecuteScript (string script) [inline], [virtual]

Execute arbitrary JavaScript code.

Parameters

script

```
8.37.2.8 virtual void Coherent.UI.View.FetchMouseOnUIQuery() [inline], [virtual]
```

Ends a mouse-on-UI query. Waits for the result. Should be called as far apart from IssueMouseOnUIQuery in order to maximize the chances that the query has finished at the time of this call and no waiting will be performed

```
8.37.2.9 virtual ViewErrorType Coherent.UI.View.FetchSurface( ) [inline], [virtual]
```

Returns the requested surface. Works only for on-demand views. All buffered view should use the system's Fetch-Surfaces method. This call will block until the surface is ready. (available only in Full versions of

Returns

the outcome of the operation

```
8.37.2.10 virtual float Coherent.UI.View.GetClickThroughAlphaThreshold() [inline], [virtual]
```

Get the currently set alpha threshold for click-through queries.

Returns

the currently set alpha threshold

```
8.37.2.11 virtual string Coherent.UI.View.GetCurentViewPath() [inline], [virtual]
Get the last requested or navigated-to path.
Returns
     the path as null-terminated string
8.37.2.12 virtual int Coherent.UI.View.GetHeight() [inline], [virtual]
Gets the height of the
Returns
     the height of the View
8.37.2.13 virtual string Coherent.UI.View.GetLastFailedPath() [inline], [virtual]
Get the last failed path for the
Returns
     the path as null-terminated string
8.37.2.14 virtual string Coherent.UI.View.GetLastLoadedPath() [inline], [virtual]
Get the last successfully loaded path for the
Returns
     the path as null-terminated string
8.37.2.15 virtual string Coherent.UI.View.GetLastRequestedPath() [inline], [virtual]
Get the last requested path to load for the
Returns
     the path as null-terminated string
8.37.2.16 virtual int Coherent.UI.View.GetTargetFramerate() [inline], [virtual]
Get the currently set target frame-rate for the
Returns
     the current target frame-rate (available only in Full versions of Coherent UI)
8.37.2.17 virtual ViewType Coherent.UI.View.GetViewType() [inline], [virtual]
Get the type of the view.
Returns
     the type of the view
Reimplemented in Coherent.UI.BrowserView.
```

```
8.37.2.18 virtual int Coherent.UI.View.GetWidth() [inline], [virtual]
```

Gets the width of the

Returns

the width of the View

8.37.2.19 virtual ViewErrorType Coherent.UI.View.HasMouseQueryFinished() [inline], [virtual]

Returns the status of the mouse query.

Returns

the result will be Success if the query has finished, QueryNotReady otherwise. If no query has been issued InvalidCall will be returned.

8.37.2.20 virtual void Coherent.UI.View.IMEActivate (bool active) [inline], [virtual]

Sets if the

Parameters

active whether to activate IME handling for this view

8.37.2.21 virtual bool Coherent.UI.View.IMECancelComposition() [inline], [virtual]

Cancels the current IME composition.

Returns

the outcome of the operation (will fail if IME is inactive for this view)

8.37.2.22 virtual bool Coherent.UI.View.IMEConfirmComposition (string composition) [inline], [virtual]

Confirms the current IME composition.

Parameters

composition the string to confirm

Returns

the outcome of the operation (will fail if IME is inactive for this view)

8.37.2.23 virtual bool Coherent.UI.View.IMEIsActive() [inline], [virtual]

Tells if IME events are currently active for this view.

Returns

if the view has IME active

8.37.2.24 virtual bool Coherent.UI.View.IMESetComposition (string composition, uint cursorPos, uint targetStart, uint targetEnd) [inline], [virtual]

Updates the internal state of the IME composition in the

Parameters

composition	the composition string so far
the	cursor position in the composition
targetStart	the index at the start of the selection
targetEnd	the index at the end of the selection

Returns

the outcome of the operation (will fail if IME is inactive for this view)

8.37.2.25 virtual void Coherent.UI.View.InterceptURLRequests (bool intercept) [inline], [virtual]

Controls intercepting URL requests. For each request

Parameters

intercept	whether to intercept all URL requests

8.37.2.26 virtual bool Coherent.UI.View.lsMouseOnView() [inline], [virtual]

Checks if the mouse is currently on the logical view (a part of the view that has elements on it) or not (click-through). Uses the coordinates last set in IssueMouseOnUIQuery. Calling the method while a query is in-flight (between a call to IssueMouseOnUIQuery and FetchMouseOnUIQuery) results in a warning and the return result is undefined

Returns

true if the mouse is on the view

8.37.2.27 virtual bool Coherent.UI.View.IsOnDemand() [inline], [virtual]

Tells if this is an on-demand view. Frames must be explicitly requested for on-demand views (available only in Full versions of 'Coherent::UI::View::RequestFrame'

Returns

true if this is an on-demand view

8.37.2.28 virtual void Coherent.UI.View.IssueMouseOnUIQuery (float normX, float normY) [inline], [virtual]

Issues a query on the Calling IsMouseOnView while a query is in-flight is an error and will be logged - the result returned by IsMouseOnView in that case is undefined.

Put as much processing as possible between IssueMouseOnUIQuery and the corresponding FetchMouseOnUIQuery, this allows leveraging the cost of the query and to reduce it to \sim 0. The best way to do this is call Issue-MouseOnUIQuery early in the frame, perform all game rendering and the call FetchMouseOnUIQuery followed by IsMouseOnView to update the needed data.

Parameters

normY | the y coordinate of the mouse in the normalized space of the view [0..1]

8.37.2.29 virtual bool Coherent.UI.View.lsTransparent() [inline], [virtual]

Tells if this view is transparent or not.

Returns

true if the view is transparent

8.37.2.30 virtual void Coherent.UI.View.KeyEvent(KeyEventData arg0) [inline], [virtual]

Sends a key event to the UI renderer.

Parameters

```
event the key event
```

8.37.2.31 virtual void Coherent.UI.View.KillFocus() [inline], [virtual]

Removes the focus from this view.

8.37.2.32 virtual void Coherent.UI.View.Load (string path) [inline], [virtual]

Loads a new path in the

Parameters

```
path the path to load
```

8.37.2.33 virtual void Coherent.UI.View.MouseActivate() [inline], [virtual]

Sends a mouse event to the UI renderer.

8.37.2.34 virtual void Coherent.UI.View.MouseEvent(MouseEventData arg0) [inline], [virtual]

Sends a mouse event to the UI renderer.

Parameters

```
event the mouse event
```

```
8.37.2.35 virtual ViewErrorType Coherent.UI.View.PeekFrameReady( ) [inline], [virtual]
```

Tells if the last requested frame is ready or not. Does not block. This call must always be made between calls to RequestFrame and FetchSurface. (available only in Full versions of 'Coherent::UI::View::RequestFrame' 'Coherent::UI::View::FetchSurface'

Returns

VE_Success; VE_FrameNotReady; VE_FrameNotRequeted; VE_InvalidCall

```
8.37.2.36 virtual void Coherent.UI.View.Redraw() [inline], [virtual]
```

Request a redraw of the current view.

8.37.2.37 BoundEventHandle Coherent.UI.View.RegisterForEvent (string name, System.Delegate handler) [inline]

Expose C++ handler to be called when a specific event occurs.

Parameters

name	name of the event
handler	handler to be executed

Returns

bound handle so the handler can be unregistered

```
8.37.2.38 virtual void Coherent.UI.View.Reload (bool ignoreCache) [inline], [virtual]
```

Reloads the last requested or navigated-to path.

Parameters

ignoreCache	whether to ignore the cache for the reload

8.37.2.39 virtual void Coherent.UI.View.ReplyToJavaScriptMessage (bool *success*, string *userInput*) [inline], [virtual]

Sends a reply to a javascript message triggered for the view.

Parameters

success	defines whether the user replies positively to the message (i.e. clicks the OK button)
userInput	the user reply message (only used in prompt messages)

```
8.37.2.40 virtual ViewErrorType Coherent.UI.View.RequestFrame() [inline], [virtual]
```

Requests a new frame for rendering. All triggered events before this call will be accounted for in the rendered view. Only one frame per-view could be requested simultaneously (available only in Full versions of

Returns

the outcome of the operation

8.37.2.41 virtual ViewErrorType Coherent.UI.View.RequestFrame (double timeSinceArbitraryMoment) [inline], [virtual]

Requests a new frame for rendering. All triggered events before this call will be accounted for in the rendered view. Only one frame per-view could be requested simultaneously (available only in Full versions of

Returns

the outcome of the operation

8.37.2.42 virtual void Coherent.UI.View.Resize (uint width, uint height) [inline], [virtual]

Send a resize event to the UI renderer. Resize will result in multiple calls to CreateBuffers and DestroyBuffers in the listener

Parameters

width	the new width of the View
height	the new height of the View

8.37.2.43 virtual void Coherent.UI.View.SetClickThroughAlphaThreshold (float threshold) [inline], [virtual]

The alpha value of the pixels is used to determine if the mouse is on an element or on the background (click-through). All pixels below or equal to the alpha threshold (default = 0) are marked as not-belonging to the

Parameters

threshold	sets the new alpha threshold

8.37.2.44 virtual void Coherent.UI.View.SetFocus() [inline], [virtual]

Sets this view on focus.

8.37.2.45 virtual void Coherent.UI.View.SetScriptError (ScriptCallErrorType *error*, string *message*) [inline], [virtual]

Sets an error for the currently executing handler.

Parameters

error	the type of the error
message	the error message

8.37.2.46 virtual void Coherent.UI.View.SetTargetFramerate (int target) [inline], [virtual]

Sets the target frame-rate for the

Parameters

target	the new target frame-rate

8.37.2.47 virtual bool Coherent.UI.View.SupportsClickThrough() [inline], [virtual]

Tells if this view supports click-through queries or not.

Returns

true if click-through is supported

8.37.2.48 virtual void Coherent.UI.View.TouchEvent (TouchEventData events, uint count) [inline], [virtual]

Sends a touch event to the UI renderer.

Parameters

events	array of touch events
count	the count of the passed touch events in the array

8.37.2.49 virtual void Coherent.UI.View.TriggerEvent(string eventName) [inline], [virtual]

Triggers a UI event.

8.37.2.50 void Coherent.UI.View.UnbindCall (BoundEventHandle handle) [inline]

Remove a bound C++ handler.

Parameters

handle	the handle of the handler to be unbound

8.37.2.51 void Coherent.UI.View.UnbindObject (object target) [inline]

Remove all handlers bound to a specific object.

Parameters

object	the object whose handlers will be removed
- '	

8.37.2.52 void Coherent.UI.View.UnregisterFromEvent (BoundEventHandle handle) [inline]

Remove a registered C++ handler.

Parameters

handle	the handle of the event handler to be unregistered
--------	--

8.37.2.53 virtual bool Coherent.UI.View.UsesSharedMemory() [inline], [virtual]

Tells if this view uses shared memory for image transport.

Returns

true if the view uses shared memory, false if shared textures

8.38 Coherent.UI.ViewError Class Reference

Encapsulates a view-related error.

Inherits IDisposable.

Properties

• ViewErrorType ErrorCode [get, set]

Indicates an error code.

• string Error [get, set]

Error description.

8.38.1 Detailed Description

Encapsulates a view-related error.

8.38.2 Property Documentation

```
8.38.2.1 string Coherent.UI.ViewError.Error [get], [set]
```

Error description.

8.38.2.2 ViewErrorType Coherent.UI.ViewError.ErrorCode [get], [set]

Indicates an error code.

8.39 Coherent.UI. ViewInfo Class Reference

Encapsulates the options of a

Inherits IDisposable.

Properties

```
• int Width [get, set]
```

The Width of a

• int Height [get, set]

The Height of a

• bool UsesSharedMemory [get, set]

Flags if a

bool SupportClickThrough [get, set]

Defines if the view should support click-through queries. Not supporting click-through increases performance slightly.

• float ClickThroughAlphaThreshold [get, set]

The alpha threshold for click-through queries.

• bool IsTransparent [get, set]

Defines if a view is transparent or not. A transparent view can be have transparent parts that will be correctly blended with the client's surfaces. Non-transparent views are always implicitly composited as if on a white background. Don't use transparent views unless you have transparent parts in the page because non-transparent view are slightly faster. Do not blend non-transparent views.

• int TargetFrameRate [get, set]

The frame-rate of the view will never exceed the target set here. It will also never exceed the rate at which the System Update is called. (available only in Full versions of

• bool IsOnDemand [get, set]

Defines if a view is an on-demand view. On-demand views require explicit frame requests. (available only in Full versions of

• bool ControlTimeOnDemand [get, set]

Defines if the client controls the time of on-demand views himself. If not

bool ForceSoftwareRendering [get, set]

Forces the view to use software rendering. If the application is GPU-bound pure software Views might be a good choice. CSS 3D transforms, WebGL and accelerated Canvas don't work with software Views. Software Views are incompatible with the OnDemand option and work only with shared memory surfaces.

8.39.1 Detailed Description

Encapsulates the options of a

8.39.2 Property Documentation

8.39.2.1 float Coherent.UI.ViewInfo.ClickThroughAlphaThreshold [get], [set]

The alpha threshold for click-through queries.

8.39.2.2 bool Coherent.UI.ViewInfo.ControlTimeOnDemand [get], [set]

Defines if the client controls the time of on-demand views himself. If not

8.39.2.3 bool Coherent.UI.ViewInfo.ForceSoftwareRendering [get], [set]

Forces the view to use software rendering. If the application is GPU-bound pure software Views might be a good choice. CSS 3D transforms, WebGL and accelerated Canvas don't work with software Views. Software Views are incompatible with the OnDemand option and work only with shared memory surfaces.

8.39.2.4 int Coherent.UI.ViewInfo.Height [get], [set]

The Height of a

8.39.2.5 bool Coherent.UI.ViewInfo.IsOnDemand [get], [set]

Defines if a view is an on-demand view. On-demand views require explicit frame requests. (available only in Full versions of

8.39.2.6 bool Coherent.UI.ViewInfo.lsTransparent [get], [set]

Defines if a view is transparent or not. A transparent view can be have transparent parts that will be correctly blended with the client's surfaces. Non-transparent views are always implicitly composited as if on a white background. Don't use transparent views unless you have transparent parts in the page because non-transparent view are slightly faster. Do not blend non-transparent views.

8.39.2.7 bool Coherent.UI.ViewInfo.SupportClickThrough [get], [set]

Defines if the view should support click-through queries. Not supporting click-through increases performance slightly.

8.39.2.8 int Coherent.UI.ViewInfo.TargetFrameRate [get], [set]

The frame-rate of the view will never exceed the target set here. It will also never exceed the rate at which the System Update is called. (available only in Full versions of

8.39.2.9 bool Coherent.UI.ViewInfo.UsesSharedMemory [get], [set]

Flags if a


8.39.2.10 int Coherent.UI.ViewInfo.Width [get], [set]

The Width of a

8.40 Coherent.UI.ViewListener Class Reference

Interface that allows clients to listen to

Inheritance diagram for Coherent.UI.ViewListener:



Public Member Functions

override void Release ()

Called when the listener is no longer needed by the UI system.

override void OnViewCreated (View view)

Called when the requested

· override void OnDraw (CoherentHandle handle, bool usesSharedMemory, int width, int height)

Called when a new surface has been drawn and is ready to use by the client.

 override void OnFinishLoad (int frameld, string validatedPath, bool isMainFrame, int statusCode, HTTP-Header[] headers)

Called when a frame has been successfully loaded.

override void OnFailLoad (int frameld, string validatedPath, bool isMainFrame, string error)

Called when a frame has been failed loading.

• override void OnURLRequest (string url, URLResponse response)

Called before an URL request is made. The default implementation allows all requests.

• override void OnReadyForBindings (int frameld, string path, bool isMainFrame)

Called when a frame is ready for bindings.

• override void OnBindingsReleased (int frameld, string path, bool isMainFrame)

Called when the bindings for frame are released.

• override void OnStartLoading ()

Called when a new path has started loading.

override void OnStopLoading ()

Called when all load operations have completed.

override void OnNavigateTo (string path)

Called when the view starts navigation to a new path.

override void OnError (ViewError error)

Called when an error occurs for this specific

 override void OnScriptMessage (ViewListenerBase.MessageLevel level, string message, string sourceld, int line)

Called when a message is sent from a script running in this specific

override void OnCursorChanged (CursorTypes cursor)

Called when the cursor has changed internally in the

override void OnCallback (string eventName, Binding.CallbackArguments arguments)

Called by the UI when there is no registered handler for this event.

override void OnJavaScriptMessage (string message, string defaultPrompt, string frameUrl, int messageType)

Called when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

override void OnGetAuthCredentials (bool isProxy, string host, uint port, string realm, string scheme)

Called when a view requires authentication credentials.

override void CreateSurface (bool sharedMemory, uint width, uint height, SurfaceResponse response)

Called when the The format for DirectX9 must be D3DFMT_A8R8G8B8 The format for DirectX10 and DirectX11 must be B8G8R8A8_UNORM

override void DestroySurface (CoherentHandle surface, bool usesSharedMemory)

Called when a surface is unneeded anymore and should be destroyed This function can be called from a thread different than the main UI system thread in order to support client applications with multi-threaded rendering.

override void OnCertificateError (string url, CertificateStatus status, Certificate certificate, CertificateError-Response response)

Called when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

override void OnRequestMediaStream (MediaStreamRequest request)

Called when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

override void OnTextInputTypeChanged (TextInputControlType type, bool canComposeInline)

Called when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View. View::IMEActivate

override void OnCaretRectChanged (uint x, uint y, uint width, uint height)

Called when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

override void OnIMEShouldCancelComposition ()

Called when the user must cancel the IME composition due to an event in the

override void OnFileSelectRequest (FileSelectRequest request)

Called when the view requests file selection. It could be either single file, directory or multiple files.

Events

CoherentUI_OnViewCreated ViewCreated

Fired when the requested

CoherentUI OnDraw Draw

Fired when a new surface has been drawn and is ready to use by the client.

· CoherentUI OnFinishLoad FinishLoad

Fired when a frame has been successfully loaded.

CoherentUI OnFailLoad FailLoad

Fired when a frame has been failed loading.

• CoherentUI_OnURLRequest URLRequest

Fired before an URL request is made. The default implementation allows all requests.

CoherentUI_OnReadyForBindings ReadyForBindings

Fired when a frame is ready for bindings.

· CoherentUI OnBindingsReleased BindingsReleased

Fired when the bindings for frame are released.

CoherentUI_OnStartLoading StartLoading

Fired when a new path has started loading.

CoherentUI OnStopLoading StopLoading

Fired when all load operations have completed.

CoherentUI_OnNavigateTo NavigateTo

Fired when the view starts navigation to a new path.

CoherentUI OnError Error

Fired when an error occurs for this specific

CoherentUI_OnScriptMessage ScriptMessage

Fired when a message is sent from a script running in this specific

CoherentUI OnCursorChanged CursorChanged

Fired when the cursor has changed internally in the

· CoherentUI OnCallback Callback

Fired by the UI when there is no registered handler for this event.

CoherentUI_OnJavaScriptMessage JavaScriptMessage

Fired when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

• CoherentUI OnGetAuthCredentials GetAuthCredentials

Fired when a view requires authentication credentials.

CoherentUI OnCertificateError CertificateError

Fired when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

CoherentUI_OnRequestMediaStream RequestMediaStream

Fired when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

CoherentUI_OnTextInputTypeChanged TextInputTypeChanged

Fired when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View. View::IMEActivate

CoherentUI_OnCaretRectChanged CaretRectChanged

Fired when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

• CoherentUI_OnIMEShouldCancelComposition IMEShouldCancelComposition

Fired when the user must cancel the IME composition due to an event in the

CoherentUI_OnFileSelectRequest FileSelectRequest

Fired when the view requests file selection. It could be either single file, directory or multiple files.

Additional Inherited Members

8.40.1 Detailed Description

Interface that allows clients to listen to

8.40.2 Member Function Documentation

8.40.2.1 override void Coherent.UI.ViewListener.CreateSurface (bool sharedMemory, uint width, uint height, SurfaceResponse response) [inline], [virtual]

Called when the The format for DirectX9 must be D3DFMT_A8R8G8B8 The format for DirectX10 and DirectX11 must be B8G8R8A8 UNORM

Parameters

sharedMemory	true if the surface should be created in shared memory (4 * width * height bytes); false if a
	shared texture must be created.
width	the width of the surface in pixels
height	the height of the surface in pixels
response	
	object to hold the response when the surface is created or fails it's creation - must be signaled

Returns

a handle to the created surface

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.2 override void Coherent.UI.ViewListener.DestroySurface (CoherentHandle *surface*, bool *usesSharedMemory*) [inline], [virtual]

Called when a surface is unneeded anymore and should be destroyed This function can be called from a thread different than the main UI system thread in order to support client applications with multi-threaded rendering.

Parameters

surface	handle to the surface
usesShared-	determines whether the surface parameter is a handle to shared memory or shared texture
Memory	

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.3 override void Coherent.UI.ViewListener.OnBindingsReleased (int *frameld*, string *path*, bool *isMainFrame*) [inline], [virtual]

Called when the bindings for frame are released.

Parameters

frameld	the id of the frame
path	the path in the frame
isMainFrame	true if this is the main frame of the view

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.4 override void Coherent.UI.ViewListener.OnCallback (string eventName, Binding.CallbackArguments arguments) [inline], [virtual]

Called by the UI when there is no registered handler for this event.

Parameters

eventName	name of the event
arguments	arguments of the event invocation

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.5 override void Coherent.UI.ViewListener.OnCaretRectChanged (uint x, uint y, uint width, uint height) [inline], [virtual]

Called when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

Parameters

the	x position of the selection caret
the	y position of the selection caret
the	width of the selection caret
the	height of the selection caret

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.6 override void Coherent.UI.ViewListener.OnCertificateError (string *url*, CertificateStatus *status*, Certificate

certificate, CertificateErrorResponse response) [inline], [virtual]

Called when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

Parameters

url	the url of the request
status	the error status of the certificate
certificate	the certificate details. This pointer will be valid only for this call
response	object to signal whether to continue loading the URL. This pointer will be valid only for this
	call

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.7 override void Coherent.UI.ViewListener.OnCursorChanged (CursorTypes cursor) [inline], [virtual]

Called when the cursor has changed internally in the

Parameters

cursor

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.8 override void Coherent.UI.ViewListener.OnDraw (CoherentHandle handle, bool usesSharedMemory, int width, int height) [inline], [virtual]

Called when a new surface has been drawn and is ready to use by the client.

Parameters

handle	a handle to one of the buffers created by CreateSurface. May be a shared memory buffer or a shared texture depending on the way the View was created. The handle is valid only during this call
usesShared-	determines whether the handle parameter is a handle to shared memory or shared texture
Memory	
width	the width of the surface
height	the height of the surface

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.9 override void Coherent.UI.ViewListener.OnError (ViewError error) [inline], [virtual]

Called when an error occurs for this specific

Parameters

error	error description

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.10 override void Coherent.UI.ViewListener.OnFailLoad (int *frameld*, string *validatedPath*, bool *isMainFrame*, string *error*) [inline], [virtual]

Called when a frame has been failed loading.

Parameters

frameld	the id of the frame
validatedPath	the path in the frame

isMainFrame	true if this is the main frame of the View
error	error message for the failure

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.11 override void Coherent.UI.ViewListener.OnFileSelectRequest (FileSelectRequest request) [inline], [virtual]

Called when the view requests file selection. It could be either single file, directory or multiple files.

Parameters

request	contains the file selection params for the request

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.12 override void Coherent.UI.ViewListener.OnFinishLoad (int frameld, string validatedPath, bool isMainFrame, int statusCode, HTTPHeader[] headers) [inline], [virtual]

Called when a frame has been successfully loaded.

Parameters

frameld	the id of the loaded frame
validatedPath	the path loaded in the frame
isMainFrame	true if this is the main frame of the View
statusCode	the status code of the response
headers	an array of header fields
headersCount	the count of items in the headers array

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.13 override void Coherent.UI.ViewListener.OnGetAuthCredentials (bool *isProxy*, string *host*, uint *port*, string *realm*, string *scheme*) [inline], [virtual]

Called when a view requires authentication credentials.

Parameters

isProxy	whether the request came from a server or a proxy
host	the host which triggered the request
port	the port at which the request was triggered
realm	realm of the authentication challenge. Encoded in UTF-8
scheme	the authentication scheme used, e.g. "basic" or "digest". Encoded in ASCII

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.14 override void Coherent.UI.ViewListener.OnIMEShouldCancelComposition() [inline], [virtual]

Called when the user must cancel the IME composition due to an event in the

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.15 override void Coherent.UI.ViewListener.OnJavaScriptMessage (string message, string defaultPrompt, string frameUrl, int messageType) [inline], [virtual]

Called when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

Parameters

message	the JavaScript message
defaultPrompt	the default value of the prompt text box, in case the message type is prompt
frameUrl	the URL which created the message
messageType	the type of the message (alert/confirm/prompt)

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.16 override void Coherent.UI.ViewListener.OnNavigateTo (string path) [inline], [virtual]

Called when the view starts navigation to a new path.

Parameters

path	URL that the view is navigating to
------	------------------------------------

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.17 override void Coherent.UI.ViewListener.OnReadyForBindings (int *frameld*, string *path*, bool *isMainFrame*) [inline], [virtual]

Called when a frame is ready for bindings.

Parameters

frameld	the id of the frame
path	the path in the frame
isMainFrame	true if this is the main frame of the view

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.18 override void Coherent.UI.ViewListener.OnRequestMediaStream (MediaStreamRequest request) [inline], [virtual]

Called when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

Parameters

request	contains the available media streams for the request

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.19 override void Coherent.UI.ViewListener.OnScriptMessage (ViewListenerBase.MessageLevel level, string message, string sourceld, int line) [inline], [virtual]

Called when a message is sent from a script running in this specific

Parameters

level	message level
message	the text of the message
sourceld	id of the script (usually file name)
line	the number of the line in which the message was sent

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.20 override void Coherent.UI.ViewListener.OnStartLoading() [inline], [virtual]

Called when a new path has started loading.

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.21 override void Coherent.UI.ViewListener.OnStopLoading() [inline], [virtual]

Called when all load operations have completed.

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.22 override void Coherent.UI.ViewListener.OnTextInputTypeChanged (TextInputControlType type, bool canComposeInline) [inline], [virtual]

Called when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View.:IMEActivate

Parameters

type	the type of the currently focused text input control by the user
canCompose-	if the IME composition could be performed in-line in the control
Inline	

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.23 override void Coherent.UI.ViewListener.OnURLRequest (string *url*, URLResponse *response*) [inline], [virtual]

Called before an URL request is made. The default implementation allows all requests.

Parameters

url	the request URL
response	response whether to allow the request and may be redirect it. This pointer will be valid only
	for this call

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.24 override void Coherent.UI.ViewListener.OnViewCreated (View view) [inline], [virtual]

Called when the requested

Parameters

view	the instance of the view containing all manipulation methods

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.2.25 override void Coherent.UI.ViewListener.Release () [inline], [virtual]

Called when the listener is no longer needed by the UI system.

Reimplemented from Coherent.UI.ViewListenerBase.

8.40.3 Event Documentation

8.40.3.1 CoherentUI_OnBindingsReleased Coherent.UI.ViewListener.BindingsReleased

Fired when the bindings for frame are released.

8.40.3.2 CoherentUI_OnCallback Coherent.UI.ViewListener.Callback

Fired by the UI when there is no registered handler for this event.

8.40.3.3 CoherentUI_OnCaretRectChanged Coherent.UI.ViewListener.CaretRectChanged

Fired when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

8.40.3.4 CoherentUI_OnCertificateError Coherent.UI.ViewListener.CertificateError

Fired when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

8.40.3.5 CoherentUI_OnCursorChanged Coherent.UI.ViewListener.CursorChanged

Fired when the cursor has changed internally in the

8.40.3.6 CoherentUI OnDraw Coherent.UI.ViewListener.Draw

Fired when a new surface has been drawn and is ready to use by the client.

8.40.3.7 CoherentUI_OnError Coherent.UI.ViewListener.Error

Fired when an error occurs for this specific

8.40.3.8 CoherentUI_OnFailLoad Coherent.UI.ViewListener.FailLoad

Fired when a frame has been failed loading.

8.40.3.9 CoherentUI_OnFileSelectRequest Coherent.UI.ViewListener.FileSelectRequest

Fired when the view requests file selection. It could be either single file, directory or multiple files.

8.40.3.10 CoherentUI_OnFinishLoad Coherent.UI.ViewListener.FinishLoad

Fired when a frame has been successfully loaded.

8.40.3.11 CoherentUI OnGetAuthCredentials Coherent.UI.ViewListener.GetAuthCredentials

Fired when a view requires authentication credentials.

8.40.3.12 CoherentUI_OnIMEShouldCancelComposition Coherent.UI.ViewListener.IMEShouldCancelComposition

Fired when the user must cancel the IME composition due to an event in the

8.40.3.13 CoherentUI_OnJavaScriptMessage Coherent.UI.ViewListener.JavaScriptMessage

Fired when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

8.40.3.14 CoherentUI_OnNavigateTo Coherent.UI.ViewListener.NavigateTo

Fired when the view starts navigation to a new path.

8.40.3.15 CoherentUI_OnReadyForBindings Coherent.UI.ViewListener.ReadyForBindings

Fired when a frame is ready for bindings.

8.40.3.16 CoherentUI_OnRequestMediaStream Coherent.UI.ViewListener.RequestMediaStream

Fired when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

8.40.3.17 CoherentUI_OnScriptMessage Coherent.UI.ViewListener.ScriptMessage

Fired when a message is sent from a script running in this specific

8.40.3.18 CoherentUI_OnStartLoading Coherent.UI.ViewListener.StartLoading

Fired when a new path has started loading.

8.40.3.19 CoherentUI_OnStopLoading Coherent.UI.ViewListener.StopLoading

Fired when all load operations have completed.

8.40.3.20 CoherentUI_OnTextInputTypeChanged Coherent.UI.ViewListener.TextInputTypeChanged

Fired when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View. View::IMEActivate

8.40.3.21 CoherentUI_OnURLRequest Coherent.UI.ViewListener.URLRequest


Fired before an URL request is made. The default implementation allows all requests.

8.40.3.22 CoherentUI_OnViewCreated Coherent.UI.ViewListener.ViewCreated

Fired when the requested

8.41 Coherent. UI. View Listener Base Class Reference

Interface all view listeners inherit. For an easier to use interface inherit instead -. Coherent::UI::ViewListener Inheritance diagram for Coherent.UI.ViewListenerBase:



Public Types

• enum MessageLevel

Levels of script messages.

8.41.1 Detailed Description

Interface all view listeners inherit. For an easier to use interface inherit instead -. Coherent::UI::ViewListener

8.41.2 Member Enumeration Documentation

8.41.2.1 enum Coherent.UI.ViewListenerBase.MessageLevel

Levels of script messages.

Index

All	Coherent.UI.Binding.CallbackArguments, 59
Coherent::UI::Binding, 44	Coherent.UI.Binding.CoherentProperty, 63
AllowCookies	Coherent.UI.Binding.CoherentType, 63
Coherent::UI::SystemSettingsBase, 79	Coherent.UI.Binding.InvalidValueCastException, 70
AppendExtraHeaderValue	Coherent.UI.Binding.UnsupportedPrimitiveTypeException,
Coherent::UI::URLRequest, 84	83
Arguments	Coherent.UI.Binding.Value, 86
Coherent::UI::Binding::CallbackArguments, 60	Coherent.UI.Binding.ValueObject, 95
Array	Coherent.UI.BoundEventHandle, 45
Coherent::UI::Binding, 44	Coherent.UI.BrowserView, 46
Assert	Coherent.UI.BrowserViewListener, 47
Coherent::UI::ILogHandler, 69	Coherent.UI.BrowserViewListenerBase, 59
AuthCredentialsResponse	Coherent.UI.Certificate, 60
Coherent::UI::View, 98	Coherent.UI.CertificatePrincipal, 61
	Coherent.UI.ChildViewInfo, 62
BindCall	Coherent.UI.Download, 64
Coherent::UI::View, 98	Coherent.UI.EventListener, 66
BindMethods	Coherent.UI.EventModifiersState, 67
Coherent::UI::Binding::BoundObject, 45	Coherent.UI.EventMouseModifiersState, 67
BindingsReleased	Coherent.UI.FileHandler, 67
Coherent::UI::BrowserViewListener, 57	Coherent.UI.HTTPHeader, 68
Coherent::UI::ViewListener, 117	•
Boolean	Coherent III Image Date 69
Coherent::UI::Binding, 44	Coherent.UI.ImageData, 69
Button	Coherent.UI.KeyEventData, 70
Coherent::UI::MouseEventData, 73	Coherent.UI.MediaStreamDevice, 71
Byte	Coherent.UI.MediaStreamRequest, 72
Coherent::UI::Binding, 44	Coherent.UI.MouseEventData, 73
	Coherent.UI.ResourceData, 74
CachePath	Coherent.UI.ResourceResponse, 75
Coherent::UI::SystemSettings, 78	Coherent.UI.SurfaceResponse, 76
Callback	Coherent.UI.SystemError, 76
Coherent::UI::BrowserViewListener, 57	Coherent.UI.SystemSettings, 77
Coherent::UI::ViewListener, 117	Coherent.UI.SystemSettingsBase, 78
Cancel	Coherent.UI.TouchEventData, 80
Coherent::UI::Download, 64	Coherent.UI.UISystem, 81
CaretRectChanged	Coherent.UI.URLRequest, 83
Coherent::UI::BrowserViewListener, 57	Coherent.UI.View, 95
Coherent::UI::ViewListener, 117	Coherent.UI.ViewError, 107
CertificateError	Coherent.UI.ViewInfo, 108
Coherent::UI::BrowserViewListener, 57	Coherent.UI.ViewListener, 110
Coherent::UI::ViewListener, 118	Coherent.UI.ViewListenerBase, 119
CertificateStatus	Coherent::UI
Coherent::UI, 41	DET_DownloadOperationFailed, 42
ClickThroughAlphaThreshold	DET_Success, 42
Coherent::UI::ViewInfo, 109	SCE_ArgumentType, 42
Coherent, 39	SCE_NoResult, 42
Coherent.UI, 39	SCE_NoSuchMethod, 42
Coherent.UI.Binding, 43	SCE_Success, 42
Coherent.UI.Binding.BoundObject, 45	SE_InternalError, 42

SE InvalidKey, 42	operator byte, 90
SE_MissingComponent, 42	operator Dictionary< string, Value >, 91
SE_Success, 42	operator double, 91
VE AbnormalTermination, 43	operator float, 91
VE_ChildCompositionFailed, 43	operator int, 91
VE_ClickThroughFailed, 43	operator sbyte, 91
VE_FailedCreation, 43	operator string, 93
VE_FailedRenderingCreation, 43	operator uint, 93
VE_FrameAlreadyInFlight, 43	operator==, 93
VE_FrameNotReady, 43	Type, 95
VE_FrameNotRequeted, 43	Value, 87, 88, 90
VE_InvalidCall, 43	Coherent::UI::BrowserView
VE_InvalidPath, 43	GetHistory, 46
VE_QueryNotReady, 43	GetViewType, 46
VE_QueryNotheady, 43 VE Success, 43	GoBack, 46
Coherent::UI::Binding	Goback, 46 GoForward, 46
	Coherent::UI::BrowserViewListener
All, 44	
Array, 44	BindingsReleased, 57
Boolean, 44	Callback, 57
Byte, 44	CaretRectChanged, 57
Explicit, 44	CertificateError, 57
Instance, 44	CreateSurface, 49
Integer, 44	CursorChanged, 57
Null, 44	DestroySurface, 49
Number, 44	Draw, 58
Object, 44	Error, 58
SByte, 44	FailLoad, 58
Static, 44	FileSelectRequest, 58
String, 44	FinishLoad, 58
UInteger, 44	GetAuthCredentials, 58
Coherent::UI	IMEShouldCancelComposition, 58
CertificateStatus, 41	JavaScriptMessage, 58
CursorTypes, 41	NavigateTo, 58
Direct3DInterfaceType, 41	OnBindingsReleased, 51
DownloadErrorType, 41	OnCallback, 51
FileSelectionMode, 42	OnCaretRectChanged, 51
JavaScriptMessageType, 42	OnCertificateError, 51
MediaStreamType, 42	OnCursorChanged, 52
RenderingDeviceType, 42	OnDraw, 52
ScriptCallErrorType, 42	OnError, 52
SystemErrorType, 42	OnFailLoad, 52
TextInputControlType, 42	OnFileSelectRequest, 52
UserAgentType, 42	OnFinishLoad, 53
ViewErrorType, 42	OnGetAuthCredentials, 53
ViewType, 43	OnIMEShouldCancelComposition, 53
Coherent::UI::Binding	OnJavaScriptMessage, 53
PropertyBindingFlags, 44	OnNavigateTo, 53
ValueType, 44	OnReadyForBindings, 55
Coherent::UI::Binding::BoundObject	OnRequestMediaStream, 55
	OnScriptMessage, 55
BindMethods, 45	• •
Coherent::UI::Binding::CallbackArguments	OnStartLoading, 55
Arguments, 60	OnStopLoading, 55
Coherent::UI::Binding::CoherentProperty	OnTextInputTypeChanged, 55
CoherentProperty, 63	OnURLRequest, 57
Coherent::UI::Binding::Value	OnViewCreated, 57
Equals, 90	ReadyForBindings, 58
GetHashCode, 90	Release, 57
operator bool, 90	RequestMediaStream, 58

ScriptMessage, 58	IsNumPad, 71
StartLoading, 59	KeyCode, 71
StopLoading, 59	Modifiers, 71
TextInputTypeChanged, 59	Type, 71
URLRequest, 59	Coherent::UI::MediaStreamDevice
ViewCreated, 59	Deviceld, 72
Coherent::UI::Certificate	Name, 72
Fingerprint, 60	Type, 72
FingerprintCA, 60	Coherent::UI::MediaStreamRequest
Issuer, 61	Devices, 72
SerialNumber, 61	Respond, 72
Subject, 61	Coherent::UI::MouseEventData
ValidEnd, 61	Button, 73
ValidStart, 61	Modifiers, 73
Coherent::UI::CertificatePrincipal	MouseModifiers, 73
•	
CommonName, 62	Type, 73
CountryName, 62	WheelX, 73
DomainComponents, 62	WheelY, 73
LocalityName, 62	X, 74
OrganizationNames, 62	Y, 74
OrganizationUnitNames, 62	Coherent::UI::ResourceData
StateOrProvinceName, 62	GetBuffer, 74
StreetAddresses, 62	GetSize, 74
Coherent::UI::ChildViewInfo	SignalFailure, 74
Listener, 63	SignalSuccess, 75
NewViewInfo, 63	Coherent::UI::ResourceResponse
Coherent::UI::Download	GetBuffer, 75
Cancel, 64	SignalFailure, 75
Destroy, 64	SignalSuccess, 75
GetDownloadedBytesSoFar, 65	Coherent::UI::SurfaceResponse
GetFilename, 65	Signal, 76
Getld, 65	Coherent::UI::SystemError
GetReferrer, 65	Error, 77
GetTotalBytes, 65	ErrorCode, 77
GetURL, 65	Coherent::UI::SystemSettings
HasFailed, 65	CachePath, 78
IsCancelled, 66	CookiesResource, 78
IsComplete, 66	CustomUserAgentString, 78
Coherent::UI::EventListener	D3DObject, 78
OnDownloadComplete, 66	FocusWindow, 78
OnDownloadFailed, 66	HTML5LocalStoragePath, 78
OnDownloadStarted, 67	HostDirectory, 78
OnError, 67	MinidumpFolder, 78
SystemReady, 67	Coherent::UI::SystemSettingsBase
Coherent::UI::FileHandler	AllowCookies, 79
ReadFile, 68	CustomUserAgentString, 79
WriteFile, 68	D3DInterfaceType, 79
Coherent::UI::HTTPHeader	DebuggerPort, 79
Content, 68	DisableWebSecurity, 79
Field, 68	EnableProxy, 80
Coherent::UI::ILogHandler	EnableSupportForProprietaryCodecs, 80
Assert, 69	ForceDisablePluginFullscreen, 80
WriteLog, 69	UserAgent, 80
Coherent::UI::ImageData	WriteMinidumps, 80
Destroy, 70	Coherent::UI::TouchEventData
Update, 70	HasRadiusInformation, 81
Coherent::UI::KeyEventData	ld, 81
IsAutoRepeat, 71	RadiusX, 81

RadiusY, 81	PeekFrameReady, 103
Type, 81	Redraw, 103
X, 81	RegisterForEvent, 103
Y, 81	Reload, 105
Coherent::UI::UISystem	ReplyToJavaScriptMessage, 105
CreateView, 82	RequestFrame, 105
FetchSurfaces, 82	Resize, 105
Uninitialize, 82	SetClickThroughAlphaThreshold, 106
Update, 83	SetFocus, 106
Coherent::UI::URLRequest	SetScriptError, 106
AppendExtraHeaderValue, 84	SetTargetFramerate, 106
Deny, 84	SupportsClickThrough, 106
GetExtraHeader, 84	TouchEvent, 106
GetExtraHeaders, 84	TriggerEvent, 107
GetMethod, 84	UnbindCall, 107
GetReferrer, 84	UnbindObject, 107
GetURL, 85	UnregisterFromEvent, 107
RemoveExtraHeader, 85	UsesSharedMemory, 107
SetExtraHeader, 85	Coherent::UI::ViewError
SetExtraHeaders, 85	Error, 108
SetMethod, 85	ErrorCode, 108
SetReferrer, 85	Coherent::UI::ViewInfo
SetURL, 86	ClickThroughAlphaThreshold, 109
Coherent::UI::View	ControlTimeOnDemand, 109
AuthCredentialsResponse, 98	ForceSoftwareRendering, 109
BindCall, 98	Height, 109
CreateImageData, 98	IsOnDemand, 109
Destroy, 98	IsTransparent, 109
DownloadUrl, 98	SupportClickThrough, 109
DrawSurface, 98	TargetFrameRate, 109
ExecuteScript, 99	UsesSharedMemory, 109
FetchMouseOnUIQuery, 99	Width, 109
FetchSurface, 99	Coherent::UI::ViewListener
GetClickThroughAlphaThreshold, 99	BindingsReleased, 117
GetCurentViewPath, 99	Callback, 117
GetHeight, 99	CaretRectChanged, 117
GetLastFailedPath, 99	CertificateError, 118
GetLastLoadedPath, 100	CreateSurface, 112
GetLastRequestedPath, 100	CursorChanged, 118
GetTargetFramerate, 100	DestroySurface, 112
GetViewType, 100	Draw, 118
GetWidth, 100	Error, 118
HasMouseQueryFinished, 100	FailLoad, 118
IMEActivate, 101	FileSelectRequest, 118
IMECancelComposition, 101	FinishLoad, 118
IMEConfirmComposition, 101	GetAuthCredentials, 118
IMEIsActive, 101	IMEShouldCancelComposition, 118
IMESetComposition, 101	JavaScriptMessage, 118
InterceptURLRequests, 102	NavigateTo, 118
IsMouseOnView, 102	OnBindingsReleased, 113
IsOnDemand, 102	OnCallback, 113
IsTransparent, 102	OnCaretRectChanged, 113
IssueMouseOnUIQuery, 102	OnCertificateError, 113
KeyEvent, 103	OnCursorChanged, 114
KillFocus, 103	OnDraw, 114
Load, 103	OnError, 114
MouseActivate, 103	OnFailLoad, 114
MouseEvent, 103	OnFileSelectRequest, 114

OnFinishLoad, 115	Coherent::UI, 42
OnGetAuthCredentials, 115	DebuggerPort
OnIMEShouldCancelComposition, 115	Coherent::UI::SystemSettingsBase, 79
OnJavaScriptMessage, 115	Deny
OnNavigateTo, 116	Coherent::UI::URLRequest, 84
OnReadyForBindings, 116	Destroy
OnRequestMediaStream, 116	Coherent::UI::Download, 64
OnScriptMessage, 116	Coherent::UI::ImageData, 70
OnStartLoading, 116	Coherent::UI::View, 98
OnStopLoading, 116	DestroySurface
OnTextInputTypeChanged, 117	Coherent::UI::BrowserViewListener, 49
OnURLRequest, 117	Coherent::UI::ViewListener, 112
OnViewCreated, 117	DeviceId
ReadyForBindings, 118	Coherent::UI::MediaStreamDevice, 72
Release, 117	Devices
RequestMediaStream, 119	Coherent::UI::MediaStreamRequest, 72
ScriptMessage, 119	Direct3DInterfaceType
StartLoading, 119	Coherent::UI, 41
StopLoading, 119	DisableWebSecurity
TextInputTypeChanged, 119	Coherent::UI::SystemSettingsBase, 79
URLRequest, 119	DomainComponents
ViewCreated, 119	Coherent::UI::CertificatePrincipal, 62
Coherent::UI::ViewListenerBase	DownloadErrorType
MessageLevel, 120	Coherent::UI, 41
CoherentProperty	DownloadUrl
Coherent::UI::Binding::CoherentProperty, 63	Coherent::UI::View, 98
CommonName	Draw
Coherent::UI::CertificatePrincipal, 62	Coherent::UI::BrowserViewListener, 58
Content	Coherent::UI::ViewListener, 118
Coherent::UI::HTTPHeader, 68	DrawSurface
ControlTimeOnDemand	Coherent::UI::View, 98
Coherent::UI::ViewInfo, 109	
CookiesResource	EnableProxy
Coherent::UI::SystemSettings, 78	Coherent::UI::SystemSettingsBase, 80
CountryName	EnableSupportForProprietaryCodecs
Coherent::UI::CertificatePrincipal, 62	Coherent::UI::SystemSettingsBase, 80
CreateImageData	Equals
Coherent::UI::View, 98	Coherent::UI::Binding::Value, 90
CreateSurface	Error
Coherent::UI::BrowserViewListener, 49	Coherent::UI::BrowserViewListener, 58
Coherent::UI::ViewListener, 112	Coherent::UI::SystemError, 77
CreateView	Coherent::UI::ViewError, 108
Coherent::UI::UISystem, 82	Coherent::UI::ViewListener, 118
CursorChanged	ErrorCode
Coherent::UI::BrowserViewListener, 57	Coherent::UI::SystemError, 77
Coherent::UI::ViewListener, 118	Coherent::UI::ViewError, 108
CursorTypes	ExecuteScript
Coherent::UI, 41	Coherent::UI::View, 99
CustomUserAgentString	Explicit
Coherent::UI::SystemSettings, 78	Coherent::UI::Binding, 44
Coherent::UI::SystemSettingsBase, 79	FailLoad
D3DInterfaceType	Coherent::UI::BrowserViewListener, 58
Coherent::UI::SystemSettingsBase, 79	Coherent::UI::ViewListener, 118
D3DObject	FetchMouseOnUIQuery
Coherent::UI::SystemSettings, 78	Coherent::UI::View, 99
DET_DownloadOperationFailed	FetchSurface
Coherent::UI, 42	Coherent::UI::View, 99
DET_Success	FetchSurfaces

Coherent::UI::UISystem, 82	GetSize
Field	Coherent::UI::ResourceData, 74
Coherent::UI::HTTPHeader, 68	GetTargetFramerate
FileSelectRequest	Coherent::UI::View, 100
Coherent::UI::BrowserViewListener, 58	GetTotalBytes
Coherent::UI::ViewListener, 118	Coherent::UI::Download, 65
FileSelectionMode	GetURL
Coherent::UI, 42	Coherent::UI::Download, 65
Fingerprint	Coherent::UI::URLRequest, 85
Coherent::UI::Certificate, 60	GetViewType
FingerprintCA	Coherent::UI::BrowserView, 46
Coherent::UI::Certificate, 60	Coherent::UI::View, 100
FinishLoad	GetWidth
Coherent::UI::BrowserViewListener, 58	Coherent::UI::View, 100
Coherent::UI::ViewListener, 118	GoBack
FocusWindow	Coherent::UI::BrowserView, 46
Coherent::UI::SystemSettings, 78	GoForward
ForceDisablePluginFullscreen	Coherent::UI::BrowserView, 46
Coherent::UI::SystemSettingsBase, 80	
ForceSoftwareRendering	HTML5LocalStoragePath
Coherent::UI::ViewInfo, 109	Coherent::UI::SystemSettings, 78
	HasFailed
GetAuthCredentials	Coherent::UI::Download, 65
Coherent::UI::BrowserViewListener, 58	HasMouseQueryFinished
Coherent::UI::ViewListener, 118	Coherent::UI::View, 100
GetBuffer	HasRadiusInformation
Coherent::UI::ResourceData, 74	Coherent::UI::TouchEventData, 81
Coherent::UI::ResourceResponse, 75	Height
GetClickThroughAlphaThreshold	Coherent::UI::ViewInfo, 109
Coherent::UI::View, 99	HostDirectory
GetCurentViewPath	Coherent::UI::SystemSettings, 78
Coherent::UI::View, 99	
GetDownloadedBytesSoFar	IMEActivate
Coherent::UI::Download, 65	Coherent::UI::View, 101
GetExtraHeader	IMECancelComposition
Coherent::UI::URLRequest, 84	Coherent::UI::View, 101
GetExtraHeaders	IMEConfirmComposition
Coherent::UI::URLRequest, 84	Coherent::UI::View, 101
GetFilename	IMEIsActive
Coherent::UI::Download, 65	Coherent::UI::View, 101
GetHashCode	IMESetComposition
Coherent::UI::Binding::Value, 90	Coherent::UI::View, 101
GetHeight	IMEShouldCancelComposition
Coherent::UI::View, 99	Coherent::UI::BrowserViewListener, 58
GetHistory	Coherent::UI::ViewListener, 118
Coherent::UI::BrowserView, 46	ld
Getld	Coherent::UI::TouchEventData, 81
Coherent::UI::Download, 65	Instance
GetLastFailedPath	Coherent::UI::Binding, 44
Coherent::UI::View, 99	Integer
GetLastLoadedPath	Coherent::UI::Binding, 44
Coherent::UI::View, 100	InterceptURLRequests
GetLastRequestedPath	Coherent::UI::View, 102
Coherent::UI::View, 100	IsAutoRepeat
GetMethod	Coherent::UI::KeyEventData, 71
Coherent::UI::URLRequest, 84	IsCancelled
GetReferrer	Coherent::UI::Download, 66
Coherent::UI::Download, 65	IsComplete
Coherent::UI::URLRequest, 84	Coherent::UI::Download, 66

IsMouseOnView	Coherent::UI::Binding, 44
Coherent::UI::View, 102	Number
IsNumPad	Coherent::UI::Binding, 44
Coherent::UI::KeyEventData, 71	
IsOnDemand	Object
Coherent::UI::View, 102	Coherent::UI::Binding, 44
Coherent::UI::ViewInfo, 109	OnBindingsReleased
IsTransparent	Coherent::UI::BrowserViewListener, 51
Coherent::UI::View, 102	Coherent::UI::ViewListener, 113
Coherent::UI::ViewInfo, 109	OnCallback
IssueMouseOnUIQuery	Coherent::UI::BrowserViewListener, 51
Coherent::UI::View, 102	Coherent::UI::ViewListener, 113
Issuer	OnCaretRectChanged
Coherent::UI::Certificate, 61	Coherent::UI::BrowserViewListener, 51
	Coherent::UI::ViewListener, 113
JavaScriptMessage	OnCertificateError
Coherent::UI::BrowserViewListener, 58	Coherent::UI::BrowserViewListener, 51
Coherent::UI::ViewListener, 118	Coherent::UI::ViewListener, 113
JavaScriptMessageType	OnCursorChanged
Coherent::UI, 42	Coherent::UI::BrowserViewListener, 52
	Coherent::UI::ViewListener, 114
KeyCode	OnDownloadComplete
Coherent::UI::KeyEventData, 71	Coherent::UI::EventListener, 66
KeyEvent	OnDownloadFailed
Coherent::UI::View, 103	Coherent::UI::EventListener, 66
KillFocus	OnDownloadStarted
Coherent::UI::View, 103	Coherent::UI::EventListener, 67
	OnDraw
Listener	Coherent::UI::BrowserViewListener, 52
Coherent::UI::ChildViewInfo, 63	Coherent::UI::ViewListener, 114
Load	OnError
Coherent::UI::View, 103	Coherent::UI::BrowserViewListener, 52
LocalityName	Coherent::UI::EventListener, 67
Coherent::UI::CertificatePrincipal, 62	Coherent::UI::ViewListener, 114
	OnFailLoad
MediaStreamType	Coherent::UI::BrowserViewListener, 52
Coherent::UI, 42	Coherent::UI::ViewListener, 114
MessageLevel	OnFileSelectRequest
Coherent::UI::ViewListenerBase, 120	Coherent::UI::BrowserViewListener, 52
MinidumpFolder	Coherent::UI::ViewListener, 114
Coherent::UI::SystemSettings, 78	OnFinishLoad
Modifiers	Coherent::UI::BrowserViewListener, 53
Coherent::UI::KeyEventData, 71	Coherent::UI::ViewListener, 115
Coherent::UI::MouseEventData, 73	OnGetAuthCredentials
MouseActivate	Coherent::UI::BrowserViewListener, 53
Coherent::UI::View, 103	Coherent::UI::ViewListener, 115
MouseEvent	OnIMEShouldCancelComposition
Coherent::UI::View, 103	Coherent::UI::BrowserViewListener, 53
MouseModifiers	Coherent::UI::ViewListener, 115
Coherent::UI::MouseEventData, 73	OnJavaScriptMessage
	Coherent::UI::BrowserViewListener, 53
Name	Coherent::UI::ViewListener, 115
Coherent::UI::MediaStreamDevice, 72	OnNavigateTo
NavigateTo	Coherent::UI::BrowserViewListener, 53
Coherent::UI::BrowserViewListener, 58	Coherent::UI::ViewListener, 116
Coherent::UI::ViewListener, 118	OnReadyForBindings
NewViewInfo	Coherent::UI::BrowserViewListener, 55
Coherent::UI::ChildViewInfo, 63	Coherent::UI::ViewListener, 116
Null	OnRequestMediaStream

Coherent::UI::BrowserViewListener, 55	Redraw
Coherent::UI::ViewListener, 116	Coherent::UI::View, 103
OnScriptMessage	RegisterForEvent
Coherent::UI::BrowserViewListener, 55	Coherent::UI::View, 103
Coherent::UI::ViewListener, 116	Release
OnStartLoading	Coherent::UI::BrowserViewListener, 57
Coherent::UI::BrowserViewListener, 55	Coherent::UI::ViewListener, 117
Coherent::UI::ViewListener, 116	Reload
OnStopLoading	Coherent::UI::View, 105
Coherent::UI::BrowserViewListener, 55	RemoveExtraHeader
Coherent::UI::ViewListener, 116	Coherent::UI::URLRequest, 85
OnTextInputTypeChanged	RenderingDeviceType
Coherent::UI::BrowserViewListener, 55	Coherent::UI, 42
Coherent::UI::ViewListener, 117	ReplyToJavaScriptMessage
OnURLRequest	Coherent::UI::View, 105
Coherent::UI::BrowserViewListener, 57	RequestFrame
Coherent::UI::ViewListener, 117	Coherent::UI::View, 105
OnViewCreated	RequestMediaStream
Coherent::UI::BrowserViewListener, 57	Coherent::UI::BrowserViewListener, 58
Coherent::UI::ViewListener, 117	Coherent::UI::ViewListener, 119
operator bool	Resize
Coherent::UI::Binding::Value, 90	Coherent::UI::View, 105
operator byte	Respond
Coherent::UI::Binding::Value, 90	Coherent::UI::MediaStreamRequest, 72
operator Dictionary< string, Value >	Concretioriviediaotreami tequest, 72
•	SByte
Coherent::UI::Binding::Value, 91	Coherent::UI::Binding, 44
operator double	SCE_ArgumentType
Coherent::UI::Binding::Value, 91	Coherent::UI, 42
operator float	SCE NoResult
Coherent::UI::Binding::Value, 91	Coherent::UI, 42
operator int	SCE NoSuchMethod
Coherent::UI::Binding::Value, 91	Coherent::UI, 42
operator sbyte	SCE Success
Coherent::UI::Binding::Value, 91	Coherent::UI, 42
operator string	SE InternalError
Coherent::UI::Binding::Value, 93	Coherent::UI, 42
operator uint	SE_InvalidKey
Coherent::UI::Binding::Value, 93	Coherent::UI, 42
operator==	SE_MissingComponent
Coherent::UI::Binding::Value, 93	Coherent::UI, 42
OrganizationNames	
Coherent::UI::CertificatePrincipal, 62	SE_Success
OrganizationUnitNames	Coherent::UI, 42
Coherent::UI::CertificatePrincipal, 62	ScriptCallErrorType
	Coherent::UI, 42
PeekFrameReady	ScriptMessage
Coherent::UI::View, 103	Coherent::UI::BrowserViewListener, 58
PropertyBindingFlags	Coherent::UI::ViewListener, 119
Coherent::UI::Binding, 44	SerialNumber
	Coherent::UI::Certificate, 61
RadiusX	SetClickThroughAlphaThreshold
Coherent::UI::TouchEventData, 81	Coherent::UI::View, 106
RadiusY	SetExtraHeader
Coherent::UI::TouchEventData, 81	Coherent::UI::URLRequest, 85
ReadFile	SetExtraHeaders
Coherent::UI::FileHandler, 68	Coherent::UI::URLRequest, 85
ReadyForBindings	SetFocus
Coherent::UI::BrowserViewListener, 58	Coherent::UI::View, 106
Coherent::UI::ViewListener, 118	SetMethod

Coherent::UI::URLRequest, 85	UInteger
SetReferrer	Coherent::UI::Binding, 44
Coherent::UI::URLRequest, 85	URLRequest
SetScriptError	Coherent::UI::BrowserViewListener, 59
Coherent::UI::View, 106	Coherent::UI::ViewListener, 119
SetTargetFramerate	UnbindCall
Coherent::UI::View, 106	Coherent::UI::View, 107
SetURL	UnbindObject
Coherent::UI::URLRequest, 86	Coherent::UI::View, 107
Signal	Uninitialize
Coherent::UI::SurfaceResponse, 76	Coherent::UI::UISystem, 82
SignalFailure	UnregisterFromEvent
Coherent::UI::ResourceData, 74	Coherent::UI::View, 107
Coherent::UI::ResourceResponse, 75	Update
SignalSuccess	Coherent::UI::ImageData, 70
Coherent::UI::ResourceData, 75	Coherent::UI::UISystem, 83
Coherent::UI::ResourceResponse, 75	UserAgent
StartLoading	Coherent::UI::SystemSettingsBase, 80
Coherent::UI::BrowserViewListener, 59	UserAgentType
Coherent::UI::ViewListener, 119	Coherent::UI, 42
StateOrProvinceName	UsesSharedMemory
	Coherent::UI::View, 107
Coherent::UI::CertificatePrincipal, 62	
Static Colography I I v Dinding 44	Coherent::UI::ViewInfo, 109
Coherent::UI::Binding, 44	VE AbnormalTermination
StopLoading	Coherent::UI, 43
Coherent::UI::BrowserViewListener, 59	VE_ChildCompositionFailed
Coherent::UI::ViewListener, 119	Coherent::UI, 43
StreetAddresses	VE_ClickThroughFailed
Coherent::UI::CertificatePrincipal, 62	Coherent::UI, 43
String	
Coherent::UI::Binding, 44	VE_FailedCreation
Subject	Coherent::UI, 43
Coherent::UI::Certificate, 61	VE_FailedRenderingCreation
SupportClickThrough	Coherent::UI, 43
Coherent::UI::ViewInfo, 109	VE_FrameAlreadyInFlight
SupportsClickThrough	Coherent::UI, 43
Coherent::UI::View, 106	VE_FrameNotReady
SystemErrorType	Coherent::UI, 43
Coherent::UI, 42	VE_FrameNotRequeted
SystemReady	Coherent::UI, 43
Coherent::UI::EventListener, 67	VE_InvalidCall
	Coherent::UI, 43
TargetFrameRate	VE_InvalidPath
Coherent::UI::ViewInfo, 109	Coherent::UI, 43
TextInputControlType	VE_QueryNotReady
Coherent::UI, 42	Coherent::UI, 43
TextInputTypeChanged	VE_Success
Coherent::UI::BrowserViewListener, 59	Coherent::UI, 43
Coherent::UI::ViewListener, 119	ValidEnd
TouchEvent	Coherent::UI::Certificate, 61
Coherent::UI::View, 106	ValidStart
TriggerEvent	Coherent::UI::Certificate, 61
Coherent::UI::View, 107	Value
Type	Coherent::UI::Binding::Value, 87, 88, 90
Coherent::UI::Binding::Value, 95	ValueType
Coherent::UI::KeyEventData, 71	Coherent::UI::Binding, 44
Coherent::UI::MediaStreamDevice, 72	ViewCreated
Coherent::UI::MouseEventData, 73	Coherent::UI::BrowserViewListener, 59
Coherent::UI::TouchEventData, 81	Coherent::UI::ViewListener, 119

```
ViewErrorType
    Coherent::UI, 42
ViewType
    Coherent::UI, 43
WheelX
    Coherent::UI::MouseEventData, 73
WheelY
    Coherent::UI::MouseEventData, 73
Width
    Coherent::UI::ViewInfo, 109
WriteFile
    Coherent::UI::FileHandler, 68
WriteLog
    Coherent::UI::ILogHandler, 69
WriteMinidumps
    Coherent::UI::SystemSettingsBase, 80
Χ
    Coherent::UI::MouseEventData, 74
    Coherent::UI::TouchEventData, 81
Υ
    Coherent::UI::MouseEventData, 74
    Coherent::UI::TouchEventData, 81
```