
Chapter 8: Main Memory





Chapter 8: Memory Management

- Background
- Swapping
- Contiguous Memory Allocation
- Segmentation
- Paging
- Structure of the Page Table
- Example: The Intel 32 and 64-bit Architectures
- Example: ARM Architecture





Objectives

- To provide a detailed description of various ways of organizing memory hardware
- To discuss various memory-management techniques, including paging and segmentation
- To provide a detailed description of the Intel Pentium, which supports both pure segmentation and segmentation with paging





Background


- Program must be brought (from disk) into memory and placed within a process for it to be run
- Main memory and registers are the only storage CPU can access directly
- Memory unit only sees a stream of addresses + read-requests, or address + data and write-requests
- Register can be accessed in one CPU clock (or less)
- Main memory access can take many cycles, causing a stall
- Cache sits between main memory and CPU registers, typically on CPU chip
- Protection of memory required to ensure correct operation
 - between processes from OS and users, and between processes from users
 - provided by hardware support, otherwise too costly to involve OS






Base and Limit Registers

- A pair of base and limit registers define the logical address space
 - these registers are loaded only by OS in kernel mode, with privileged instructions
- CPU must check every memory access generated in user mode to be sure it is between the base and limit for that user
- OS can access any OS and user's memory, in order to complete its tasks





Hardware Address Protection with Base and Limit Registers







Address Binding

- Programs on disk, ready to be brought into memory to execute, form an input queue
 - Without support, must be loaded into address 0000
- Inconvenient to have first user process physical address always at 0000
- Addresses represented in different ways at different stages of a program's life
 - Source code addresses usually symbolic (variable name)
 - Compiled code addresses bind to relocatable addresses
 - i.e. "14 bytes from beginning of this module"
 - Linker or loader will bind relocatable addresses to absolute addresses
 - i.e. 74014
 - Each binding maps one address space to another






Binding of Instructions and Data to Memory

- Address binding of instructions and data to memory addresses can happen at three different stages
 - **Compile time**: If memory location known a priori, **absolute code** can be generated and binding is done when compiling; must recompile code if starting location changes
 - **Load time**: Compiler must generate **relocatable code** if memory location is not known at compile time, and binding is done when loading; must reload if starting location changes
 - **Execution time**: Binding delayed until run time if the process can be moved during its execution from one memory segment to another
 - Need hardware support for address maps (e.g., base and limit registers)





Multistep Processing of a User Program







Logical vs. Physical Address Space

- The concept of a logical address space that is bound to a separate physical address space is central to proper memory management
 - Logical address generated by the CPU; also referred to as virtual address
 - Physical address address seen by the memory unit (MMU)
- Logical and physical addresses are the same in *compile-time and load-time address-binding schemes*
- Logical (virtual) and physical addresses differ in execution-time address-binding scheme
- Logical address space is the set of all logical addresses generated by a program
- Physical address space is the set of all physical addresses generated by a program






Memory-Management Unit (MMU)

- Hardware device that at run time maps virtual to physical address
- Many methods possible, covered in the rest of this chapter
- To start, consider simple scheme where the value in the *relocation register* is added to every address generated by a user process at the time it is sent to memory
 - Base register now called relocation register
 - MS-DOS on Intel 80x86 used 4 relocation registers
- The user program deals with *logical* addresses; it never sees the *real* physical addresses
 - Execution-time binding occurs when reference is made to location in memory
 - Logical address bound to physical addresses



Dynamic Relocation Using a Relocation Register

- Routine is not loaded until it is called
- Better memory-space utilization; unused routine is never loaded
- All routines kept on disk in relocatable load format
- When called, routine is checked if not in memory, and if so, it is loaded. The program address tables are updated, and control is passed to the newly loaded routine
- Useful when large amounts of code are needed to handle infrequently occurring cases
- No special support from the operating system is required
 - Implemented through program design
 - OS can help by providing libraries to implement dynamic loading







Dynamic Linking

- Static linking system libraries and program code combined by the loader into the binary program image
 - some OSes support only static linking
- Dynamic linking linking postponed until execution time
- Small piece of code, stub, used to locate the appropriate memory-resident library routine
- Stub replaces itself with the address of the routine, and executes the routine
- Operating system checks if routine is in processes' memory address
 - If not in address space, add to address space
- Dynamic linking is particularly useful for libraries
- System also known as shared libraries
- Consider applicability to patching system libraries
 - Versioning may be needed
- OS needs to support if the processes can access the shared library in the same memory space (more later...)






Swapping

- A process can be swapped temporarily out of memory to a backing store, and then brought back into memory for continued execution
 - Total physical memory space of processes can exceed physical memory
- Backing store fast disk large enough to accommodate copies of all memory images for all users; must provide direct access to these memory images
- Roll out, roll in swapping variant used for priority-based scheduling algorithms
 - lower-priority process is swapped out so higher-priority process can be loaded and executed
- Major part of swap time is transfer time; total transfer time is directly proportional to the amount of memory swapped
- System maintains a ready queue of ready-to-run processes which have memory images on disk
- Does the swapped out process need to swap back in to same physical addresses?
 - Depends on address binding method
 - Plus consider pending I/O to / from process memory space
- Modified versions of swapping are found on many systems (i.e., UNIX, Linux, and Windows)
 - Swapping normally disabled
 - Started if more than threshold amount of memory allocated
 - Disabled again once memory demand reduced below threshold





Schematic View of Swapping





Context Switch Time including Swapping

- If next processes to be put on CPU is not in memory, need to swap out a process and swap in target process
- Context switch time can then be very high
- 100MB process swapping to hard disk with transfer rate of 50MB/sec
 - Swap out time of 2000 ms
 - Plus swap in of same sized process
 - Total context switch swapping component time of 4000ms (4 seconds)
- Can reduce if reduce size of memory swapped by knowing how much memory really being used
 - System calls to inform OS of memory use via request memory() and release memory()
- Other constraints as well on swapping
 - Pending I/O cannot swap out as I/O would occur to wrong process
 - Or always transfer I/O to kernel space, then to I/O device
 - Known as double buffering, adds overhead
- Standard swapping not used in modern operating systems
 - But modified version common
 - Swap only when free memory extremely low





Swapping on Mobile Systems

- Not typically supported
 - Flash memory based
 - Small amount of space
 - Limited number of write cycles
 - Poor throughput between flash memory and CPU on mobile platform
- Instead use other methods to free memory if low
 - iOS asks apps to voluntarily relinquish allocated memory
 - Read-only data thrown out and reloaded from flash if needed
 - Failure to free can result in termination of a given process
 - Android terminates apps if low free memory, but first writes application state to flash for fast restart
 - Both OSes support paging as discussed below






Contiguous Allocation

- Main memory must support both OS and user processes
- Limited resource, must allocate efficiently
- Contiguous allocation is one early method
- Main memory usually into two partitions:
 - Resident operating system, usually held in low memory with interrupt vector
 - User processes then held in high memory
 - Each process contained in single contiguous section of memory
- Relocation registers used to protect user processes from each other, and from changing operating-system code and data
 - Base register contains value of smallest physical address
 - Limit register contains range of logical addresses each logical address must be less than the limit register
 - MMU maps logical address dynamically
 - Can then allow actions such as kernel code being transient and kernel changing size



Hardware Support for Relocation and Limit Registers








Contiguous Allocation (cont.)

- Multiple-partition allocation
 - With fixed-size partitions, degree of multiprogramming limited by number of partitions
 - Variable-partition sizes for efficiency (sized to a given process' needs)
 - Hole block of available memory; holes of various sizes are scattered throughout memory
 - When a process arrives, it is allocated memory from a hole large enough to accommodate it
 - Process exiting frees its partition, adjacent free partitions are combined
 - Operating system maintains information about:
 a) allocated partitions
 b) free partitions (hole)





How to satisfy a request of size *n* from a list of free holes?

- First-fit: Allocate the *first* hole that is big enough; can search from current location
- **Best-fit**: Allocate the *smallest* hole that is big enough; must search entire list, unless ordered by size
 - Produces the smallest leftover hole
- **Worst-fit**: Allocate the *largest* hole; must also search entire list
 - Produces the largest leftover hole

First-fit and best-fit are better than worst-fit in terms of speed and storage utilization





Fragmentation

- External Fragmentation total memory space exists to satisfy a request, but it is not contiguous
- Internal Fragmentation allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used
- First fit analysis reveals that given *N* blocks allocated, 0.5 *N* blocks are lost to fragmentation
 - 1/3 may be unusable -> 50-percent rule





Fragmentation (cont.)

- Reduce external fragmentation by compaction
 - Shuffle memory contents to place all free memory together in one large block
 - Compaction is possible only if relocation is dynamic, and is done at execution time
 - I/O problem
 - ▶ Latch job in memory while it is involved in I/O
 - Do I/O only into OS buffers
- Now consider that backing store has same fragmentation problems (general to storage problems)





Segmentation

- Memory-management scheme that supports user view of memory
- A program is a collection of segments
 - A segment is a logical unit such as:

```
main program
```

procedure

function

method

object

local variables, global variables

common block

stack


symbol table

arrays






User's View of a Program








Logical View of Segmentation





physical memory space





Segmentation Architecture

- Logical address consists of a two tuple:
 - < segment-number, offset >
- **Segment table** maps two-dimensional physical addresses; each table entry has:
 - base contains the starting physical address where the segments reside in memory
 - limit specifies the length of the segment
- Segment-table base register (STBR) points to the segment table's location in memory
- Segment-table length register (STLR) indicates number of segments used by a program;

segment number s is legal if s < STLR






Segmentation Architecture (cont.)

- Protection
 - With each entry in segment table associate:
 - validation bit = $0 \Rightarrow$ illegal segment
 - read/write/execute privileges
- Protection bits associated with segments; code sharing occurs at segment level
- Since segments vary in length, memory allocation is a dynamic storage-allocation problem
- A segmentation example is shown in the following diagram





Segmentation Hardware



8.29



Paging

- Physical address space of a process can be noncontiguous; process is allocated physical memory whenever the latter is available
 - Avoids external fragmentation
 - Avoids problem of varying sized memory chunks
- Divide physical memory into fixed-sized blocks called frames
 - Size is power of 2, between 512 bytes and 16 Mbytes
- Divide logical memory into blocks of same size called pages
- Keep track of all free frames
- To run a program of size **N** pages, need to find **N** free frames and load program
- Set up a page table to translate logical to physical addresses
- Backing store likewise split into pages
- Still have Internal fragmentation





Address Translation Scheme

- Address generated by CPU is divided into:
 - Page number (p) used as an index into a page table which contains base address of each page
 in physical memory
 - Page offset (d) combined with base address to define the physical memory address that is sent to the memory unit


| page number | page offset |
|-------------|---------------|
| р | d |
| (m-n) bits | <i>n</i> bits |

For given logical address space 2^m and page size 2ⁿ





Paging Hardware





Paging Model of Logical and Physical Memory

page 0

page 1

page 2

page 3

logical memory

page table

frame number

0

1 page 0

2

page 2

page 1

5


6

7 page 3

physical memory



Paging Example



n = 2 and m = 4 32-byte memory and 4-byte pages






Paging (cont.)

- Calculating internal fragmentation
 - Page size = 2,048 bytes
 - Process size = 72,766 bytes
 - 35 pages + 1,086 bytes
 - Internal fragmentation of 2,048 1,086 = 962 bytes
 - Worst case fragmentation = 1 frame + 1 byte
 - On average fragmentation = 1 / 2 frame size
 - So small frame sizes desirable?
 - But each page table entry takes memory to track
 - Page sizes growing over time
 - Solaris supports two page sizes 8 KB and 4 MB
- Process view and physical memory now very different
- By implementation, a process can only access its own memory





Free Frames



Before allocation

After allocation





Implementation of Page Table

- Page table is kept in main memory
- Page-table base register (PTBR) points to the page table
- Page-table length register (PTLR) indicates size of the page table
- In this scheme every data/instruction access requires two memory accesses
 - One for the page table and one for the data / instruction
- The two memory access problem can be solved by the use of a special fast-lookup *hardware cache* called associative memory or translation look-aside buffers (TLBs)
- Some TLBs store address-space identifiers (ASIDs) in each TLB entry uniquely identifies each process to provide address-space protection for that process
 - Otherwise need to flush at every context switch
- TLBs typically small (64 to 1024 entries)
- On a TLB miss, value is loaded into the TLB for faster access next time
 - Replacement policies must be considered (LRU, RR, etc.)
 - Some entries can be wired down for permanent fast access





Associative Memory


Associative memory – parallel search

| Page # | Frame # |
|--------|---------|
| | |
| | |
| | |
| | |

- Address translation (p, d)
 - If *p* is in associative register, get frame # out
 - Otherwise get frame # from page table in memory



Paging Hardware with TLB





Effective Access Time

- Associative Lookup = ε time unit
 - Can be < 10% of memory access time
- Hit ratio = α
 - Hit ratio percentage of times that a page number is found in the associative registers; ratio related to number of associative registers
- Consider $\alpha = 80\%$, $\varepsilon = 20$ ns for TLB search, m=100ns for memory access
- **■** Effective Access Time (EAT)

EAT =
$$(\varepsilon + 1m) \alpha + (\varepsilon + 2m)(1 - \alpha)$$

= $2m + \varepsilon - m \alpha$

- Consider α = 80%, ϵ = 20ns for TLB search, 100ns for memory access
 - EAT = 0.80 x (20+100) + 0.20 x (20+200) = 140ns
- Consider more realistic hit ratio -> α = 99%, ϵ = 20ns for TLB search, 100ns for memory access
 - EAT = $0.99 \times (20+100) + 0.01 \times (20+200) = 121$ ns






Memory Protection


- Memory protection implemented by associating protection bit with each frame to indicate if read-only or read-write access is allowed
 - Can also add more bits to indicate page execute-only, and so on
- Two methods to indicate valid entries in page table:
 - Valid-invalid bit attached to each entry in the page table:
 - "valid" indicates that the associated page is in the process' logical address space, and is thus a legal page
 - "invalid" indicates that the page is not in the process' logical address space
 - OR use page-table length register (PTLR)
 - this method wastes less memory for the page table
- Any violations result in a trap to the kernel





Valid (v) or Invalid (i) Bit in a Page Table







Shared Pages

Shared code

- One copy of read-only (reentrant) code shared among processes (i.e., text editors, compilers, window systems)
- Similar to multiple threads sharing the same process space
- Also useful for interprocess communication if sharing of read-write pages is allowed


Private code and data

- Each process keeps a separate copy of the code and data
- The pages for the private code and data can appear anywhere in the logical address space





Shared Pages Example





Structure of the Page Table

- Memory structures for paging can get huge using straight-forward methods
 - Consider a 32-bit logical address space as on modern computers
 - Page size of 4 KB (2¹²)
 - Page table would have more than 1 million entries (2³² / 2¹²)
 - If each entry is 4 bytes, it amounts to 4 MB of physical address space / memory for page table alone
 - That amount of memory used to cost a lot
 - Do not want to allocate that contiguously in main memory
- Hierarchical Paging
- Hashed Page Tables
- Inverted Page Tables






Hierarchical Page Tables

- Break up the logical address space into multiple page tables
- A simple technique is a two-level page table
- We then page the page table





Two-Level Page-Table Scheme







Two-Level Paging Example

- A logical address (on 32-bit machine with 1 KB page size) is divided into:
 - a page number consisting of 22 bits
 - a page offset consisting of 10 bits
- Since the page table is paged, the page number is further divided into:
 - a 12-bit page number
 - a 10-bit page offset
- Thus, a logical address is as follows:

| page | number | page offset | | | | |
|-------|--------|-------------|--|--|--|--|
| p_1 | p_2 | d | | | | |
| 12 | 10 | 10 | | | | |


where p_1 is an index into the outer page table, and p_2 is the displacement within the page of the inner page table

■ Known as forward-mapped page table





Address-Translation Scheme








64-bit Logical Address Space

- Even two-level paging scheme not sufficient for a 64-bit machine
- If page size is 4 KB (2¹²)
 - Then page table has 252 entries
 - If two-level scheme, with an inner page table that could be 2¹⁰ x 4-byte entries
 - Address would look like

| outer page | inner page | page offset |
|------------|------------|-------------|
| p_1 | p_2 | d |
| 42 | 10 | 12 |

- Outer page table has 2⁴² entries or 2⁴⁴ bytes
- One solution is to add a 2nd outer page table
- But in the following example the 2nd outer page table is still 2³⁴ bytes in size
 - And possibly 4 memory access to get to one physical memory location





Three-level Paging Scheme

| outer page | inner page | offset |
|------------|------------|--------|
| p_1 | p_2 | d |
| 42 | 10 | 12 |

| 2nd outer page | outer page | inner page | offset |
|----------------|------------|------------|--------|
| p_1 | p_2 | p_3 | d |
| 32 | 10 | 10 | 12 |






Hashed Page Tables

- Common in address spaces > 32 bits
- The virtual page number is hashed into a page table
 - This page table contains a chain of elements hashing to the same location
- Each element contains
 - (1) the virtual page number
 - (2) the value of the mapped page frame
 - (3) a pointer to the next element
- Virtual page numbers are compared in this chain, searching for a match
 - If a match is found, the corresponding physical frame is extracted
- Variation for 64-bit addresses is clustered page tables
 - Similar to hashed but each entry refers to several pages (such as 16) rather than 1
 - Especially useful for sparse address spaces (where memory references are non-contiguous and scattered)



Hashed Page Table








Inverted Page Table

- Rather than each process having a page table and keeping track of all possible logical pages, track all physical pages
- One entry for each real page of memory
- Entry consists of the virtual address of the page stored in that real memory location, with information about the process that owns that page
- Decreases memory needed to store each page table, but increases time needed to search the table when a page reference occurs
- Use hash table to limit the search to one or at most a few page-table entries
 - TLB can accelerate access
- But how to implement shared memory?
 - One mapping of a virtual address to the shared physical address





Inverted Page Table Architecture





Oracle SPARC Solaris

- Consider modern, 64-bit operating system example with tightly integrated hardware
 - Goals are efficiency, low overhead
- Based on hashing, but more complex
- Two hash tables
 - One for kernel processes and one for all user processes
 - Each maps memory addresses from virtual to physical memory
 - Each entry represents a contiguous area of mapped virtual memory
 - More efficient than having a separate hash-table entry for each page
 - Each entry has base address and span (indicating the number of pages the entry represents)
- TLB holds translation table entries (TTEs) for fast hardware lookups
 - A cache of TTEs reside in a translation storage buffer (TSB)
 - Includes an entry per recently accessed page
- Virtual address reference causes TLB search
 - If miss, hardware walks the in-memory TSB looking for the TTE corresponding to the address
 - If match found, the CPU copies the TSB entry into the TLB and translation completes
 - If no match found, kernel interrupted to search the hash table
 - The kernel then creates a TTE from the appropriate hash table and stores it in the TSB, Interrupt handler returns control to the MMU, which completes the address translation.



- Dominant industry chips
- Pentium CPUs are 32-bit and called IA-32 architecture
- Current Intel CPUs are 64-bit and called IA-64 architecture
- Many variations in the chips, cover the main ideas here





Example: The Intel IA-32 Architecture

- Supports both segmentation and segmentation with paging
 - Each segment can be 4 GB
 - Up to 16 K segments per process
 - Divided into two partitions
 - First partition of up to 8 K segments are private to process (kept in local descriptor table (LDT))
 - Second partition of up to 8K segments shared among all processes (kept in global descriptor table (GDT))
- CPU generates logical address
 - Selector given to segmentation unit
 - Which produces linear addresses

| S | 8 | р |
|----|---|---|
| 13 | 1 | 2 |


segment number, local/global, protection

- Linear address given to paging unit
 - Which generates physical address in main memory
 - Paging units form equivalent of MMU
 - Pages sizes can be 4 KB or 4 MB





Logical to Physical Address Translation in IA-32




| page n | umber | page offset | | | | |
|--------|-------|-------------|--|--|--|--|
| p_1 | p_2 | d | | | | |
| 10 | 10 | 12 | | | | |






Intel IA-32 Segmentation








Intel IA-32 Paging Architecture





Intel IA-32 Page Address Extensions

- 32-bit address limits led Intel to create page address extension (PAE), allowing 32-bit apps access to more than 4GB of memory space
 - Paging went to a 3-level scheme
 - Top two bits refer to a page directory pointer table
 - Page-directory and page-table entries moved to 64-bits in size
 - Net effect is increasing address space to 36 bits 64GB of physical memory





Intel x86-64

- Current generation Intel x86 architecture
- 64 bits is ginormous (> 16 exabytes)
- In practice only implement 48 bit addressing
 - Page sizes of 4 KB, 2 MB, 1 GB
 - Four levels of paging hierarchy
- Can also use PAE so virtual addresses are 48 bits and physical addresses are 52 bits


| | | page map |) | page | e directory | | page | | page | | | |
|--------|------|----------|----|------|-------------|----|-----------|-------|-------|-------|--------|---|
| unused | | level 4 | | poi | nter table | | directory | | table | | offset | |
| 63 | 48 4 | 47 | 39 | 38 | 30 | 29 | 2 | 21 20 | | 12 11 | | 0 |





Example: ARM Architecture

- Dominant mobile platform chip (Apple iOS and Google Android devices for example)
- Modern, energy efficient, 32-bit CPU
- 4 KB and 16 KB pages
- 1 MB and 16 MB pages (termed sections)
- One-level paging for sections, two-level for smaller pages
- Two levels of TLBs
 - Outer level has two micro TLBs (one data, one instruction)
 - Inner is single main TLB
 - First inner is checked, on miss outers are checked, and on miss page table walk performed by CPU





End of Chapter 8

